# Configure XCP

XCP 1.6.2

NetApp October 27, 2020

 $This\ PDF\ was\ generated\ from\ https://docs.netapp.com/us-en/xcp/xcp-create-the-json-configuration-file.html\ on\ October\ 27,\ 2020.\ Always\ check\ docs.netapp.com\ for\ the\ latest.$ 



# **Table of Contents**

C	onfigure XCP	1
	Configure the INI file for XCP NFS	1
	Performance tuning (NFS only)	1
	Environment variable (NFS only).	2
	Logging for NFS and SMB (optional)	2
	Create the JSON configuration file	5

### **Configure XCP**

### Configure the INI file for XCP NFS

Follow these steps to configure the INI file for XCP NFS.

#### **Steps**

1. Add the catalog location for the XCP server in the host configuration file using the vi editor.



Catalog location should be exported before modifying the details in the xcp.ini XCP configuration file. Catalog location (NFSv3) should be mountable by the XCP Linux host but not necessarily be mounted.

```
[root@localhost /]# vi /opt/NetApp/xFiles/xcp/xcp.ini
```

2. Verify that the XCP Linux client host configuration file entries for the catalog were modified.

```
[root@localhost /]# cat /opt/NetApp/xFiles/xcp/xcp.ini
# Sample xcp config
[xcp]
catalog = 10.61.82.210:/vol/xcpvol/
```

### Performance tuning (NFS only)

For the optimal performance and reliability, NetApp recommends setting the following Linux kernel TCP performance parameters in /etc/sysctl.conf on the XCP Linux client host. Run sysctl -p or the reboot command to commit the changes:

```
net.core.rmem_default = 1342177

37Tnet.core.rmem_max = 16777216

37Tnet.core.rmem_max = 16777216

37Tnet.core.wmem_default = 1342177

37Tnet.core.wmem_max = 16777216

37Tnet.ipv4.tcp_rmem = 4096 1342177 16777216

37Tnet.ipv4.tcp_wmem = 4096 1342177 16777216

37Tnet.core.netdev_max_backlog = 300000

37Tnet.ipv4.tcp_fin_timeout = 10
```

### **Environment variable (NFS only)**

The environment variable XCP\_CONFIG\_DIR overrides the default location, /opt/NetApp/xFiles/xcp. If set, the value should be an OS filesystem path, possibly to a mounted NFS directory. When a custom configuration directory is set, the log file is named xcp.hostname.log instead of the default, xcp.log.

```
[root@localhost /]# export XCP_CONFIG_DIR ='/tmp/xcp_config_dir_path'
```

The environment variable XCP\_LOG\_DIR overrides the default location that stores the XCP log in the configuration directory. If set, the value should be an OS filesystem path, possibly to a mounted NFS directory. When a custom log directory is set, the log file is named xcp.hostname.log instead of the default, xcp.log.

```
[root@localhost /]# export XCP_LOG_DIR='/tmp/xcp_log_dir_path'
```

The environment variable XCP\_CATALOG\_PATH overrides the setting in xcp.ini. If set, the value should be in the xcp path format, server:export[:subdirectory].

```
[root@localhost /]# export XCP_CATALOG_PATH='10.61.82.210:/vol/xcpvol/'
```

### Logging for NFS and SMB (optional)

XCP supports configuring multiple optional features by using the xcpLogConfig.json JSON configuration file. To enable only specific features, manually create the xcpLogConfig.json configuration file, You can use the xcpLogConfig.json configuration file to enable:

- · event log messages
- syslog client for XCP
- custom XCP logging

Event log messages and the syslog client are disabled in the default configuration. Configuration is common for both NFS and SMB.

Config JSON file location	NFS	SMB
Config file default location	/opt/NetApp/xFiles/xcp/	C:\NetApp\XCP\ConfigFile
Custom location requires the XCP_CONFIG_DIR environment variable	Error! Reference source not found.	NA

The JSON configuration file options are case sensitive. These options are the same for XCP NFS and XCP

Sub Options Name	JSON Data Type	Default	Description
logConfig			Option to customize XCP logging.
"level"	String	INFO	Log message severity filter level.  XCP log messages support five severity levels in order of decreasing severity:  CRITICAL, ERROR,  WARNING, INFO,  DEBUG  (NetApp strongly recommends using INFO or DEBUG)
"maxBytes"	Integer	52428800	Size of each rotating log file. Max supported rotation files are 10.
"name"	String	xcp.log	Option to set custom log file name.
eventlog			Option to configure event log message.
"isEnabled"	Boolean	false	This boolean option is used to enable event messaging. Setting it false will not generate any event messages and no event logs will be published to event log file.
"level"	String	INFO	Event message severity filter level. Event messaging support five severity levels in order of decreasing severity: CRITICAL, ERROR, WARNING, INFO, DEBUG

Sub Options Name	JSON Data Type	Default	Description
syslog			Option to configure syslog messaging.
"isEnabled"	Boolean	false	This boolean option is used to enable syslog client in XCP.
"level"	String	INFO	Message severity filter level.  XCP event log messages support five severity levels in order of decreasing severity:  CRITICAL, ERROR,  WARNING, INFO,  DEBUG
"serverIp"	String	None	Remote syslog server IP addresses or hostname.
"port"	Integer	514	Remote syslog receiver port. Syslog receivers accepting syslog datagrams on a different port can be configured with port option UDP port 514 but you can also configure to the desired port.

Sub Options Name	JSON Data Type	Default	Description
"sanitize"	Boolean	false	A common option for XCP support; setting its value to true will hide sensitive information (IP and username) in the messages going to support (logging, events, syslog, etc.) For example, with the sanitize option as false  • 2020-07-17 03:10:23,779 - INFO - 12806 xcp xcp Paths: ['10.234.104.251:/cat_vol']  • 2020-07-17 03:10:23,778 - INFO - 12806 xcp xcp User Name: root With the sanitize option as true • 2020-07-17 03:13:51,596 - INFO - 12859 xcp xcp Paths: ['IP: XX.XX.XX.XX:/cat_vol'] • 2020-07-17 03:13:51,595 - INFO - 12859 xcp xcp User Name:

## Create the JSON configuration file

If you want to enable event log messages, the syslog client, or customer logging, complete the following steps.

### **Steps**

- 1. Open any text editor, such as notepad or vi.
- 2. Create a new file with the following JSON template.

```
{
 "logConfig": {
   "level": "INFO",
    "maxBytes": 52428800,
    "name": "xcp.log"
 },
  "eventlog": {
    "isEnabled": false,
    "level": "INFO"
 },
  "syslog": {
    "isEnabled": false,
   "level": "INFO",
    "serverIp": "10.234.219.87",
    "port": 514
 },
  "sanitize": false
}
```

- 3. For any features you want to enable, change the is Enabled value to true.
- 4. Name the file xcpLogConfig.json and sae it to the file location mentioned in Error! Reference source not found.

#### Default configuration

```
{
  "logConfig": {
    "level": "INFO",
    "maxBytes": 52428800,
    "name": "xcp.log"
  },
  "sanitize": false
}
```

#### Example json configuration file

```
"logConfig": {
   "level": "INFO",
    "maxBytes": 52428800,
    "name": "xcp.log"
 },
  "eventlog": {
    "isEnabled": false,
    "level": "INFO"
 },
  "syslog": {
    "isEnabled": false,
    "level": "INFO",
    "serverIp": "10.234.219.87",
    "port": 514
 },
  "sanitize": false
}
```

#### **Copyright Information**

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval systemwithout prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.