
CONCEPT

The COsmological N-body CodE in PyThon

User's Guide

Jeppe Mosgaard Dakin jeppe.mosgaard.dakin(at)post.au.dk October 19, 2015



This document serves as a user's guide to the CONCEPT code. It is split up into two parts, the first of which gives a basic overview of the functionality of the program, while the second is much more in-depth.

The GitHub page for the CONCEPT code can be found at https://github.com/jmd-dk/concept/

Contents

Ι	Overview	3
1	Introduction	4
	1.1 Jargon	5
2	Basic Usage	6
	2.1 Installation	6
	2.2 Files and Directories	6
	2.3 Running the Code	7
	2.3.1 Parameters and Output	7
II	In-depth Guide	10
3	Installation	11
	3.1 Dependencies	11
	3.2 The installer	12
	3.2.1 Using Pre-installed Libraries	13
	3.2.2 Requesting Specific Versions	14
	3.3 Manual Installation	14
4	Running the Code	16
	4.1 Local vs. Remote Execution	16
	4.2 The concept Command-Line Interface	18
	4.3 Manual Build and Run	20
	4.4 Cleaning	20
5	Parameters	22
6	Snapshot Formats	27
	6.1 The Standard CONCEPT Snapshot Format	27
7	Utilities	30
8	Tests	33

Part I Overview

1 Introduction

Concept (COsmological N-body CodE in PyThon) is a free and open-source code for cosmological N-body simulations on massively parallel computers with distributed memory. As of the time of writing, collisionless dark matter is the only implemented particle species. Gravity can be computed using the PP, PM or the P^3M algorithm. The goal of CONCEPT is to make it pleasant to work with cosmological N-body simulations — for the cosmologist as well as for the source code developer.

CONCEPT is easy to use and has good performance. The source code is properly structured, well-commented and consist almost exclusively of PEP 8 compliant* Python code.

CONCEPT relies on the Cython compiler, which translates (or *cythonizes*) Python source code to equivalent C source code, which are then compiled as any other C program. The computationally expensive parts of the code are written such that they translate very directly into C code, while the inexpensive parts are written using the whole spectrum of modern Python constructs, which are only poorly translated into C code[†]. In effect this allow for high performance and rapid development.

In addition to running CONCEPT in compiled mode, it is also possible to run it as any other Python script, though with a hefty performance penalty.

The CONCEPT code is written in version 3 of the Python language. Among other things, this allows for Unicode literals in strings and variable names, which CONCEPT takes advantage of. All source files are therefore encoded in UTF-8. This unconventional and slightly dangerous choice is made in the name of æsthetics.

Although CONCEPT is intended for computer clusters, it really runs on anything down to single-core laptops. Communication between CPUs is done explicitly by means of the message passing interface (MPI). The code has been tested and found to work on a large number of Linux systems.

^{*}Pep 8 is the official style guide for writing clean and idiomatic Python code.

[†]When no equivalent C construct exists for a given Python construct, Cython simply generates the CPython C API calls corresponding to the given Python construct.

1.1 Jargon

The particles of the simulation lives within a periodic box which constitutes the simulated universe. A file containing the total state of the system (the positions and momenta of all N particles) at any given time is referred to as a snapshot. The initial snapshot constituting the initial conditions is then called the initial condition file, or IC file for short. Besides the initial conditions, a particular simulation is defined by the values of a set of parameters, controlling the cosmology, physics and numerical schemes and accuracies of the simulation. A file containing the collective set of parameter values is called a parameter file. The user-defined input to each simulation is then an IC file and a parameter file. A particular instance of a simulation is referred to as a run.

2 Basic Usage

Here we state the very basic functionalities of CONCEPT in a tutorial-like manner*. For a much more in-depth description, see part II of this document.

2.1 Installation

To install CONCEPT along with all the dependency programs it needs, simply run the command

```
bash <(wget -0- --no-ch bit.ly/concept_nbody)</pre>
```

from a terminal, which will download and launch the CONCEPT installer. You will be prompted for an installation directory in which everything will be placed. To uninstall CONCEPT, simply delete this directory. The installation will consume slightly less than 1 GB of disk space and will complete within 1–2 hours on modern hardware.

2.2 Files and Directories

A stripped down version of CONCEPT's directory tree is shown in figure 2.1. The concept directory contains four subdirectories and the concept executable, which is just a Bash script. The ICs subdirectory is intended for storage of IC files. As part of the CONCEPT distribution, an example IC file is provided. This IC file is written in CONCEPT's so-called "standard" HDF5 format. Similarly to ICs, the params subdirectory is intended for the storage of parameter files. An example parameter file, which is just a text file of definitions, is provided. Parameter and IC files are described in detail in chapters 5 and 6, respectively.

The output directory is the default directory for CONCEPT to dump its output, while logs is where it save log files. Everything printed to the screen in each run will be logged automatically.

^{*}If this is your first experience with CONCEPT, it is advised that you try it out on a local computer rather than on a remote host, as the behavior of CONCEPT differs somewhat for these two cases.




Figure 2.1 – Basic directory tree for CONCEPT. The colors indicate directories (blue), Bash scripts (green), text files (black) and HDF5 files (gray).

2.3 Running the Code

The simplest possible invocation of CONCEPT — assuming that you are in the concept directory — is

```
./concept
```

You will be told that you did not specify neither the number of processes nor the parameter file to use. Concept then resorts to running a single process and using its internal default values for all parameters. If this is the first run or the code is not built for some other reason, Concept will now do so. When the build process is completed, the actual run will begin and immediately finish, without really doing anything.

To control the number of processes to use and specify a parameter file, invoke CONCEPT like e.g.

```
./concept -n 2 -p params/example
```

which will use two processes to run the simulation defined by the example parameter file. As ordered by the parameter file, a snapshot will be produced in the output directory.

The concept script has many more options, which will be described in detail in section 4.2. For now you may take a quick look at the available options using

```
./concept -h
```

2.3.1 Parameters and Output

Let us take a short look at some of the parameters in the example parameter file. Opening the file we see that the parameters are grouped into categories. In the first category, input/output, the IC file together with any wanted output is specified. Below some of the parameters in this category are given new values:

```
# Input/output
IC_file = 'ICs/example'
snapshot_type = 'standard'
output_dirs = {
    'snapshot' : 'output',
    'powerspec': 'output/powerspec',
              : ',
output_bases = {
    'snapshot' : 'spam',
    'powerspec': 'ham',
    'render'
               : 'eggs',
output_times = {
    'snapshot'
                     : 1,
    'powerspec'
                     : (0.5, 1),
                     : linspace(0.05, 1, 5),
    'render'
    'terminal render': [sqrt(i) for i in (0.3, 0.4, 0.5)],
```

As listed in the output_times variable, four different kinds of output are available:

Snapshots

This is simply a dump of the raw state of the particle system, in the format specified by snapshot_type.

Power spectra

Instead of simply outputting the raw data, you may be more interested in some reduced form of it. The power spectrum is one such form. The primary power spectrum output is a text file containing the power spectrum data. Optionally, CONCEPT is able to also plot the power spectrum and produce an image file (look for the powerspec_plot parameter in the graphics category). Throughout the CONCEPT code, a power spectrum is referred to as a powerspec.

Renders

CONCEPT is able to produce 3D graphical visualizations of the particles. Each render output is an image of one such visualization. The appearance of the renders can be adjusted using parameters in the graphics category.

Terminal renders

Like renders, terminal renders are graphical visualizations of the particles. Unlike renders however, terminal renders get printed directly in the terminal and are not saved to disk (disregarding the log file). The

appearance of the terminal renders can be adjusted using parameters in the graphics category.

Since all four kinds of output have non-empty output times in the parameter file snippet above, they are all going to be produced. An output will be produced during the simulation when the scale factor matches a value given in output_times. As demonstrated above, CONCEPT accepts values for output_times in a variety of different formats. It holds generally for all parameters that any meaningful and valid Python statement may be used as their definition.

The values in output_dirs are the directories in which to dump the different kinds of output. These — as well as all other relative paths in the CONCEPT code — should be stated relative to the concept directory. In the parameter file snippet above, we see that snapshots will be placed in the standard output directory, while power spectra will be placed in the non-standard output/powerspec directory. Any non-existing output directories will be created as needed. Lastly, we see that no output directory is assigned to renders. As renders are going to be produced, CONCEPT assigns output as the render output directory. This is an example of CONCEPT's use of default parameter values. You can leave out any parameter from your parameter files and they will be handled for you in a similar manner. It is however not generally advised to write parameter files which depend on the choice of such default assignments.

The values in output_bases serves as filename prefixes given to the different output. This together with the output time labels the output files. The parameter file snippet above will e.g. produce the output files output/spam_a=1.00, output/powerspec/spam_a=1.00 and output/eggs_a=1.00.png.

Part II In-depth Guide

3 Installation

The CONCEPT code should be able to compile and run on virtually any Linux system. The software stack needed to build and run the code is quite large, taking up nearly 1 GB of disk space. To ease the process of installation of this stack, CONCEPT comes with an installer script, which automates this process.

Some basic system dependencies* are required to run even the installer. These programs are pre-installed on most Linux systems. If installer is run while some system dependencies are missing, these will be reported to you. Additionally, if the installer finds an installed package-manager, it will prompt for installation of the missing system dependencies (requiring root privileges).

3.1 Dependencies

The CONCEPT code has the following free and open-source software dependencies:

GSL The GNU Scientific Library.

MPI Any implementation of the Message Passing Interface (version 3.0 or newer).

HDF5 The Hierarchical Data Format, linked to the MPI library and configured to be parallel. It has the zlib library as a dependency.

FFTW The Fastest Fourier Transform in the West (version 3.3 or newer), linked to the MPI library and configured to be parallel.

Python The standard C-implementation of the Python programming language (version 3.3 or newer). For pip[†] to be installed as part of Python, Python

^{*}By "system dependencies" we mean software components which are usually installed system-wide by the root user. The complete list of system dependencies are AWK, Bash (version 4.0 or newer), sed, GNU Coreutils, GNU Make, GCC, GFortran, G++, gzip, Perl, tar and wget. Only the first six of these are strictly necessary to run the CONCEPT code, though all of them are needed to run the installer script.

[†]The Python package manager pip is handy when it comes to installing Python packages.

needs to be built against the OpenSSL and zlib libraries. The Python package Blessings depends on the _curses module, which is installed as part of Python provided that Python is built against the neurses library. The following* Python site-packages are required:

Blessings This package depends on the curses Python module.

Cython Version 0.22.0 or newer, though not 0.23.

Cython GSL This needs to be linked to the GSL library.

H5Py Version 2.4 or newer, linked to the HDF5 library and configured to be parallel.

Matplotlib This package depends on the FreeType library.

MPI4Py Version 1.3.1 or newer, linked to the MPI library.

NumPy

Pexpect

ImageMagick This is only needed for producing renders when running with more than 1 CPU and can be omitted. ImageMagick needs to be built with png and zlib features, which require the pnglib and zlib libraries.

GADGET The GAlaxies with Dark matter and Gas intEracT N-body code (version 2.0.7). This is only needed for running some tests and can be omitted. GADGET is also dependent on GSL, MPI and FFTW. Note that GADGET is incompatible with FFTW 3.x, so a separate FFTW 2.x must also be installed.

3.2 The installer

The CONCEPT code and all of the dependencies listed in the previous section (including the dependencies of the dependencies ...) can be installed and linked together automatically by running the installer Bash script. You can find the script in the GitHub repository[†], or you can simply run^{‡§}

```
bash <(wget -0- --no-ch bit.ly/concept_nbody) [install_dir]</pre>
```

to automatically fetch and execute the script. Here, <code>install_dir</code> is the path to the directory in which CONCEPT should be installed. If you leave out this path, you will be prompted for it. Naturally, it is also possible to save the <code>installer</code> to disk and invoke it like e.g.

^{*}Some of these depend on other Python packages which are not listed. If installing via pip, these additional Python packages will automatically be installed.

[†]https://raw.githubusercontent.com/jmd-dk/concept/master/installer

[‡]The bit.ly/concept_nbody part refers to the URL http://bit.ly/concept_nbody, which redirects to the installer script on GitHub. If the short version does not work, use the full URL.

[§]The square bracket indicates an optional argument.

```
./installer [install_dir]
```

The installer script will use MPICH for the needed MPI implementation*. Besides the listed Python packages and their own Python package dependencies, the installer will install the pip and Yolk3k Python packages, which is used to install the primary packages.

The installer script will install CONCEPT and the entire dependency stack within the chosen installation directory. Uninstalling everything therefore simply amounts to removing this directory.

On modern hardware, it takes the installer around 1–2 hours to complete the installation. This is mainly because the installer script insists on installing everything from source, rather than using pre-compiled binaries. One benefit from this choice is that the installed software becomes tailor-made for the hardware in question, optimizing the performance. The primary reason for this choice is however portability (e.g. the installer is able to install CONCEPT and the dependency stack on both 32-bit and 64-bit architectures).

A significant fraction of the installation time is spent running the test suites that the many programs provide. To speed up the installation (and leave potential errors unnoticed!), you may skip these tests by invoke the installer with the --fast option:

```
# from local copy of installer
./installer --fast [install_dir]

# from the installer on GitHub
bash <(wget -0- --no-ch bit.ly/concept_nbody) --fast [install_dir]</pre>
```

To decrease the installation time further, the --fast option also sets any idle time to zero, decreasing the chances for successful downloading for questionable connections.

3.2.1 Using Pre-installed Libraries

By default, any pre-installed versions of the above software will be ignored. Should you wish the installer to use such pre-installed components, you have to declare their directory paths through <code>name_dir</code> environment variables, where <code>name</code> is the name[†] of the pre-installed program. E.g. to use a pre-installed GSL library, invoke the installer like so:

^{*}Note on possible problems related to using MPICH on clusters with several nodes: MPICH uses ssh to launch MPI-threads on remote nodes, which require that password-less login to the cluster nodes is enabled (this is not to be confused with password-less login to the cluster itself). Should you encounter problems when running multi-node CONCEPT jobs, this may be the problem. In addition, newer version of ssh blocks password-less login if your home-directory has group write access.

[†]The valid *name*s are exactly those of the dependencies listed in section 3.1, written in all lowercase. For the fftw 2.x library used by GADGET, use fftw_for_gadget_dir.

```
# from local copy of installer
gsl_dir=/path/to/gsl ./installer [...]

# from the installer on GitHub
gsl_dir=/path/to/gsl bash <(wget -0- --no-ch bit.ly/concept_nbody) [...]</pre>
```

Here and in what follows, [···] stands for a space-seperated list of optional arguments (e.g. install_dir and --fast). Multiple program paths are specified as a space-separated list.

Should you choose to use a pre-installed Python distribution, it needs to satisfy the following requirements:

- The pip Python package needs to be installed if any of the required Python packages are not installed.
- The curses Python module needs to be installed.

Pre-installed Python packages are automatically detected when the python_dir environment variable is set. That is, you do not have to set e.g. blessings_dir.

3.2.2 Requesting Specific Versions

Should you wish to install a specific version of some dependency, simply set the environment variable *name_version* when invoking the installer. This also works for Python packages. E.g. to install version 1.15 of GSL:

```
# from local copy of installer
gsl_version=1.15 ./installer [...]

# from the installer on GitHub
gsl_version=1.15 bash <(wget -0- --no-ch bit.ly/concept_nbody) [...]</pre>
```

Multiple program versions are specified as a space-separated list.

3.3 Manual Installation

To do a manual installation of any of the dependency programs, we refer to their individual online documentation.

To install just the CONCEPT code without any of the dependency programs, simply download the CONCEPT code from its GitHub repository* and extract it into some directory. To make CONCEPT aware of the installed dependency programs, simply edit the .paths file, which you will find in the topmost directory. The .paths file contains the *absolute* paths to every[†] file and directory which CONCEPT needs to know about. No path information is ever

^{*}https://github.com/jmd-dk/concept/archive/master.tar.gz

 $^{^\}dagger \mathrm{With}$ the exception of system dependencies (e.g. AWK) which are expected to be on the PATH.

drawn from anywhere else. The description of each variable within the .paths file itself should constitute enough documentation of which variable should contain which path.

All the paths specified in the .paths file are read in at runtime by CONCEPT. Should you ever wish to make CONCEPT aware of additional paths, simply add them to the .paths file.

4 Running the Code

In this chapter the primary functionalities and invocation methods of CONCEPT are described. In addition, CONCEPT implements secondary functionalities — called *utilities* — which are not used to run simulations directly, but serve as convenient tools within the program environment. For these secondary uses of CONCEPT, see chapter 7.

A directory tree of CONCEPT is shown in figure 4.1. Disregarding IC and parameter files, the concept script is the only file that the user should ever have to interact with directly in order to run the code. In the simplest case (see the next section for the differences between local and remote execution), executing the concept script will build and run the code.

As compilation is performed automatically when the code is executed, before describing how to run the code in detail, a brief description of this build process is in order. When the concept script is executed, it invokes the Makefile which builds the program. The compiled program consists of a set of shared object (.so) files; precisely one for each of the modules (the Python .py files grouped together in figure 4.1). To run the program, the main module, main.so, is invoked via the Python interpreter, which itself is started by MPI. Running in so-called "pure Python mode", meaning without first having compiled the code, amounts to skipping the entire build process but otherwise invoking the main module (now main.py) in a similar fashion. For the exact commands needed to run CONCEPT manually, see section 4.3.

Each CONCEPT run will be assigned a unique ID. The combined output to stdout and stderr will always be logged to the file logs/ID, where ID is the ID of the current run in question. The output from stderr alone will similarly be saved to logs/ID_err.

4.1 Local vs. Remote Execution

Running the concept script on a local machine will build (if necessary) and run the code. When logged on to a remote host though, the default behavior is to build the program and do nothing more. This behavior is chosen in order to bring the user in control of how the program should be executed. Often, computer clusters utilizes a job scheduling mechanism, such as PBS (Portable




Figure 4.1 – Directory tree for CONCEPT. As in figure 2.1, the colors indicate directories (blue), Bash scripts (green), text files (black) and HDF5 files (grey). In addition we now have C source code files (red), makefiles (purple), PDF files (yellow) and Python files (orange). Two of the Python files are listed separately, while the others are grouped together. The files in this group are referred to as Python *modules*.

Batch System). The CONCEPT script is able to autogenerate and submit PBS job scripts*. If this feature is desired, you need to edit the first couple of lines in the concept script as follows:

^{*}Even though several versions of PBS exist (such us OpenPBS, TORQUE and PBS Professional), each with slightly different functionality, the core components used by concept are the same in all of them.

Populate the queues and ppns variables with queue names and corresponding numbers of CPUs per node. As an example, imagine that we wish CONCEPT to be aware of the queues 'q8' and 'q4', which have 8 and 4 CPUs per node, respectively. In that case, we would set the variables as queues=(q8 q4) ppns=(8 4)

Now when executing the concept script on the remote host, a queue from the queues variable will be chosen for the job, based on its number of CPUs per node. To ensure maximum exploitation of the available resources, a queue will only be deemed fit for use if the number of requested processes is divisible by the number of CPUs per node in the queue (so that the job utilizes every CPU on the nodes it occupy). If no queue satisfies this requirement, the job will not be submitted. If multiple queues satisfy the requirement, the one listed first in the queues variable will be used. A job script will then be generated, saved as

Should you wish to run CONCEPT directly, without the use of PBS, even though you are not working on a local machine, invoke concept with the --local option:

```
./concept --local
```

concept/jobscript and submitted.

The next section lists with the full set of options available when executing concept.

4.2 The concept Command-Line Interface

As already demonstrated, several optional options may be given when invoking the concept script. As is customary for UNIX shell scripts, a list of available options together with brief descriptions will be shown when invoking the concept script with the -h or --help option. Here follows the same list but with much extended descriptions. Remember that supplied paths may be either absolute or relative to the concept directory.

-h, --help

Show the help message and exit.

-m MAIN, --main MAIN

Sets the main entry point of the code to the path MAIN. The default value is concept/main.py. This option is used internally by CONCEPT when running tests, but does not currently have other use cases.

-n NPROCS, --nprocs NPROCS

Sets the number of MPI processes to NPROCS. The default value is 1. Note that this can take on values larger than the number of available CPUs, at the cost of performance.

-p PARAMS, --params PARAMS

Sets the parameter file to be used to PARAMS. If not set, default parameters as specified in commons.py are used.

-q QUEUE, --queue QUEUE

Sets the queue to be used when submitting as a remote PBS job to QUEUE. The specified queue must be predefined in the queues and ppns variables in the top of the concept script. If this option is not set, the first queue in the queues variable which have a matching number of CPUs per node will be chosen.

-t TEST, --test TEST

Instead of running a simulation, run the test TEST. The possible values for TEST are the names of the subdirectories within the concept/tests directory, possibly with the relative or absolute path included. In addition it is possible to run all tests by setting TEST to all. See chapter 8 for details.

-u UTIL [···], --util UTIL [···]

Instead of running a simulation, run the utility UTIL. The possible values for UTIL are the names of the subdirectories within the concept/utilities directory, possibly with the relative or absolute path included. Most utilities require an additional argument to be passed. See chapter 7 for details.

-w WALLTIME, --walltime WALLTIME

Sets the PBS walltime to WALLTIME, in whole hours. The default is 72 hours.

--local

Build and run the code as if working on a local machine, regardless of whether this is actually the case. That is, even if working remotely, the code will be executed directly, rather than submitted as a PBS job.

--pure-python

Skips the build process. The code will then resort to use the raw Python files directly. This is generally not preferred due to the severe performance penalty this entails, but it can be useful for debugging and running the code with a main entry point not suited for cythonization. If the code is already fully built, the shared object (.so) files will be renamed to .so_, in order for Python not to pick up these compiled modules. The next time concept is invoked without the --pure-python option, the compiled module files will be renamed back to .so.

4.3 Manual Build and Run

Should you ever need to build and run CONCEPT manually, i.e. without invoking the concept script, this section lists the needed commands. When running the code manually, logging is your responsibility.

To build the code, simply type

make

within the concept directory. When the code is fully built, you can execute it as

```
mpiexec -n NPROCS python -B -m main.so "params='PARAMS'"
```

where mpiexec and python are, respectively, the MPI executable and the Python interpreter, the paths of which should be written in the .paths file. As in section 4.2, NPROCS and PARAMS are the number of processes and the path to the parameter file, respectively.

Should you wish to run in pure Python mode, you first have to remove the shared object files. To remove all files resulting from compilation, type

```
make clean
```

Now to run CONCEPT in pure Python mode, execute is as

```
mpiexec -n NPROCS python -B main.py "params='PARAMS'"
```

4.4 Cleaning

Sometimes it is useful to be able to quickly remove a particular set of files. Therefore the Makefile defines the following clean targets:

clean

Removes all files created by the build process.

clean_auxiliary

Removes files generated by running CONCEPT itself, like the jobscript and FFTW wisdom.

clean logs

Removes all files in the logs directory.

clean output

Removes all files and directories in the output directory.

clean tests

Removes all files in the subdirectories of the test directory, which were created by running tests.

clean utilities

Remove all files generated as a bi-product of using utilities.

distclean

Calls all of the targets above. If you yourself have not created any additional files, the CONCEPT environment is now in a distribution ready state.

5 Parameters

The parameters of a given run must be supplied in a parameter file, which is just a text file containing Python assignments. An example of such a parameter file is concept/params/example. In it, a short description of each parameter is written next to it. A complete description of each parameter is given below.

When assigning values to a parameter with some physical unit, the user is strongly urged to write this unit explicitly in the value. As an example consider the specification of boxsize, the linear size of the simulation box:

```
boxsize = 100*Mpc # Great!
boxsize = 100 # Will probably work, but bad!
```

Here, the first definition is much preferable to the latter, even though CONCEPT by default uses Mpc as the base unit for lengths, and so numerically the definitions are equivalent. For one, having implicit units floating around is not good practice. More importantly, it will lead to trouble if someone were to redefine the internal unit system used by CONCEPT, which can easily be done by changing a few lines in the Units class in commons.py. Should you wish to extend the set of units known by CONCEPT, this is also the place to go.

In addition to physical units, any valid Python construct are allowed in parameter definitions. All normal mathematical as well as NumPy functions and constants are also available. As always, paths may be absolute or relative to the concept directory. In addition, paths from the .paths file are accessible as e.g. paths['concept_dir'] for the concept directory. The directory of the parameter file itself is accessible as paths['params_dir'].

Here follows a full list of parameters, grouped into five sections.

Input/output

IC_file

Path to the snapshot file containing the initial conditions for the simulation. The snapshot may be in any format known to CONCEPT. The code will automatically figure out the snapshot format at load time.

snapshot_type

The format of the output snapshots. The implemented snapshot formats are described in detail in chapter 6. At the time of writing,

CONCEPT implements two snapshot formats, called 'standard' and 'GADGET 2', referring to the code's own HDF5 snapshot type and the secondary snapshot type defined by GADGET-2, respectively.

output_dirs

This is a dictionary with keys (left of colon) corresponding to output types and values (right of colon), giving the paths to the respective output directories. That is, its general form is like the following:

```
output_dirs = {
    'snapshot' : '/path/to/snapshots',
    'powerspec': '/path/to/powerspecs',
    'render' : '/path/to/renders',
    }
```

Output directories of snapshots, power spectra and renders are thus defined individually. If a specified directory does not exist, it will be created.

output_bases

This is a dictionary of the same form as output_dirs. Its values refer to the basenames (prefixes) of the output files.

output_times

This is a dictionary of the same form as output_dirs, though with the additional 'terminal render' key. The values correspond to those values of the scale factor for which an output should be produced. A value can be a single number or any Python sequence of numbers. Leave a value empty (set it to e.g. '') or remote its key completely in order not to produce output of this kind.

Numerical parameters

boxsize

The linear, comoving size of the cubic simulation box. The simulated, comoving volume is then boxsize³.

ewald_gridsize

Linear size of the grid of Ewald corrections. The total number of tabulated Ewald corrections is then ewald_gridsize³.

PM_gridsize

Linear size of the grid used by the PM method as well as the power spectrum computation. The simulation volume will then be discretized into PM_gridsize³ grid points.

PM_scale

The scale of the gravitational force splitting into a long-range component and a short-range component, used in the P^3M method. The scale should be given in units of the linear size of a PM cell. A value slightly above 1 should be optimal.

P3M_cutoff

Distance beyond which short-range forces are ignored in the P³M method. This distance should be given in units of P3M_scale. A value of at least 4.8 guarantees that the force components left unaccounted for constitutes less than 1% of the total force.

softeningfactors

Mapping from particle species to values of their respective gravitational softening. The values given correspond to the radius of a softening Plummer sphere, in units of the mean inter-particle distance $\mathtt{boxsize}/N^{1/3}$. For dark matter, a value of a couple of percent is optimal.

Δt_factor

The global time step size, given in units of the instantaneous age of the universe.

R_tophat

Radius of the top-hat used to compute σ , the rms density variation, from the power spectrum.

Cosmological parameters

НО

The Hubble parameter at the present time (a = 1). If this does not match the corresponding value in the IC_file, a warning will be thrown.

 $\Omega m \,$

The matter density parameter at the present time (a = 1). If this does not match the corresponding value in the IC_file, a warning will be thrown.

ΩΛ

The dark energy density parameter at the present time (a = 1). If this does not match the corresponding value in the IC_file, a warning will be thrown.

a_begin

The value of the scale factor at the beginning of the simulation. If this does not match the value of the scale factor in the IC_file, a warning will be thrown.

Graphics

powerspec_plot

Boolean value determining whether or not when outputting a power spectrum (a text file of data), a plot of the data should also be made.

color

The color of the particles in the renders. This can be a number in the range 0-1 (grayscale), any sequence of 3 numbers in the range 0-1 (RGB values) or a string containing any of the color names defined by Matplotlib. See http://matplotlib.org/mpl_examples/color/named_colors.hires.png for the entire repertoire.

bgcolor

The background color on the renders. The format is similar to that of color.

resolution

The height and width of the saved renders, in pixels. Note that the images will always be square.

liverender

Path to the file where the latest frame should be saved, resulting in a "live" visualization of the simulation. Set an empty path to disable this feature.

remote_liverender

If live render is used, this parameter allows for uploading of the live render to a remote host. Secure copy (scp) is used. The parameter takes the usual scp form; 'user@host:/path/to/liveframe'. When using this parameter, CONCEPT will prompt you once for your password to the host. Use an empty string to disable this feature.

terminal_colormap

Sets the colormap used in terminal renders. This can be any colormap defined by Matplotlib. See http://matplotlib.org/examples/color/colormaps_reference.html for a complete list.

terminal_resolution

The width of the terminal renders, in characters. The height is chosen to be half as big as the width, resulting in roughly rectangular (pixelwise) terminal renders on modern terminals where each character is about twice as high as they are wide.

Simulation options

kick_algorithms

Mapping from particle species to the algorithm which should be used when kicking particles of that species. Implemented kick algorithms are 'PP', 'PM' and 'P3M'.

use_Ewald

This should normally be set to **True**, in which case periodic corrections to the gravitational force will be computed via Ewald summation, when using the PP method. Otherwise, no Ewald corrections will be computed.

fftw_rigor

The "rigor level" used when acquiring FFTW wisdom. It can be any of 'estimate', 'measure', 'patient' or 'exhaustive'. For the official FFTW documentation about each rigor level, see http://www.fftw.org/doc/Planner-Flags.html. If FFTW wisdom of the right kind but for a higher level rigor than requested exists, this higher level rigor is used instead.

Each parameter has an associated default value, defined in the commons.py file. If your run does not make use of every parameter, it may be desirable to remove those parameter definitions from the parameter file, leaving a more comprehensible file, only stating the definitions you actually care about. An example would be to remove the entire graphics category, if your run does not output any renders or terminal renders. It is however not advised to use these default values in situations where your run depend upon which value is given to some parameter.

6 Snapshot Formats

At the time of writing, two snapshot formats are supported by CONCEPT. One of them is simply referred to as the "standard" CONCEPT snapshot format, while the other is the GADGET-2 format of the second kind*. When using a GADGET-2 snapshot with CONCEPT, certain restrictions apply:

- In the jargon of GADGET-2, dark matter particles are referred to as "halo" particles or particles of type 1. As dark matter is the only implemented species in CONCEPT, for a GADGET-2 snapshot to be usable by CONCEPT, it must consist exclusively of particles of type 1.
- Gadget-2 supports distributing a single snapshot across multiple files. This is not implemented in Concept, and so for a Gadget-2 snapshot to be readable by Concept, the snapshot must be completely contained within a single file.

The reason for making CONCEPT at least somewhat compatible with foreign snapshot types is to connect it with existing software, where the GADGET-2 snapshot format are somewhat standard. The standard CONCEPT snapshot format is however preferable, as it uses the well-established HDF5 format[†].

6.1 The Standard CONCEPT Snapshot Format

CONCEPT's own snapshot format, the "standard" format, is really just an HDF5 file with some particular layout. This layout is shown in figure 6.1. The root group contains all of the cosmological parameters also present in parameter files[‡]. This allows CONCEPT to do sanity checks when reading in an IC file.

Beside attributes containing information about the cosmology, the root group also contains the three units attributes. Their values are strings telling which physical unit is used as the base unit, for length, time and mass. When a

^{*}For details of the GADGET-2 format of the second kind, see http://wwwmpa.mpa-garching.mpg.de/gadget/users-guide.pdf chapter 6.

 $^{^{\}dagger}$ As gadget-2 *is* able to read and write snapshots in the HDF5 format, this is not a critique of gadget-2 itself.

[‡]Here, the scale factor is simply called **a** rather than **a_begin**, as the snapshot is not necessarily intended as an IC file.




Figure 6.1 – Layout of the standard HDF5 snapshot format used by CONCEPT. The colors indicate groups (blue), attributes (black) and datasets (gray).

standard snapshot is read in by CONCEPT, all physical quantities gets multiplied by the appropriate unit. With the unit information contained in the snapshot, the internal base unit of the current run may differ from that which produced the snapshot. This makes the snapshots more general and self-documenting.

Even with only a single implemented particle species, one may wish to use several groups of particles, which differ in e.g. mass. At the time of writing, the CONCEPT code is not capable of reading in snapshots containing different particles, but the structure of the snapshots allows it. Each group of particles gets a distinctive label called its type. In figure 6.1, the only group within the root group is particles, which in turn stores all particle types as subgroups. In figure 6.1, halo is shown as an example of a particle type. This group contains a mass attribute, giving the mass of each particle of the halo type in units of unit mass, together with a species attribute, which currently must equal 'dark matter'. The particle positions and momenta are stored as 6 datasets; posx, posy, posz for the position components and momx, momy, momz for the momenta components. Note that since these datasets know their own size, the number of particles is not saved as an attribute. The positions are given in units of units length, while the momenta are given in units of

(unit length) \times (unit mass)/(unit time). Naturally, these are the *comoving* positions and momenta.

7 Utilities

The content of concept/utilities is missing from figure 4.1. This is instead shown in figure 7.1. Each Bash script is its own utility, capable of performing a small task. These should be called via the concept script as described in section 4.2, i.e. via the -u option. Here follows a description of each utility.

powerspec

This utility uses CONCEPT to compute power spectra of particles in snapshots. Invoke it as

```
./concept -u powerspec PATH
```

where PATH is a path to either a snapshot or a directory containing (maybe among other files) at least one snapshot. All the usual options of the concept script still apply. If no parameter file is specified, powerspec.params is used.

render

This utility uses CONCEPT to produce renders of particles in snapshots. Invoke it as

./concept -u render PATH




Figure 7.1 – Directory tree focusing on the utilities directory. The color codes are identical to those of figure 4.1.

where PATH is a path to either a snapshot or a directory containing (maybe among other files) at least one snapshot. All the usual options of the concept script still apply. If no parameter file is specified, render.params is used.

snapshot_info

This utility will print out the information contained within snapshots. Invoke it as

./concept -u snapshot_info PATH

where PATH is a path to either a snapshot or a directory containing (maybe among other files) at least one snapshot. This utility will always be run locally in pure Python mode, using a single CPU. For standard snapshots, it will simply print out the values of the attributes described in section 6.1, along with the number of particles and their type. The same information is stored in GADGET-2 snapshots, but in very different units. When using the snapshot_info utility on a GADGET-2 snapshot, its attribute values will be converted to the "standard" form before being printed out. Comparing a standard snapshot to a GADGET-2 is thus made easy, as all the unit conversions are being taken care of. A GADGET-2 snapshot also contains a lot of other, GADGET-2 specific parameters. These will also get printed out, in their raw form.

update

This utility will update all of the CONCEPT source files to their latest versions, including the update script itself. Invoke it either as

```
./concept -u update
```

or directly as

utilities/update

Needless to say, this utility will always be run locally using a single CPU. Before actually doing the update, a backup of the original CONCEPT code will be placed in ../concept_backup.

watch

This script will continuously print out the output of a CONCEPT run, after it has been submitted as a PBS job. It does this by reading the produced logfile. If you have multiple jobs submitted, the one submitted most recently will be chosen. Alternatively, the PBS job ID can be passed as an argument when calling the script. That is, call this script either as

./concept -u watch [ID]

or directly as

utilities/watch [ID]

Needless to say, this utility will always be run locally using a single CPU. After CONCEPT auto-submits a PBS job, this script is automatically called.

8 Tests

Code validation is achieved through unit tests. Each subdirectory within the tests constitutes such a test, the name of which is equal to the directory name. To run e.g. the basic test, invoke concept like this:

./concept -t basic

Each test is controlled by a Bash script named run_test, which (with the help of other files in the same directory) runs the CONCEPT code with a certain set of parameters, analyses the output and report any problems. Often, suitable initial conditions are generated for the test, which are then evolved by both CONCEPT and GADGET-2, after which the produced snapshots are compared. Besides subdirectories containing tests, the tests directory contains a Bash script called environment which handles the setup and teardown of the test environment for all tests.

If a test produces files when run, it should contain a Bash script named clean, which when executed deletes these files. The Makefile will then execute this script every time you call the clean_tests target.

All tests are run locally, meaning without the use of PBS, even when working remotely. The list of available tests is as follows.

basic

Performs a basic test of the CONCEPT environment, making sure that all of the software is correctly built and linked. It simply runs the code without any parameter file in both compiled and pure Python mode, using 1, 2 and 4 processes.

concept_vs_gadget_P3M

Performs a comparison test between CONCEPT's P³M and GADGET-2's TreePM implementation. Only a single process is used.

concept_vs_gadget_PM

Performs a comparison test between CONCEPT's and GADGET-2's PM implementations. Since GADGET-2 do not expose its pure PM method to the user, edited versions of the GADGET-2 source files pm_periodic.c and timestep.c are used. Only a single process is used.

concept_vs_gadget_PP

Performs a comparison test between CONCEPT's PP and GADGET-2's tree implementation. Only a single process is used.

drift

Performs a test of CONCEPT's drift operation, by comparing it to that of GADGET-2. ICs containing a particle configuration with no net forces and equal initial velocities are constructed. The particle trajectories are now independent of gravity, making it possible to test the comoving equations of motions. Since gravity is not simply turned off, but rather delicately balanced to produce no net effect, its periodicity is also tested during this test. To test periodicity further, the particles will go trough the side of the box during the simulation. The PP method is used for gravity, and only a single process is used.

gadget

As GADGET-2 is used by many of the other tests, it is important that GADGET-2 itself works properly. This test is simply a shortened version of GADGET-2's own lcdm_gas test.

kick_PP_with_Ewald

Performs a test of CONCEPT's PP implementation, by comparing it to GADGET-2's tree implementation. ICs containing a particle configuration with net forces only in the x-direction are constructed. The particles start out with zero velocities, making the study of the kick operation in isolation easy. Any errors in the implementation of the Ewald method should be detected.

kick_PP_without_Ewald

Performs a test of CONCEPT's PP implementation with Ewald summation disabled, by comparing it to GADGET-2's tree implementation. GADGET-2 do not provide a switch to turn off the Ewald summation. To achieve this, the GADGET-2 source file forcetree.c is edited accordingly. ICs containing a particle configuration with net forces only in the x-direction are constructed. The particles start out with zero velocities, making the study of the kick operation in isolation easy. Any simple errors in the PP algorithm, having to do with units and the like, should be detected.

nprocs_P3M

Performs a test of the P³M implementation, comparing runs using different numbers of processes. Specifically, 1, 2 4 and 8 processes will be used.

nprocs_PM

Performs a test of the PM implementation, comparing runs using different numbers of processes. Specifically, 1, 2, 4 and 8 processes will be used.

nprocs_PP

Performs a test of the PP implementation, comparing runs using different numbers of processes. Specifically, 1, 2, 4 and 8 processes will be used.

powerspec

Performs a test of the power spectrum computation by comparing σ_8 from this computation with an estimate obtained by taking the rms of the number of particles within cubes the size of spheres with radius 8 Mpc.

pure_python_P3M

Performs a test of the P³M implementation, comparing a compiled run on a single process to pure Python runs with different numbers of processes. Specifically, 1, 2, and 4 processes will be used. Deviations between the compiled run and the pure Python runs signals an error in the translation from Python to C.

pure_python_PM

Performs a test of the PM implementation, comparing a compiled run on a single process to pure Python runs with different numbers of processes. Specifically, 1, 2, and 4 processes will be used. Deviations between the compiled run and the pure Python runs signals an error in the translation from Python to C.

pure_python_PP

Performs a test of the PP implementation, comparing a compiled run on a single process to pure Python runs with different numbers of processes. Specifically, 1, 2, and 4 processes will be used. Deviations between the compiled run and the pure Python runs signals an error in the translation from Python to C.

render

Generates a random snapshot and renders it first using 1 process and giving the render utility the exact path to the snapshot (with and without specifying a render parameter file). Two copies of this snapshot is then placed in a separate directory. Using 2 processes, the render utility is then given the path to this directory, which should produce a render for each snapshot. Different render parameters are used for the two calls to the render utility. The test will fail if the two renders of the identical snapshots are not themselves identical. The image resolution is also checked. Finally, it is checked whether the text stating the scale factor is clearly visible on both dark and bright backgrounds.

All of the available tests can be run one after another, by

./concept -t all

This is done as the last step of the CONCEPT installation when using the installer, unless the --fast option is given.