
### **Module 10: Virtual Memory**

- Background
- Demand Paging
- Performance of Demand Paging
- Page Replacement
- Page-Replacement Algorithms
- Allocation of Frames
- Thrashing
- Other Considerations
- Demand Segmentation

### **Background**

- Virtual memory separation of user logical memory from physical memory.
  - Only part of the program needs to be in memory for execution.
  - Logical address space can therefore be much larger than physical address space.
  - Need to allow pages to be swapped in and out.
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation





- Bring a page into memory only when it is needed.
  - Less I/O needed
  - Less memory needed
  - Faster response
  - More users
- Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - not-in-memory ⇒ bring to memory

#### **Valid-Invalid Bit**

- With each page table entry a valid–invalid bit is associated (1 ⇒ in-memory, 0 ⇒ not-in-memory)
- Initially valid—invalid but is set to 0 on all entries.
- Example of a page table snapshot.


Frame #	valid-invalid bit	
	1	
	1	
	1	
	1	
	0	
:		
	0	
	0	

page table

 During address translation, if valid–invalid bit in page table entry is 0 ⇒ page fault.

### **Page Fault**

- If there is ever a reference to a page, first reference will trap to OS ⇒ page fault
- OS looks at another table to decide:
  - Invalid reference ⇒ abort.
  - Just not in memory.
- Get empty frame.
- Swap page into frame.
- Reset tables, validation bit = 1.
- Restart instruction: Least Recently Used
  - block move



auto increment/decrement location

### 10.04 page is on backing store operating system reference trap load M (6) restart page table instruction free frame bring in reset page table missing page physical memory

## What happens if there is no free frame?

- Page replacement find some page in memory, but not really in use, swap it out.
  - algorithm
  - performance want an algorithm which will result in minimum number of page faults.
- Same page may be brought into memory several times.

# **Performance of Demand Paging**

- Page Fault Rate  $0 \le p \le 1.0$ 
  - if p = 0 no page faults
  - if p = 1, every reference is a fault
- Effective Access Time (EAT)

 $EAT = (1 - p) \times memory access$ 

- + p (page fault overhead
- + [swap page out]
- + swap page in
- + restart overhead)

## **Demand Paging Example**

- Memory access time = 1 microsecond
- 50% of the time the page that is being replaced has been modified and therefore needs to be swapped out.
- Swap Page Time = 10 msec = 10,000 msec

EAT = 
$$(1 - p) \times 1 + p (15000)$$
  
1 + 15000P (in msec)

### Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement.
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk.
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory.

## **Page-Replacement Algorithms**

- Want lowest page-fault rate.
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string.
- In all our examples, the reference string is

1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5.

# First-In-First-Out (FIFO) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)

4 frames

- FIFO Replacement Belady's Anomaly
  - more frames ⇒ less page faults

### **Optimal Algorithm**


- Replace page that will not be used for longest period of time.
- 4 frames example

1 4
 2 6 page faults
 3 4
 5

- How do you know this?
- Used for measuring how well your algorithm performs.

# Least Recently Used (LRU) Algorithm

• Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5



- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter.
  - When a page needs to be changed, look at the counters to determine which are to change.

# LRU Algorithm (Cont.)

- Stack implementation keep a stack of page numbers in a double link form:
  - Page referenced:
    - \* move it to the top
    - \* requires 6 pointers to be changed
  - No search for replacement

## **LRU Approximation Algorithms**

- Reference bit
  - With each page associate a bit, initially -= 0
  - When page is referenced bit set to 1.
  - Replace the one which is 0 (if one exists). We do not know the order, however.
- Second chance
  - Need reference bit.
  - Clock replacement.
  - If page to be replaced (in clock order) has reference bit = 1.
     then:
    - \* set reference bit 0.
    - \* leave page in memory.
    - \* replace next page (in clock order), subject to same rules.

### **Counting Algorithms**

- Keep a counter of the number of references that have been made to each page.
- LFU Algorithm: replaces page with smallest count.
- MFU Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used.

#### **Allocation of Frames**

- Each process needs minimum number of pages.
- Example: IBM 370 6 pages to handle SS MOVE instruction:
  - instruction is 6 bytes, might span 2 pages.
  - 2 pages to handle from.
  - 2 pages to handle to.
- Two major allocation schemes.
  - fixed allocation
  - priority allocation

#### **Fixed Allocation**

- Equal allocation e.g., if 100 frames and 5 processes, give each 20 pages.
- Proportional allocation Allocate according to the size of process.
  - $-s_i = \text{size of process } p_i$
  - $-S = \sum S_i$
  - -m = total number of frames
  - $a_i$  = allocation for  $p_i = \frac{s_i}{S} \times m$  m = 64  $s_i = 10$   $s_2 = 127$   $a_1 = \frac{10}{137} \times 64 \approx 5$  $a_2 = \frac{127}{137} \times 64 \approx 59$

### **Priority Allocation**

- Use a proportional allocation scheme using priorities rather than size.
- If process P<sub>i</sub> generates a page fault,
  - select for replacement one of its frames.
  - select for replacement a frame from a process with lower priority number.


#### Global vs. Local Allocation

- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another.
- Local replacement each process selects from only its own set of allocated frames.

### **Thrashing**

- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
  - low CPU utilization.
  - operating system thinks that it needs to increase the degree of multiprogramming.
  - another process added to the system.

### **Thrashing Diagram**



- Why does paging work? Locality model
  - Process migrates from one locality to another.
  - Localities may overlap.
- Why does thrashing occur?
   Σ size of locality > total memory size


### **Working-Set Model**

- $\Delta \equiv$  working-set window  $\equiv$  a fixed number of page references Example: 10,000 instruction
- $WSS_i$  (working set of Process  $P_i$ ) = total number of pages referenced in the most recent  $\Delta$  (varies in time)
  - if  $\Delta$  too small will not encompass entire locality.
  - if  $\Delta$  too large will encompass several localities.
  - if  $\Delta$  = ∞ ⇒ will encompass entire program.
- $D = \Sigma WSS_i \equiv \text{total demand frames}$
- if  $D > m \Rightarrow$  Thrashing
- Policy if D > m, then suspend one of the processes.

# **Keeping Track of the Working Set**

- Approximate with interval timer + a reference bit
- Example:  $\Delta = 10,000$ 
  - Timer interrupts after every 5000 time units.
  - Keep in memory 2 bits for each page.
  - Whenever a timer interrupts copy and sets the values of all reference bits to 0.
  - If one of the bits in memory = 1  $\Rightarrow$  page in working set.
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units.

### **Page-Fault Frequency Scheme**



- Establish "acceptable" page-fault rate.
  - If actual rate too low, process loses frame.
  - If actual rate too high, process gains frame.

### **Other Considerations**

- Preparing
- Page size selection
  - fragmentation
  - table size
  - I/O overhead
  - locality

### Other Consideration (Cont.)

- Program structure
  - int A[][] = new integer[128][128];
  - Each row is stored in one page
  - One frame
  - Program 1

128 x 128 page faults


- Program 2


128 page faults


I/O interlock and addressing


### **Demand Segmentation**


- Used when insufficient hardware to implement demand paging.
- OS/2 allocates memory in segments, which it keeps track of through segment descriptors
- Segment descriptor contains a valid bit to indicate whether the segment is currently in memory.
  - If segment is in main memory, access continues,
  - If not in memory, segment fault.

























page frames









reference string

4 7 0 7 1 0 1 2 1 2 7 1 2

 2
 7

 1
 2

 0
 1

 7
 0

 4
 4

stack stack before after a b

