## Chapter 3. Creating Natural Materials in Cycles

In this chapter, we will cover the following recipes:

- Creating a rock material using image maps
- Creating a rock material using procedural textures
- Creating a sand material using procedural textures
- Creating a simple ground material using procedural textures
- Creating a snow material using procedural textures
- Creating an ice material using procedural textures

## Introduction

Replicating nature can be difficult. Natural materials are usually the most difficult to recreate in a satisfying way using computers, mainly because the chaos of nature is not the best fit for the orderly logic of an electronic machine.

Too often, we even see cubes that look obviously computer-generated because of the neatness and regularity of their shapes or surfaces. Actually, in reproducing true to life a natural object (or material as well), we have to start from the absolute regularity of the computer simulation, and then blemish it step by step in a controlled way to reach a more natural look.

## Creating a rock material using image maps

In this recipe, we will create a realistic rock material that looks like the samples shown in the following screenshot, using an image map. We'll see a material made with procedurals in the this recipe.



The image-based rock material as it appears in the final rendering

Image maps are particularly useful for several reasons: they already have the necessary color information of a natural surface ready to be used; they can be easily edited in any image editor to obtain different kinds of information, for example, high levels for the bump maps; and they are processed faster than procedurals by the software (procedural textures must be calculated every time). Moreover, they can nowadays be found easily on the Web for free, in several sizes and resolutions.

For our recipe, we'll use the rockcolor\_tileable\_low.png image map, which you can find in the textures folder provided with this cookbook. This is just a low-resolution texture image provided for the sake of this exercise. Obviously, you can use any other different image with a bigger resolution. Here is a screenshot of the tileable rock image texture for your reference:



The tileable rock image texture provided with this cookbook

In any case, for any image you are going to use, just remember to make it tileable in your preferred image editor. In GIMP, this task can be automatically done by a plugin that can be found by navigating to **Filter** | **Map** | **Make Tileable**.

## Getting ready

Start Blender and load the 99310S\_02\_interface.blend file, which saw in the previous chapter. Remember that all the blend files and the textures needed for the exercises of this module can be downloaded from the support page on the Packt Publishing website.

Now, we'll create a new file named 99310S\_start.blend, and we'll be using it as the starting point for the most of our recipes. To do so, perform the following steps:


- 1. Select the Spheroid and (just for the purpose of this exercise) delete it by pressing X.
- 2. Ensure that the 3D cursor is at the center of the scene (Shift + C), and with the mouse pointer in the 3D window, press Shift + A to pop up the **Add** menu. Then add a new Cube primitive (press Shift + A and navigate to **Mesh** | **Cube**).
- 3. Press *Tab* to go out of **Edit Mode** if needed (this depends on whether you are using Blender with the factory settings or not), and move the cube 2 units up on the z axis.
- 4. Go to the **Outliner** and select the **Lamp** item, in the **Object data** window under the **Properties** panel, switch the **Type of Lamp** to **Sun**. Then set the **Strength** to 2.000 and the color values to 1.000 for **R**, 0.872 for **G**, and 0.737 for **B**.

5. Reselect the Cube, go to the **Material** window under the **Properties** panel, and save the file as 99310S start.blend.

### How to do it...


Now carry out the following steps to create the rock material:

- 1. Click on the **New** button in the **Material** window under the **Properties** panel, or in the toolbar of the **Node Editor** window.
- 2. Rename Material.001 as Rock\_01 (the numbering is because I assume that you are going to experiment with several values, especially colors, producing more and different kind of rock materials) and save the file as 99310S 03 Rock imagemap.blend.
- 3. Put the mouse on the **Node Editor** window and add an **Image Texture** node (press *Shift* + *A* and navigate to **Texture** | **Image Texture**). Then add a **Mapping** node (press *Shift* + *A* and navigate to **Vector** | **Mapping**), and a **Texture Coordinate** node (press *Shift* + *A* and navigate to **Input** | **Texture Coordinate**).
- 4. Connect the **Generated** output socket of the **Texture Coordinate** node to the **Vector** input socket of the **Mapping** node, and its **Vector** output to the **Vector** input of the **Image Texture** node. Also connect the **Color** output of the **Image Texture** node to the **Color** input of the **Diffuse BSDF** shader node.
- 5. Set the **Viewport Shading** mode of the **Camera** view to **Rendered** by pressing Shift + Z with the mouse cursor in the 3D window. The rendered Cube turns pink because there is no image texture loaded yet, as shown in the following screenshot:




The overall view of Blender's customized Default screen with the rendered preview of the pink Cube

- 6. Click on the **Open** button in the **Image Texture** node, browse to the textures folder, and select the rockcolor tileable low.png image.
- 7. As we selected **Generated** as the mapping mode, the image is mapped flat on the Cube from the z axis and appears stretched on the sides. Disconnect the **Generated** output of the **Texture Coordinate** node and connect the **Object** node instead. Then click on the **Flat** button on the **Image Texture** node to select the **Box** item. The texture looks now correctly mapped on each face of the Cube, as shown in this screenshot:




The rock image texture loaded in the Image Texture node

- 8. Go to the **Object modifiers** window and assign a **Subdivision Surface** modifier to the Cube. Set the **Subdivisions** levels to 4 both for **View** and **Render**. Then check the **Optimal Display** item.
- 9. Press *Shift* + *Z* to go out of the viewport's **Rendered** mode. Then press *Tab* to go to **Edit Mode** and scale all the vertices to double (press *Tab*, then press *S*, enter the digit 2, and finally, press *Enter*). Now, go out of **Edit Mode**.
- 10. Press *T* to make the **Tool Shelf** panel appear in the **Camera** view, and click on the **Smooth** button under the **Tools** tab. Press *T* again.
- 11. Go to the **Mapping** node in the **Node Editor** window and set the **Scale** values for **X**, **Y**, and **Z** to 0.250.
- 12. Although the image map we used is tileable, there are visible seams at the corners of the subdivided Cube. In the **Image Texture** node, set **Blend factor** to 0.200 to soften the seams (this factor is used to blend the edges of the faces of the Cube that, remember, is still a six-faced solid at its lower level, though looks like a Spheroid as of now). The output of blurring effect of the Blend factor is shown in the following screenshot:




The edges seams visible on the surface of the subdivided Cube, and the blurring effect of the Blend factor

13. Now add a **ColorRamp** node (press *Shift* + *A* and navigate to **Converter** | **ColorRamp**) between the **Image Texture** node and the **Diffuse BSDF** shader. Set the interpolation to **B-Spline**, move the marker of the black color to position (**Pos:**) 0.495 and the white marker to position 0.235, as shown in this screenshot:




The ColorRamp node pasted between the Image Texture and the Diffuse BSDF nodes

14. Add a **Bump** node (press *Shift* + A and navigate to **Vector** | **Bump**). Connect the **Color** output of the **ColorRamp** to the **Height** input of the **Bump** node, and the **Normal** output of the latter to the **Normal** input of the **Diffuse BSDF** shader. Detach the **Color** link from the **Color** input of the **Diffuse BSDF** node and leave the **Bump** node's **Strength** value to 1.000, as shown in the following screenshot:




The Bump node pasted between the ColorRamp and Diffuse BSDF nodes

15. Add a **Mix Shader** node and a **Glossy BSDF** shader, and connect them to be mixed with the **Diffuse BSDF** shader. Set the **Glossy BSDF** node's **Roughness** value to 0.150 and the **Mix Shader** node's **Fac** value to 0.300. Connect the **Normal** output of the **Bump** node to the **Normal** input socket of the **Glossy BSDF** shader, as shown in this screenshot:




Adding the Mix Shader and the Glossy BSDF nodes

- 16. Add an RGB node (press *Shift* + A and navigate to **Input** | **RGB**) and a **MixRGB** node (press *Shift* + A and navigate to **Color** | **MixRGB**). Connect both the **Color** outputs of the **RGB** and **Image Texture** nodes to the **Color1** and **Color2** input sockets of the **MixRGB** node. Connect the **Color** output of the **MixRGB** node to the **Color** input sockets of the **Diffuse BSDF** and **Glossy BSDF** shaders.
- 17. Set the **Fac** value of the **MixRGB** node to 0.800. Click on the color slider of the **RGB** node and set the values to 0.407 for **R**, 0.323 for **G**, and 0.293 for **B**, as shown in the following screenshot:




Setting the color for the material

- 18. Add a new MixRGB node (press Shift + A and navigate to  $Color \mid MixRGB$ ). Drag it to be pasted between the first MixRGB node and the Diffuse BSDF shader, and set Blend Type to Add.
- 19. Connect the **Color** output of the second **MixRGB** node (which we can call the **Add-MixRGB** node) to the **Color** input socket of the **Glossy BSDF** shader node, and set its **Fac** value to 1.000.
- 20. Connect the Color output of the Image Texture node to the Color1 input socket of the Add-MixRGB node so that the preceding connection coming from the first MixRGB node (which we can call Mix-MixRGB) switches automatically to the Color2 input socket of the Add-MixRGB node, as shown in this screenshot:



Adding more variations to the rock color

21. If you wish, model a very quick rock mesh by sculpting or deforming the subdivided Cube in proportional **Edit Mode**, and assign to it the Rock\_01 material as shown in the following screenshot:



#### How it works...

We mapped a colored image of a rock with the **Box** option available in the **Image Texture** node (developed by the Project Mango team for open movie production of *Tears of Steel* to quickly map objects without the need to unwrap them), and set the **Blend** factor to 0.200 to have smooth transitions at the corners. Although we had a tileable image texture, this has been necessary because we set the **Scale** values for the three axes in the **Mapping** node to 0.250.

First, by connecting the **MixRGB** node's **Color** output directly to the **Color** input of the **Diffuse BSDF** shader node, we had a quick visual feedback of the image mapping, and thanks to the **ColorRamp** node, we achieved the following goals:

- We converted the colored image to a gray-scale image to be used for the bump.
- By moving the color markers, we remapped the values of the **ColorRamp** node's position values to reverse and increase the contrast (we could have obtained the same result by processing the color map in GIMP, for example, by desaturating it and playing with the curve tool). In any case, it's possible to visualize the **ColorRamp** node itself on the object by temporarily connecting it to the **Color** input socket of the **Diffuse BSDF** shader or an **Emission** shader node connected to the **Material Output** node.

This contrasted result has been applied as a bump map to both the **Diffuse BSDF** and **Glossy BSDF** shaders.

Then we mixed a brownish color (the **RGB** node) with the **Color** output of the image of the rock, and the result was added to the **Image Texture** node's output.


## There's more...

We can improve the rocky effect by adding displacement to the geometry. Unlike bump or normal effects on the mesh surface, which are just optical illusions giving an impression of perturbing the mesh surface, displacement is an actual deformation of the mesh based on the gray-scale values of a texture.

At least in this case, there is no need for precise correspondence between the already textured surface and the displacement because it would be barely noticeable. Therefore, we can use object modifiers to obtain a fast but effective result, by performing the following steps:

- 1. Starting from the Rock\_imagemap.blend file we just created, select the Cube and go to the **Object modifiers** window under the **Properties** panel. In the **Subdivision Surface** modifier already assigned, lower the **Subdivisions** levels for both **View** and **Render** to 3.
- 2. Add a new **Subdivision Surface** modifier and set the levels to 4.
- 3. Now add a **Displace** modifier. Click on the **Show textures in texture tab** button, the last button on the right of the **Texture** slot. This switches to the **Texture** window, where we can click on the **New** button and then change the default **Clouds** texture to a **Voronoi** texture node. Set the **Size** value to 2.00 and leave the rest of the values unchanged. Go back to the **Object modifiers** window and set the modifier's **Strength** value to 0.800.

- 4. Add a new **Displace** modifier. Switch to the **Texture** window and assign a new **Voronoi Texture** node. Change the **Size** value to 1.20. Back in the modifier, set the **Strength** value to 0.300.
- 5. Add one more **Displace** modifier. This time, we are going to use the default **Clouds** texture as it is. Just go to the **Object modifiers** window and set the **Strength** value to 0.150, as shown in this screenshot:




A different rock model, thanks to displacement

Of course, these are just basic values. You can change them and also play with different kinds of procedural textures to obtain several rock shapes.

# Creating a rock material using procedural textures

In this recipe, we will try to reach a result similar to the rock material we made through image maps in the previous recipe, but using only procedural textures. The output will look like what is shown in the following screenshot:




The procedural rock material as it appears in the final rendering

## **Getting ready**

Start Blender and load the 99310S start.blend file.

- 1. Select the Cube, go to the **Object modifiers** window, and assign a **Subdivision Surface** modifier. Set the **Subdivisions** levels for **View** and **Render** to 4. Go back to the **Material** window.
- 2. Press *T* and in the **Tool Shelf**, click on the **Smooth** button under the **Shading** subpanel. Press *T* again to get rid of the **Tool Shelf**.
- 3. Press *Tab* to go to **Edit Mode**. If necessary, select all the vertices by pressing the *A* key and scale everything to double the current size (press *S*, enter the digit 2, and press *Enter*). Go out of **Edit Mode**.
- 4. Save the file as 99310S\_start\_smoothed.blend. The customized Default screen will now look as shown in the following screenshot:




The customized Default screen with the subdivided Cube

### How to do it...


Now we are going to create the rock material by performing the following steps:

- 1. Select the Spheroid (the smoothed Cube) and click on **New** in the **Material** window under the **Properties** panel or in the **Node Editor** toolbar. Rename the material Rock proc 01.
- 2. In the **Node Editor** window, add a **Noise Texture** node (press *Shift* + *A* and navigate to **Texture** | **Noise Texture**). Then press *Shift* + *D* to duplicate it three times. Adjust the four **Noise Texture** nodes in a column, and in the **Properties** panel to the right (press *N* key if it is not already present), label them Noise Texture01, Noise Texture02, Noise Texture03, and Noise Texture04.
- 3. Add a **Texture Coordinate** node (press *Shift* + *A* and navigate to **Input** | **Texture Coordinate**) and a **Mapping** node (press *Shift* + *A* and navigate to **Vector** | **Mapping**). Connect the **Object** output of the **Texture Coordinate** node to the blue **Vector** input of the **Mapping** node. Then connect the **Mapping** node's **Vector** output to the **Vector** input sockets of the four texture nodes. Set the **Mapping** node's **Location** values to 0.100 for **X** and -0.100 for **Y** and **Z**, as shown in the following screenshot:



The first steps to build the bump effect for the rock material


- 4. Add a **MixRGB** node (press *Shift* + A and navigate to **Color** | **MixRGB**). Connect the first two **Noise Texture** nodes' **Color** output to the **Color1** and **Color2** input of the **MixRGB** node. Set **Blend Type** to **Overlay** and the **Fac** value to 1.000.
- 5. Connect the **Overlay-MixRGB** node's output to the **Color** input socket of the **Diffuse BSDF** shader node.
- 6. Put the mouse cursor in the Camera view and press Shift + Z to set it to Rendered mode.
- 7. Go to the **Noise Texture01** node and set **Scale** to 4.000 and the **Distortion** value to 1.400. Then go to the **Noise Texture02** node and set **Scale** to 6.000, **Detail** to 1.000, and the **Distortion** value to 0.700.
- 8. Press *Shift* + *D* to duplicate the **MixRGB** node, and paste it between the **Overlay-MixRGB** and the **Diffuse BSDF** nodes. Connect the **Color** output of the **Noise Texture03** node to the **Color2** input socket and set the **Blend Type** to **Darken**. Go to the **Noise Texture03** node, and set **Scale** to 15.000 and **Detail** to 3.000.
- 9. Add a ColorRamp node (press *Shift* + *A* and navigate to Converter | ColorRamp) and paste it between the Darken-MixRGB and the Diffuse BSDF nodes. Label it ColorRamp01 and set Interpolation to Ease, the black cursor's position to 0.364, and the white cursor's position to 0.632.
- 10. Press Shift + D to duplicate the **ColorRamp** node, and move it close to the **Noise Texture04** node. Label the duplicated node ColorRamp02 and set the white cursor's position to 0.340 and the black cursor's position to 0.400.
- 11. Set the **Noise Texture04** node's **Scale** value to 45.000, **Detail** value to 0.100, and **Distortion** to 1.000, as shown in the following screenshot:



Starting to mix the different procedurals together


- 12. Connect the **Color** output of the **Noise Texture04** node to the **Fac** input socket of the **ColorRamp02** node. Then add a **MixRGB** node (press *Shift* + *A* and navigate to **Color** | **MixRGB**) and label it Mix01.
- 13. Paste the Mix01 node after the ColorRamp01 node. Then connect the Color output of the ColorRamp02 node to the Color2 input socket of the Mix01 node. Also connect the Fac output of the Noise Texture01 node to the Fac input socket of the Mix01 node.
- 14. Add a new **MixRGB** node (press Shift + A and navigate to **Color** | **MixRGB**) and label it Mix02. Paste it between the **ColorRamp02** and the **Mix01** nodes.
- 15. Add a **Bump** node (press *Shift* + *A* and navigate to **Vector** | **Bump**) and connect the **Color** output of the **Mix01** node to the **Height** input socket of the **Bump** node. Connect the **Normal** output of the **Bump** node to the **Normal** input socket of the **Diffuse BSDF** shader node. Click on the **Invert** item checkbox.

The steps that are detailed after this screenshot will result in the bump effect:



The BUMP frame containing the nodes to build the bump effect

- 16. Add a Glossy BSDF shader node (press *Shift* + A and navigate to **Shader** | Glossy BSDF) and a Mix Shader node (press *Shift* + A and navigate to **Shader** | Mix Shader). Paste the Mix Shader node between the Diffuse BSDF and the Material Output nodes, and connect the Glossy BSDF output to the second Shader input socket.
- 17. Connect the **Normal** output of the **Bump** node to the **Normal** input socket of the **Glossy BSDF** shader. Set the **Glossy BSDF** shader's **Roughness** to 0.150 and the **Fac** value of the **Mix Shader** node to 0.300.
- 18. Add an **RGB** node (press *Shift* + A and navigate to **Input** | **RGB**) and connect it to the **Color** input socket of the **Diffuse BSDF** shader node. Set the color values to 0.407 for **R**, 0.323 for **G**, and 0.293 for **B**.
- 19. Add a MixRGB node, label it Mix03, and paste it between the RGB and the Diffuse BSDF nodes. Connect the Color output of the Darken-MixRGB node to the Color2 input socket of the Mix03 node.
- 20. Add a new MixRGB node. Set Blend Type to Add and the Fac value to 0.800. Connect the Color output of the ColorRamp01 node to the Color1 input socket, and the output of the Mix03 node to the Color2 input socket of the MixRGB node. Connect the Color output of the Add-MixRGB node to the Color input socket of the Diffuse BSDF node.
- 21. Add an **RGB Curves** node (press *Shift* + *A* and navigate to **Color** | **RGB Curves**) and paste it between the **Add-MixRGB** and the **Diffuse BSDF** nodes. Connect its output to the **Color** input socket of the **Glossy BSDF** shader node.
- 22. Click on the **RGB Curves** node's little window to create a new point. Set its position values to 0.24545 for **X** and 0.38125 for **Y**. Then create another point and set the position values to 0.74545 for **X** and 0.51875 for **Y**, as shown in the following screenshot:




Screenshot of the COLOR frame connected to the Diffuse and Glossy shaders

## How it works...

Even if this material looks a bit complex at first sight, you must note that we just mixed four procedural noise textures with different settings and iterations to build the bump effect and create the color pattern to some extent:


- In the first stage, from steps 2 to 15, we built the bump pattern by mixing the output of the noise textures (the Overlay, Darken, Mix01, and Mix02 nodes converging to the input socket of the Bump node) through MixRGB nodes, and in some cases also edited their levels using the ColorRamp nodes to obtain a more random, natural look (ColorRamp1 and ColorRamp2, all the nodes inside the BUMP frame).
- In the second stage, from steps 18 to 22, we built the color pattern by mixing a simple color output with the output of some of the **Noise Texture** nodes, and then edited the result using an **RGB Curves** node (nodes inside the **COLOR** frame).
- The results of both the bump and the color patterns were then piped into the appropriate sockets of the nodes inside the **SHADER** frame, that is, the **Diffuse BSDF** node was mixed with the **Glossy BSDF** node to add specularity (steps 16 and 17). The overall material network in the **Node Editor** window is shown in the following screenshot:



 ${\it The\ overall\ vision\ of\ the\ material\ network}$ 

# Creating a sand material using procedural textures

In this recipe, we will create a sand material that looks like what is shown in the following screenshot, which is good for both close and distant objects:




The sand material as it appears in the final rendering

## **Getting ready**

Start Blender and switch to the Cycles Render engine. Then perform the following steps:


- 1. Delete the default Cube and add a Plane (press Shift + A and navigate to Mesh | Plane).
- 2. Press *Tab* to go to **Edit Mode** and scale it nine times bigger, with 18 units per side (press *S*, enter the digit *9*, and press *Enter*). Go out of **Edit Mode**.
- 3. Go to the **World** window and click on the **Use Nodes** button under the **Surface** subpanel in the **Properties** panel to the right of the screen. Then click on the little square with a dot on the right side of the **Color** slot. Select the **Sky Texture** item from the pop-up menu. Set the **Strength** value to 1.900.
- 4. Select the Lamp, go to the Object data window, and click on the Use Nodes button. Then change the Type of Lamp to Sun and set Strength to 3.000. Change the color values to 1.000 for R, 0.935 for G, and 0.810 for B. In orthogonal top view, rotate the Sun lamp by 45°, as shown in the following screenshot:



The scene from the top with the Sun Lamp selected

- 5. Add a Cube and a UV Sphere to the scene and place them leaning on the Plane.
- 6. Select the Cube and click on the **Smooth** button in the **Shading** subpanel under the **Tools** tab to the left of the 3D window (press the *T* key to make it appear if it is not present).
- 7. Select the UV Sphere and perform the same actions as given in step 6.
- 8. Select the Cube, and in the **Object modifiers** window, add a **Bevel** modifier. Set **Width** to 0.1000, **Segments** to 2, and **Profile** to 0.15. Assign a **Subdivision Surface** modifier, set both the **Subdivisions** levels to 4, and check the **Optimal Display** item. Assign a **Smooth** modifier and set **Factor** to 1.000 and **Repeat** to 15.
- 9. Select the UV Sphere and assign a **Subdivision Surface** modifier with **Subdivisions** levels set to 2 and the usual **Optimal Display** item checked.
- 10. Select the Plane, click on the **Smooth** button, and then go to **Edit Mode** and press *W*. In the **Specials** pop-up menu, select the **Subdivide** item. Press the *F6* key to call the **Options** pop-up menu (or go to the panel at the bottom of the **Tool Shelf** tabs) and set **Number of Cuts** to 10.
- 11. Go out of **Edit Mode**, go to the **Object modifiers** window, and assign a **Subdivision Surface** modifier. Switch to the **Simple** subdivision algorithm and set both **Subdivisions** to 3. Check the **Optimal Display** item.
- 12. Assign a **Displace** modifier and then click on the **Show texture in texture tab** button to the side of the **New** button. In the **Texture** window, click on the **New** button and switch the default **Clouds** texture with the **Voronoi** texture. Set the **Size** value to 5.00.
- 13. Assign a new **Displace** modifier, click on the **Show texture in texture tab** button, and load a **Voronoi** texture again. Leave the **Size** value at 0.25.
- 14. Assign a **Smooth** modifier and set **Factor** to 1.000 and the **Repeat** value to 5.

- 15. Place the Camera to have a nice angle on the Plane and switch from the 3D view to a Camera view (by pressing the  $\theta$  key on the numeric keypad).
- 16. Split the 3D window into two horizontal rows and change the upper row to a **Node Editor** window. Put the mouse cursor in the 3D view and press *Shift* + *Z* to set the **Camera** view mode to **Rendered**.
- 17. Go to the **Render** window. Under the **Sampling** subpanel, set both the **Clamp Direct** and **Clamp Indirect** values to 1.000. Go to the **Light Path** subpanel and set the **Filter Glossy** value to 1.000.
- 18. Set the **Render** samples to 25. The **Rendered** preview is shown in the following screenshot for your reference:




The prepared scene as it appears in the Rendered preview, with the rendering settings to the right

## How to do it...

We have prepared the scene. Now let's start with the creation of the sand material using the following steps:


- 1. Select the Plane and click on the **New** button in the **Material** window under the **Properties** panel or in the **Node Editor** toolbar. Rename the material Sand 01.
- 2. Keeping the *Shift* key pressed, select the UV Sphere, the Cube, and for last one, the Plane (that is the active object of the multi-selection) by right-clicking on them. Press Ctrl + L, and in the **Make Links** pop-up menu, select the **Material** item to assign the same material to the other two objects. The Sand 01 material is now assigned to all three objects.

- 3. In the **Material** window under the **Properties** panel to the right, switch the **Diffuse BSDF** shader with a **Mix Shader** node. In both the **Shader** slots, assign a **Diffuse BSDF** shader.
- 4. In the **Node Editor**, add an **RGB** node (press *Shift* + *A* and navigate to **Input** | **RGB**) and an **RGB Curves** node (press *Shift* + *A* and navigate to **Color** | **RGB Curves**). Connect the output of the **RGB** node to the **Color** input socket of the first **Diffuse BSDF** shader and to the **Color** input socket of the **RGB Curves** node. Then connect the output of the **RGB Curves** node to the **Color** input socket of the second **Diffuse BSDF** shader node.
- 5. Change the color values of the **RGB** node to 0.500 for **R**, 0.331 for **G**, and 0.143 for **B**. Click on the **RGB Curves** node window to create a new point, and set the coordinates to 0.48182 for **X** and 0.56875 for **Y**.
- 6. Add a **Noise Texture** node (press Shift + A and navigate to **Texture** | **Noise Texture**), a **Texture** Coordinate node (press Shift + A and navigate to **Input** | **Texture Coordinate**), and a **Mapping** node (press Shift + A and navigate to **Vector** | **Mapping**).
- 7. Connect the **Object** output of the **Texture Coordinate** node to the **Vector** input of the **Mapping** node, and then connect the **Vector** output to the **Vector** input of the **Noise Texture** node.
- 8. Connect the **Fac** output of the **Noise Texture** node to the **Fac** input of the **Mix Shader** node. Increase the **Detail** value of the texture to 5.000.
- 9. Press *Shift* + *D* to duplicate the **Mix Shader** node and paste it between the first **Mix Shader** node and the **Material Output** node. Add a **Glossy BSDF** shader node (press *Shift* + *A* and navigate to **Shader** | **Glossy BSDF**), set its **Roughness** to 0.700, and connect its output to the second **Shader** input socket of the second **Mix Shader** node. Set the **Fac** value to 0.100.
- 10. Connect the **Color** output of the **RGB** node to the **Color** input socket of the **Glossy BSDF** shader node.
- 11. Add a **Frame** (press *Shift* + *A* and navigate to **Layout** | **Frame**), press *Shift* and multi-select the **RGB** node, the **RGB Curves** node, the **Noise Texture** node, the two **Diffuse BSDF** nodes, the **Glossy BSDF** shader, the two **Mix Shader** nodes, and the **Frame**, and press Ctrl + P to parent them. In the **Properties** panel (press *N* key in the **Node Editor** window), label the **Frame** as SAND COLOR, as shown in the following screenshot:




The total vision of the SAND COLOR frame and the rendered effect on the objects

- 12. Add a new **Noise Texture** node and a **Wave Texture** node (press *Shift* + *A* and navigate to **Texture** | ...). Select both and press *Shift* + *D* to duplicate them. Label them Wave Texture01, Wave Texture02, Noise Texture01, and Noise Texture02.
- 13. Arrange the four texture nodes in a column like this: Wave Texture01, Noise Texture01, Noise Texture02, and Wave Texture02. Connect the Mapping output to the texture nodes' Vector input.
- 14. Set the Scale value of Wave Texture01 to 3.000, Distortion to 25.000, and Detail to 10.000. Set the Detail value of Noise Texture01 to 10.000 and Distortion to 0.500. Set the Detail value of Noise Texture02 to 10.000 as well. Finally, set the Wave Texture02 node's Scale value to 25.000, Distortion to 15.000, and Detail Scale value to 5.000.
- 15. Add a MixRGB node (press Shift + A and Color | MixRGB) and label it Mix01. Connect the Wave Texture01 node's Color output to the Color1 input and the Noise Texture01 node's Color output to the Color2 input.
- 16. Select the **MixRGB** node and press *Shift* + *D* to duplicate it. Label it Mix02 and connect the **Color** output of the **Mix01** node to the **Color1** input of the **Mix02** node. Then connect the **Wave Texture02** node's **Color** output to its **Color2** input.
- 17. Connect the **Color** output of the **Noise Texture02** node to the **Fac** input socket of the **Mix02** node. Now the **Node Editor** window looks like what is shown in the following screenshot:




Building the bump pattern

18. Add a **Math** node (press *Shift* + A and navigate to **Converter** | **Math**) and label it Bump\_Strength. Change **Operation** to **Multiply** and connect the output of the **Mix02** node to the first **Value** input socket. Set the second **Value** input socket's value to 1.000 and connect the node output to the **Displacement** input socket of the **Material Output** node, as shown in this screenshot:




The effect of the total output of the bump nodes connected to the Displacement input of the Material Output node

- 19. Add a **Hue/Saturation** node (press *Shift* + *A* and navigate to **Color** | **Hue/Saturation**), label it Hue Saturation Value01, and drag it onto the link connecting the **Noise Texture01** node to the **Mix01** node to paste it in between. Set **Value** to 10.000.
- 20. Press Shift + D to duplicate the **Hue/Saturation** node, label the duplicate Hue Saturation Value02, and drag it onto the link connecting the **Wave Texture02** node to the **Mix02** node. Set **Value** to 0.100.
- 21. Press *Shift* + *D* to duplicate it again, name the duplicate Hue Saturation Value03, and drag it between the **Mix02** node and the **Bump Strength** node. Set **Value** to 0.350. The following screenshot shows the effect of adding variation to the bump:



Adding variation to the bump pattern


- 22. Add a **Bright/Contrast** node (press *Shift* + *A* and navigate to **Color** | **Bright Contrast**). Drag it so that it's pasted between the **Noise Texture02** node and the **Mix02** factor input. Set the **Bright** value to -0.250 and the **Contrast** value to 1.000.
- 23. Add a **Frame**, press *Shift* (or box-select (press *B* key) these 11 nodes and then the **Frame**), and press *Ctrl* + *P* to parent them. Label the **Frame** SAND BUMP, as shown in the following screenshot:



The SAND BUMP frame containing all the bump nodes


- 24. Select the **Wave Texture02** node and press *Shift* + *D* to duplicate it twice (if the node is still parented to the **SAND BUMP** frame after duplication, press *Alt* + *P* to unparent it). Label them Wave Texture03 and Wave Texture04. Then duplicate the **Bright/Contrast** node twice and name the duplicates Bright/Contrast02 and Bright/Contrast03.
- 25. Select one of the **MixRGB** nodes and press Shift + D to duplicate it. Set **Blend Type** (and the label) to **Divide** and the **Factor** to 1.000.
- 26. Connect the **Mapping** vector output to the **Vector** input sockets of the two new wave textures.
- 27. Connect each Color output of the two new wave textures to the respective Color input of the Bright/Contrast02 nodes. Then connect their color output to the Color1 and Color2 input of the Divide node.
- 28. In the Wave Texture03 node, set Scale to 0.500, Distortion to 25.000, Detail to 10.000, and Detail Scale to 1.000. In the Bright/Contrast02 node, set the Bright value to 0.000 and the Contrast value to -0.800.
- 29. In the Wave Texture04 node, set Scale to 1.000, Distortion to 10.000, Detail to 5.000, and Detail Scale to 1.000. In the respective Bright/Contrast03 node, set the Bright value to 0.000 and the Contrast value to -0.800.
- 30. Add a Math node (press Shift + A and navigate to Converter | Math). Set Operation to Multiply, label it Multiply01, and leave the first Value as it is—the same as the Scale value of the Wave Texture03 node (0.500). Set the second Value to 1.000. Connect the Value output to the Scale input socket of the Wave Texture03 node.
- 31. Press *Shift* + *D* to duplicate the **Math** node (label it Multiply02). Move it to the side of the **Wave Texture04** node and set the first **Value** to be the same as the **Scale** value of the texture

- node (1.000). Set the second Value to 1.000 as well, and connect the Value output to the Scale input of the Wave Texture04 node.
- 32. Add a **Value** node (press *Shift* + *A* and navigate to **Input** | **Value**). Connect the output to the second **Value** input sockets of both the **Multiply-Math** nodes. Label it Waves\_size and set the input value to 1.000.
- 33. Add a **Frame**, parent the last added nodes, and label it BIG WAVES, as shown in the following screenshot:




A new frame containing a new bump effect to be added to the previous one

- 34. Duplicate the **Bump\_Strength** node, unparent it from the **SAND BUMP** node, and set the **Operation** to **Add**. Drag it onto the link between the **Bump\_Strength** node and the **Material Output** node, and label it Add Bump01.
- 35. Connect the **Divide** node output of **BIG WAVES** to the second **Value** input socket of the **Add Bump01** node, as shown in this screenshot:




The output of the two bump frames added together

- 36. Duplicate a Noise Texture node (label it Noise Texture03), a Bright/Contrast node (label it Bright/Contrast04), and a Math node (label it Grain\_Strength). Connect the Mapping output to the Vector input of the texture node. Then connect the Noise Texture node's Color output to the Bright/Contrast04 node's Color input and its output to the first Value input socket of the Grain\_Strength node. Set its operation to Multiply and the second Value to 0.250.
- 37. Set the texture Scale to 200.000, Detail to 1.000, and Distortion to 0.000. Set the Bright/Contrast04 node's Bright value to 0.000 and Contrast to 0.200.
- 38. Add a **Frame**, parent the three nodes to it, and label it **GRANULARITY**, as shown in the following screenshot:




One more bump effect frame

- 39. Duplicate the Add\_Bump01 node, and label it Add\_Bump02, and paste it between the Add\_Bump01 node and the Material Output node. Connect the Grain\_Strength output of the GRANULARITY frame to the second Value input socket of the Add\_Bump02 node.
- 40. Duplicate the Add\_Bump02 node and paste it just before the Material Output node. label it TOTAL BUMP STRENGTH, set the node Operation to Multiply, and set the second Value to 0.500, as shown in this screenshot:




The GRANULARITY frame output added to the previous bump ones

So here we are now—the sand shader is complete, and this is how the nodes' network looks in the **Node Editor** window:



To obtain the image shown at the beginning of this recipe, we also added a few elements to the scene:

- A new Cube primitive, with a simple diffuse pure white material, added just for reference to light intensity.
- An Ico Sphere primitive, set as invisible and disabled for the rendering in **Outliner**. It works as target **Object** for a Boolean modifier assigned to the sand Cube and is placed in the stack between the **Subdivision Surface** and **Smooth** modifiers, as shown in the following screenshot:



### How it works...

The concept behind the structure of this material is basically the same as that for the procedural rock, and it can be subdivided into stages as well:


- From step 1 to step 10, we built the color part of the shader, blending two differently colored **Diffuse BSDF** nodes on the ground of a **Noise Texture** factor, and building a basic shader with the **Glossy BSDF** component.
- From step 12 to step 22, we built the main bump effect, this time piped directly as whole in the **Displacement** input of the **Material Output** node rather than to the **Normal** input sockets per shader.
- From step 24 to step 32, we built a supplementary bump effect, this time to simulate the big waves you usually see on a desert's sand dunes. This effect was left apart from the main bump to be easily reduced or eliminated if required. Then we added two **Math** nodes set to **Multiply** and driven by a **Value** node to automatically set the size of the big sand waves. Actually, this is more a repeating effect, and the bigger the value, the smaller and closer the waves.
- In steps 36 and 37, we built a last bump effect to add the sand grain if necessary, for example, for objects very close to the camera. In steps 39 and 40, we summed all the bump effects, to be driven by the last **Math** node value.

Every stage has been framed and properly labeled to make it more easily readable in the **Node Editor** window.

## There's more...


One more thing we can do to improve this material is combine everything into a handy group node, at the same time leaving the fundamental values to be tweaked exposed on the node group interface. To do this follow these steps:

- 1. Put the mouse cursor in the **Node Editor** window and press the *B* key. Two horizontal and a vertical lines appear at the location of the mouse cursor. Click and drag the mouse to encompass the framed nodes, leaving outside only the **Texture Coordinate** node, the **Mapping** node, and the **Material Output** nodes. After the mouse button is released, everything you encompassed is selected.
- 2. Press Ctrl + G and create the group. Then press N in the **Node Editor** window to call the **Properties** panel on the right side.



The previous sand material network inside a node group


3. Press *Tab* to go out of **Edit Mode**. Then click on the little window on the interface to change the name from NodeGroup to Sand\_Group.



The closed node group

As you can see, inside the group, the **Group Input** node collects all the **Vector** sockets from which the various texture nodes take their mapping coordinates, so we now have eight **Vector** sockets in the outer interface, all connected to the same **Object** output of the **Mapping** node. However, we need only one **Vector** input to map all the textures inside the group, so let's perform the following steps:


- 1. Press *Tab* to go to **Edit Mode** again and deselect everything by pressing the *A* key.
- 2. Select the first bottom Vector output by clicking on the list of names in the little Inputs window under the Properties/Interface panel. Delete the corresponding Vector socket from the Group Input node by clicking on the X icon to the side of the newly appeared Name slot. Then click on the X icon again, and go on like this to delete all the Vector sockets except the last socket at the top of the list as shown in the following screenshot:



- 3. Now press *Shift*, select the **Group Input** node and the first texture node, and press *F* to automatically connect them.
- 4. Repeat to connect all the eight texture nodes to the **Vector** socket of the **Group Input** node.


Now we need to expose some of the values to modify the material from the interface, so let's perform the following steps:

1. From the second **Value** socket of the **Bump\_Strength** node inside the **SAND BUMP** frame, click and drag a link to the bottom free socket in the **Group Input** node. In the **Input** window under the **Properties** panel, double-click on the newly appeared input socket name, **Value**, and write Sand strength.




All the Vector input sockets of the nodes are connected to a single socket on the Group Input node, and the Bump Strength value is exposed by a new connection

- 2. Repeat step 1 for the second Value socket of the Waves\_Strength and the Grain\_Strength nodes, and rename the respective input as Waves\_strength and Granularity.
- 3. Now click on the Waves\_size node inside the BIG WAVES frame and delete it. Click and drag the second Value socket of the Multiply01 node to the Group Input node, and rename the new socket Waves\_size. Click and drag a link from the second Value socket of the Multiply02 node, and connect it to the Waves size socket as well.
- 4. We also need to expose the second **Value** socket of the **TOTAL BUMP STRENGTH** frame. Rename the new socket on the interface as Total strength. This is in fact the value for the overall bump of the material.
- 5. After this, we can do the following: expose the color input by deleting the RGB node in the SAND COLOR frame and connecting the Color input sockets of the Diffuse BSDF, RGB Curves, and Glossy BSDF shader node's to the Color socket on the Group Input node; expose the sand's grain size value, connecting the Scale input socket of the Noise Texture03 node to a Grain\_size socket; and finally, by clicking on the arrows in the Properties panel, order the position of the input sockets on the Group Input node as shown in this screenshot:



The sockets created on the Group Input node and reflected in the Interface subpanel

6. Press *Tab* to close the group. On the interface, we now have the controls to increase or decrease the overall bump effect, the sand color and grain, the wave strength, and scale/repetition, as we can see in the following screenshot:




#### The final Sand Group node with all the exposed input on its interface

The group is now available under the **Add** menu, and its shortcut involves pressing Shift + A and navigating to **Group** | **Sand\_Group**. It can be reused for other materials in the same scene and also with different interface values, or linked/appended from a library in other blend files.

# Creating a simple ground material using procedural textures

In this recipe, we will create a basic, raw ground material as shown in this screenshot:




The ground material as it appears in the final rendering

## **Getting ready**

Start Blender and switch to Cycles Render. Then perform the following steps:

- 1. Delete the default Cube and add a Plane. Go to **Edit Mode** and scale it 15 times bigger (30 units per side; press *Tab*, then press *S*, enter the digit *15*, and press *Enter*). Go out of **Edit Mode**.
- 2. Go to the **Object modifiers** window and assign a **Subdivision Surface** modifier to the Plane. Switch from **Catmull-Clark** to **Simple**, and set the levels of **Subdivisions** for both **View** and **Render** to 4. Check the **Optimal Display** item.
- 3. Assign a second **Subdivision Surface** modifier. Again, switch to **Simple**, set the levels of **Subdivisions** for both **View** and **Render** to 4, and check the **Optimal Display** item.
- 4. Assign a **Displace** modifier. Click on the **Show texture in texture tab** button to the side of the **New** button. In the **Texture** window, click on the **New** button, select **Voronoi** texture, and increase the **Size** value to 1.80. Go back to the **Object modifiers** window and set the displacement **Strength** to 0.100.
- 5. Assign a second **Displace** modifier and select the default **Clouds** texture. Set the **Size** value to 0.75, the **Depth** value to 5, and the displacement **Strength** value to 0.150.
- 6. Assign a third **Displace** modifier. Again, select the default **Clouds** texture and increase the **Size** value to 4.00 (the slider arrives at a maximum of 2.00, but you can click on the value and enter higher values) and the **Depth** value to 4. Then switch **Noise** from **Soft** to **Hard** and click

- on the Basis button to change Noise Basis from Blender Original to Voronoi F4. Go to the Colors subpanel above the Clouds subpanel, and adjust the Brightness value to 0.900 and the Contrast value to 1.500. Set the displacement strength to 0.500.
- 7. In the **Shading** subpanel (which is accessible from the **Transform** menu), under the **Tool Shelf** tabs to the left of the 3D view, click on the **Smooth** button.
- 8. Go to the **World** window and click on the **Use Nodes** button in the **Surface** subpanel under the **Properties** panel. Then click on the little square with a dot on the right side of the **Color** slot. From the menu, select **Sky Texture**. Set the **Strength** value to 1.400.
- 9. Go to the **Outliner** and select the **Lamp** item. Go to the **Object data** window and click on **Use Nodes**. Then change **Type of Lamp** to **Sun** and set the **Strength** value to 1.400. Change the light color values to 1.000 for **R**, 0.935 for **G**, and 0.810 for **B**. In the orthogonal top view (press the 7 and 5 keys in the numeric keypad), rotate the Sun Lamp by 90°.
- 10. Place the **Camera** to have a nice angle on the Plane (you can also use the **Lock Camera to View** item in the (press N) **Properties** side panel), and switch from the 3D view to the **Camera** view (by pressing 0 from the numeric keypad).
- 11. Split the 3D window into two horizontal rows. Change the upper row to a **Node Editor** window.
- 12. Go to the **Render** window, and under the **Sampling** subpanel, set both the **Clamp Direct** and **Clamp Indirect** values to 1.000. Go to the **Light Path** subpanel and set the **Filter Glossy** value to 1.000.
- 13. Reselect the **Plane** and go to the **Material** window under the **Properties** panel. Disable the transformation widget by clicking on the icon in the 3D window toolbar or by pressing *Ctrl* and the spacebar, as shown in the following screenshot:




Screenshot in the Solid viewport shading mode of the ground scene

In the final scene, I added three UV Spheres with simple diffuse colors, just for lighting reference. Obviously, you can skip this step.

#### How to do it...

Let's now start with the ground material:


- 1. Put the mouse cursor in the Camera view and press *Shift* + *Z* to switch the Viewport Shading mode to Rendered.
- 2. Click on the **New** button in the **Material** window or in the **Node Editor** toolbar. Rename the material Ground 01.
- 3. In the **Node Editor** window, add a **Texture Coordinate** node (press *Shift* + *A* and navigate to **Input** | **Texture Coordinate**), a **Mapping** node (press *Shift* + *A* and navigate to **Vector** | **Mapping**), and a **Musgrave Texture** node (press *Shift* + *A* and navigate to **Texture** | **Musgrave Texture**).
- 4. Connect the **Object** output of the **Texture Coordinate** node to the **Vector** input of the **Mapping** node and the **Vector** output of this node to the **Vector** input of the **Musgrave Texture** node.
- 5. Connect the **Color** output of the **Musgrave Texture** node to the **Color** input of the **Diffuse BSDF** shader. In the **Properties** panel, label the **Diffuse BSDF** shader as Diffuse01. Set the **Scale** value of the **Musgrave Texture** node to 0.500.
- 6. Add a Wave Texture node (press Shift + A and navigate to Texture | Wave Texture) and a MixRGB node (press Shift + A and navigate to Color | MixRGB). Paste the MixRGB node between the Musgrave Texture node and the Diffuse01 shader node, and connect the Wave Texture node's color output to the Color2 input socket of the MixRGB node.
- 7. Set the MixRGB node's Blend Type to Subtract and label it Subtract01. Connect the Mapping output to the Wave Texture node's Vector input.
- 8. Set the Wave Texture node's Scale value to 0.200, Distortion to 20.000, Detail to 16.000, and Detail Scale to 5.000.
- 9. Add a **ColorRamp** node (press *Shift* + *A* and navigate to **Converter** | **ColorRamp**) and drag it onto the link connecting the **Wave Texture** node to the **Subtract01** node to paste it between them. Label it ColorRamp01, change the **Interpolation** mode to **B-Spline**, and move the black stop to the 0.230 position (**Pos:**).
- 10. Add two **Noise Texture** nodes (press *Shift* + A, navigate to **Texture** | **Noise Texture**, and then press *Shift* + D to duplicate it) and name them Noise Texture01 and Noise Texture02. Connect the **Mapping** node to them. Select the **Subtract01** node, press *Shift* + D to duplicate it twice, and change **Blend Type** to **Divide** and **Dodge**. Connect the **Color** output of the **Subtract01** node to the **Color1** input of the **Divide** node, and connect the **Color** output of the **Noise Texture01** node to the **Color2** input of the **Divide** node.
- 11. Then connect the **Color** output of the **Divide** node to the **Color1** input of the **Dodge** node, and the **Color** output of the **Noise Texture02** node to the **Color2** input of the **Dodge** node.
- 12. Label the **Dodge** node <code>Dodge01</code> and connect its output to the **Color** input of the **Diffuse01** shader. Set the **Noise Texture01** scale to 10.000, **Detail** to 5.000, and **Distortion** to 0.300. For **Noise Texture02**, set **Scale** to 35.000, **Detail** to 5.000, and **Distortion** to 1.000, as shown in the following screenshot:



The first steps to build the bump effect for the ground material


- 13. Add two **Voronoi Texture** nodes (press *Shift* + *A*, navigate to **Texture** | **Voronoi Texture**, and rename the nodes Voronoi Texture01 and Voronoi Texture02) and a new **MixRGB** node (press *Shift* + *A* and navigate to **Color** | **MixRGB**). Set the **Blend Type** to **Subtract** and label it Subtract02. Connect the color output of the **Voronoi Texture01** node to the **Color1** input socket, and the color output of the **Voronoi Texture02** node to the **Color2** input socket.
- 14. Set the **Subtract02** node's **Fac** value to 1.000, and then go to the **Voronoi Texture01** node. Set **Coloring** to **Cells** and **Scale** to 18.100. Go to the **Voronoi Texture02** node, leave **Coloring** as **Intensity**, and set the **Scale** value to 18.000.
- 15. Select the two **Voronoi Texture** nodes and the **Subtract02** node, and press *Shift* + *D* to duplicate them. Label the texture nodes as Voronoi Texture03 and Voronoi Texture04, and the **MixRGB** node as Subtract03.
- 16. Connect the **Mapping** node output to the **Vector** input sockets of the four **Voronoi Texture** nodes.
- 17. Change the Coloring of the Voronoi Texture03 node back to Intensity, and set the Scale value to 18.500. Set the Scale value of Voronoi Texture04 to 6.500.
- 18. Add a new MixRGB node (press Shift + A and navigate to Color | MixRGB) and change the Blend Type to Dodge. Label it Dodge02 and set the Fac value to 1.000. Connect the output of the Subtract02 node to the Color1 input socket and the output of the Subtract03 node to the Color2 input socket.
- 19. Add a **MixRGB** node again (press *Shift* + *A* and navigate to **Color** | **MixRGB**). Change the **Blend Type** to **Add** and paste it between the **Dodge01** node and the **Diffuse01** shader node. Then connect the output of the **Dodge02** node to the **Color2** input socket.

- 20. Disconnect the link between the **Add** output and the **Color** input socket of the **Diffuse01** shader node, and add a **Bump** node (press *Shift* + *A* and navigate to **Vector** | **Bump**). Connect the output of the **Add** node to the **Height** input socket of the **Bump** node. Then connect the **Normal** output of the **Bump** node to the **Normal** input socket of the **Diffuse01** shader. Set the **Add** node's **Fac** value to 0.280 and the **Bump** node's **Strength** value to 0.800.
- 21. Add a **ColorRamp** node (press *Shift* + *A* and navigate to **Converter** | **ColorRamp**) and label it ColorRamp02. Paste it between the **Dodge02** and the **Add** nodes. Set **Interpolation** to **B-Spline** and move the black color slider and stop at position 0.330.
- 22. Add a **RGB to BW** node (press Shift + A and navigate to **Converter** | **RGB to BW**) and paste it between the **Add** and the **Bump** nodes.



The total BUMP network for the ground material


23. Parent the nodes to a **Frame** (press *Shift* + *A* and navigate to **Layout** | **Frame**) and label it BUMP, as shown in the following screenshot:



The BUMP frame

- 24. Add a **Mix Shader** node (press *Shift* + A and navigate to **Shader** | **Mix Shader**) and a second **Diffuse BSDF** shader (press *Shift* + A and navigate to **Shader** | **Diffuse BSDF**). Name them Mix Shader01 and Diffuse02, respectively. Then paste the **Mix Shader01** node between the **Diffuse01** and the **Material Output** nodes, and connect the **Diffuse02** node to the second **Shader** input socket of the **Mix Shader01** node.
- 25. Once again, add a **Mix Shader** node (press *Shift* + A and navigate to **Shader** | **Mix Shader**) and a **Diffuse BSDF** shader (press *Shift* + A and navigate to **Shader** | **Diffuse BSDF**). Label them Mix Shader02 and Diffuse03. Then paste the **Mix Shader02** node between the **Mix Shader01** node and the **Material Output** node, and connect the **Diffuse03** node to the second **Shader** input socket.
- 26. Connect the **Bump** node output to the **Normal** input of the **Diffuse02** and **Diffuse03** shader nodes.
- 27. Change the **Diffuse01** color values to 0.593 for **R**, 0.460 for **G**, and 0.198 for **B**; the **Diffuse02** color values to 0.423 for **R**, 0.234 for **G**, and 0.092 for **B**; and the **Diffuse03** color values to 0.700 for **R**, 0.620 for **G**, and 0.329 for **B**.
- 28. Once more, add a Mix Shader node (press Shift + A and navigate to Shader | Mix Shader) and a Glossy BSDF shader (press Shift + A and navigate to Shader | Glossy BSDF). Label the first node Mix Shader03 and paste it between the Mix Shader02 and the Material Output nodes. Connect the Glossy BSDF shader to the second Shader input socket of the Mix Shader03 node, and set its Roughness value to 0.300 and the color values to 0.593 for R, 0.460 for G, and 0.198 for B, just like the Diffuse01 color.
- 29. Connect the **Bump** node output to the **Normal** input socket of the **Glossy BSDF** node.


- 30. Add a **Layer Weight** node (press *Shift* + A and navigate to **Input** | **Layer Weight**), connect the **Fresnel** output to the **Fac** input socket of the **Mix Shader03** node, and set the **Blend** value to 0.300.
- 31. Parent these recently added nodes to a new **Frame** and label it COLOR.



#### The COLOR frame

- 32. Add one more **Noise Texture** node (press *Shift* + *A* and navigate to **Texture** | **Noise Texture**) and a new **ColorRamp** node (press *Shift* + *A* and navigate to **Converter** | **ColorRamp**). Connect the **Mapping** node output to the **Noise Texture** node's **Vector** input (label it Noise Texture03) and the **Fac** output of **Noise Texture** to the **Fac** input of the **ColorRamp** node (label it ColorRamp03).
- 33. For the last time, add a MixRGB node and set the Blend Type to Difference. Then connect the Color output of the ColorRamp03 node to the Color1 input socket of the Difference node, and the Color output of the Difference node to the Fac input socket of the Mix Shader01 node. Set the Fac value of the Difference node to 0.255.
- 34. Set the **Noise Texture03** node's scale to 1.000 and the **Detail** value to 5.000. Switch the **ColorRamp03** node's **Interpolation** to **B-Spline**, move the **0** value of **color stop** to position 0.285, move the **1** color stop to position 0.740, and click on the + icon to add a new color stop. Set its color to black and move it to position 0.320.
- 35. Connect the output of the **Dodge01** node inside the **BUMP** frame to the **Color2** input socket of the **Difference** node. Connect the **Color** output of the **ColorRamp02** node inside the **BUMP** frame to the **Fac** input socket of the **Mix Shader02** node inside the **COLOR** frame.

And we're done! Here is a screenshot of what the Blender UI will now look like:




Part of the bump output is connected to the COLOR frame by the three upper nodes and the bottom ColorRamp node

### How it works...

The way this material works is very similar to the sand material of the previous recipe, although a lot simpler:

• We mixed two slightly different colors using the values of a **Noise Texture** node as the stencil factor, then mixed a third, similar color on the ground of the bump output to obtain the whitish, pebble-like effect you see in the rendered image. We created the ground roughness using an ensemble of procedural textures mixed in several ways, whose total sum was then connected to the **Normal** input sockets of the three **Diffuse BSDF** nodes and of the **Glossy BSDF** shader, as shown in the following screenshot:



The overall vision of the ground material network

# Creating a snow material using procedural textures

In this recipe, we will create a snow material, as shown in the following screenshot, and also fake a slight and cheap Subsurface Scattering effect:



The snow material as it appears in the final rendering

## **Getting ready**

Start Blender and open the 99310S Snow start.blend file.


In this file, there is a prepared scene with a Spheroid (the usual Cube with a four-level **Subdivision Surface** modifier), a Suzanne (press *Shift* + *A* and navigate to **Add** | **Mesh** | **Monkey**) with a **Subdivision Surface** modifier as well, and the famous Stanford bunny (<a href="http://en.wikipedia.org/wiki/Stanford\_bunny">http://en.wikipedia.org/wiki/Stanford\_bunny</a>), leaning on a subdivided, displaced, and smoothed Plane renamed Snow\_ground. Suzanne is Blender's mascot and an alternative to free test models such as the Stanford bunny itself. By the way, I thought of grouping them in the same scene to have different shapes to test the material.

In the file, there is also a Plane working as mesh-light and a Spot pointing in the opposite direction to try to enhance the translucency of the snow.

#### How to do it...

Let's start creating the snow material:


- 1. Go to the **World** window and click on the **New** button. Then click on the little square with a dot on the right side of the **Color** slot. From the menu, select **Sky Texture**.
- 2. Go to the **Material** window and select the **Snow\_ground** item in the **Outliner**. Click on the **New** button in the **Material** window under the **Properties** panel or in the **Node Editor** toolbar. Rename the material as Snow 01.
- 3. Press *Shift* and select the Spheroid, Suzanne, and the Stanford bunny. Then select the Plane to have it as the active object. Press Ctrl + L and go to **Materials**.
- 4. Put the mouse cursor in the Camera view and press *Shift* + *Z* to set the Viewport Shading mode to Rendered.
- 5. In the **Material** window under the **Properties** panel to the right, under the **Surface** subpanel, switch the **Diffuse BSDF** shader with a **Mix Shader** node. In the first **Shader** slot, select a **Diffuse BSDF** shader, and in the second slot, select a **Glossy BSDF** shader.
- 6. Set the **Roughness** value of the **Glossy BSDF** shader to 0.300.
- 7. Add a **Fresnel** node (press *Shift* + A and navigate to **Input** | **Fresnel**) and a **Math** node (press *Shift* + A and navigate to **Converter** | **Math**). Set the **IOR** (short for **Index Of Refraction**) value of the **Fresnel** node to 1.300. Then connect its **Fac** output to the first **Value** socket of the **Math** node. Set the second **Value** to 10.000 and the operation mode to **Divide**. Finally, connect its **Value** output to the **Fac** input socket of the **Mix Shader** node.
- 8. Add a **Translucent BSDF** node (press *Shift* + *A* and navigate to **Shader** | **Translucent BSDF**). Set its color values to 0.598 for **R**, 0.721 for **G**, and 1.000 for **B**.
- 9. Select the **Mix Shader** node, press *Shift* + *D* to duplicate it, and paste it between the first **Mix Shader** node and the **Material Output** node. Connect the **Translucent BSDF** node's output to the second input socket. Set the **Fac** value of the second **Mix Shader** node to 0.300. Here is a screenshot of the basic shader for your reference:



- 10. Add a **Noise Texture** node (press Shift + A and navigate to **Texture** | **Noise Texture**) and press Shift + D to duplicate it. In the **Properties** panel of the **Node Editor** window (press the N key to make this appear if necessary), label them Noise Texture01 and Noise Texture02.
- 11. Add a **Texture Coordinate** node (press *Shift* + *A* and navigate to **Input** | **Texture Coordinate**) and a **Mapping** node (press *Shift* + *A* and navigate to **Vector** | **Mapping**). Connect the **Object** output of the **Texture Coordinate** node to the **Vector** input of the **Mapping** node. Then connect the **Vector** output of the **Mapping** node to both the **Vector** input sockets of the **Noise Texture** nodes.
- 12. Add a **Math** node (press *Shift* + *A* and navigate to **Converter** | **Math**) and press *Shift* + *D* to duplicate it three times so that you obtain four **Math** nodes. Label them Math01, Math02, Math03, and Math04.
- 13. Connect the **Noise Texture01** node's **Fac** output (the gray one) to the first **Value** input of the **Math01** node and set the second **Value** to 2.000. Set the **Operation** to **Multiply**.
- 14. Connect the Fac output of the Noise Texture02 node to the first Value input of the Math02 node and let its second Value be the default, which is 0.500. Set the Operation to Multiply.
- 15. Now connect both the output of the two previous **Math** nodes to the input **Value** sockets of the **Math03** node. Set the **Operation** to **Add**.
- 16. Connect the output of the Math03 node to the first Value input of the Math04 node. Set its Operation to Multiply and let the second Value be the default, which is 0.500.
- 17. Connect the **Math04** node output to the **Displacement** input socket of the **Material Output** node.
- 18. Now go to the **Noise Texture02** node and change the **Scale** value to 15.000. Leave the other values (also for the **Noise Texture01** node) as they are (that is, 5.000 for **Scale**, 2.000 for **Detail**, and 0.000 for **Distortion**).
- 19. Go to the **Mapping** node and set the **Scale** value to 0.500 for all three axes. Now the Blender UI will look like what is shown in this screenshot:



20. Add two **Frames**, label them SNOW COLOR and SNOW BUMP, and parent the appropriate nodes to them as shown in the following screenshot:



The overall vision of the snow material network

#### How it works...


As usual, to understand the creation of this material more easily, we will divide it into two stages: the first stage for the general color and consistency of the snow, and the second stage to add bumpiness to the surface. These stages are explained in detail as follows:

- First stage: We just made a basic shader by mixing the Diffuse BSDF and the Glossy BSDF shaders by the IOR value of the Fresnel node. The Fresnel output value is divided by the Math-Divide node to obtain a softer transition (try to change the second value from 10.000 to 1.000 to see a totally different effect). Then we also mixed a bluish Translucent shader but gave predominance to the basic shader by setting the factor value in the second Mix Shader node to 0.300. The Translucent shader gives the appearance of light seeping through snow and showing in the shadowed areas of the object, working as a very fast and cheap Subsurface Scattering effect.
- Second stage: We added two Noise Texture nodes with different scale values to simulate the bumpiness of soft snow. The first two Multiply-Math nodes set the influence of each noise separately. These values were merged by the Add-Math node and piped in one more Math node, set to Multiply as well, to establish the overall weight of the bump effect that, being

| directly connected to the <b>Displacement</b> input in the <b>Material Output</b> node, affects all the shaders in the network. |
|---|
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |
|   |

# Creating an ice material using procedural textures

In this recipe, we will create a semi-transparent ice material that will look like this:




The ice material as it appears in the final rendering


## **Getting ready**

Start Blender, load the 99310S start.blend file, and perform the following steps:

- 1. Delete the **UV/Image Editor** window by joining it with the 3D view.
- 2. Select the **Plane** item, go to **Edit Mode**, and scale it eight times bigger (press *Tab*, then press *S*, enter the digit  $\delta$ , and press *Enter*). Go out of **Edit Mode** and move the Plane 1 unit upward (press *Tab*, then press *G*, enter the digit *I*, press *Z*, and finally, press *Enter*).
- 3. Select the **Cube** and press N to make the **Properties** panel visible. Go to the **View** subpanel and check the **Lock Camera to View** item. The borders of the **Camera** view turn red, which mean that you can directly use the mouse to move, zoom in, and adjust the position of the Camera around the selected object (the Cube in this case) to obtain a view similar what is shown in the right half of this screenshot:



- 4. Next, uncheck the Lock Camera to View item.
- 5. Go to the **World** window and set **Color** to black.
- 6. Select Sun Lamp in the Outliner, and in the Object data window, set the Strength value to 3.000, Size to 1.000, and the Color values to 0.900 for R, 0.872 for G, and 0.737 for B.
- 7. Select the **Cube**, go to **Edit Mode**, and press the *W* key. In the **Specials** pop-up menu, select **Subdivide**. Press the *F6* key, and in the **Subdivide** pop-up panel under the 3D Cursor position, set **Number of Cuts** to 2. Go out of **Edit Mode**.
- 8. Go to the **Object modifier** window and assign a **Subdivision Surface** modifier to the Cube. Switch from **Catmull-Clark** to **Simple**. Set the **Subdivisions** levels to 5 for both **View** and **Render**. Check the **Optimal Display** item.
- 9. Assign a **Displace** modifier, and in the **Textures** window, click on **New** and select the **Voronoi** texture. Set the **Size** value to 1.20. Back in the **Object modifiers** window, set the displacement **Strength** to 0.050.
- 10. Assign a new **Displace** modifier and select **Voronoi** texture again, but this time, set the **Size** value to 0.80. Set the displacement **Strength** value to 0.075.
- 11. Assign a third **Displace** modifier, select the **Voronoi** texture, and leave the default size (0.25) as it is. Set the displacement **Strength** value to 0.020. Here is a screenshot of the displaced Cube primitive for your reference:



A screenshot in the Solid viewport shading mode of the displaced Cube primitive


12. Switch the Camera's **Viewport Shading** to the **Rendered** mode.

#### How to do it...

After preparing the scene, we are going to create the material:

- 1. Select the **Cube** and click on **New** in the **Material** window under the **Properties** panel or in the **Node Editor** toolbar. Rename the material Ice 01.
- 2. In the **Material** window to the right of the screen, under the **Surface** subpanel, switch the **Diffuse BSDF** shader with a **Mix Shader** node. In the first **Shader** slot, select a **Glass BSDF** shader, and in the second slot, select a **Transparent BSDF** shader.
- 3. Set the Glass BSDF shader's color totally white and the IOR value to 1.309. Set the Transparent BSDF shader's color values to 0.448 for R, 0.813 for G, and 1.000 for B.
- 4. Add a **Fresnel** node (press Shift + A and navigate to **Input** | **Fresnel**) and connect it to the **Fac** input socket of the **Mix Shader** node. Then set the **IOR** value to 1.309.
- 5. Add a Glossy BSDF shader (press Shift + A and navigate to Shader | Glossy BSDF). Set the color to pure white and the Roughness value to 0.050.
- 6. Select the **Mix Shader** node and press *Shift* + *D* to duplicate it. Connect the output of the first Mix Shader node to the first Shader input socket of the duplicated one, and the **Glossy BSDF** shader output to the second **Shader** input socket. Add a **Layer Weight** node (press *Shift* + *A* and navigate to **Input** | **Layer Weight**) and connect the **Facing** output to the **Fac** socket of the second **Mix Shader** node.

- 7. Add a **Voronoi Texture** node (press *Shift* + *A* and navigate to **Texture** | **Voronoi Texture**). Set **Coloring** to **Cells** and the **Scale** value to 25.000.
- 8. Add a **Noise Texture** node (press Shift + A and navigate to **Texture** | **Noise Texture**) and set only the **Scale** value to 25.000.
- 9. Add a **Math** node (press *Shift* + A and navigate to **Converter** | **Math**) and set **Operation** to **Maximum**. Connect the **Fac** output of the **Voronoi Texture** and **Noise Texture** nodes to the first and the second **Value** input of the **Math** node.
- 10. Add a **Bump** node (press *Shift* + A and navigate to **Vector** | **Bump**). Connect the **Maximum-Math** node output to the **Height** input of the **Bump** node, and its **Normal** output to the **Normal** input sockets of the **Glass BSDF** and **Glossy BSDF** shaders.
- 11. Set the **Strength** value of the **Bump** node to 0.250.
- 12. Add an **RGB Curves** node (press *Shift* + *A* and navigate to **Color** | **RGB Curves**) and paste it between the **Maximum-Math** and the **Bump** nodes. Set the point in the little window of the node interface at these coordinates: 0.25455 for **X** and 0.28125 for **Y**. Click on the little window to create a new point and set its coordinates to 0.74091 for **X** and 0.26250 for **Y**.
- 13. Add a **Texture Coordinate** node (press *Shift* + *A* and navigate to **Input**| **Texture Coordinate**) and a **Mapping** node (press *Shift* + *A* and navigate to **Vector** | **Mapping**). Connect the **Object** output of the **Texture Coordinate** node to the **Vector** input of the **Mapping** node. Then connect the **Vector** output of the **Mapping** node to the **Vector** input sockets of both the **Voronoi Texture** and **Noise Texture** nodes, as shown in the following screenshot:



The quite simple network of nodes for the ice material

#### How it works...

This time, we started by mixing a **Glass BSDF** shader and a **Transparent** shader node, modulated by a **Fresnel** node, and we set the **IOR** values of both the **Fresnel** and the **Glass BSDF** to the refraction value of ice. We also added a **Glossy BSDF** shader to provide specularity, mixed by a **Layer Weight** node set on **Facing** (because the more a mesh normal faces the point of view, the more evident the specular effect is).

Then, using mixed procedural textures, we created the bump effect to perturb the surface of the object (note that the bump also affects the material's refraction).

#### See also

Here are some links to lists of IOR values that can be used in mixing the **Diffuse BSDF** component with the **Glossy BSDF** component through a **Fresnel** node:

- http://blenderartists.org/forum/showthread.php?71202-Material-IOR-Value-reference
- <a href="http://blenderartists.org/forum/showthread.php?117271-The-IOR-of-diferent-materials">http://blenderartists.org/forum/showthread.php?117271-The-IOR-of-diferent-materials</a>

The following is a computational and scientific search engine that allows you to quickly research the IOR of a given substance by typing its name:

• <a href="http://www.wolframalpha.com/">http://www.wolframalpha.com/</a>

# **Chapter 4. Creating Man-made Materials in Cycles**

In this chapter, we will cover the following recipes:

- Creating a generic plastic material
- Creating a Bakelite material
- Creating an expanded polystyrene material
- Creating a clear (glassy) polystyrene material
- Creating a rubber material
- Creating an antique bronze material with procedurals
- Creating a multipurpose metal node group
- Creating a rusty metal material with procedurals
- Creating a wood material with procedurals

# Introduction

On most occasions, artificial materials are quite easy to recreate in Cycles.

In the previous chapters we discussed the mechanics of building materials through procedural textures using the Cycles render engine. In this chapter, we'll discuss some artificial materials. Starting with one or two examples of simple materials, such as plastic, we will progress to more complex materials. We'll also take a look at the decayed material shaders and treat them as worn or rusty metals.

Note that in Cycles, it's not actually necessary to add the nodes for the texture mapping coordinates to any shader network. This is because, by default and if not otherwise specified, Cycles automatically uses the **Generated** mapping coordinates for procedural textures and any existing UV coordinate layer for the image textures.

Anyway, I think it's a good habit to add both the **Texture Coordinate** and the **Mapping** nodes to all the materials to permit easy reutilization of the shaders on different objects with different mapping options, scales, and locations.