

SDK API

Reference Manual

API Version 1.17



LEGAL DISCLAIMER

INFORMATION IN THIS DOCUMENT IS PROVIDED IN CONNECTION WITH INTEL PRODUCTS. NO LICENSE, EXPRESS OR IMPLIED, BY ESTOPPEL OR OTHERWISE, TO ANY INTELLECTUAL PROPERTY RIGHTS IS GRANTED BY THIS DOCUMENT. EXCEPT AS PROVIDED IN INTEL'S TERMS AND CONDITIONS OF SALE FOR SUCH PRODUCTS, INTEL ASSUMES NO LIABILITY WHATSOEVER AND INTEL DISCLAIMS ANY EXPRESS OR IMPLIED WARRANTY, RELATING TO SALE AND/OR USE OF INTEL PRODUCTS INCLUDING LIABILITY OR WARRANTIES RELATING TO FITNESS FOR A PARTICULAR PURPOSE, MERCHANTABILITY, OR INFRINGEMENT OF ANY PATENT, COPYRIGHT OR OTHER INTELLECTUAL PROPERTY RIGHT.

UNLESS OTHERWISE AGREED IN WRITING BY INTEL, THE INTEL PRODUCTS ARE NOT DESIGNED NOR INTENDED FOR ANY APPLICATION IN WHICH THE FAILURE OF THE INTEL PRODUCT COULD CREATE A SITUATION WHERE PERSONAL INJURY OR DEATH MAY OCCUR.

Intel may make changes to specifications and product descriptions at any time, without notice. Designers must not rely on the absence or characteristics of any features or instructions marked "reserved" or "undefined." Intel reserves these for future definition and shall have no responsibility whatsoever for conflicts or incompatibilities arising from future changes to them. The information here is subject to change without notice. Do not finalize a design with this information.

The products described in this document may contain design defects or errors known as errata which may cause the product to deviate from published specifications. Current characterized errata are available on request.

Contact your local Intel sales office or your distributor to obtain the latest specifications and before placing your product order.

Copies of documents which have an order number and are referenced in this document, or other Intel literature, may be obtained by calling 1-800-548-4725, or by visiting Intel's Web Site.

MPEG is an international standard for video compression/decompression promoted by ISO. Implementations of MPEG CODECs, or MPEG enabled platforms may require licenses from various entities, including Intel Corporation.

Intel and the Intel logo are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

*Other names and brands may be claimed as the property of others.

Copyright © 2007-2015, Intel Corporation. All Rights reserved.



Optimization Notice

Intel's compilers may or may not optimize to the same degree for non-Intel microprocessors for optimizations that are not unique to Intel microprocessors. These optimizations include SSE2, SSE3, and SSSE3 instruction sets and other optimizations. Intel does not guarantee the availability, functionality, or effectiveness of any optimization on microprocessors not manufactured by Intel.

Microprocessor-dependent optimizations in this product are intended for use with Intel microprocessors. Certain optimizations not specific to Intel microarchitecture are reserved for Intel microprocessors. Please refer to the applicable product User and Reference Guides for more information regarding the specific instruction sets covered by this notice.

Notice revision #20110804



Table of Contents

| Overview1 | 1 |
|-----------------------------|---|
| Document Conventions | 1 |
| Acronyms and Abbreviations | 1 |
| Architecture | 3 |
| Video Decoding | 4 |
| Video Encoding | 4 |
| Video Processing | 5 |
| Programming Guide | 9 |
| Status Codes | |
| SDK Session | |
| Multiple Sessions1 | |
| Frame and Fields 12 | |
| Frame Surface Locking1 | |
| Decoding Procedures | 2 |
| Bitstream Repositioning1 | 2 |
| Multiple Sequence Headers1 | 3 |
| Encoding Procedures | 4 |
| Configuration Change14 | 4 |
| Video Processing Procedures | 6 |
| Configuration1 | 7 |
| Region of Interest | 9 |



| Transcoding Procedures | 20 |
|---|----|
| Asynchronous Pipeline | 20 |
| Surface Pool Allocation | 21 |
| Pipeline Error Reporting | 22 |
| Working with hardware acceleration | 22 |
| Working with Microsoft* DirectX* Applications | 23 |
| Working with VA API Applications | 25 |
| Memory Allocation and External Allocators | 27 |
| Surface Type Neutral Transcoding | 29 |
| Hardware Device Error Handling | 32 |
| Function Reference | 33 |
| Global Functions | 33 |
| MFXCloneSession | 33 |
| MFXClose | 34 |
| MFXDoWork | 34 |
| MFXDisjoinSession | 35 |
| MFXGetPriority | 36 |
| MFXInit | 36 |
| MFXInitEx | 37 |
| MFXJoinSession | 38 |
| MFXQueryIMPL | 39 |
| MFXQueryVersion | 40 |
| MFXSetPriority | 40 |
| MFXVideoCORE | 41 |
| MFXVideoCORE_SetHandle | 41 |



| MFXVideoCORE_GetHandle | 42 |
|---------------------------------|----|
| MFXVideoCORE_SetBufferAllocator | 42 |
| MFXVideoCORE_SetFrameAllocator | 43 |
| MFXVideoCORE_SyncOperation | 44 |
| MFXVideoENCODE | 45 |
| MFXVideoENCODE_Query | 45 |
| MFXVideoENCODE_QueryIOSurf | 47 |
| MFXVideoENCODE_Init | 48 |
| MFXVideoENCODE_Reset | 48 |
| MFXVideoENCODE_Close | 49 |
| MFXVideoENCODE_GetVideoParam | 50 |
| MFXVideoENCODE_GetEncodeStat | 50 |
| MFXVideoENCODE_EncodeFrameAsync | 51 |
| MFXVideoENC | 53 |
| MFXVideoENC_Query | 53 |
| MFXVideoENC_QueryIOSurf | 54 |
| MFXVideoENC_Init | 55 |
| MFXVideoENC_Reset | 56 |
| MFXVideoENC_Close | 56 |
| MFXVideoENC_ProcessFrameAsync | 57 |
| MFXVideoDECODE | 58 |
| MFXVideoDECODE_DecodeHeader | 59 |
| MFXVideoDECODE_Query | 60 |
| MFXVideoDECODE_QueryIOSurf | 61 |
| MFXVideoDECODE_Init | 62 |
| MFXVideoDECODE_Reset | 63 |





| mfxExtBuffer | 84 |
|------------------------------|-----|
| mfxExtAVCRefListCtrl | 85 |
| mfxExtAVCRefLists | 87 |
| mfxExtCodingOption | 88 |
| mfxExtCodingOption2 | 92 |
| mfxExtCodingOption3 | 96 |
| mfxExtCodingOptionSPSPPS | 99 |
| mfxExtOpaqueSurfaceAlloc | 101 |
| mfxExtVideoSignalInfo | 102 |
| mfxExtPictureTimingSEI | 103 |
| mfxExtAvcTemporalLayers | 104 |
| mfxExtVppAuxData | 105 |
| mfxExtVPPDenoise | 106 |
| mfxExtVPPDetail | 107 |
| mfxExtVPPDoNotUse | 108 |
| mfxExtVPPDoUse | 108 |
| mfxExtVPPFrameRateConversion | 109 |
| mfxExtVPPProcAmp | 110 |
| mfxExtVPPImageStab | 111 |
| mfxExtVPPComposite | 112 |
| mfxExtVPPVideoSignalInfo | 115 |
| mfxExtEncoderCapability | 116 |
| mfxExtEncoderResetOption | 116 |



| mfxExtAVCEncodedFrameInfo | 118 |
|---------------------------|-----|
| mfxExtEncoderROI | 119 |
| mfxExtVPPDeinterlacing | 120 |
| mfxFrameAllocator | 121 |
| Alloc | 122 |
| Free | 123 |
| Lock | 124 |
| Unlock | 124 |
| GetHDL | 125 |
| mfxFrameAllocRequest | 126 |
| mfxFrameAllocResponse | 127 |
| mfxFrameData | 127 |
| mfxFrameInfo | 130 |
| mfxFrameSurface1 | 132 |
| mfxInfoMFX | 133 |
| mfxInfoVPP | 138 |
| mfxInitParam | 139 |
| mfxPayload | 140 |
| mfxVersion | 141 |
| mfxVideoParam | 142 |
| mfxVPPStat | 143 |
| mfxENCInput | 144 |
| mfxENCOutput | 145 |
| mfxExtLAControl | 145 |



| | mfxExtLAFrameStatistics | .147 |
|---|--------------------------|------|
| | mfxExtVPPFieldProcessing | .148 |
| | mfxExtMBQP | .149 |
| | mfxExtChromaLocInfo | .151 |
| | mfxExtHEVCTiles | .151 |
| | mfxExtMBDisableSkipMap | .152 |
| | mfxExtDecodedFrameInfo | .153 |
| | mfxExtTimeCode | .153 |
| | mfxExtHEVCRegion | .154 |
| | mfxExtThreadsParam | .155 |
| | mfxExtHEVCParam | .155 |
| | mfxExtPredWeightTable | .156 |
| | mfxExtDirtyRect | .157 |
| | mfxExtMoveRect | .158 |
| | mfxExtCodingOptionVPS | .159 |
| | mfxExtVPPRotation | .160 |
| E | Enumerator Reference | 162 |
| | BitstreamDataFlag | .162 |
| | ChromaFormatIdc | .162 |
| | CodecFormatFourCC | .163 |
| | CodecLevel | .163 |
| | CodecProfile | .165 |
| | CodingOptionValue | .166 |



| ColorFourCC | 166 |
|------------------------|-----|
| Corruption | 168 |
| ExtendedBufferID | 169 |
| ExtMemBufferType | 173 |
| ExtMemFrameType | 174 |
| FrameDataFlag | 175 |
| FrameType | 175 |
| FrcAlgm | 176 |
| GopOptFlag | 177 |
| IOPattern | 177 |
| mfxHandleType | 178 |
| mfxIMPL | 179 |
| mfxPriority | 181 |
| mfxSkipMode | 181 |
| mfxStatus | 182 |
| PicStruct | 184 |
| RateControlMethod | 186 |
| TimeStampCalc | 187 |
| TargetUsage | 188 |
| TrellisControl | 189 |
| BRefControl | 189 |
| LookAheadDownSampling | 190 |
| VPPFieldProcessingMode | 190 |



| | PicType | .191 |
|---|---|------|
| | SkipFrame | .191 |
| | DeinterlacingMode | .192 |
| | TelecinePattern | .193 |
| | HEVCRegionType | .193 |
| | GPUCopy | .193 |
| | WeightedPred | .194 |
| | ScenarioInfo | .194 |
| | ContentInfo | .195 |
| | PRefType | .195 |
| | GeneralConstraintFlags | .196 |
| | Angle | .196 |
| Д | ppendices | 198 |
| | Appendix A: Configuration Parameter Constraints | |
| | Appendix B: Multiple-Segment Encoding | |
| | Appendix C: Streaming and Video Conferencing Features | |
| | Dynamic Bitrate Change | |
| | Dynamic resolution change | 206 |
| | Forced Key Frame Generation | 206 |
| | Reference List Selection | 206 |
| | Low Latency Encoding and Decoding | 207 |
| | Reference Picture Marking Repetition SEI message | 207 |
| | Long-term Reference frame | 208 |
| | Temporal scalability | 208 |



| Appendix D: Switchable Graphics and Multiple Monitors | 209 |
|---|-----|
| Switchable Graphics | 209 |
| Multiple Monitors | 210 |
| Appendix E: Working directly with VA API for Linux* | 211 |
| Appendix F: CQP HRD mode encoding | 213 |



Overview

Intel® Media Server Studio – SDK and Intel® Integrated Native Developer Experience Media SDK for Windows*, further referred to as the SDK, is a software development library that exposes the media acceleration capabilities of Intel platforms for decoding, encoding and video processing. The API library covers a wide range of Intel platforms.

This document describes the SDK API.

Document Conventions

The SDK API uses the Verdana typeface for normal prose. With the exception of section headings and the table of contents, all code-related items appear in the <code>Courier New</code> typeface (<code>mxfStatus</code> and <code>MFXInit</code>). All class-related items appear in all cap boldface, such as **DECODE** and **ENCODE**. Member functions appear in initial cap boldface, such as **Init** and **Reset**, and these refer to members of all three classes, **DECODE**, **ENCODE** and **VPP**. Hyperlinks appear in underlined boldface, such as <code>mfxStatus</code>.

Acronyms and Abbreviations

| API | Application Programming Interface |
|------------|--|
| AVC | Advanced Video Codec (same as H.264 and MPEG-4, part 10) |
| Direct3D | Microsoft* Direct3D* version 9 or 11.1 |
| Direct3D9 | Microsoft* Direct3D* version 9 |
| Direct3D11 | Microsoft* Direct3D* version 11.1 |
| DXVA2 | Microsoft DirectX* Video Acceleration standard 2.0 |
| H.264 | ISO*/IEC* 14496-10 and ITU-T* H.264, MPEG-4 Part 10, Advanced Video Coding, May 2005 |
| HRD | Hypothetical Reference Decoder |
| IDR | Instantaneous decoding fresh picture, a term used in the H.264 specification |
| LA | Look Ahead. Special encoding mode where encoder performs pre analysis of several frames before actual encoding starts. |
| MPEG | Motion Picture Expert Group |
| MPEG-2 | ISO/IEC 13818-2 and ITU-T H.262, MPEG-2 Part 2, Information Technology- Generic Coding of Moving Pictures and Associate Audio Information: Video, 2000 |
| NAL | Network Abstraction Layer |
| NV12 | A color format for raw video frames |
| PPS | Picture Parameter Set |



QP Quantization Parameter

RGB3 Twenty-four-bit RGB color format. Also known as RGB24
RGB4 Thirty-two-bit RGB color format. Also known as RGB32

SDK Intel® Media Server Studio – SDK and Intel® Integrated Native Developer

Environment Media SDK for Windows*

SEI Supplemental Enhancement Information

SPS Sequence Parameter Set
VA API Video Acceleration API

VBR Variable Bit Rate

VBV Video Buffering Verifier

VC-1 SMPTE* 421M, SMPTE Standard for Television: VC-1 Compressed Video

Bitstream Format and Decoding Process, August 2005

video memory memory used by hardware acceleration device, also known as GPU, to hold

frame and other types of video data

VPP Video Processing

VUI Video Usability Information

YV12 A color format for raw video frames
YV12 A color format for raw video frames



Architecture

SDK functions fall into the following categories:

DECODE Decode compressed video streams into raw video frames

ENCODE Encode raw video frames into compressed bitstreams

VPP Perform video processing on raw video frames

CORE Auxiliary functions for synchronization

Misc Global auxiliary functions

With the exception of the global auxiliary functions, SDK functions are named after their functioning domain and category, as illustrated in Figure 1. Here, SDK only exposes video domain functions.




Figure 1: SDK Function Naming Convention

Applications use SDK functions by linking with the SDK dispatcher library, as illustrated in Figure 2. The dispatcher library identifies the hardware acceleration device on the running platform, determines the most suitable platform library, and then redirects function calls. If the dispatcher is unable to detect any suitable platform-specific hardware, the dispatcher redirects SDK function calls to the default software library.




Figure 2: SDK Library Dispatching Mechanism



Video Decoding

The **DECODE** class of functions takes a compressed bitstream as input and converts it to raw frames as output.

DECODE processes only pure or elementary video streams. The library cannot process bitstreams that reside in a container format, such as MP4 or MPEG. The application must first de-multiplex the bitstreams. De-multiplexing extracts pure video streams out of the container format. The application can provide the input bitstream as one complete frame of data, less than one frame (a partial frame), or multiple frames. If only a partial frame is provided, **DECODE** internally constructs one frame of data before decoding it.

The time stamp of a bitstream buffer must be accurate to the first byte of the frame data. That is, the first byte of a video coding layer NAL unit for H.264, or picture header for MPEG-2 and VC-1. **DECODE** passes the time stamp to the output surface for audio and video multiplexing or synchronization.

Decoding the first frame is a special case, since **DECODE** does not provide enough configuration parameters to correctly process the bitstream. **DECODE** searches for the sequence header (a sequence parameter set in H.264, or a sequence header in MPEG-2 and VC-1) that contains the video configuration parameters used to encode subsequent video frames. The decoder skips any bitstream prior to that sequence header. In the case of multiple sequence headers in the bitstream, **DECODE** adopts the new configuration parameters, ensuring proper decoding of subsequent frames.

DECODE supports repositioning of the bitstream at any time during decoding. Because there is no way to obtain the correct sequence header associated with the specified bitstream position after a position change, the application must supply **DECODE** with a sequence header before the decoder can process the next frame at the new position. If the sequence header required to correctly decode the bitstream at the new position is not provided by the application, **DECODE** treats the new location as a new "first frame" and follows the procedure for decoding first frames.

Video Encoding

The **ENCODE** class of functions takes raw frames as input and compresses them into a bitstream.

Input frames usually come encoded in a repeated pattern called the Group of Picture (GOP) sequence. For example, a GOP sequence can start from an I-frame, followed by a few B-frames, a P-frame, and so on. **ENCODE** uses an MPEG-2 style GOP sequence structure that can specify the length of the sequence and the distance between two key frames: I- or P-frames. A GOP sequence ensures that the segments of a bitstream do not completely depend upon each other. It also enables decoding applications to reposition the bitstream.

ENCODE processes input frames in two ways:

<u>Display order</u>: **ENCODE** receives input frames in the display order. A few GOP structure parameters specify the GOP sequence during **ENCODE** initialization. Scene change results from the video processing stage of a pipeline can alter the GOP sequence.

<u>Encoded order</u>: **ENCODE** receives input frames in their encoding order. The application must specify the exact input frame type for encoding. **ENCODE** references GOP parameters to determine when to insert information such as an end-of-sequence into the bitstream.



An **ENCODE** output consists of one frame of a bitstream with the time stamp passed from the input frame. The time stamp is used for multiplexing subsequent video with other associated data such as audio. The SDK library provides only pure video stream encoding. The application must provide its own multiplexing.

ENCODE supports the following bitrate control algorithms: constant bitrate, variable bitrate (VBR), and constant Quantization Parameter (QP). In the constant bitrate mode, **ENCODE** performs stuffing when the size of the least-compressed frame is smaller than what is required to meet the Hypothetical Reference Decoder (HRD) buffer (or VBR) requirements. (Stuffing is a process that appends zeros to the end of encoded frames.)

Video Processing

Video processing (VPP) takes raw frames as input and provides raw frames as output.



Figure 3: Video Processing Operation Pipeline

The actual conversion process is a chain operation with many single-function filters, as Figure 3 illustrates. The application specifies the input and output format, and the SDK configures the pipeline accordingly. The application can also attach one or more hint structures to configure individual filters or turn them on and off. Unless specifically instructed, the SDK builds the pipeline in a way that best utilizes hardware acceleration or generates the best video processing quality.

Table 1 shows the SDK video processing features. The application can configure supported video processing features through the video processing I/O parameters. The application can also configure optional features through hints. See "Video Processing procedure / Configuration" for more details on how to configure optional filters.



Table 1: Video Processing Features

| Video Processing Features | Configuration |
|---|-------------------------|
| Convert color format from input to output (See | I/O parameters |
| Table 2 for supported conversions) | |
| De-interlace to produce progressive frames at the output (See The SDK video processing pipeline supports limited functionality for RGB4 input. Only filters that are required to convert input format to output one are included in pipeline. All optional filters are skipped. See description of MFX_WRN_FILTER_SKIPPED warning for more details on how to retrieve list of active filters. | I/O parameters |
| Table 3 for supported conversions) | |
| Crop and resize the input frames to meet the output resolution and region of display | I/O parameters |
| Convert input frame rate to match the output | I/O parameters |
| Perform inverse telecine operations | I/O parameters |
| Remove noise | hint (optional feature) |
| Enhance picture details/edges | hint (optional feature) |
| Adjust the brightness, contrast, saturation, and hue settings | hint (optional feature) |
| Perform image stabilization | hint (optional feature) |
| Convert input frame rate to match the output, based on frame interpolation | hint (optional feature) |
| Perform detection of picture structure | hint (optional feature) |



Table 2: Color Conversion Support in VPP

| Output Color Input Color | NV12 | RGB32 | P010 | P210 | NV16 | A2RGB10 |
|--------------------------|--------------|--------------|------|------|------|---------|
| RGB4 (RGB32) | X limited | X Limited | | | | |
| NV12 | X | Х | Х | | X | |
| YV12 | Х | Х | | | | |
| UYVY | Х | | | | | |
| YUY2 | Х | Х | | | | |
| P010 | Х | | Х | Х | | Х |
| P210 | Х | | Х | Х | Х | Х |
| NV16 | Х | | | Х | Х | |

X indicates a supported function

The SDK video processing pipeline supports limited functionality for RGB4 input. Only filters that are required to convert input format to output one are included in pipeline. All optional filters are skipped. See description of MFX WRN FILTER SKIPPED warning for more details on how to retrieve list of active filters.

Table 3: Deinterlacing/Inverse Telecine Support in VPP

| Input Field Rate (fps) | Output Frame Rate (fps) Progressive | | | | | | |
|---------------------------|-------------------------------------|----|-------|----|----|-------|----|
| Interlaced | 23.976 | 25 | 29.97 | 30 | 50 | 59.94 | 60 |
| 29.97 | Inverse Telecine | | Х | | | | |
| 50 | | Х | | | Х | | |
| 59.94 | | | Χ | | | Χ | |
| 60 | | | | Х | | | Χ |

X indicates a supported function.

This table describes pure deinterlacing algorithm. The application can combine it with frame rate conversion to achieve any desirable input/output frame rate ratio. Note, that in this table input rate is field rate, i.e. number of video fields in one second of video. The SDK uses frame rate in all configuration parameters, so this input field rate should be divided by two during the SDK configuration. For example, 60i to 60p conversion in this table is represented by right bottom cell. It should be described in mfxVideoParam as input frame rate equal to 30 and output 60.



SDK support two HW-accelerated deinterlacing algorithms: BOB DI (in Linux's libVA terms VAProcDeinterlacingBob) and Advanced DI (VAProcDeinterlacingMotionAdaptive). Default is ADI (Advanced DI) which uses reference frames and has better quality. BOB DI is faster than ADI mode. So user can select as usual between speed and quality.

User can exactly configure DI modes via mfxExtVPPDeinterlacing.

There is one special mode of deinterlacing available in combination with frame rate conversion. If VPP input frame is interlaced (TFF or BFF) and output is progressive and ratio between source frame rate and destination frame rate is ½ (for example 30 to 60, 29.97 to 59.94, 25 to 50), special mode of VPP turned on: for 30 <u>interlaced</u> input frames application will get 60 <u>different progressive</u> output frames.

Table 4: Color formats supported by VPP filters

| Color | RGB4 (RGB32) | NV12 | YV12 | YUY2 | P010 | P210 | NV16 |
|--|-----------------|------|------|------|------|------|------|
| Denoise | | Χ | | | | | |
| Deinterlace | | Χ | | | | | |
| Image stabilization | | Х | | | | | |
| Frame rate conversion | | Х | | | | | |
| Resize | | Х | | | Х | Х | Х |
| Detail | | Х | | | | | |
| Color conversion (see table 2 for details) | Х | Х | Х | Х | Х | Х | Х |
| Composition | Х | Х | | | | | |
| Field copy | | Х | | | | | |

X indicates a supported function



Programming Guide

This chapter describes the concepts used in programming the SDK.

The application must use the include file, mfxvideo.h (for C programming), or mfxvideo++.h (for C++ programming), and link the SDK static dispatcher library, libmfx.lib or libmfx.a. If the application is written in C then libstdc++.a library should also be linked.

On Linux* there is slight difference between using dispatcher library from executable module or from shared object. To mitigate symbol conflict between itself and SDK shared object on Linux*, application should:

- 1. link against dispatch shared.a instead of libmfx.a
- 2. define MFX DISPATCHER EXPOSED PREFIX before any SDK includes

Status Codes

The SDK functions organize into classes for easy reference. The classes include **ENCODE** (encoding functions), **DECODE** (decoding functions), and **VPP** (video processing functions).

Init, **Reset** and **Close** are member functions within the **ENCODE**, **DECODE** and **VPP** classes that initialize, restart and de-initialize specific operations defined for the class. Call all other member functions within a given class (except **Query** and **QueryIOSurf**) within the **Init** ... **Reset** (optional) ... **Close** sequence.

The **Init** and **Reset** member functions both set up necessary internal structures for media processing. The difference between the two is that the **Init** functions allocate memory while the **Reset** functions only reuse allocated internal memory. Therefore, **Reset** can fail if the SDK needs to allocate additional memory. **Reset** functions can also fine-tune **ENCODE** and **VPP** parameters during those processes or reposition a bitstream during **DECODE**.

All SDK functions return status codes to indicate whether an operation succeeded or failed. See the <u>mfxStatus</u> enumerator for all defined status codes. The status code <u>MFX ERR NONE</u> indicates that the function successfully completed its operation. Status codes are less than <u>MFX ERR NONE</u> for all errors and greater than <u>MFX ERR NONE</u> for all warnings.



If an SDK function returns a warning, it has sufficiently completed its operation, although the output of the function might not be strictly reliable. The application must check the validity of the output generated by the function.

If an SDK function returns an error (except MFX ERR MORE DATA OR MFX ERR MORE SURFACE OR MFX ERR MORE BITSTREAM), the function aborts the operation. The application must call either the **Reset** function to put the class back to a clean state, or the **Close** function to terminate the operation. The behavior is undefined if the application continues to call any class member functions without a **Reset** or **Close**. To avoid memory leaks, always call the **Close** function after **Init**.

SDK Session

Before calling any SDK functions, the application must initialize the SDK library and create an SDK session. An SDK session maintains context for the use of any of **DECODE**, **ENCODE**, or **VPP** functions.

The function <u>MFXInit</u> starts (initializes) an SDK session. <u>MFXClose</u> closes (de-initializes) the SDK session. To avoid memory leaks, always call <u>MFXClose</u> after <u>MFXInit</u>.

The application can initialize a session as a software-based session (MFX IMPL SOFTWARE) or a hardware-based session (MFX IMPL HARDARE,). In the former case, the SDK functions execute on a CPU, and in the latter case, the SDK functions use platform acceleration capabilities. For platforms that expose multiple graphic devices, the application can initialize the SDK session on any alternative graphic device (MFX IMPL HARDWARE1...MFX IMPL HARDWARE4).

The application can also initialize a session to be automatic (MFX IMPL AUTO OR MFX IMPL AUTO ANY), instructing the dispatcher library to detect the platform capabilities and choose the best SDK library available. After initialization, the SDK returns the actual implementation through the MFXQueryIMPL function.

Multiple Sessions

Each SDK session can run exactly one instance of **DECODE**, **ENCODE** and **VPP** functions. This is good for a simple transcoding operation. If the application needs more than one instance of **DECODE**, **ENCODE** and **VPP** in a complex transcoding setting, or needs more simultaneous transcoding operations to balance CPU/GPU workloads, the application can initialize multiple SDK sessions. Each SDK session can independently be a software-based session or hardware-based session.

The application can use multiple SDK sessions independently or run a "joined" session. Independently operated SDK sessions cannot share data unless the application explicitly synchronizes session operations (to ensure that data is valid and complete before passing from the source to the destination session.)

To join two sessions together, the application can use the function MFXJoinSession.

Alternatively, the application can use the function MFXCloneSession to duplicate an existing session. Joined SDK sessions work together as a single session, sharing all session resources, threading control and prioritization operations (except hardware acceleration devices and external allocators). When joined, one of the sessions (the first join) serves as a parent session, scheduling execution resources, with all others child sessions relying on the parent session for resource management.



With joined sessions, the application can set the priority of session operations through the <u>MFXSetPriority</u> function. A lower priority session receives less CPU cycles. Session priority does not affect hardware accelerated processing.

After the completion of all session operations, the application can use the function MFXDisjoinSession to remove the joined state of a session. Do not close the parent session until all child sessions are disjoined or closed.

Frame and Fields

In SDK terminology, a frame (or frame surface, interchangeably) contains either a progressive frame or a complementary field pair. If the frame is a complementary field pair, the odd lines of the surface buffer store the top fields and the even lines of the surface buffer store the bottom fields.

Frame Surface Locking

During encoding, decoding or video processing, cases arise that require reserving input or output frames for future use. In the case of decoding, for example, a frame that is ready for output must remain as a reference frame until the current sequence pattern ends. The usual approach is to cache the frames internally. This method requires a copy operation, which can significantly reduce performance.

SDK functions define a frame-locking mechanism to avoid the need for copy operations. This mechanism is as follows:

- 1. The application allocates a pool of frame surfaces large enough to include SDK function I/O frame surfaces and internal cache needs. Each frame surface maintains a Locked counter, part of the mfxFrameData structure. Initially, the Locked counter is set to zero.
- 2. The application calls an SDK function with frame surfaces from the pool, whose Locked counter is zero. If the SDK function needs to reserve any frame surface, the SDK function increases the Locked counter of the frame surface. A non-zero Locked counter indicates that the calling application must treat the frame surface as "in use." That is, the application can read, but cannot alter, move, delete or free the frame surface.
- 3. In subsequent SDK executions, if the frame surface is no longer in use, the SDK decreases the Locked counter. When the Locked counter reaches zero, the application is free to do as it wishes with the frame surface.

In general, the application must not increase or decrease the Locked counter, since the SDK manages this field. If, for some reason, the application needs to modify the Locked counter, the operation must be atomic to avoid race condition. **Modifying the Locked counter is not recommended.**



Decoding Procedures

Example 1 shows the pseudo code of the decoding procedure. The following describes a few key points:

- The application can use the <u>MFXVideoDECODE DecodeHeader</u> function to retrieve decoding initialization parameters from the bitstream. This step is optional if such parameters are retrievable from other sources such as an audio/video splitter.
- The application uses the <u>MFXVideoDECODE QueryIOSurf</u> function to obtain the number of working frame surfaces required to reorder output frames.
- The application calls the MFXVideoDECODE DecodeFrameAsync function for a decoding operation, with the bitstream buffer (bits), and an unlocked working frame surface (work) as input parameters. If decoding output is not available, the function returns a status code requesting additional bitstream input or working frame surfaces as follows:

MFX ERR MORE DATA: The function needs additional bitstream input. The existing buffer contains less than a frame worth of bitstream data.

MFX ERR MORE SURFACE: The function needs one more frame surface to produce any output.

- Upon successful decoding, the MFX ERR NONE. However, the decoded frame data (identified by the disp pointer) is not yet available because the MFXVideoDECODE DecodeFrameAsync function is asynchronous. The application must use the MFXVideoCORE SyncOperation function to synchronize the decoding operation before retrieving the decoded frame data.
- At the end of the bitstream, the application continuously calls the
 MFXVideoDECODE DecodeFrameAsync function with a NULL bitstream pointer to drain any remaining frames cached within the SDK decoder, until the function returns
 MFX ERR MORE DATA.

Bitstream Repositioning

The application can use the following procedure for bitstream reposition during decoding:

- 1. Use the MFXVideoDECODE Reset function to reset the SDK decoder.
- 2. Optionally, if the application maintains a sequence header that decodes correctly the bitstream at the new position, the application may insert the sequence header to the bitstream buffer.
- 3. Append the bitstream from the new location to the bitstream buffer.
- 4. Resume the decoding procedure. If the sequence header is not inserted in the above steps, the SDK decoder searches for a new sequence header before starting decoding.



```
MFXVideoDECODE DecodeHeader(session, bitstream, &init param);
MFXVideoDECODE QueryIOSurf(session, &init param, &request);
allocate pool of frame surfaces (request. NumFrameSuggested);
MFXVideoDECODE Init(session, &init param);
sts=MFX ERR MORE DATA;
for (;;) {
      if (sts==MFX ERR MORE DATA && !end of stream())
            append more bitstream (bitstream);
      find unlocked surface from the pool(&work);
      bits=(end of stream())?NULL:bitstream;
      sts=MFXVideoDECODE DecodeFrameAsync(session,bits,work,&disp,&syncp);
      if (sts==MFX ERR MORE SURFACE) continue;
      if (end of bitstream() && sts==MFX ERR MORE DATA) break;
      ... // other error handling
      if (sts==MFX ERR NONE) {
            MFXVideoCORE SyncOperation(session, syncp, INFINITE);
            do something with decoded frame (disp);
      }
MFXVideoDECODE Close();
free pool of frame surfaces();
```

Example 1: Decoding Pseudo Code

Multiple Sequence Headers

The bitstream can contain multiple sequence headers. The SDK function returns a status code to indicate when a new sequence header is parsed.

The <u>MFXVideoDECODE DecodeFrameAsync</u> function returns <u>MFX WRN VIDEO PARAM CHANGED</u> if the SDK decoder parsed a new sequence header in the bitstream and decoding can continue with existing frame buffers. The application can optionally retrieve new video parameters by calling <u>MFXVideoDECODE GetVideoParam</u>.

The MFXVideoDECODE DecodeFrameAsync function returns

MFX ERR INCOMPATIBLE VIDEO PARAM if the decoder parsed a new sequence header in the bitstream and decoding cannot continue without reallocating frame buffers. The bitstream pointer moves to the first bit of the new sequence header. The application must do the following:

1. Retrieve any remaining frames by calling <u>MFXVideoDECODE DecodeFrameAsync</u> with a NULL input bitstream pointer until the function returns <u>MFX ERR MORE DATA</u>. This step is not necessary if the application plans to discard any remaining frames.



2. De-initialize the decoder by calling the <u>MFXVideoDECODE Close</u> function, and restart the decoding procedure from the new bitstream position.

Encoding Procedures

Example 2 shows the pseudo code of the encoding procedure. The following describes a few key points:

- The application uses the <u>MFXVideoENCODE QueryIOSurf</u> function to obtain the number of working frame surfaces required for reordering input frames.
- The application calls the MFXVideoENCODE EncodedFrameAsync function for the encoding operation. The input frame must be in an unlocked frame surface from the frame surface pool. If the encoding output is not available, the function returns the status code MFX ERR MORE DATA to request additional input frames.
- Upon successful encoding, the <u>MFXVideoENCODE EncodeFrameAsync</u> function returns <u>MFX ERR NONE</u>. However, the encoded bitstream is not yet available because the <u>MFXVideoENCODE EncodeFrameAsync</u> function is asynchronous. The application must use the <u>MFXVideoCORE SyncOperation</u> function to synchronize the encoding operation before retrieving the encoded bitstream.
- At the end of the stream, the application continuously calls the
 MFXVideoENCODE EncodeFrameAsync function with NULL surface pointer to drain any remaining bitstreams cached within the SDK encoder, until the function returns
 MFX ERR MORE DATA.

Configuration Change

The application changes configuration during encoding by calling MFXVideoENCODE Reset function. Depending on difference in configuration parameters before and after change, the SDK encoder either continues current sequence or starts a new one. If the SDK encoder starts a new sequence it completely resets internal state and begins a new sequence with IDR frame.

The application controls encoder behavior during parameter change by attaching

mfxExtEncoderResetOption to mfxVideoParam structure during reset. By using this structure,
the application instructs encoder to start or not to start a new sequence after reset. In some
cases request to continue current sequence cannot be satisfied and encoder fails during reset.
To avoid such cases the application may query reset outcome before actual reset by calling

MFXVideoENCODE Query function with mfxExtEncoderResetOption attached to mfxVideoParam
structure.

The application uses the following procedure to change encoding configurations:



1. The application retrieves any cached frames in the SDK encoder by calling the MFXVideoENCODE_EncodeFrameAsync function with a NULL input frame pointer until the function returns MFX ERR MORE DATA.

Note: The application must set the initial encoding configuration flag <code>EndOfStream</code> of the <code>mfxExtCodingOption</code> structure to <code>OFF</code> to avoid inserting an End of Stream (EOS) marker into the bitstream. An EOS marker causes the bitstream to terminate before encoding is complete.

- 2. The application calls the MFXVideoENCODE Reset function with the new configuration:
 - If the function successfully set the configuration, the application can continue encoding as usual.
 - If the new configuration requires a new memory allocation, the function returns MFX ERR INCOMPATIBLE VIDEO PARAM. The application must close the SDK encoder and reinitialize the encoding procedure with the new configuration.

```
MFXVideoENCODE QueryIOSurf(session, &init param, &request);
allocate pool of frame surfaces (request.NumFrameSuggested);
MFXVideoENCODE Init(session, &init param);
sts=MFX ERR MORE DATA;
for (;;) {
      if (sts==MFX ERR MORE DATA && !end of stream()) {
            find unlocked surface from the pool(&surface);
            fill content for encoding(surface);
      surface2=end of stream()?NULL:surface;
      sts=MFXVideoENCODE EncodeFrameAsync(session,NULL,surface2,bits,&syncp);
      if (end of stream() && sts==MFX ERR MORE DATA) break;
      ... // other error handling
      if (sts==MFX ERR NONE) {
            MFXVideoCORE SyncOperation(session, syncp, INFINITE);
            do something with encoded bits(bits);
MFXVideoENCODE Close();
free pool of frame surfaces();
```

Example 2: Encoding Pseudo Code



Video Processing Procedures

16

Example 3 shows the pseudo code of the video processing procedure. The following describes a few key points:

- The application uses the <u>MFXVideoVPP QueryIOSurf</u> function to obtain the number of frame surfaces needed for input and output. The application must allocate two frame surface pools, one for the input and the other for the output.
- The video processing function <u>MFXVideoVPP RunFrameVPPAsync</u> is asynchronous. The application must synchronize to make the output result ready, through the <u>MFXVideoCORE SyncOperation</u> function.
- The body of the video processing procedures covers three scenarios as follows:
 - If the number of frames consumed at input is equal to the number of frames generated at output, **VPP** returns **MFX ERR NONE** when an output is ready. The application must process the output frame after synchronization, as the **MFXVideoVPP RunFrameVPPAsync** function is asynchronous. At the end of a sequence, the application must provide a NULL input to drain any remaining frames.
 - If the number of frames consumed at input is more than the number of frames generated at output, VPP returns MFX ERR MORE DATA for additional input until an output is ready. When the output is ready, VPP returns MFX ERR NONE. The application must process the output frame after synchronization and provide a NULL input at the end of sequence to drain any remaining frames.
 - If the number of frames consumed at input is less than the number of frames generated at output, **VPP** returns either <u>MFX ERR MORE SURFACE</u> (when more than one output is ready), or <u>MFX ERR NONE</u> (when one output is ready and **VPP** expects new input). In both cases, the application must process the output frame after synchronization and provide a <u>NULL</u> input at the end of sequence to drain any remaining frames.



```
MFXVideoVPP QueryIOSurf(session, &init param, response);
allocate pool of surfaces(in pool, response[0].NumFrameSuggested);
allocate_pool_of_surfaces(out_pool, response[1].NumFrameSuggested);
MFXVideoVPP Init(session, &init param);
in=find unlocked surface and fill content(in pool);
out=find unlocked surface from the pool(out pool);
for (;;) {
      sts=MFXVideoVPP RunFrameVPPAsync(session,in,out,aux,&syncp);
      if (sts==MFX ERR MORE SURFACE || sts==MFX ERR NONE) {
            MFXVideoCore SyncOperation(session, syncp, INFINITE);
            process output frame (out);
            out=find unlocked surface from the pool(out pool);
      }
      if (sts==MFX ERR MORE DATA && in==NULL) break;
      if (sts==MFX ERR NONE || sts==MFX ERR MORE DATA) {
            in=find unlocked surface(in pool);
            fill_content_for_video_processing(in);
            if (end of input sequence()) in=NULL;
MFXVideoVPP Close(session);
free pool of surfaces (in pool);
free pool of surfaces (out pool);
```

Example 3: Video Processing Pseudo Code

Configuration

The SDK configures the video processing pipeline operation based on the difference between the input and output formats, specified in the mfxVideoParam structure. A few examples follow:

- When the input color format is YUY2 and the output color format is NV12, the SDK enables color conversion from YUY2 to NV12.
- When the input is interleaved and the output is progressive, the SDK enables deinterlacing.

In addition to specifying the input and output formats, the application can provide hints to fine-tune the video processing pipeline operation. The application can disable filters in pipeline by using mfxExtVPPDoNotUse structure; enable them by using mfxExtVPPDoUse structure and configure them by using dedicated configuration structures. See Table 4 for complete list of configurable video processing filters, their IDs and configuration structures. See the ExtendedBufferID enumerator for more details.

The SDK ensures that all filters necessary to convert input format to output one are included in pipeline. However, the SDK can skip some optional filters even if they are explicitly requested by the application, for example, due to limitation of underlying hardware. To notify application about this skip, the SDK returns warning MFX_WRN_FILTER_SKIPPED. The application can retrieve list of active filters by attaching mfxExtVPPDoUse structure to mfxVideoParam structure and calling MFXVideoVPP GetVideoParam function. The application must allocate enough memory for filter list.



Table 4 Configurable VPP filters

| Filter ID | Configuration structure |
|---------------------------------------|---------------------------------|
| MFX_EXTBUFF_VPP_DENOISE | <u>mfxExtVPPDenoise</u> |
| MFX_EXTBUFF_VPP_DETAIL | mfxExtVPPDetail |
| MFX_EXTBUFF_VPP_FRAME_RATE_CONVERSION | mfxExtVPPFrameRateConversion |
| MFX_EXTBUFF_VPP_IMAGE_STABILIZATION | mfxExtVPPImageStab |
| MFX_EXTBUFF_VPP_PICSTRUCT_DETECTION | none |
| MFX_EXTBUFF_VPP_PROCAMP | mfxExtVPPProcAmp |
| MFX_EXTBUFF_VPP_FIELD_PROCESSING | <u>mfxExtVPPFieldProcessing</u> |

Example 4 shows how to configure the SDK video processing.

```
/* enable image stabilization filter with default settings */
mfxExtVPPDoUse du;
mfxU32 al=MFX_EXTBUFF_VPP_IMAGE_STABILIZATION;
du.Header.BufferId=MFX EXTBUFF VPP DOUSE;
du.Header.BufferSz=sizeof(mfxExtVPPDoUse);
du.NumAlg=1;
du.AlqList=&al;
/* configure the mfxVideoParam structure */
mfxVideoParam conf;
mfxExtBuffer *eb=&du;
memset(&conf,0,sizeof(conf));
conf.IOPattern=MFX IOPATTERN IN SYSTEM MEMORY|
               MFX IOPATTERN OUT SYSTEM MEMORY;
conf.NumExtParam=1;
conf.ExtParam=&eb;
conf.vpp.In.FourCC=MFX FOURCC YV12;
conf.vpp.Out.FourCC=MFX FOURCC NV12;
conf.vpp.In.Width=conf.vpp.Out.Width=1920;
conf.vpp.In.Height=conf.vpp.Out.Height=1088;
/* video processing initialization */
MFXVideoVPP Init(session, &conf);
```

Example 4: Configure Video Processing



Region of Interest

During video processing operations, the application can specify a region of interest for each frame, as illustrated in Figure 4.




Figure 4: VPP Region of Interest Operation

Specifying a region of interest guides the resizing function to achieve special effects such as resizing from 16:9 to 4:3 while keeping the aspect ratio intact. Use the <code>CropX</code>, <code>CropY</code>, <code>CropW</code> and <code>CropH</code> parameters in the <code>mfxVideoParam</code> structure to specify a region of interest. Table 5 shows some examples.

Table 5: Examples of VPP Operations on Region of Interest

| | VPP I | input | VPP Output | | |
|---|--------------|-------------------------------------|--------------|-------------------------------|--|
| Operation | Width/Height | CropX, CropY, CropW, CropH | Width/Height | CropX, CropY, CropW, CropH | |
| Cropping | 720x480 | 16,16,688,448 | 720x480 | 16,16,688,448 | |
| Resizing | 720x480 | 0,0,720,480 | 1440×960 | 0,0,1440,960 | |
| Horizontal stretching | 720x480 | 0,0,720,480 | 640x480 | 0,0,640,480 | |
| 16:9 → 4:3 with letter boxing at the top and bottom | 1920×1088 | 0,0,1920,1088 | 720x480 | 0,36,720,408 | |



Transcoding Procedures

The application can use the SDK encoding, decoding and video processing functions together for transcoding operations. This section describes the key aspects of connecting two or more SDK functions together.

Asynchronous Pipeline

The application passes the output of an upstream SDK function to the input of the downstream SDK function to construct an asynchronous pipeline. Such pipeline construction is done at runtime and can be dynamically changed, as illustrated in Example 5.

```
mfxSyncPoint sp;
MFXVideoDECODE_DecodeFrameAsync(session, bs, work, vin, &sp_d);
if (going_through_vpp) {
         MFXVideoVPP_RunFrameVPPAsync(session, vin, vout, &sp_d);
         MFXVideoENCODE_EncodeFrameAsync(session, NULL, vout, bits2, &sp_e);
} else {
         MFXVideoENCODE_EncodeFrameAsync(session, NULL, vin, bits2, &sp_e);
}
MFXVideoCORE_SyncOperation(session, sp_e, INFINITE);
```

Example 5: Pseudo Code of Asynchronous Pipeline Construction

The SDK simplifies the requirement for asynchronous pipeline synchronization. The application only needs to synchronize after the last SDK function. Explicit synchronization of intermediate results is not required and in fact can slow performance.

The SDK tracks the dynamic pipeline construction and verifies dependency on input and output parameters to ensure the execution order of the pipeline function. In Example 5, the SDK will ensure MFXVideoENCODE EncodeFrameAsync does not begin its operation until MFXVideoVPP RunFrameVPPAsync has finished.

During the execution of an asynchronous pipeline, the application must consider the input data in use and must not change it until the execution has completed. The application must also consider output data unavailable until the execution has finished. In addition, for encoders, the application must consider extended and payload buffers in use while the input surface is locked.



The SDK checks dependencies by comparing the input and output parameters of each SDK function in the pipeline. Do not modify the contents of input and output parameters before the previous asynchronous operation finishes. Doing so will break the dependency check and can result in undefined behavior. An exception occurs when the input and output parameters are structures, in which case overwriting fields in the structures is allowed. (Note that the dependency check works on the pointers to the structures only.)

There are two exceptions with respect to intermediate synchronization:

- 1. The application must synchronize any input before calling the SDK function MFXVideoDecode_DecodeFrameAsync, if the input is from any asynchronous operation.
- 2. When the application calls an asynchronous function to generate an output surface in video memory and passes that surface to a non-SDK component, it must explicitly synchronize the operation before passing the surface to the non-SDK component.

Surface Pool Allocation

When connecting SDK function A to SDK function B, the application must take into account the needs of both functions to calculate the number of frame surfaces in the surface pool. Typically, the application can use the formula $\mathbf{n}_a + \mathbf{n}_b$, where \mathbf{n}_a is the frame surface needs from SDK function \mathbf{A} output, and $\mathbf{N}_{\mathbf{b}}$ is the frame surface needs from SDK function \mathbf{B} input.

For performance considerations, the application must submit multiple operations and delays synchronization as much as possible, which gives the SDK flexibility to organize internal pipelining. For example, the operation sequence, $ENCODE(f1) \rightarrow ENCODE(f2) \rightarrow SYNC(f1) \rightarrow$ SYNC (f2) is recommended, compared with ENCODE (f1) \rightarrow SYNC (f1) \rightarrow ENCODE (f2) \rightarrow SYNC(f2).

In this case, the surface pool needs additional surfaces to take into account multiple asynchronous operations before synchronization. The application can use the AsyncDepth parameter of the mfxVideoParam structure to inform an SDK function that how many asynchronous operations the application plans to perform before synchronization. The corresponding SDK QueryIOSurf function will reflect such consideration in the NumFrameSuggested value. Example 6 shows a way of calculating the surface needs based on NumFrameSuggested values.

```
async depth=4;
init param v.AsyncDepth=async depth;
MFXVideoVPP QueryIOSurf(session, &init param v, response v);
init param e.AsyncDepth=async depth;
MFXVideoENCODE QueryIOSurf(session, &init param e, &response e);
num surfaces=
                  response v[1].NumFrameSuggested
                  +response e.NumFrameSuggested
                  -async depth; /* double counted in ENCODE & VPP */
```



Example 6: Calculate Surface Pool Size

Pipeline Error Reporting

During asynchronous pipeline construction, each stage SDK function will return a synchronization point (sync point). These synchronization points are useful in tracking errors during the asynchronous pipeline operation.

Assume the pipeline is $A \rightarrow B \rightarrow C$. The application synchronizes on sync point c. If the error occurs in SDK function c, then the synchronization returns the exact error code. If the error occurs before SDK function c, then the synchronization returns MFX ERR ABORTED. The application can then try to synchronize on sync point B. Similarly, if the error occurs in SDK function B, the synchronization returns the exact error code, or else MFX ERR ABORTED. Same logic applies if the error occurs in SDK function A.

Working with hardware acceleration

To fully utilize the SDK acceleration capability, the application should support OS specific infrastructures, Microsoft* DirectX* for Micorosoft* Windows* and VA API for Linux*. The exception is transcoding scenario where opaque memory type may be used. See Surface Type Neutral Transcoding for more details.

The hardware acceleration support in application consists of video memory support and acceleration device support.

Depending on usage model, the application can use video memory on different stages of pipeline. Three major scenarios are illustrated on Figure 5.




Figure 5 Usage of video memory for hardware acceleration



The application must use the IOPattern field of the mfxVideoParam structure to indicate the I/O access pattern during initialization. Subsequent SDK function calls must follow this access pattern. For example, if an SDK function operates on video memory surfaces at both input and output, the application must specify the access pattern IOPattern at initialization in MFX_IOPATTERN_IN_VIDEO_MEMORY for input and MFX_IOPATTERN_OUT_VIDEO_MEMORY for output. This particular I/O access pattern must not change inside the Init ... Close sequence.

Initialization of any hardware accelerated SDK component requires the acceleration device handle. This handle is also used by SDK component to query HW capabilities. The application can share its device with the SDK by passing device handle through the MFXVideoCORE_SetHandle function. It is recommended to share the handle before any actual usage of the SDK.

Working with Microsoft* DirectX* Applications

The SDK supports two different infrastructures for hardware acceleration on Microsoft* Windows* OS, "Direct3D 9 DXVA2" and "Direct3D 11 Video API". In the first one the application should use the IDirect3DDeviceManager9 interface as the acceleration device handle, in the second one - ID3D11Device interface. The application should share one of these interfaces with the SDK through the MFXVideoCORE_SetHandle function. If the application does not provide it, then the SDK creates its own internal acceleration device. This internal device could not be accessed by the application and as a result, the SDK input and output will be limited to system memory only. That in turn will reduce SDK performance. If the SDK fails to create a valid acceleration device, then SDK cannot proceed with hardware acceleration and returns an error status to the application.

The application must create the Direct3D9* device with the flag D3DCREATE_MULTITHREADED. Additionally the flag D3DCREATE_FPU_PRESERVE is recommended. This influences floating-point calculations, including PTS values.

The application must also set multithreading mode for Direct3D11* device. Example 7 Setting multithreading mode illustrates how to do it.

Example 7 Setting multithreading mode

During hardware acceleration, if a Direct3D* "device lost" event occurs, the SDK operation terminates with the return status MFX_ERR_DEVICE_LOST. If the application provided the Direct3D* device handle, the application must reset the Direct3D* device.

When the SDK decoder creates auxiliary devices for hardware acceleration, it must allocate the list of Direct3D* surfaces for I/O access, also known as the surface chain, and pass the surface



chain as part of the device creation command. In most cases, the surface chain is the frame surface pool mentioned in the Frame Surface Locking section.

The application passes the surface chain to the SDK component Init function through an SDK external allocator callback. See the Memory Allocation and External Allocators section for details.

Only decoder Init function requests external surface chain from the application and uses it for auxiliary device creation. Encoder and VPP Init functions may only request internal surfaces. See the ExtMemFrameType enumerator for more details about different memory types.

Depending on configuration parameters, SDK requires different surface types. It is strongly recommended to call one of the MFXVideoENCODE_QueryIOSurf, MFXVideoDECODE_QueryIOSurf or MFXVideoVPP QueryIOSurf functions to determine the appropriate type.

Table 6: Supported SDK Surface Types and Color Formats for Direct3D9 shows supported Direct3D9 surface types and color formats. Table 7: Supported SDK Surface Types and Color Formats for Direct3D11 shows Direct3D11 types and formats. Note, that NV12 is the major encoding and decoding color format. Additionally, JPEG/MJPEG decoder supports RGB32 and YUY2 output, JPEG/MJPEG encoder supports RGB32 and YUY2 input for Direct3D9/Direct3D11 and YV12 input for Direct3D9 only, and VPP supports RGB32 output.

Table 6: Supported SDK Surface Types and Color Formats for Direct3D9

| e o. Supported SDR Surface Types and Color Formats for DirectSDS | | | | |
|--|------------------------------------|-----------------------------------|----------------------------|--------------------------|
| SDK | SDK Function Input | | SDK Function Output | |
| Class | Surface Type | Color Format | Surface Type | Color Format |
| DECODE | Not Appli | cable | Decoder Render Target | NV12 |
| | | | Decoder Render Target | RGB32, YUY2 JPEG only |
| VPP | Decoder/Processor Render Target | Listed in ColorFourCC | Decoder Render Target | NV12 |
| | | | Processor Render Target | RGB32 |
| ENCODE | Decoder Render Target | NV12 | Not Appl | icable |
| | Decoder Render Target | RGB32, YUY2, YV12 JPEG only | | |

Note: "Decoder Render Target" corresponds to DXVA2_ VideoDecoderRenderTarget type, "Processor Render Target" to DXVA2_ VideoProcessorRenderTarget.

Table 7: Supported SDK Surface Types and Color Formats for Direct3D11



| SDK | SDK Function Input | | SDK Function Output | |
|--------|--|--------------------------|--|--------------------------|
| Class | Surface Type | Color Format | Surface Type | Color Format |
| DECODE | Not Appli | cable | Decoder Render Target | NV12 |
| | | | Decoder /Processor Render Target | RGB32, YUY2 JPEG only |
| VPP | Decoder/Processor Render Target | Listed in ColorFourCC | Processor Render Target | NV12 |
| | | | Processor Render Target | RGB32 |
| ENCODE | Decoder/Processor Render Target | NV12 | Not Appl | icable |
| | Decoder /Processor Render Target | RGB32, YUY2 JPEG only | | |

Note: "Decoder Render Target" corresponds to D3D11 BIND DECODER flag, "Processor Render Target" to D3D11 BIND RENDER TARGET.

Working with VA API Applications

The SDK supports single infrastructure for hardware acceleration on Linux* - "VA API". The application should use the VADisplay interface as the acceleration device handle for this infrastructure and share it with the SDK through the MFXVideoCORE SetHandle function. Because the SDK does not create internal acceleration device on Linux, the application must always share it with the SDK. This sharing should be done before any actual usage of the SDK, including capability query and component initialization. If the application fails to share the device, the SDK operation will fail.

Example 8 Obtaining VA display from X Window System and Example 9 Obtaining VA display from Direct Rendering Manager show how to obtain and share VA display with the SDK.

```
Display
          *x11 display;
VADisplay va display;
x11_display = XOpenDisplay(current display);
va display = vaGetDisplay(x11 display);
MFXVideoCORE SetHandle(session, MFX HANDLE VA DISPLAY,
                       (mfxHDL) va display);
```



Example 8 Obtaining VA display from X Window System

Example 9 Obtaining VA display from Direct Rendering Manager

When the SDK decoder creates hardware acceleration device, it must allocate the list of video memory surfaces for I/O access, also known as the surface chain, and pass the surface chain as part of the device creation command. The application passes the surface chain to the SDK component Init function through an SDK external allocator callback. See the Memory Allocation and External Allocators section for details.

Only decoder Init function requests external surface chain from the application and uses it for device creation. Encoder and VPP Init functions may only request internal surfaces. See the ExtMemFrameType enumerator for more details about different memory types.

The VA API does not define any surface types and the application can use either MFX_MEMTYPE_VIDEO_MEMORY_DECODER_TARGET or MFX MEMTYPE VIDEO MEMORY PROCESSOR TARGET to indicate data in video memory.

Table 8: Supported SDK Surface Types and Color Formats for VA API shows supported by VA API color formats.

Table 8: Supported SDK Surface Types and Color Formats for VA API

| SDK | SDK Function Input | SDK Function Output |
|--------|-----------------------|--------------------------|
| Class | Color Format | Color Format |
| DECODE | Not Applicable | NV12 |
| | | RGB32, YUY2 JPEG only |
| VPP | Listed in ColorFourCC | NV12, RGB32 |
| ENCODE | NV12 | Not Applicable |



RGB32, YUY2, YV12 JPEG only

Memory Allocation and External Allocators

All SDK implementations delegate memory management to the application. The application must allocate sufficient memory for input and output parameters and buffers, and de-allocate it when SDK functions complete their operations. During execution, the SDK functions use callback functions to the application to manage memory for video frames through external allocator interface mfxFrameAllocator.

mfxBufferAllocator interface is deprecated.

If an application needs to control the allocation of video frames, it can use callback functions through the mfxFrameAllocator interface. If an application does not specify an allocator, an internal allocator is used. However, if an application uses video memory surfaces for input and output, it must specify the hardware acceleration device and an external frame allocator using mfxFrameAllocator.

The external frame allocator can allocate different frame types:

- in system memory and
- in video memory, as "decoder render targets" or "processor render targets." See the section Working with hardware acceleration for additional details.

The external frame allocator responds only to frame allocation requests for the requested memory type and returns MFX ERR UNSUPPORTED for all others. The allocation request uses flags, part of memory type field, to indicate which SDK class initiates the request, so the external frame allocator can respond accordingly. Example 10 illustrates a simple external frame allocator.



```
typedef struct {
      mfxU16 width, height;
      mfxU8 *base;
} mid struct;
mfxStatus fa alloc(mfxHDL pthis, mfxFrameAllocRequest *request,
mfxFrameAllocResponse *response) {
      if (!(request→type&MFX MEMTYPE SYSTEM MEMORY))
             return MFX ERR UNSUPPORTED;
      if (request→Info→FourCC!=MFX FOURCC NV12)
            return MFX ERR UNSUPPORTED;
      response→NumFrameActual=request→NumFrameMin;
      for (int i=0;i<request→NumFrameMin;i++) {</pre>
            mid_struct *mmid=(mid_struct *)malloc(sizeof(mid struct));
            mmid→width=ALIGN32(request→Info→Width);
            mmid→height=ALIGN32 (request→Info→Height);
            mmid→base=(mfxU8*) malloc(mmid→width*mmid→height*3/2);
            response→mids[i]=mmid;
      return MFX ERR NONE;
mfxStatus fa lock(mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr) {
      mid struct *mmid=(mid struct *) mid;
      ptr→pitch=mmid→width;
      ptr→Y=mmid→base;
      ptr→U=ptr→Y+mmid→width*mmid→height;
      ptr\rightarrowV=ptr\rightarrowU+1;
      return MFX ERR NONE;
mfxStatus fa unlock(mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr) {
      if (ptr) ptr\rightarrowY=ptr\rightarrowU=ptr\rightarrowV=ptr\rightarrowA=0;
      return MFX ERR NONE;
mfxStatus fa gethdl(mfxHDL pthis, mfxMemId mid, mfxHDL *handle) {
      return MFX ERR UNSUPPORTED;
mfxStatus fa free(mfxHDL pthis, mfxFrameAllocResponse *response) {
      for (int i=0;i<response→NumFrameActual;i++) {</pre>
            mid struct *mmid=(mid struct *)response→mids[i];
            free (mmid→base); free (mid);
      return MFX ERR NONE;
```

Example 10: Example Frame Allocator

For system memory, it is highly recommended to allocate memory for all planes of the same frame as a single buffer (using one single malloc call).



Surface Type Neutral Transcoding

Performance wise, software SDK library (running CPU instructions) prefers system memory I/O, and SDK platform implementation (accelerated by platform graphic devices) prefers video memory surface I/O. The application needs to manage both surface types (thus two data paths in a transcoding $A \rightarrow B$) to achieve the best performance in both cases.

The SDK provides a third surface type: opaque surface. With opaque surface, the SDK will map the surface type to either system memory buffer or video memory surface at runtime. The application only needs to manage one surface type, or one transcoding data path.

It is recommended the application use opaque surfaces for any transcoding intermediate data. For example, the transcoding pipeline can be **DECODE** → Opaque Surfaces → **VPP** → Opaque Surfaces → **ENCODE**. It is possible to copy an opaque surface to a "real" surface through a **VPP** operation.

The application uses the following procedure to use opaque surface, assuming a transcoding pipeline SDK A \rightarrow SDK B:

- As described in section Surface Pool Allocation, the application queries SDK component A and B and calculates the surface pool size. The application needs to use MFX IOPATTERN IN OPAQUE MEMORY and/or MFX IOPATTERN OUT OPAQUE MEMORY While specifying the I/O pattern. It is possible that SDK component A returns a different memory type than SDK component B, as the QueryIOSurf function returns the native allocation type and size. In this case, the surface pool type and size should follow only one SDK component: either A or B.
- The application allocates the surface pool, which is an array of the mfxFrameSurface1 structures. Within the structure, specify Data.Y= Data.V= Data.A= Data.MemId=0 for all array members.
- During initialization, the application communicates the allocated surface pool to both SDK components by attaching the mfxExtOpaqueSurfaceAlloc structure as part of the initialization parameters. The application needs to use MFX IOPATTERN IN OPAQUE MEMORY and/or MFX IOPATTERN OUT OPAQUE MEMORY While specifying the I/O pattern.
- During decoding, encoding, and video processing, the application manages the surface pool and passes individual frame surface to SDK component A and B as described in section Decoding Procedures, section Encoding Procedures, and section Video *Processing Procedures*, respectively.

Example 11 shows the opaque procedure sample code.

Since the SDK manages the association of opaque surface to "real" surface types internally, the application cannot read the content of opaque surfaces. Also the application does not get any opaque-type surface allocation requests if the application specifies an external frame allocator.



If the application shares opaque surfaces among different SDK sessions, the application must join the sessions before SDK component initialization and ensure that all joined sessions have the same hardware acceleration device handle. Setting device handle is optional only if all components in pipeline belong to the same session.

30



```
mfxExtOpqueSurfaceAlloc osa, *posa=&osa;
memset(&osa, 0, sizeof(osa));
// query frame surface allocation needs
MFXVideoDECODE QueryIOSurf(session, &decode param, &request decode);
MFXVideoENCODE QueryIOSurf(session, &encode param, &request encode);
// calculate the surface pool surface type and numbers
if (MFX MEMTYPE BASE(request decode.Type) ==
   MFX MEMTYPE BASE (request encode. Type)) {
    osa.Out.NumSurface = request decode.NumFrameSuggested +
        request encode.NumFrameSuggested - decode param.AsyncDepth;
    osa.Out.Type=request decode.Type;
} else {
   // it is also ok to use decode's NumFrameSuggested and Type.
    osa.Out.NumSurface=request encode.NumFrameSuggested;
    osa.Out.Type=request encode.Type;
// allocate surface pool and zero MemId/Y/U/V/A pointers
osa.Out.Surfaces=alloc mfxFrameSurface1(osa.Out.NumSurface);
// attach the surface pool during decode & encode initialization
osa.Header.BufferId=MFX EXTBUFF OPAQUE SURFACE ALLOCATION;
osa.Header.BufferSz=sizeof(osa);
decode param.NumExtParam=1;
decode param.ExtParam=&posa;
MFXVideoDECODE Init(session, &decode param);
memcpy(&osa.In, &osa.Out, sizeof(osa.Out));
encode param.NumExtParam=1;
encode param.ExtParam=&posa;
MFXVideoENCODE Init(session, &encode param);
```

Example 11: Pseudo-Code of Opaque Surface Procedure



Hardware Device Error Handling

The SDK accelerates decoding, encoding and video processing through a hardware device. The SDK functions may return the following errors or warnings if the hardware device encounters errors:

| MFX_ERR_DEVICE_FAILED | Hardware device returned unexpected errors. SDK was unable to restore operation. |
|------------------------------|--|
| MFX_ERR_DEVICE_LOST | Hardware device was lost due to system lock or shutdown. |
| MFX_WRN_PARTIAL_ACCELERATION | The hardware does not fully support the specified configuration. The encoding, decoding, or video processing operation may be partially accelerated. |
| MFX_WRN_DEVICE_BUSY | Hardware device is currently busy. |

SDK functions Query, QueryIOSurf, and Init return MFX WRN PARTIAL ACCELERATION to indicate that the encoding, decoding or video processing operation can be partially hardware accelerated or not hardware accelerated at all. The application can ignore this warning and proceed with the operation. (Note that SDK functions may return errors or other warnings overwriting MFX WRN PARTIAL ACCELERATION, as it is a lower priority warning.)

SDK functions return MFX WRN DEVICE BUSY to indicate that the hardware device is busy and unable to take commands at this time. Resume the operation by waiting for a few milliseconds and resubmitting the request. Example 12 shows the decoding pseudo-code. The same procedure applies to encoding and video processing.

SDK functions return MFX ERR DEVICE LOST OF MFX ERR DEVICE FAILED to indicate that there is a complete failure in hardware acceleration. The application must close and reinitialize the SDK function class. If the application has provided a hardware acceleration device handle to the SDK, the application must reset the device.

```
mfxStatus sts=MFX_ERR_NONE;
for (;;) {
    ...
    sts=MFXVideoDECODE_DecodeFrameAsync(session, bitstream,
surface_work, &surface_disp, &syncp);
    if (sts == MFX_WRN_DEVICE_BUSY) Sleep(5);
}
```

Example 12: Pseudo-Code to Handle MFX_ERR_DEVICE_BUSY



Function Reference

This section describes SDK functions and their operations.

In each function description, only commonly used status codes are documented. The function may return additional status codes, such as <u>MFX ERR INVALID HANDLE</u> or <u>MFX ERR NULL PTR</u>, in certain case. See the <u>mfxStatus</u> enumerator for a list of all status codes.

Global Functions

Global functions initialize and de-initialize the SDK library and perform query functions on a global scale within an application.

| Member Functions | Description | |
|-------------------|--|--|
| MFXInit | Initializes an SDK session | |
| MFXQueryIMPL | Queries the implementation type | |
| MFXQueryVersion | Queries the implementation version | |
| MFXJoinSession | Join two sessions together | |
| MFXCloneSession | Clone the current session | |
| MFXSetPriority | Set session priority | |
| MFXGetPriority | Obtain session priority | |
| MFXDisjoinSession | Remove the join state of the current session | |
| MFXClose | De-initializes an SDK session | |

MFXCloneSession

Syntax

mfxStatus MFXCloneSession(mfxSession session, mfxSession *clone);

Parameters

session

SDK session handle



clone

Pointer to the cloned session handle

Description

This function creates a clean copy of the current session. The cloned session is an independent session. It does not inherit any user-defined buffer, frame allocator, or device manager handles from the current session. This function is a light-weight equivalent of MFXJoinSession after MFXInit.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.1.

MFXClose

Syntax

mfxStatus MFXClose(mfxSession session);

Parameters

session

SDK session handle

Description

This function completes and de-initializes an SDK session. Any active tasks in execution or in queue are aborted. The application cannot call any SDK function after this function.

All child sessions must be disjoined before closing a parent session.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXDoWork

Syntax



mfxStatus MFXDoWork(mfxSession session);

Parameters

session

SDK session handle

Description

This function complements MFXInitEx with external threading mode on. Application expected to create no less than two work threads per session and pass them to SDK via this function. This function won't return control to application unless session is closed.

In case of joined sessions, application should call MFXDoWork only for parent session.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.14.

MFXDisjoinSession

Syntax

mfxStatus MFXDisjoinSession(mfxSession session);

Parameters

session

SDK session handle

Description

This function removes the joined state of the current session. After disjoining, the current session becomes independent. The application must ensure there is no active task running in the session before calling this function.

Return Status

MFX ERR NONE The function completed successfully.

MFX WRN IN EXECUTION Active tasks are in execution or in queue. Wait for

the completion of the tasks and then call this

function again.

MFX ERR UNDEFINED BEHAVIOR The session is independent, or this session is the

parent of all joined sessions.



Change History

This function is available since SDK API 1.1.

MFXGetPriority

Syntax

mfxStatus MFXGetPriority(mfxSession session, mfxPriority *priority);

Parameters

session SDK session handle

priority Pointer to the priority value

Description

This function returns the current session priority.

Return Status

MFX ERR NONE The function completed successfully.

Change History

This function is available since SDK API 1.1.

MFXInit

Syntax

```
mfxStatus MFXInit(mfxIMPL impl, mfxVersion *ver, mfxSession *session);
```

Parameters

impl mfxIMPL enumerator that indicates the desired SDK

implementation

Pointer to the minimum library version or zero, if not ver

specified

session Pointer to the SDK session handle

Description



This function creates and initializes an SDK session. Call this function before calling any other SDK functions. If the desired implementation specified by impl is MFX IMPL AUTO, the function will search for the platform-specific SDK implementation. If the function cannot find it, it will use the software implementation.

The argument ver indicates the desired version of the library implementation. The loaded SDK will have an API version compatible to the specified version (equal in the major version number, and no less in the minor version number.) If the desired version is not specified, the default is to use the API version from the SDK release, with which an application is built.

We recommend that production applications always specify the minimum API version that meets their functional requirements. For example, if an application uses only H.264 decoding as described in API v1.0, have the application initialize the library with API v1.0. This ensures backward compatibility.

Return Status

MFX_ERR_NONE The function completed successfully. The output

parameter contains the handle of the session.

MFX_ERR_UNSUPPORTED The function cannot find the desired SDK

implementation or version.

Change History

This function is available since SDK API 1.0.

MFXInitEx

Syntax

mfxStatus MFXInitEx(mfxInitParam par, mfxSession *session);

Parameters

par mfxInitParam structure that indicates the desired SDK

implementation, minimum library version and desired

threading mode

session Pointer to the SDK session handle

Description

This function creates and initializes an SDK session. Call this function before calling any other SDK functions. If the desired implementation specified by par.

Implementation is MFX IMPL AUTO, the function will search for the platform-specific SDK implementation. If the function cannot find it, it will use the software



implementation.

The argument par. Version indicates the desired version of the library implementation. The loaded SDK will have an API version compatible to the specified version (equal in the major version number, and no less in the minor version number.) If the desired version is not specified, the default is to use the API version from the SDK release, with which an application is built.

We recommend that production applications always specify the minimum API version that meets their functional requirements. For example, if an application uses only H.264 decoding as described in API v1.0, have the application initialize the library with API v1.0. This ensures backward compatibility.

The argument par.ExternalThreads specifies threading mode. Value 0 means that SDK should internally create and handle work threads (this essentially equivalent of regular MFXInit). If this parameter set to 1 then SDK will expect that application should create work threads and pass them to SDK via single-entry function MFXDoWork. Setting par. External Threads to 1 requires setting minimum API version to 1.14, as previous versions of SDK didn't have such functionality.

Return Status

MFX ERR NONE The function completed successfully. The output

parameter contains the handle of the session.

MFX ERR UNSUPPORTED The function cannot find the desired SDK

implementation or version.

Change History

This function is available since SDK API 1.14.

MFXJoinSession

Syntax

mfxStatus MFXJoinSession(mfxSession session, mfxSession child);

Parameters

session The current session handle

child The child session handle to be joined

Description

This function joins the child session to the current session.

After joining, the two sessions share thread and resource scheduling for asynchronous operations. However, each session still maintains its own device manager and buffer/frame allocator. Therefore, the application must use a compatible device manager and buffer/frame allocator to share data between two joined sessions.



The application can join multiple sessions by calling this function multiple times. When joining the first two sessions, the current session becomes the parent responsible for thread and resource scheduling of any later joined sessions.

Joining of two parent sessions is not supported.

Return Status

MFX ERR NONE The function completed successfully.

MFX WRN IN EXECUTION Active tasks are executing or in queue in one of the

sessions. Call this function again after all tasks are

completed.

MFX ERR UNSUPPORTED The child session cannot be joined with the current

session.

Change History

This function is available since SDK API 1.1.

MFXQueryIMPL

Syntax

mfxStatus MFXQueryIMPL(mfxSession session, mfxIMPL *impl);

Parameters

session SDK session handle

impl Pointer to the implementation type

Description

This function returns the implementation type of a given session.

Return Status

MFX ERR NONE The function completed successfully.

Change History

This function is available since SDK API 1.0.



MFXQueryVersion

Syntax

mfxStatus MFXQueryVersion(mfxSession session, mfxVersion *version);

Parameters

session SDK session handle

version Pointer to the returned implementation version

Description

This function returns the SDK implementation version.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXSetPriority

Syntax

mfxStatus MFXSetPriority(mfxSession session, mfxPriority priority);

Parameters

SDK session handle session

priority Priority value

Description

This function sets the current session priority.

Return Status

MFX ERR NONE The function completed successfully.

Change History

This function is available since SDK API 1.1.



MFXVideoCORE

This class of functions consists of auxiliary functions that all functions of the SDK implementation can call.

Member Functions

| MFXVideoCORE SetHandle | Sets system handles that the SDK implementation might need |
|---------------------------------|---|
| MFXVideoCORE GetHandle | Obtains system handles previously set |
| MFXVideoCORE SetBufferAllocator | Sets the external system buffer allocator |
| MFXVideoCORE SetFrameAllocator | Sets the external frame allocator |
| MFXVideoCORE SyncOperation | Initializes execution of the specified sync point and returns a status code |

MFXVideoCORE_SetHandle

Syntax

mfxStatus MFXVideoCORE_SetHandle(mfxSession session, mfxHandleType type, mfxHDL hdl);

Parameters

session SDK session handle

Handle type type

hdl Handle to be set

Description

This function sets any essential system handle that SDK might use.

If the specified system handle is a COM interface, the reference counter of the COM interface will increase. The counter will decrease when the SDK session closes.

Return Status



MFX ERR NONE The function completed successfully.

MFX ERR UNDEFINED BEHAVIOR The same handle is redefined. For example, the

function has been called twice with the same handle type or internal handle has been created by

the SDK before this function call.

Change History

This function is available since SDK API 1.0.

MFXVideoCORE GetHandle

Syntax

mfxStatus MFXVideoCORE GetHandle(mfxSession session, mfxHandleType type, mfxHDL *hdl);

Parameters

session SDK session handle

type Handle type

hdl Pointer to the handle to be set

Description

This function obtains system handles previously set by the MFXVideoCORE SetHandle function. If the handler is a COM interface, the reference counter of the interface increases. The calling application must release the COM interface.

Return Status

MFX ERR NONE The function completed successfully.

MFX ERR NOT FOUND Specified handle type not found.

Change History

This function is available since SDK API 1.0.

MFXVideoCORE SetBufferAllocator

Syntax



mfxStatus MFXVideoCORE SetBufferAllocator(mfxSession session, mfxBufferAllocator *allocator);

Parameters

session SDK session handle

allocator Pointer to the mfxBufferAllocator structure

Description

This function is deprecated.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

Deprecated since SDK API 1.17.

MFXVideoCORE SetFrameAllocator

Syntax

mfxStatus MFXVideoCORE SetFrameAllocator(mfxSession session, mfxFrameAllocator *allocator);

Parameters

session SDK session handle

allocator Pointer to the mfxFrameAllocator structure

Description

This function sets the external allocator callback structure for frame allocation. If the allocator argument is NULL, the SDK uses the default allocator, which allocates frames from system memory or hardware devices.

The behavior of the SDK is undefined if it uses this function while the previous allocator is in use. A general guideline is to set the allocator immediately after initializing the session.

Return Status

MFX ERR NONE The function completed successfully.



Change History

This function is available since SDK API 1.0.

MFXVideoCORE SyncOperation

Syntax

mfxStatus MFXVideoCORE SyncOperation(mfxSession session, mfxSyncPoint syncp, mfxU32 wait);

Parameters

session SDK session handle

syncp Sync point

wait Wait time in milliseconds

Description

This function initiates execution of an asynchronous function not already started and returns the status code after the specified asynchronous operation completes. If wait is zero, the function returns immediately.

Return Status

MFX ERR NONE The function completed successfully.

MFX WRN IN EXECUTION The specified asynchronous function is in execution.

MFX ERR ABORTED The specified asynchronous function aborted due to

data dependency on a previous asynchronous

function that did not complete.

Change History

This function is available since SDK API 1.0.

Remarks

See status codes for specific asynchronous functions.



MFXVideoENCODE

This class of functions performs the entire encoding pipeline from the input video frames to the output bitstream.

Member Functions

| MFXVideoENCODE Query | Queries the feature capability |
|---------------------------------|--|
| MFXVideoENCODE QueryIOSurf | Queries the number of input surface frames required for encoding |
| MFXVideoENCODE Init | Initializes the encoding operation |
| MFXVideoENCODE Reset | Resets the current encoding operation and prepares for the next encoding operation |
| MFXVideoENCODE Close | Terminates the encoding operation and de-allocates any internal memory |
| MFXVideoENCODE GetVideoParam | Obtains the current working parameter set |
| MFXVideoENCODE_GetEncodeStat | Obtains the statistics collected during encoding |
| MFXVideoENCODE EncodeFrameAsync | Performs the encoding and returns the compressed bitstream |

MFXVideoENCODE_Query

Syntax

mfxStatus MFXVideoENCODE_Query(mfxSession session, mfxVideoParam *in,
mfxVideoParam *out);

Parameters

| session | SDK session handle |
|---------|---|
| in | Pointer to the mfxVideoParam structure as input |
| out | Pointer to the mfxVideoParam Structure as output |

Description

This function works in either of four modes:

1. If the in pointer is zero, the function returns the class configurability in the output mfxVideoParam structure. A non-zero value in each field of the output



structure indicates that the SDK implementation can configure the field with **Init**.

- 2. If the in parameter is non-zero, the function checks the validity of the fields in the input mfxVideoParam structure. Then the function returns the corrected values in the output mfxVideoParam structure. If there is insufficient information to determine the validity or correction is impossible, the function zeroes the fields. This feature can verify whether the SDK implementation supports certain profiles, levels or bitrates.
- 3. If the in parameter is non-zero and mfxExtEncoderResetOption structure is attached to it, then the function queries for the outcome of the MFXVideoENCODE Reset function and returns it in the mfxExtEncoderResetOption structure attached to out. The query function succeeds if such reset is possible and returns error otherwise. Unlike other modes that are independent of the SDK encoder state, this one checks if reset is possible in the present SDK encoder state. This mode also requires completely defined mfxVideoParam structure, unlike other modes that support partially defined configurations. See mfxExtEncoderResetOption description for more details.
- 4. If the in parameter is non-zero and mfxExtEncoderCapability structure is attached to it, then the function returns encoder capability in mfxExtEncoderCapability structure attached to out. It is recommended to fill in mfxVideoParam structure and set hardware acceleration device handle before calling the function in this mode.

The application can call this function before or after it initializes the encoder. The **CodecId** field of the output **mfxVideoParam** structure is a mandated field (to be filled by the application) to identify the coding standard.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_UNSUPPORTED | The function failed to identify a specific implementation for the required features. |
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters; The encoding may be partially accelerated. Only SDK HW implementations may return this status code. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.0.



MFXVideoENCODE_QueryIOSurf

Syntax

mfxStatus MFXVideoENCODE QueryIOSurf(mfxSession session, mfxVideoParam *par, mfxFrameAllocRequest *request);

Parameters

| session | SDK session handle |
|---------|---|
| par | Pointer to the <pre>mfxVideoParam</pre> structure as input |
| request | Pointer to the $\frac{\text{mfxFrameAllocRequest}}{\text{as output}}$ structure as output |

Description

This function returns minimum and suggested numbers of the input frame surfaces required for encoding initialization and their type. **Init** will call the external allocator for the required frames with the same set of numbers.

The use of this function is recommended. For more information, see the section Working with hardware acceleration.

This function does not validate I/O parameters except those used in calculating the number of input surfaces.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters. The encoding may be partially accelerated. Only SDK HW implementations may return this status code. |
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.0.



MFXVideoENCODE Init

Syntax

mfxStatus MFXVideoENCODE Init(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure

Description

This function allocates memory and prepares tables and necessary structures for encoding. This function also does extensive validation to ensure if the configuration, as specified in the input parameters, is supported.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters. The encoding may be partially accelerated. Only SDK HW implementations may return this status code. |
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |
| MFX_ERR_UNDEFINED_BEHAVIOR | The function is called twice without a close; |

Change History

This function is available since SDK API 1.0.

MFXVideoENCODE Reset

Syntax

mfxStatus MFXVideoENCODE Reset(mfxSession session, mfxVideoParam *par);



Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure

Description

This function stops the current encoding operation and restores internal structures or parameters for a new encoding operation, possibly with new parameters.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected that video parameters are wrong or they conflict with initialization parameters. Reset is impossible. |
| MFX_ERR_INCOMPATIBLE_VIDEO_P ARAM | The function detected that provided by the application video parameters are incompatible with initialization parameters. Reset requires additional memory allocation and cannot be executed. The application should close the SDK component and then reinitialize it. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.0.

MFXVideoENCODE Close

Syntax

mfxStatus MFXVideoENCODE Close(mfxSession session);

Parameters

SDK session handle session

Description

This function terminates the current encoding operation and de-allocates any internal tables or structures.



Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoENCODE GetVideoParam

Syntax

Parameters

session

SDK session handle

par

Pointer to the corresponding parameter structure

Description

This function retrieves current working parameters to the specified output structure. If extended buffers are to be returned, the application must allocate those extended buffers and attach them as part of the output structure.

The application can retrieve a copy of the bitstream header, by attaching the mfxExtCodingOptionSPSPPS structure to the mfxVideoParam structure.

Returned information

MFX_ERR_NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoENCODE GetEncodeStat

Syntax

mfxStatus
*stat);
MFXVideoENCODE_GetEncodeStat(mfxSession session, mfxEncodeStat

Parameters



session SDK session handle

stat Pointer to the mfxEncodeStat Structure

Description

This function obtains statistics collected during encoding.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoENCODE_EncodeFrameAsync

Syntax

```
mfxStatus MFXVideoENCODE EncodeFrameAsync(mfxSession session,
mfxEncodeCtrl *ctrl, mfxFrameSurface1 *surface, mfxBitstream *bs,
mfxSyncPoint *syncp);
```

Parameters

Session SDK session handle

ctrl Pointer to the mfxEncodeCtrl structure for

> per-frame encoding control; this parameter is optional—it can be NULL—if the encoder

works in the display order mode.

surface Pointer to the frame surface structure

bs Pointer to the output bitstream

syncp Pointer to the returned sync point associated

with this operation

Description

This function takes a single input frame in either encoded or display order and generates its output bitstream. In the case of encoded ordering the mfxEncodeCtrl structure must specify the explicit frame type. In the case of display ordering, this function handles frame order shuffling according to the GOP structure parameters specified during initialization.

Since encoding may process frames differently from the input order, not every call of



the function generates output and the function returns MFX ERR MORE DATA. If the encoder needs to cache the frame, the function locks the frame. The application should not alter the frame until the encoder unlocks the frame. If there is output (with return status MFX ERR NONE), the return is a frame worth of bitstream.

It is the calling application's responsibility to ensure that there is sufficient space in the output buffer. The value <code>BufferSizeInKB</code> in the <code>mfxVideoParam</code> structure at encoding initialization specifies the maximum possible size for any compressed frames. This value can also be obtained from <code>MFXVideoENCODE GetVideoParam</code> after encoding initialization.

To mark the end of the encoding sequence, call this function with a NULL surface pointer. Repeat the call to drain any remaining internally cached bitstreams—one frame at a time—until MFX ERR MORE DATA is returned.

This function is asynchronous.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|----------------------------------|--|
| MFX_ERR_NOT_ENOUGH_BUFFER | The bitstream buffer size is insufficient. |
| MFX_ERR_MORE_DATA | The function requires more data to generate any output. |
| MFX_ERR_DEVICE_LOST | Hardware device was lost; See Working with Microsoft* DirectX* Applications section for further information. |
| MFX_WRN_DEVICE_BUSY | Hardware device is currently busy. Call this function again in a few milliseconds. |
| MFX_ERR_INCOMPATIBLE_VIDEO_PARAM | Inconsistent parameters detected not conforming to Appendix A. |

Change History

This function is available since SDK API 1.0.

Remarks

If the <u>EncodedOrder</u> field in the <u>mfxInfoMFX</u> structure is true, input frames enter the encoder in the order of their encoding. However, the <u>FrameOrder</u> field in the <u>mfxFrameData</u> structure of each frame must be set to the display order. If <u>EncodedOrder</u> is false, the function ignores the <u>FrameOrder</u> field.

52 SDK API Reference Manual API Version 1.17



MFXVideoENC

This class of functions performs the first step of encoding process – motion estimation, intra prediction and mode decision. These functions are declared in mfxenc.h file.

| Member Functions | |
|-------------------------------|--|
| MFXVideoENC_Query | Queries the feature capability |
| MFXVideoENC_QueryIOSurf | Queries the number of input surface frames required for encoding |
| MFXVideoENC_Init | Initializes the encoding operation |
| MFXVideoENC_Reset | Resets the current encoding operation and prepares for the next encoding operation |
| MFXVideoENC_Close | Terminates the encoding operation and de-allocates any internal memory |
| MFXVideoENC_ProcessFrameAsync | Performs the first step of encoding process and returns intermediate data. |

MFXVideoENC_Query

Syntax

mfxStatus MFXVideoENC_Query(mfxSession session, mfxVideoParam *in,
mfxVideoParam *out);

Parameters

| session | SDK session handle |
|---------|---|
| in | Pointer to the mfxVideoParam structure as input |
| out | Pointer to the mfxVideoParam structure as output |

Description

This function works in either of two modes:

- 1. If the in pointer is zero, the function returns the class configurability in the output mfxVideoParam structure. A non-zero value in each field of the output structure indicates that the SDK implementation can configure the field with Init.
- 2. If the in parameter is non-zero, the function checks the validity of the fields in



the input mfxVideoParam structure. Then the function returns the corrected values in the output mfxVideoParam structure. If there is insufficient information to determine the validity or correction is impossible, the function zeroes the fields. This feature can verify whether the SDK implementation supports certain profiles, levels or bitrates.

The application can call this function before or after it initializes the ENC.

Return Status

MFX ERR NONE The function completed successfully. MFX ERR UNSUPPORTED The function failed to identify a specific implementation for the required features. MFX WRN INCOMPATIBLE VIDEO P The function detected some video parameters ARAM were incompatible with others; incompatibility resolved.

Change History

This function is available since SDK API 1.10.

MFXVideoENC QueryIOSurf

Syntax

mfxStatus MFXVideoENC QueryIOSurf(mfxSession session, mfxVideoParam *par, mfxFrameAllocRequest *request);

Parameters

session SDK session handle par Pointer to the mfxVideoParam structure as input request Pointer to the mfxFrameAllocRequest Structure as output

Description

This function returns minimum and suggested numbers of the input frame surfaces required for ENC initialization and their type.

This function does not validate I/O parameters except those used in calculating the number of input surfaces.

Return Status



MFX_ERR_NONE

The function completed successfully.

The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved.

MFX_WRN_INCOMPATIBLE_VIDEO_P
ARAM

The function detected some video parameters were incompatible with others; incompatibility resolved.

Change History

This function is available since SDK API 1.10.

MFXVideoENC Init

Syntax

mfxStatus MFXVideoENC Init(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure

Description

This function performs ENC initialization.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |
| MFX ERR UNDEFINED BEHAVIOR | The function is called twice without a close; |

Change History



This function is available since SDK API 1.10.

MFXVideoENC Reset

Syntax

mfxStatus MFXVideoENC Reset(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

Pointer to the mfxVideoParam structure

Description

This function stops the current encoding operation and restores internal structures or parameters for a new encoding operation, possibly with new parameters.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected that video parameters are wrong or they conflict with initialization parameters. Reset is impossible. |
| MFX_ERR_INCOMPATIBLE_VIDEO_P ARAM | The function detected that provided by the application video parameters are incompatible with initialization parameters. Reset requires additional memory allocation and cannot be executed. The application should close the SDK component and then reinitialize it. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.10.

MFXVideoENC_Close

Syntax



mfxStatus MFXVideoENC Close(mfxSession session);

Parameters

session SDK session handle

Description

This function terminates the current encoding operation and de-allocates any internal tables or structures.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.10.

MFXVideoENC_ProcessFrameAsync

Syntax

mfxStatus MFXVideoENC_ProcessFrameAsync(mfxSession session, mfxENCInput
*in, mfxENCOutput *out, mfxSyncPoint *syncp);

Parameters

Session

SDK session handle

Input parameters for ENC operation.

Output parameters of encoding operation.

Syncp

Pointer to the returned sync point associated with this operation

Description

This function performs the first step of encoding process – motion estimation, intra prediction and mode decision. Its exact operation, input and output parameters depend on usage model.

This function is stateless, i.e. each function call is independent from other calls.

This function is asynchronous.

Return Status



MFX_ERR_NONE

The function completed successfully.

Change History

This function is available since SDK API 1.10.

MFXVideoDECODE

This class of functions implements a complete decoder that decompresses input bitstreams directly to output frame surfaces.

| Member Functions | | |
|---------------------------------|--|--|
| MFXVideoDECODE Query | Queries the feature capability | |
| MFXVideoDECODE_QueryIOSurf | Queries the number of frames required for decoding | |
| MFXVideoDECODE DecodeHeader | Parses the bitstream to obtain the video parameters for initialization | |
| MFXVideoDECODE Init | Initializes the decoding operation | |
| MFXVideoDECODE Reset | Resets the current decoding operation and prepares for the next decoding operation | |
| MFXVideoDECODE Close | Terminates the decoding operation and de-allocates any internal memory | |
| MFXVideoDECODE GetVideoParam | Obtains the current working parameter set | |
| MFXVideoDECODE GetDecodeStat | Obtains statistics during decoding | |
| MFXVideoDECODE GetPayload | Obtains user data or SEI messages embedded in the bitstream | |
| MFXVideoDECODE SetSkipMode | Set decoder skip mode | |
| MFXVideoDECODE DecodeFrameAsync | Performs decoding from the input bitstream to the output frame surface | |



MFXVideoDECODE DecodeHeader

Syntax

mfxStatus MFXVideoDECODE_DecodeHeader(mfxSession session, mfxBitstream
*bs, mfxVideoParam *par);

Parameters

session SDK session handle

bs Pointer to the bitstream

par Pointer to the mfxVideoParam structure

Description

This function parses the input bitstream and fills the <u>mfxVideoParam</u> structure with appropriate values, such as resolution and frame rate, for the **Init** function. The application can then pass the resulting <u>mfxVideoParam</u> structure to the <u>MFXVideoDECODE Init</u> function for decoder initialization.

An application can call this function at any time before or after decoder initialization. If the SDK finds a sequence header in the bitstream, the function moves the bitstream pointer to the first bit of the sequence header. Otherwise, the function moves the bitstream pointer close to the end of the bitstream buffer but leaves enough data in the buffer to avoid possible loss of start code.

The CodecId field of the $\frac{mfxVideoParam}{mfxVideoParam}$ structure is a mandated field (to be filled by the application) to identify the coding standard.

The application can retrieve a copy of the bitstream header, by attaching the mfxExtCodingOptionSPSPPS structure to the mfxVideoParam structure.

Return Status

MFX_ERR_NONE The function successfully filled mfxVideoParam

structure. It does not mean that the stream can be decoded by SDK. The application should call MFXVideoDECODE Query function to check if

decoding of the stream is supported.

MFX ERR MORE DATA The function requires more bitstream data.

Change History

This function is available since SDK API 1.0.



MFXVideoDECODE_Query

Syntax

mfxStatus MFXVideoDECODE Query(mfxSession session, mfxVideoParam *in, mfxVideoParam *out);

Parameters

| session | SDK session handle |
|---------|---|
| in | Pointer to the mfxVideoParam structure as input |
| out | Pointer to the mfxVideoParam structure as output |

Description

This function works in one of two modes:

- 1. If the in pointer is zero, the function returns the class configurability in the output mfxVideoParam structure. A non-zero value in each field of the output structure indicates that the field is configurable by the SDK implementation with the MFXVideoDECODE Init function).
- 2. If the in parameter is non-zero, the function checks the validity of the fields in the input mfxVideoParam structure. Then the function returns the corrected values to the output mfxVideoParam structure. If there is insufficient information to determine the validity or correction is impossible, the function zeros the fields. This feature can verify whether the SDK implementation supports certain profiles, levels or bitrates.

The application can call this function before or after it initializes the decoder. The CodecId field of the output mfxVideoParam structure is a mandated field (to be filled by the application) to identify the coding standard.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_UNSUPPORTED | The function failed to identify a specific implementation. |
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters; The decoding may be partially accelerated. Only SDK HW implementations may return this status code. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |



Change History

This function is available since SDK API 1.0.

MFXVideoDECODE_QueryIOSurf

Syntax

mfxStatus MFXVideoDECODE_QueryIOSurf(mfxSession session, mfxVideoParam
*par, mfxFrameAllocRequest *request);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure as input

request Pointer to the mfxFrameAllocRequest Structure

as output

Description

The function returns minimum and suggested numbers of the output frame surfaces required for decoding initialization and their type. **Init** will call the external allocator for the required frames with the same set of numbers.

The use of this function is recommended. For more information, see the section Working with hardware acceleration.

The CodecId field of the mfxVideoParam structure is a mandated field (to be filled by the application) to identify the coding standard.

This function does not validate I/O parameters except those used in calculating the number of output surfaces.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|------------------------------|---|
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters; The decoding may be partially accelerated. Only SDK HW implementations may return this status code. |
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. |



MFX_WRN_INCOMPATIBLE_VIDEO_P

The function detected some video parameters were incompatible with others; incompatibility resolved.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE Init

Syntax

mfxStatus MFXVideoDECODE Init(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure

Description

This function allocates memory and prepares tables and necessary structures for decoding. This function also does extensive validation to determine whether the configuration is supported as specified in the input parameters.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|--|
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters; The decoding may be partially accelerated. Only SDK hardware implementations return this status code. |
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of parameters resulted in an incompatibility error. Incompatibility was not resolved. |
| MFX_WRN_INCOMPATIBLE_VIDEO_ PARAM | The function detected some video parameters were incompatible; Incompatibility resolved. |
| MFX_ERR_UNDEFINED_BEHAVIOR | The function is called twice without a close. |

Change History



This function is available since SDK API 1.0.

MFXVideoDECODE Reset

Syntax

mfxStatus MFXVideoDECODE Reset(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure

Description

This function stops the current decoding operation and restores internal structures or parameters for a new decoding operation.

Reset serves two purposes:

- It recovers the decoder from errors.
- It restarts decoding from a new position.

The function resets the old sequence header (sequence parameter set in H.264, or sequence header in MPEG-2 and VC-1). The decoder will expect a new sequence header before it decodes the next frame and will skip any bitstream before encountering the new sequence header.

Return Status

MEN EDD NONE

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected that video parameters are wrong or they conflict with initialization parameters. Reset is impossible. |
| MFX_ERR_INCOMPATIBLE_VIDEO_ PARAM | The function detected that provided by the application video parameters are incompatible with initialization parameters. Reset requires additional memory allocation and cannot be executed. The application should close the SDK component and then reinitialize it. |
| MFX_WRN_INCOMPATIBLE_VIDEO_ PARAM | The function detected some video parameters were incompatible; Incompatibility resolved. |

Change History



This function is available since SDK API 1.0.

MFXVideoDECODE Close

Syntax

mfxStatus MFXVideoDECODE Close(mfxSession session);

Parameters

session

SDK session handle

Description

This function terminates the current decoding operation and de-allocates any internal tables or structures.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE GetVideoParam

Syntax

mfxStatus
*par);
MFXVideoDECODE_GetVideoParam(mfxSession session, mfxVideoParam
mfxVideoParam

Parameters

session

SDK session handle

par

Pointer to the corresponding parameter structure

Description

This function retrieves current working parameters to the specified output structure. If extended buffers are to be returned, the application must allocate those extended buffers and attach them as part of the output structure.

The application can retrieve a copy of the bitstream header, by attaching the mfxExtCodingOptionSPSPPS structure to the mfxVideoParam structure.



Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE GetDecodeStat

Syntax

```
mfxStatus
*stat);
MFXVideoDECODE_GetDecodeStat(mfxSession session, mfxDecodeStat
```

Parameters

session

SDK session handle

stat

Pointer to the mfxDecodeStat structure

Description

This function obtains statistics collected during decoding.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE_GetPayload

Syntax

```
mfxStatus MFXVideoDECODE_GetPayload(mfxSession session, mfxU64 *ts,
mfxPayload *payload);
```

Parameters

session SDK session handle

Pointer to the user data time stamp in units of 90 KHz; divide ts by

90,000 (90 KHz) to obtain the time in seconds; the time stamp



matches the payload with a specific decoded frame.

payload

Pointer to the mfxPayload structure; the payload contains user data in MPEG-2 or SEI messages in H.264.

Description

This function extracts user data (MPEG-2) or SEI (H.264) messages from the bitstream. Internally, the decoder implementation stores encountered user data or SEI messages. The application may call this function multiple times to retrieve the user data or SEI messages, one at a time.

If there is no payload available, the function returns with $payload \rightarrow NumBit=0$.

Return Status

MFX ERR NONE The function completed successfully and the

output buffer is ready for decoding.

MFX ERR NOT ENOUGH BUFFER The payload buffer size is insufficient.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE SetSkipMode

Syntax

mfxStatus MFXVideoDECODE SetSkipMode (mfxSession session, mfxSkipMode mode);

Parameters

session SDK session handle

mode Decoder skip mode. See the mfxSkipMode

enumerator for details.

Description

This function sets the decoder skip mode. The application may use it to increase decoding performance by sacrificing output quality. The rising of skip level firstly results in skipping of some decoding operations like deblocking and then leads to frame skipping; firstly, B then P. Particular details are platform dependent.

Return Status

MFX ERR NONE The function completed successfully and the



output surface is ready for decoding.

MFX WRN VALUE NOT CHANGED

The skip mode is not affected as the maximum or minimum skip range is reached.

Change History

This function is available since SDK API 1.0.

MFXVideoDECODE DecodeFrameAsync

Syntax

```
mfxStatus MFXVideoDECODE DecodeFrameAsync(mfxSession session,
mfxBitstream *bs, mfxFrameSurface1 *surface work, mfxFrameSurface1
**surface out, mfxSyncPoint *syncp);
```

Parameters

| Session | SDK session handle |
|--------------|---|
| Bs | Pointer to the input bitstream |
| surface_work | Pointer to the working frame buffer for the decoder |
| surface_out | Pointer to the output frame in the display order |
| Syncp | Pointer to the sync point associated with this |

operation

Description

This function decodes the input bitstream to a single output frame.

The surface work parameter provides a working frame buffer for the decoder. The application should allocate the working frame buffer, which stores decoded frames. If the function requires caching frames after decoding, the function locks the frames and the application must provide a new frame buffer in the next call.

If, and only if, the function returns MFX ERR NONE, the pointer surface out points to the output frame in the display order. If there are no further frames, the function will reset the pointer to zero and return the appropriate status code.

Before decoding the first frame, a sequence header—sequence parameter set in H.264 or sequence header in MPEG-2 and VC-1—must be present. The function skips any bitstreams before it encounters the new sequence header.

The input bitstream bs can be of any size. If there are not enough bits to decode a frame, the function returns MFX ERR MORE DATA, and consumes all input bits except if a partial start code or sequence header is at the end of the buffer. In this case, the



API Version 1.17

function leaves the last few bytes in the bitstream buffer. If there is more incoming bitstream, the application should append the incoming bitstream to the bitstream buffer. Otherwise, the application should ignore the remaining bytes in the bitstream buffer and apply the end of stream procedure described below.

The application must set bs to <code>NULL</code> to signal end of stream. The application may need to call this function several times to drain any internally cached frames until the function returns <code>MFX ERR MORE DATA</code>.

If more than one frame is in the bitstream buffer, the function decodes until the buffer is consumed. The decoding process can be interrupted for events such as if the decoder needs additional working buffers, is readying a frame for retrieval, or encountering a new header. In these cases, the function returns appropriate status code and moves the bitstream pointer to the remaining data.

The decoder may return MFX ERR NONE without taking any data from the input bitstream buffer. If the application appends additional data to the bitstream buffer, it is possible that the bitstream buffer may contain more than 1 frame. It is recommended that the application invoke the function repeatedly until the function returns MFX ERR MORE DATA, before appending any more data to the bitstream buffer.

This function is asynchronous.

Return Status

| MFX_ERR_NONE | The function completed successfully and the output surface is ready for decoding. |
|----------------------------------|--|
| MFX_ERR_MORE_DATA | The function requires more bitstream at input before decoding can proceed. |
| MFX_ERR_MORE_SURFACE | The function requires more frame surface at output before decoding can proceed. |
| MFX_ERR_DEVICE_LOST | Hardware device was lost; See the <u>Working</u> <u>with Microsoft* DirectX* Applications</u> section for further information. |
| MFX_WRN_DEVICE_BUSY | Hardware device is currently busy. Call this function again in a few milliseconds. |
| MFX_WRN_VIDEO_PARAM_CHANGED | The decoder detected a new sequence header in the bitstream. Video parameters may have changed. |
| MFX_ERR_INCOMPATIBLE_VIDEO_PARAM | The decoder detected incompatible video parameters in the bitstream and failed to follow them. |

Change History

This function is available since SDK API 1.0.



MFXVideoVPP

This class of functions performs video processing before encoding.

| _ | _ | | | | _ | | | | | | | |
|---|----|---|---|----|---|---|---|---|----|---|---|---|
| N | 70 | m | h | ar | | ш | n | ~ | ٠ī | ^ | n | c |
| | | | | | | ш | | • | _ | u | | - |

| MFXVideoVPP Query | Queries the feature capability |
|------------------------------|---|
| MFXVideoVPP QueryIOSurf | Queries the number of input and output surface frames required for video processing |
| MFXVideoVPP Init | Initializes the VPP operation |
| MFXVideoVPP Reset | Resets the current video processing operation and prepares for the next operation |
| MFXVideoVPP Close | Terminates the video processing operation and de- allocates internal memory |
| MFXVideoVPP GetVideoParam | Obtains the current working parameter set |
| MFXVideoVPP GetVPPStat | Obtains statistics collected during video processing |
| MFXVideoVPP RunFrameVPPAsync | Performs video processing on the frame level |

MFXVideoVPP_Query

Syntax

```
mfxStatus MFXVideoVPP_Query(mfxSession session, mfxVideoParam *in,
mfxVideoParam *out);
```

Parameters

| session | SDK session handle |
|---------|---|
| in | Pointer to the mfxVideoParam structure as input |
| out | Pointer to the <pre>mfxVideoParam</pre> structure as output |

Description

This function works in either of two modes:

1. If in is zero, the function returns the class configurability in the output



- mfxVideoParam structure. A non-zero value in a field indicates that the SDK implementation can configure it with **Init**.
- 2. If in is non-zero, the function checks the validity of the fields in the input mfxVideoParam structure. Then the function returns the corrected values in the output mfxVideoParam structure. If there is insufficient information to determine the validity or correction is impossible, the function zeroes the

The application can call this function before or after it initializes the preprocessor.

Return Status

MFX ERR NONE The function completed successfully. MFX ERR UNSUPPORTED The SDK implementation does not support the specified configuration. MFX WRN PARTIAL ACCELERATION The underlying hardware does not fully support the specified video parameters; The video processing may be partially accelerated. Only SDK HW implementations may return this status code. MFX WRN INCOMPATIBLE VIDEO PARAM The function detected some video parameters were incompatible with others; incompatibility resolved.

Change History

This function is available since SDK API 1.0.

MFXVideoVPP_QueryIOSurf

Syntax

mfxStatus MFXVideoVPP QueryIOSurf(mfxSession session, mfxVideoParam *par, mfxFrameAllocRequest request[2]);

Parameters

| session | SDK session handle |
|---------|---|
| par | Pointer to the mfxVideoParam structure as input |
| request | Pointer to the output mfxFrameAllocRequest structure; use request [0] for input requirements and request [1] for output requirements for video processing. |



This function returns minimum and suggested numbers of input and output frame surfaces required for video processing initialization and their type. The parameter request[0] refers to the input requirements; request[1] refers to output requirements. **Init** will call the external allocator for the required frames with the same set of numbers.

The function is recommended. For more information, see the Working with hardware acceleration.

This function does not validate I/O parameters except those used in calculating the number of input and output surfaces.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|----------------------------------|---|
| MFX_WRN_PARTIAL_ACCELERATION | The underlying hardware does not fully support the specified video parameters; The video processing may be partially accelerated. Only SDK HW implementation may return this status code. |
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. |
| MFX_WRN_INCOMPATIBLE_VIDEO_PARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.0.

MFXVideoVPP Init

Syntax

mfxStatus MFXVideoVPP_Init(mfxSession session, mfxVideoParam *par);

Parameters

Session SDK session handle

Par Pointer to the mfxVideoParam structure



This function allocates memory and prepares tables and necessary structures for video processing. This function also does extensive validation to ensure the configuration, as specified in the input parameters, is supported.

Return Status

MFX ERR NONE The function completed successfully. MFX WRN PARTIAL ACCELERATION The underlying hardware does not fully support the specified video parameters; The video processing may be partially accelerated. Only SDK HW implementation may return this status code. MFX ERR INVALID VIDEO PARAM The function detected invalid video parameters. These parameters may be out of the valid range, or the combination of them resulted in incompatibility. Incompatibility not resolved. MFX WRN INCOMPATIBLE VIDEO PARAM The function detected some video parameters were incompatible with others; incompatibility resolved. MFX ERR UNDEFINED BEHAVIOR The function was called twice without a close. MFX WRN FILTER SKIPPED The VPP skipped one or more filters requested by the application.

Change History

This function is available since SDK API 1.0. SDK API 1.6 added new return status, MFX WRN FILTER SKIPPED.

MFXVideoVPP Reset

Syntax

mfxStatus MFXVideoVPP Reset(mfxSession session, mfxVideoParam *par);

Parameters

session SDK session handle

par Pointer to the mfxVideoParam structure



This function stops the current video processing operation and restores internal structures or parameters for a new operation.

Return Status

| MFX_ERR_NONE | The function completed successfully. |
|--------------------------------------|---|
| MFX_ERR_INVALID_VIDEO_PARAM | The function detected that video parameters are wrong or they conflict with initialization parameters. Reset is impossible. |
| MFX_ERR_INCOMPATIBLE_VIDEO_P ARAM | The function detected that provided by the application video parameters are incompatible with initialization parameters. Reset requires additional memory allocation and cannot be executed. The application should close the SDK component and then reinitialize it. |
| MFX_WRN_INCOMPATIBLE_VIDEO_P ARAM | The function detected some video parameters were incompatible with others; incompatibility resolved. |

Change History

This function is available since SDK API 1.0.

MFXVideoVPP Close

Syntax

mfxStatus MFXVideoVPP Close(mfxSession session);

Parameters

session

SDK session handle

Description

This function terminates the current video processing operation and de-allocates internal tables and structures.

Return Status

MFX ERR NONE

The function completed successfully.

Change History



This function is available since SDK API 1.0.

MFXVideoVPP GetVideoParam

Syntax

```
mfxStatus MFXVideoVPP GetVideoParam(mfxSession session, mfxVideoParam
```

Parameters

session SDK session handle

par Pointer to the corresponding parameter structure

Description

This function obtains current working parameters to the specified output structure. To return extended buffers, the application must allocate those extended buffers and attach them as part of the output structure.

Return Status

MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoVPP GetVPPStat

Syntax

```
mfxStatus MFXVideoVPP GetVPPStat(mfxSession session, mfxVPPStat *stat);
```

Parameters

session SDK session handle

stat Pointer to the mfxVPPStat structure

Description

This function obtains statistics collected during video processing.

Return Status



MFX ERR NONE

The function completed successfully.

Change History

This function is available since SDK API 1.0.

MFXVideoVPP_RunFrameVPPAsync

Syntax

```
mfxStatus MFXVideoVPP RunFrameVPPAsync (mfxSession session,
mfxFrameSurface1 *in, mfxFrameSurface1 *out, mfxExtVppAuxData *aux,
mfxSyncPoint *syncp);
```

Parameters

| session | SDK session handle |
|---------|--|
| in | Pointer to the input video surface structure |
| out | Pointer to the output video surface structure |
| aux | Optional pointer to the auxiliary data structure |
| syncp | Pointer to the output sync point |

Description

This function processes a single input frame to a single output frame. Retrieval of the auxiliary data is optional; the encoding process may use it.

The video processing process may not generate an instant output given an input. See section Video Processing Procedures for details on how to correctly send input and retrieve output.

At the end of the stream, call this function with the input argument in=NULL to retrieve any remaining frames, until the function returns MFX ERR MORE DATA.

This function is asynchronous.

Return Status

| MFX_ERR_NONE | The output frame is ready after synchronization. |
|----------------------|--|
| MFX_ERR_MORE_DATA | Need more input frames before VPP can produce an output |
| MFX_ERR_MORE_SURFACE | The output frame is ready after synchronization. Need more surfaces at output for additional output |



frames available.

MFX_ERR_DEVICE_LOST Hardware device was lost; See the Working with

Microsoft* DirectX* Applications section for further

information.

MFX_WRN_DEVICE_BUSY Hardware device is currently busy. Call this

function again in a few milliseconds.

Change History

76

This function is available since SDK API 1.0.



Structure Reference

In the following structure references, all reserved fields must be zero.

mfxBitstream

Definition

```
typedef struct mfxBitStream {
   union {
       struct {
           mfxEncryptedData* EncryptedData;
           mfxExtBuffer **ExtParam;
           mfxU16 NumExtParam;
       };
       mfxU32 reserved[6];
         mfxI64 DecodeTimeStamp;
   mfxU64 TimeStamp;
   mfxU8* Data;
   mfxU32 DataOffset;
   mfxU32 DataLength;
   mfxU32 MaxLength;
   mfxU16 PicStruct;
   mfxU16 FrameType;
   mfxU16 DataFlag;
   mfxU16 reserved2;
} mfxBitstream;
```

Description

The mfxBitstream structure defines the buffer that holds compressed video data.

Members

EncryptedData Reserved and must be zero.



ExtParam Array of extended buffers for additional bitstream configuration. See

the ExtendedBufferID enumerator for a complete list of extended

buffers.

NumExtParam The number of extended buffers attached to this structure.

DecodeTimeStamp Decode time stamp of the compressed bitstream in units of 90KHz. A

value of MFX TIMESTAMP UNKNOWN indicates that there is no time

stamp.

This value is calculated by the SDK encoder from presentation time stamp provided by the application in mfxFrameSurface1 structure and from frame rate provided by the application during the SDK encoder

initialization.

TimeStamp Time stamp of the compressed bitstream in units of 90KHz. A value of

MFX TIMESTAMP UNKNOWN indicates that there is no time stamp.

Data Bitstream buffer pointer—32-bytes aligned

DataOffset Next reading or writing position in the bitstream buffer

DataLength Size of the actual bitstream data in bytes

MaxLength Allocated bitstream buffer size in bytes

PicStruct Type of the picture in the bitstream; this is an output parameter.

FrameType Frame type of the picture in the bitstream; this is an output

parameter.

DataFlag Indicates additional bitstream properties; see the BitstreamDataFlag

enumerator for details.

Change History

This structure is available since SDK API 1.0.

SDK API 1.1 extended the DataFlag field definition.

SDK API 1.6 adds DecodeTimeStamp field.

SDK API 1.7 adds ExtParam and NumExtParam fields.

mfxBufferAllocator

Definition



The mfxBufferAllocator structure is deprecated.

Members

| pthis | Pointer to the allocator object |
|--------|---|
| Alloc | Pointer to the function that allocates a linear buffer |
| Lock | Pointer to the function that locks a memory block and returns the pointer to the buffer |
| Unlock | Pointer to the function that unlocks a linear buffer; after unlocking, any pointer to the linear buffer is invalid. |
| Free | Pointer to the function that de-allocates memory |

Change History

This structure is available since SDK API 1.0.

Deprecated since API 1.17

Alloc

Syntax

```
mfxStatus
*mid);
(*Alloc)(mfxHDL pthis, mfxU32 nbytes, mfxU16 type, mfxMemId
```

Parameters

pthis

Pointer to the allocator object



nbytes Number of bytes in the linear buffer

Memory type; see the **ExtMemBufferType** enumerator type

for details.

mid Pointer to the allocated memory ID

Description

This function allocates a linear buffer and returns its block ID. The allocated memory must be 32-byte aligned.

Return Status

MFX ERR NONE The function successfully allocated the memory block.

MFX ERR MEMORY ALLOC The function ran out of the specified type of memory.

Change History

This function is available since SDK API 1.0.

Free

Syntax

mfxStatus (*Free) (mfxHDL pthis, mfxMemId mid);

Parameters

pthis Pointer to the allocator object

mid Memory block ID

Description

This function de-allocates memory specified by mid.

Return Status

The function successfully de-allocated the memory block. MFX ERR NONE

MFX ERR_INVALID_HANDLE The memory block ID is invalid.

Change History

This function is available since SDK API 1.0.



Lock

Syntax

```
mfxStatus (*Lock) (mfxHDL pthis, mfxMemId mid, mfxU8 **ptr);
```

Parameters

pthis Pointer to the allocator object

mid Memory block ID

ptr Pointer to the returned linear buffer pointer

Description

This function locks the linear buffer and returns its pointer. The returned buffer must be 32-byte aligned.

Return Status

MFX ERR NONE The function successfully locked the memory block.

MFX ERR INVALID HANDLE The memory block ID is invalid.

MFX ERR LOCK MEMORY The function failed to lock the linear buffer.

Change History

This function is available since SDK API 1.0.

Unlock

Syntax

```
mfxStatus (*Unlock) (mfxHDL pthis, mfxMemId mid);
```

Parameters

pthis Pointer to the allocator object

mid Memory block ID

Description

This function unlocks the linear buffer and invalidates its pointer.



Return Status

```
MFX_ERR_NONE The function successfully unlocked the memory block.

MFX_ERR_INVALID_HANDLE The memory block ID is invalid.
```

Change History

This function is available since SDK API 1.0.

mfxDecodeStat

Definition

Description

The mfxDecodeStat structure returns statistics collected during decoding.

Members

NumFrame Number of total decoded frames

NumSkippedFrame Number of skipped frames

NumError Number of errors recovered

NumCachedFrame Number of internally cached frames

Change History

This structure is available since SDK API 1.0.



mfxEncodeCtrl

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU32 reserved[5];
    mfxU16 SkipFrame;

    mfxU16 QP;

    mfxU16 FrameType;
    mfxU16 NumExtParam;
    mfxU16 NumPayload;
    mfxU16 reserved2;

    mfxExtBuffer **ExtParam;
    mfxPayload **Payload;
} mfxEncodeCtrl;
```

Description

The mfxEncodeCtrl structure contains parameters for per-frame based encoding control.

Members

| cinibers | |
|-------------|---|
| SkipFrame | Indicates that current frame should be skipped or number of missed frames before the current frame. See the <pre>mfxExtCodingOption2::SkipFrame</pre> for details. |
| QP | If nonzero, this value overwrites the global QP value for the current frame in the constant QP mode. |
| FrameType | Encoding frame type; see the <u>FrameType</u> enumerator for details. If the encoder works in the encoded order, the application must specify the frame type. If the encoder works in the display order, only key frames are enforceable. |
| NumExtParam | Number of extra control buffers. |
| NumPayload | Number of payload records to insert into the bitstream. |
| ExtParam | Pointer to an array of pointers to external buffers that provide additional information or control to the encoder for this frame or field pair; a typical usage is to pass the VPP auxiliary data generated by the video processing pipeline to the encoder. See the ExtendedBufferID for the list of extended buffers. |

Pointer to an array of pointers to user data (MPEG-2) or SEI

messages (H.264) for insertion into the bitstream; for field pictures, odd payloads are associated with the first field and even payloads are associated with the second field. See the mfxPayload structure

Payload



for payload definitions.

Change History

This structure is available since SDK API 1.0. SDK API 1.1 extended the QP field. Since SDK API 1.3 specification of QP in display order mode is allowed.

mfxEncodeStat

Definition

Description

The mfxEncodeStat structure returns statistics collected during encoding.

Members

NumFrame Number of encoded frames

NumCachedFrame Number of internally cached frames

NumBit Number of bits for all encoded frames

Change History

This structure is available since SDK API 1.0.

mfxExtBuffer

Definition

```
typedef struct _mfxExtBuffer {
    mfxU32 BufferId;
```



```
mfxU32 BufferSz;
} mfxExtBuffer;
```

The mfxExtBuffer structure is the common header definition for external buffers and video processing hints.

Members

BufferId Identifier of the buffer content. See the ExtendedBufferID

enumerator for a complete list of extended buffers.

BufferSz Size of the buffer

Change History

This structure is available since SDK API 1.0.

mfxExtAVCRefListCtrl

Definition

```
typedef struct {
   mfxExtBuffer
                    Header;
   mfxU16
                    NumRefIdxL0Active;
   mfxU16
                    NumRefIdxL1Active;
    struct {
       mfxU32
                    FrameOrder;
       mfxU16
                    PicStruct;
       mfxU16
                    ViewId;
       mfxU16
                    LongTermIdx;
       mfxU16
                    reserved[3];
    } PreferredRefList[32], RejectedRefList[16], LongTermRefList[16];
                ApplyLongTermIdx;
   mfxU16
   mfxU16
                reserved[15];
} mfxExtAVCRefListCtrl;
```

Description

The mfxExtAVCRefListCtrl structure configures reference frame options for the



H.264 encoder. See Reference List Selection and Long-term Reference frame chapters for more details.

Not all implementations of the SDK encoder support LongTermIdx and ApplyLongTermIdx fields in this structure. The application has to use query mode 1 to determine if such functionality is supported. To do so, the application has to attach this extended buffer to mfxVideoParam structure and call MFXVideoENCODE Query function. If function returns MFX ERR NONE and these fields were set to one, then such functionality is supported. If function fails or sets fields to zero then this functionality is not supported.

Members

| Header.BufferId | Must be MFX EXTBUFF AVC REFLIST CTRL |
|-------------------|--|
| NumRefIdxL0Active | Specify the number of reference frames in the active reference list LO. This number should be less or equal to the NumRefFrame parameter from encoding initialization. |
| NumRefIdxL1Active | Specify the number of reference frames in the active reference list L1. This number should be less or equal to the NumRefFrame parameter from encoding initialization. |
| PreferredRefList | Specify list of frames that should be used to predict the current frame. |
| RejectedRefList | Specify list of frames that should not be used for prediction. |
| LongTermRefList | Specify list of frames that should be marked as long-term reference frame. |
| FrameOrder | Together these fields are used to identify reference picture. |
| PicStruct | Use FrameOrder = MFX_FRAMEORDER_UNKNOWN to mark unused entry. |
| ViewID | Reserved and must be zero. |
| LongTermIdx | Index that should be used by the SDK encoder to mark long-term reference frame. |
| ApplyLongTermIdx | If it is equal to zero, the SDK encoder assigns long-term index according to internal algorithm. If it is equal to one, the SDK encoder uses ${\tt LongTermIdx}$ value as long-term index. |

Change History

This structure is available since SDK API 1.3.

The SDK API 1.7 adds LongTermIdx and ApplyLongTermIdx fields.



mfxExtAVCRefLists

Definition

```
typedef struct {
   mfxExtBuffer
                    Header;
   mfxU16
                    NumRefIdxL0Active;
   mfxU16
                    NumRefIdxL1Active;
   mfxU16
                    reserved[2];
    struct mfxRefPic{
        mfxU32
                    FrameOrder;
        mfxU16
                    PicStruct;
       mfxU16
                    reserved[5];
    } RefPicList0[32], RefPicList1[32];
}mfxExtAVCRefLists;
```

Description

The mfxExtAVCRefLists structure specifies reference lists for the SDK encoder. It may be used together with the mfxExtAVCRefListCtrl structure to create customized reference lists. If both structures are used together, then the SDK encoder takes reference lists from mfxExtAVCRefLists structure and modifies them according to the mfxExtAVCRefListCtrl instructions.

Not all implementations of the SDK encoder support this structure. The application has to use query function to determine if it is supported

Members

| Header.BufferId | Must be MFX EXTBUFF AVC REFLISTS |
|-----------------------------|--|
| NumRefIdxL0Active | Specify the number of reference frames in the active reference list LO. This number should be less or equal to the NumRefFrame parameter from encoding initialization. |
| NumRefIdxL1Active | Specify the number of reference frames in the active reference list L1. This number should be less or equal to the NumRefFrame parameter from encoding initialization. |
| RefPicList0, RefPicList1 | Specify L0 and L1 reference lists. |
| FrameOrder | Together these fields are used to identify reference picture. |



PicStruct Use FrameOrder = MFX FRAMEORDER UNKNOWN to mark unused

entry.

Only progressive frames are supported for now.

Change History

This structure is available since SDK API 1.9.

mfxExtCodingOption

Definition

```
typedef struct {
     mfxExtBuffer
                        Header;
     mfxU16
                        reserved1;
     mfxU16
                        RateDistortionOpt;
     mfxU16
                        MECostType;
     mfxU16
                        MESearchType;
     mfxI16Pair
                        MVSearchWindow;
     mfxU16
                        EndOfSequence;
     mfxU16
                        FramePicture;
      union {
                              /* AVC */
            struct
                  mfxU16
                              CAVLC;
                  mfxU16
                              reserved2[2];
                  mfxU16
                               RecoveryPointSEI;
                  mfxU16
                               ViewOutput;
                  mfxU16
                              NalHrdConformance;
                  mfxU16
                               SingleSeiNalUnit;
                  mfxU16
                               VuiVclHrdParameters;
                  mfxU16
                               RefPicListReordering;
                  mfxU16
                               ResetRefList;
                  mfxU16
                               RefPicMarkRep;
```



```
mfxU16
                               FieldOutput;
                  mfxU16
                               IntraPredBlockSize;
                  mfxU16
                               InterPredBlockSize;
                  mfxU16
                              MVPrecision;
                  mfxU16
                               MaxDecFrameBuffering;
                  mfxU16
                               AUDelimiter;
                  mfxU16
                               EndOfStream;
                  mfxU16
                               PicTimingSEI;
                  mfxU16
                               VuiNalHrdParameters;
            };
      };
} mfxExtCodingOption;
```

The mfxExtCodingOption structure specifies additional options for encoding.

The application can attach this extended buffer to the mfxVideoParam structure to configure initialization.

Members

| Header.BufferId | Must be MFX EXTBUFF CODING OPTION |
|-------------------|---|
| RateDistortionOpt | Set this flag if rate distortion optimization is needed. See the CodingOptionValue enumerator for values of this option. |
| MECostType | Motion estimation cost type; this value is reserved and must be zero. |
| MESearchType | Motion estimation search algorithm; this value is reserved and must be zero. |
| MVSearchWindow | Rectangular size of the search window for motion estimation; this parameter is reserved and must be $(0, 0)$. |
| EndOfSequence | Deprecated. |
| CAVLC | If set, CAVLC is used; if unset, CABAC is used for encoding. See the CodingOptionValue enumerator for values of this option. |
| NalHrdConformance | If this option is turned ON, then AVC encoder produces HRD conformant bitstream. If it is turned OFF, then AVC encoder may, but not necessary does, violate HRD conformance. I.e. this option can force encoder to produce HRD conformant |



stream, but cannot force it to produce unconformant stream. See the CodingOptionValue enumerator for values of this option.

SingleSeiNalUnit

If set, encoder puts all SEI messages in the singe NAL unit. It includes both kinds of messages, provided by application and created by encoder. It is three states option, see CodingOptionValue enumerator for values of this option:

UNKNOWN - put each SEI in its own NAL unit,

ON - put all SEI messages in the same NAL unit,

OFF - the same as unknown

VuiVclHrdParameters If set and VBR rate control method is used then VCL HRD

> parameters are written in bitstream with identical to NAL HRD parameters content. See the CodingOptionValue enumerator

for values of this option.

RefPicListReordering Set this flag to activate reference picture list reordering; this

value is reserved and must be zero.

ResetRefList Set this flag to reset the reference list to non-IDR I-frames of

a GOP sequence. See the CodingOptionValue enumerator for

values of this option.

RefPicMarkRep Set this flag to write the reference picture marking repetition

SEI message into the output bitstream. See the

CodingOptionValue enumerator for values of this option.

FieldOutput Set this flag to instruct the AVC encoder to output bitstreams

> immediately after the encoder encodes a field, in the fieldencoding mode. See the CodingOptionValue enumerator for

values of this option.

ViewOutput Set this flag to instruct the MVC encoder to output each view

> in separate bitstream buffer. See the CodingOptionValue enumerator for values of this option and SDK Reference Manual for Multi-View Video Coding for more details about

usage of this flag.

IntraPredBlockSize Minimum block size of intra-prediction; This value is reserved

and must be zero.

InterPredBlockSize Minimum block size of inter-prediction; This value is reserved

and must be zero.

MVPrecision Specify the motion estimation precision; this parameter is

reserved and must be zero.



MaxDecFrameBuffering Specifies the maximum number of frames buffered in a DPB.

A value of zero means "unspecified."

AUDelimiter Set this flag to insert the Access Unit Delimiter NAL. See the

CodingOptionValue enumerator for values of this option.

EndOfStream Deprecated.

PicTimingSEI Set this flag to insert the picture timing SEI with pic_struct

syntax element. See sub-clauses D.1.2 and D.2.2 of the ISO*/IEC* 14496-10 specification for the definition of this syntax element. See the CodingOptionValue enumerator for

values of this option. The default value is ON.

VuiNalHrdParameters Set this flag to insert NAL HRD parameters in the VUI header.

See the CodingOptionValue enumerator for values of this

option.

FramePicture Set this flag to encode interlaced fields as interlaced frames;

this flag does not affect progressive input frames. See the CodingOptionValue enumerator for values of this option.

RecoveryPointSEI Set this flag to insert the recovery point SEI message at the

beginning of every intra refresh cycle. See the description of IntRefType in mfxExtCodingOption2 structure for details on

how to enable and configure intra refresh.

If intra refresh is not enabled then this flag is ignored.

See the CodingOptionValue enumerator for values of this

option.

Change History

This structure is available since SDK API 1.0.

SDK API 1.3 adds RefPicMarkRep, FieldOutput, NalHrdConformance, SingleSeiNalUnit and VuiVclHrdParameters fields.

SDK API 1.4 adds ViewOutput field.

SDK API 1.6 adds RecoveryPointSEI field.

SDK API 1.17 deprecates EndOfSequence and EndOfStream fields.



mfxExtCodingOption2

Definition

```
typedef struct {
   mfxExtBuffer Header;
   mfxU16
              IntRefType;
   mfxU16
mfxI16
              IntRefCycleSize;
             IntRefQPDelta;
            MaxFrameSize;
   mfxU32
   mfxU32
             MaxSliceSize;
          BitrateLimit;
MBBRC;
                                    /* tri-state option */
   mfxU16
   mfxU16
                                     /* tri-state option */
             ExtBRC;
   mfxU16
                                     /* tri-state option */
   mfxU16
             LookAheadDepth;
   mfxU16
             Trellis;
             RepeatPPS;
                                     /* tri-state option */
   mfxU16
             BRefType;
AdaptiveI;
   mfxU16
   mfxU16
mfxU16
                                    /* tri-state option */
             AdaptiveB;
                                     /* tri-state option */
   mfxU16 LookAheadDS;
mfxU16 NumMbPerSlice;
   mfxU16
             SkipFrame;
                                    /* 1..51, 0 = default */
   mfxU8
             MinQPI;
                                    /* 1..51, 0 = default */
   mfxU8
             MaxQPI;
            MinQPP;
MaxQPP;
MinQPB;
                                    /* 1..51, 0 = default */
   mfxU8
                                    /* 1..51, 0 = default */
   mfxU8
   mfxU8
                                    /* 1..51, 0 = default */
             MaxQPB;
                                    /* 1..51, 0 = default */
   mfxU8
             FixedFrameRate; /* tri-state option */
   mfxU16
   mfxU16
             DisableDeblockingIdc;
   mfxU16
             DisableVUI;
             BufferingPeriodSEI;
   mfxU16
                                    /* tri-state option */
   mfxU16
             EnableMAD;
              UseRawRef;
                                    /* tri-state option */
   mfxU16
} mfxExtCodingOption2;
```

Description

The mfxExtCodingOption2 structure together with mfxExtCodingOption structure specifies additional options for encoding.

The application can attach this extended buffer to the $\frac{mfxVideoParam}{deoParam}$ structure to configure initialization and to the $\frac{mfxEncodeCtrl}{deoParam}$ during runtime.

Members

| Header.BufferId | Must be MFX EXTBUFF CODING OPTION2. |
|-----------------|--|
| IntRefType | Specifies intra refresh type. The major goal of intra refresh is improvement of error resilience without significant impact on |



encoded bitstream size caused by I frames. The SDK encoder achieves this by encoding part of each frame in refresh cycle using intra MBs. Zero value means no refresh. One means vertical refresh, by column of MBs. This parameter is valid only during initialization. When used with temporal scalability, intra refresh applied only to base layer.

IntRefCycleSize

Specifies number of pictures within refresh cycle starting from 2. 0 and 1 are invalid values. This parameter is valid only during initialization

IntRefOPDelta

Specifies QP difference for inserted intra MBs. This is signed value in [-51, 51] range. This parameter is valid during initialization and runtime.

MaxFrameSize

Specify maximum encoded frame size in byte. This parameter is used in AVBR and VBR bitrate control modes and ignored in others. The SDK encoder tries to keep frame size below specified limit but minor overshoots are possible to preserve visual quality. This parameter is valid during initialization and runtime.

MaxSliceSize

Specify maximum slice size in bytes. If this parameter is specified other controls over number of slices are ignored.

Not all codecs and SDK implementations support this value. Use ouery function to check if this feature is supported.

BitrateLimit

Turn off this flag to remove bitrate limitations imposed by the SDK encoder. This flag is intended for special usage models and usually the application should not set it. Setting this flag may lead to violation of HRD conformance and severe visual artifacts. See the CodingOptionValue enumerator for values of this option. The default value is ON, i.e. bitrate is limitted. This parameter is valid only during initialization.

MBBRC

Setting this flag enables macroblock level bitrate control that generally improves subjective visual quality. Enabling this flag may have negative impact on performance and objective visual quality metric. See the CodingOptionValue enumerator for values of this option. The default value depends on target usage settings.

ExtBRC

Deprecated.

LookAheadDepth

Specifies the depth of look ahead rate control algorithm. It is the number of frames that SDK encoder analyzes before encoding. Valid value range is from 10 to 100 inclusive. To instruct the SDK encoder to use the default value the application should zero this field.

93 SDK API Reference Manual



Trellis This option is used to control trellis quantization in AVC

> encoder. See TrellisControl enumerator for possible values of this option. This parameter is valid only during initialization.

RepeatPPS This flag controls picture parameter set repetition in AVC

> encoder. Turn ON this flag to repeat PPS with each frame. See the CodingOptionValue enumerator for values of this option. The default value is ON. This parameter is valid only during

initialization.

BRefType This option controls usage of B frames as reference. See

BRefControl enumerator for possible values of this option.

This parameter is valid only during initialization.

AdaptiveI This flag controls insertion of I frames by the SDK encoder.

> Turn ON this flag to allow changing of frame type from P and B to I. This option is ignored if GopOptFlag in mfxInfoMFX

structure is equal to MFX GOP STRICT. See the

CodingOptionValue enumerator for values of this option. This

parameter is valid only during initialization.

AdaptiveB This flag controls changing of frame type from B to P. Turn ON

this flag to allow such changing. This option is ignored if

GopOptFlag in mfxInfoMFX structure is equal to

MFX GOP STRICT. See the CodingOptionValue enumerator for

values of this option. This parameter is valid only during

initialization.

LookAheadDS This option controls down sampling in look ahead bitrate

> control mode. See LookAheadDownSampling enumerator for possible values of this option. This parameter is valid only

during initialization.

NumMbPerSlice This option specifies suggested slice size in number of

> macroblocks. The SDK can adjust this number based on platform capability. If this option is specified, i.e. if it is not equal to zero, the SDK ignores mfxInfoMFX::NumSlice

parameter.

SkipFrame This option enables usage of mfxEncodeCtrl::SkipFrame

parameter. See the **SkipFrame** enumerator for values of this

option.

Not all codecs and SDK implementations support this value.

Use Query function to check if this feature is supported.

MinQPI, MaxQPI

Minimum and maximum allowed QP values for different frame MinQPP, MaxQPP types. Valid range is 1..51 inclusive. Zero means default MinQPB, MinQPB

value, i.e.no limitations on QP.

Not all codecs and SDK implementations support this value.



Use Query function to check if this feature is supported.

FixedFrameRate This option sets fixed_frame_rate_flag in VUI.

Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported.

DisableDeblockingIdc This option disable deblocking.

Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported.

Disable VUI This option completely disables VUI in output bitstream.

Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported.

BufferingPeriodSEI This option controls insertion of buffering period SEI in the

encoded bitstream. It should be one of the following values:

MFX_BPSEI_DEFAULT - encoder decides when to insert BP SEI,

MFX_BPSEI_IFRAME - BP SEI should be inserted with every I

frame.

EnableMAD Turn ON this flag to enable per-frame reporting of Mean

Absolute Difference. This parameter is valid only during

initialization.

UseRawRef Turn ON this flag to use raw frames for reference instead of

reconstructed frames. This parameter is valid during initialization and runtime (only if was turned ON during

initialization).

Not all codecs and SDK implementations support this value. Use **Query** function to check if this feature is supported.

Change History

This structure is available since SDK API 1.6.

The SDK API 1.7 added LookAheadDepth and Trellis fields.

The SDK API 1.8 adds RepeatPPS, BRefType, AdaptiveI, AdaptiveB, LookAheadDS and NumMbPerSlice fields.

The SDK API 1.9 adds MaxSliceSize, SkipFrame, MinQPI, MaxQPI, MinQPP, MaxQPP, MinQPB, MinQPB, FixedFrameRate and DisableDeblockingIdc fields.

The SDK API 1.10 adds DisableVUIfields and BufferingPeriodSEI fields.

The SDK API 1.11 adds EnableMAD field.

The SDK API 1.13 adds UseRawRef field.

The SDK API 1.17 deprecates ExtBRC field.



mfxExtCodingOption3

```
typedef struct {
   mfxExtBuffer Header;
   mfxU16
                NumSliceI;
   mfxU16
                NumSliceP;
                NumSliceB;
   mfxU16
   mfxU16
                WinBRCMaxAvgKbps;
   mfxU16
                WinBRCSize;
   mfxU16
                QVBRQuality;
   mfxU16
                EnableMBQP;
   mfxU16
                IntRefCycleDist;
   mfxU16
                DirectBiasAdjustment;
                                                /* tri-state option */
   mfxU16
                GlobalMotionBiasAdjustment;
                                               /* tri-state option */
                MVCostScalingFactor;
   mfxU16
   mfxU16
                MBDisableSkipMap;
                                                /* tri-state option */
   mfxU16
                WeightedPred;
   mfxU16
                WeightedBiPred;
   mfxU16
                AspectRatioInfoPresent;
                                                 /* tri-state option */
                OverscanInfoPresent;
                                                /* tri-state option */
   mfxU16
   mfxU16
                OverscanAppropriate;
                                                /* tri-state option */
   mfxU16
                TimingInfoPresent;
                                                 /* tri-state option */
                                                 /* tri-state option */
   mfxU16
                BitstreamRestriction;
                reserved1[4];
   mfxU16
   mfxU16
                ScenarioInfo;
                ContentInfo;
   mfxU16
```



```
mfxU16 PRefType;
mfxU16 FadeDetection;
mfxU16 reserved[225];
} mfxExtCodingOption3;
```

The mfxExtCodingOption3 structure together with mfxExtCodingOption and mfxExtCodingOption2 structures specifies additional options for encoding.

The application can attach this extended buffer to the $\underline{\texttt{mfxVideoParam}}$ structure to configure initialization and to the $\underline{\texttt{mfxEncodeCtrl}}$ during runtime.

Members

| Header.BufferId | Must be MFX EXTBUFF CODING OPTION3. |
|----------------------|--|
| NumSliceI | The number of slices for I, P and B frames separately. |
| NumSliceP | Not all codecs and SDK implementations support these |
| NumSliceB | values. Use Query function to check if this feature is supported |
| WinBRCMaxAvgKbps | When rate control method is $\underline{\texttt{MFX}}$ RATECONTROL LA or $\underline{\texttt{MFX}}$ RATECONTROL LA HRD this parameter specifies the maximum bitrate averaged over a sliding window specified by $\underline{\texttt{WinBRCSize}}$. |
| WinBRCSize | When rate control method is $\underline{\text{MFX}}$ RATECONTROL LA or $\underline{\text{MFX}}$ RATECONTROL LA HRD this parameter specifies sliding window size in frames. Set this parameter to zero to disable sliding window. |
| QVBRQuality | When rate control method is MFX_RATECONTROL_QVBR this parameter specifies quality factor. It is a value in the 151 range, where 1 corresponds to the best quality. |
| EnableMBQP | Turn ON this flag to enable per-macroblock QP control, rate control method must be MFX RATECONTROL CQP . See the CodingOptionValue enumerator for values of this option. This parameter is valid only during initialization. |
| IntRefCycleDist | Distance between the beginnings of the intra-refresh cycles in frames. Zero means no distance between cycles. |
| DirectBiasAdjustment | Turn ON this flag to enable the ENC mode decision |



algorithm to bias to fewer B Direct/Skip types. Applies only to B frames, all other frames will ignore this setting. See the CodingOptionValue enumerator for values of this option.

GlobalMotionBiasAdjustment

Enables global motion bias. See the CodingOptionValue

enumerator for values of this option.

MVCostScalingFactor

MV cost scaling ratio. It is used when GlobalMotionBiasAdjustment is ON.

Values are:

0: set MV cost to be 0

scale MV cost to be 1/2 of the default value
 scale MV cost to be 1/4 of the default value
 scale MV cost to be 1/8 of the default value

MBDisableSkipMap

Turn ON this flag to enable usage of mfxExtMBDisableSkipMap. See the CodingOptionValue enumerator for values of this option. This parameter is valid only during initialization.

WeightedPred
WeightedBiPred

Weighted prediction mode. See the <u>WeightedPred</u> enumerator for values of these options.

AspectRatioInfoPresent

Instructs encoder whether aspect ratio info should present in VUI parameters. See the CodingOptionValue enumerator for values of this option.

OverscanInfoPresent

Instructs encoder whether overscan info should present in VUI parameters. See the CodingOptionValue enumerator for values of this option.

OverscanAppropriate

ON indicates that the cropped decoded pictures output are suitable for display using overscan. OFF indicates that the cropped decoded pictures output contain visually important information in the entire region out to the edges of the cropping rectangle of the picture. See the CodingOptionValue enumerator for values of this option.

TimingInfoPresent

Instructs encoder whether frame rate info should present in VUI parameters. See the CodingOptionValue enumerator for values of this option.

BitstreamRestriction

Instructs encoder whether bitstream restriction info should present in VUI parameters. See the CodingOptionValue enumerator for values of this option.



ScenarioInfo Provides a hint to encoder about the scenario for the

encoding session. See the ScenarioInfo enumerator for

values of this option.

ContentInfo Provides a hint to encoder about the content for the

encoding session. See the **ContentInfo** enumerator for

values of this option.

PRefType When GopRefDist=1, specifies the model of reference list

construction and DPB management. See the **PRefType**

enumerator for values of this option.

FadeDetection Instructs encoder whether internal fade detection algorithm

should be used for calculation of weigh/offset values for

pred_weight_table unless application provided
mfxExtPredWeightTable for this frame. See the

CodingOptionValue enumerator for values of this option.

Change History

This structure is available since SDK API 1.11.

The SDK API 1.13 adds EnableMBQP, MBDisableSkipMap, DirectBiasAdjustment, GlobalMotionBiasAdjustment and MVCostScalingFactor fields.

The SDK API 1.16 adds IntRefCycleDist, WeightedPred, WeightedBiPred, AspectRatioInfoPresent, OverscanInfoPresent, OverscanAppropriate, TimingInfoPresent, BitstreamRestriction, ScenarioInfo, ContentInfo, PRefType fields.

The SDK API 1.17 adds FadeDetection field.

mfxExtCodingOptionSPSPPS

```
struct {
    mfxExtBuffer Header;
    mfxU8 *SPSBuffer;
    mfxU8 *PPSBuffer;
    mfxU16 SPSBufSize;
    mfxU16 PPSBufSize;
    mfxU16 SPSId;
    mfxU16 PPSId;
```



} mfxExtCodingOptionSPSPPS;

Description

Attach this structure as part of the <u>mfxVideoParam</u> extended buffers to configure the SDK encoder during <u>MFXVideoENCODE Init</u>. The sequence or picture parameters specified by this structure overwrite any such parameters specified by the <u>mfxVideoParam</u> structure or any other extended buffers attached therein.

For H.264, SPSBuffer and PPSBuffer must point to valid bitstreams that contain the sequence parameter set and picture parameter set, respectively. For MPEG-2, SPSBuffer must point to valid bitstreams that contain the sequence header followed by any sequence header extension. The PPSBuffer pointer is ignored. The SDK encoder imports parameters from these buffers. If the encoder does not support the specified parameters, the encoder does not initialize and returns the status code MFX ERR INCOMPATIBLE VIDEO PARAM.

Check with the <u>MFXVideoENCODE Query</u> function for the support of this multiple segemnt encoding feature. If this feature is not supported, the query returns <u>MFX ERR UNSUPPORTED</u>.

Members

| Header.BufferId | Must be <pre>MFX_EXTBUFF_CODING_OPTION_SPSPPS.</pre> |
|-----------------|---|
| SPSBuffer | Pointer to a valid bitstream that contains the SPS (sequence parameter set for H.264 or sequence header followed by any sequence header extension for MPEG-2) buffer; can be ${\tt NULL}$ to skip specifying the SPS. |
| PPSBuffer | Pointer to a valid bitstream that contains the PPS (picture parameter set for H.264 or picture header followed by any picture header extension for MPEG-2) buffer; can be \mathtt{NULL} to skip specifying the PPS. |
| SPSBufSize | Size of the SPS in bytes |
| PPSBufSize | Size of the PPS in bytes |
| SPSId | SPS identifier; the value is reserved and must be zero. |
| PPSId | PPS identifier; the value is reserved and must be zero. |

Change History

This structure is available since SDK API 1.0.



mfxExtOpaqueSurfaceAlloc

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU32 reserved1[2];
    struct {
        mfxFrameSurface1 **Surfaces;
        mfxU32 reserved2[4];
        mfxU16 Type;
        mfxU16 NumSurface;
    } In, Out;
} mfxExtOpaqueSurfaceAlloc;
```

Description

The ${\tt mfxExtOpaqueSurfaceAlloc}$ structure defines the opaque surface allocation information.

Members

| Header.BufferId | Must be MFX EXTBUFF OPAQUE SURFACE ALLOCATION |
|-----------------|---|
| Type | Surface type chosen by the application. Any valid combination of flags may be used, for example: MFX_MEMTYPE_SYSTEM_MEMORY MFX_MEMTYPE_FROM_DECODE MFX_MEMTYPE_EXTERNAL_FRAME. |
| | The SDK ignores any irrelevant flags. See the ExtMemFrameType enumerator for details. |
| NumSurface | The number of allocated frame surfaces. |
| Surfaces | The array pointers of allocated frame surfaces. |
| In, Out | In refers to surface allocation for input and out refers to surface allocation for output. For decoding, In is ignored. For encoding, Out is ignored. |

Change History

This structure is available since SDK API 1.3.



mfxExtVideoSignalInfo

Definition

```
typedef struct {
     mfxExtBuffer
                      Header;
     mfxU16
                       VideoFormat;
     mfxU16
                       VideoFullRange;
     mfxU16
                       ColourDescriptionPresent;
     mfxU16
                        ColourPrimaries;
     mfxU16
                       TransferCharacteristics;
     mfxU16
                       MatrixCoefficients;
} mfxExtVideoSignalInfo;
```

Description

The mfxExtVideoSignalInfo structure defines the video signal information.

Members

| Header.BufferId | Must be MFX EXTBUFF VIDEO SIGNAL INFO |
|--------------------------|---|
| VideoFormat | These parameters define the video signal information. |
| VideoFullRange | For H.264, see Annex E of the ISO*/IEC* 14496-10 |
| ColourPrimaries | specification for the definition of these parameters. |
| TransferCharacteristics | For MPEG-2, see section 6.3.6 of the ITU* H.262 specification for the definition of these parameters. The field |
| MatrixCoefficients | VideoFullRange is ignored. |
| ColourDescriptionPresent | For VC-1, see section 6.1.14.5 of the SMPTE* 421M specification. The fields videoFormat and videoFullRange are ignored. |
| | If ColourDescriptionPresent is zero, the color description information (including ColourPrimaries, |
| | TransferCharacteristics, and MatrixCoefficients) will/does not present in the bitstream. |

Change History

This structure is available since SDK API 1.3.



mfxExtPictureTimingSEI

Definition

```
typedef struct {
 mfxExtBuffer
                  Header;
 mfxU32
                  reserved[14];
  struct {
      mfxU16
                ClockTimestampFlag;
      mfxU16
                CtType;
      mfxU16
                NuitFieldBasedFlag;
      mfxU16
                CountingType;
      mfxU16
                FullTimestampFlag;
      mfxU16
                DiscontinuityFlag;
      mfxU16
                CntDroppedFlag;
      mfxU16
                NFrames;
      mfxU16
                SecondsFlag;
      mfxU16
                MinutesFlag;
      mfxU16
                HoursFlag;
      mfxU16
                SecondsValue:
      mfxU16
                MinutesValue;
                HoursValue;
      mfxU16
      mfxU32
                TimeOffset;
  } TimeStamp[3];
} mfxExtPictureTimingSEI;
```

Description

The mfxExtPictureTimingSEI structure configures the H.264 picture timing SEI message. The encoder ignores it if HRD information in stream is absent and PicTimingSEI option in mfxExtCodingOption structure is turned off. See mfxExtCodingOption for details.

If the application attaches this structure to the <u>mfxVideoParam</u> structure during initialization, the encoder inserts the picture timing SEI message based on provided template in every access unit of coded bitstream.

If application attaches this structure to the <u>mfxEncodeCtrl</u> structure at runtime, the encoder inserts the picture timing SEI message based on provided template in access unit that represents current frame.



Members

Header.BufferId ClockTimestampFlag CtType NuitFieldBasedFlag CountingType FullTimestampFlag DiscontinuityFlag CntDroppedFlag NFrames SecondsFlag MinutesFlag HoursFlag SecondsValue MinutesValue HoursValue TimeOffset

Must be MFX EXTBUFF PICTURE TIMING SEI

These parameters define the picture timing information. An invalid value of 0xFFFF indicates that application does not set the value and encoder must calculate it.

See Annex D of the ISO*/IEC* 14496-10 specification for the definition of these parameters.

Change History

This structure is available since SDK API 1.3.

mfxExtAvcTemporalLayers

```
typedef struct {
    mfxExtBuffer Header;
    mfxU32 reserved1[4];
    mfxU16 reserved2;
    mfxU16 BaseLayerPID;

struct {
        mfxU16 Scale;
        mfxU16 reserved[3];
```



```
} Layer[8];
} mfxExtAvcTemporalLayers;
```

The mfxExtAvcTemporalLayers structure configures the H.264 temporal layers hierarchy. If application attaches it to the mfxVideoParam structure during initialization, the SDK encoder generates the temporal layers and inserts the prefix NAL unit before each slice to indicate the temporal and priority IDs of the layer.

This structure can be used with the display-order encoding mode only.

Members

| Header.BufferId | Must be MFX EXTBUFF AVC TEMPORAL LAYERS |
|-----------------|--|
| BaseLayerPID | The priority ID of the base layer; the SDK encoder increases the ID for each temporal layer and writes to the prefix NAL unit. |
| Scale | The ratio between the frame rates of the current temporal layer and the base layer. |
| Layer | The array of temporal layers; Use Scale=0 to specify absent layers. |

Change History

This structure is available since SDK API 1.3.

mfxExtVppAuxData

```
typedef struct {
    mfxExtBuffer Header;
    union{
        struct{
            mfxU32 SpatialComplexity;
            mfxU32 TemporalComplexity;
        };
        struct{
            mfxU16 PicStruct;
```



```
mfxU16 reserved[3];
};
};
mfxU16 SceneChangeRate;
mfxU16 RepeatedFrame;
} mfxExtVppAuxData;
```

The mfxExtVppAuxData structure returns auxiliary data generated by the video processing pipeline. The encoding process may use the auxiliary data by attaching this structure to the mfxEncodeCtrl structure.

Members

Header.BufferId Must be MFX EXTBUFF VPP AUXDATA

PicStruct Detected picture structure - top field first, bottom field first,

progressive or unknown if video processor cannot detect picture structure. See the **PicStruct** enumerator for definition of these

values.

By default, detection is turned off and the application should explicitly enable it by using $\frac{\text{mfxExtVPPDoUse}}{\text{mfxExtVPPDoUse}}$ buffer and

MFX EXTBUFF VPP PICSTRUCT DETECTION algorithm.

SpatialComplexity Deprecated

TemporalComplexity Deprecated

SceneChangeRate Deprecated

RepeatedFrame Deprecated

Change History

This structure is available since SDK API 1.0. SDK API 1.6 adds PicStruct field and deprecates SpatialComplexity, TemporalComplexity, SceneChangeRate and RepeatedFrame fields.

mfxExtVPPDenoise

```
typedef struct {
```



```
mfxExtBuffer Header;
mfxU16 DenoiseFactor;
} mfxExtVppDenoise;
```

The mfxExtVPPDenoise structure is a hint structure that configures the **VPP** denoise filter algorithm.

Members

Header.BufferId Must be MFX EXTBUFF VPP DENOISE

DenoiseFactor Value of 0-100 (inclusive) indicates the level of noise to remove.

Change History

This structure is available since SDK API 1.1.

mfxExtVPPDetail

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU16 DetailFactor;
} mfxExtVppDetail;
```

Description

The mfxExtVPPDetail structure is a hint structure that configures the **VPP** detail/edge enhancement filter algorithm.

Members

Header.BufferId Must be MFX EXTBUFF VPP DETAIL

DetailFactor 0-100 value (inclusive) to indicate the level of details to be

enhanced.

Change History

This structure is available since SDK API 1.1.



mfxExtVPPDoNotUse

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU32 NumAlg;
    mfxU32 *AlgList;
} mfxExtVPPDoNotUse;
```

Description

The mfxExtVPPDoNotUse structure tells the **VPP** not to use certain filters in pipeline. See "Table 4 Configurable VPP filters" for complete list of configurable filters.

The user can attach this structure to the $\frac{mfxVideoParam}{}$ structure when initializing video processing.

Members

```
NumAlg

NumList

NumL
```

Change History

This structure is available since SDK API 1.0.

mfxExtVPPDoUse

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU32 NumAlg;
    mfxU32 *AlgList;
} mfxExtVPPDoUse;
```

Description

The mfxExtVPPDoUse structure tells the **VPP** to include certain filters in pipeline.



Each filter may be included in pipeline by two different ways. First one, by adding filter ID to this structure. In this case, default filter parameters are used. Second one, by attaching filter configuration structure directly to the mfxVideoParam structure. In this case, adding filter ID to mfxExtVPPDoUse structure is optional. See "Table 4 Configurable VPP filters" for complete list of configurable filters, their IDs and configuration structures.

The user can attach this structure to the $\frac{mfxVideoParam}{}$ structure when initializing video processing.

NOTE: MFX EXTBUFF VPP COMPOSITE cannot be enabled using mfxExtVPPDoUse because default parameters are undefined for this filter. Application must attach appropriate filter configuration structure directly to the mfxVideoParam structure to enable it.

Members

Header.BufferId Must be MFX EXTBUFF VPP DOUSE

NumAlg Number of filters (algorithms) to use

AlgList Pointer to a list of filters (algorithms) to use

Change History

This structure is available since SDK API 1.3.

mfxExtVPPFrameRateConversion

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU16 Algorithm;
    mfxU16 reserved;
    mfxU32 reserved2[15];
} mfxExtVPPFrameRateConversion;
```

Description

The mfxExtVPPFrameRateConversion structure configures the **VPP** frame rate conversion filter. The user can attach this structure to the <u>mfxVideoParam</u> structure when initializing video processing, resetting it or query its capability.

On some platforms advanced frame rate conversion algorithm, algorithm based on frame interpolation, is not supported. To query its support the application should add MFX FRCALGM FRAME INTERPOLATION flag to Algorithm value in



mfxExtVPPFrameRateConversion Structure, attach it to mfxVideoParam Structure and call MFXVideoVPP Query function. If filter is supported the function returns MFX ERR NONE status and copies content of input structure to output one. If advanced filter is not supported then simple filter will be used and function returns MFX WRN INCOMPATIBLE VIDEO PARAM, copies content of input structure to output one and corrects Algorithm value.

If advanced FRC algorithm is not supported both MFXVideoVPP Init and MFXVideoVPP Reset functions returns MFX WRN INCOMPATIBLE VIDEO PARAM status.

Members

Header.BufferId Must be MFX EXTBUFF VPP FRAME RATE CONVERSION.

Algorithm See the FrcAlgm enumerator for a list of frame rate conversion

algorithms.

Change History

This structure is available since SDK API 1.3.

mfxExtVPPProcAmp

Definition

```
typedef struct {
     mfxExtBuffer
                       Header;
                Brightness;
     mfxF64
     mfxF64
                Contrast;
     mfxF64
                Hue;
     mfxF64
                 Saturation;
} mfxExtVPPProcAmp;
```

Description

The mfxExtVPPProcAmp structure is a hint structure that configures the **VPP** ProcAmp filter algorithm. The structure parameters will be clipped to their corresponding range and rounded by their corresponding increment.

Members

Header.BufferId Must be MFX EXTBUFF VPP PROCAMP

Brightness The brightness parameter is in the range of -100.0F to 100.0F, in

increments of 0.1F. The default brightness value is 0.0F.



Contrast The contrast parameter is in the range of 0.0F to 10.0F, in

increments of 0.01F. The default contrast value is 1.0F.

Hue The hue parameter is in the range of -180F to 180F, in increments of

0.1F. The default hue value is 0.0F.

Saturation The saturation parameter is in the range of 0.0F to 10.0F, in

increments of 0.01F. The default saturation value is 1.0F.

Change History

This structure is available since SDK API 1.1.

mfxExtVPPImageStab

Definition

```
typedef struct {
    mfxExtBuffer Header;
    mfxU16 Mode;
    mfxU16 reserved[11];
} mfxExtVPPImageStab;
```

Description

The mfxExtVPPImageStab structure is a hint structure that configures the **VPP** image stabilization filter.

On some platforms this filter is not supported. To query its support, the application should use the same approach that it uses to configure VPP filters - by adding filter ID to mfxExtVPPDoUse structure or by attaching mfxExtVPPDoUse structure and calling mfxVideoVPPQuery function. If this filter is supported function returns mfxMFX_ERR_NONE status and copies content of input structure to output one. If filter is not supported function returns MFX_WRN_FILTER_SKIPPED, removes filter form mfxExtVPPDoUse structure and zeroes mfxExtVPPDoUse structure.

If image stabilization filter is not supported, both MFXVideoVPP Init and MFXVideoVPP Reset functions returns MFXVideoVPP Init and MFXVideoVPP Init and MFXVideoVPP Init and

The application can retrieve list of active filters by attaching <u>mfxExtVPPDoUse</u> structure to <u>mfxVideoParam</u> function. The application must allocate enough memory for filter list.

Members

Header.BufferId Must be MFX EXTBUFF VPP IMAGE STABILIZATION

Mode Specify the image stabilization mode. It should be one of the next

values:



MFX_IMAGESTAB_MODE_UPSCALE MFX_IMAGESTAB_MODE_BOXING

Change History

This structure is available since SDK API 1.6.

mfxExtVPPComposite

```
typedef struct mfxVPPCompInputStream {
        mfxU32 DstX;
        mfxU32 DstY;
        mfxU32 DstW;
        mfxU32 DstH;
        mfxU16 LumaKeyEnable;
       mfxU16 LumaKeyMin;
mfxU16 LumaKeyMax;
        mfxU16 GlobalAlphaEnable;
        mfxU16 GlobalAlpha;
        mfxU16 PixelAlphaEnable;
        mfxU16 reserved2[18];
} mfxVPPCompInputStream;
typedef struct {
    mfxExtBuffer
                   Header;
    /* background color*/
    union {
       mfxU16 Y;
       mfxU16 R;
    };
    union {
       mfxU16 U;
       mfxU16
    };
    union {
       mfxU16
               V;
       mfxU16
               B;
    };
    mfxU16
                reserved1[24];
                NumInputStream;
    mfxU16
    mfxVPPCompInputStream *InputStream;
} mfxExtVPPComposite;
```



The mfxExtVPPComposite structure is used to control composition of several input surfaces in the one output. In this mode, the VPP skips any other filters. The VPP returns error if any mandatory filter is specified and filter skipped warning for optional filter. The only supported filters are deinterlacing and interlaced scaling. The only supported combinations of input and output color formats are:

- RGB to RGB,
- NV12 to NV12,
- RGB and NV12 to NV12, for per pixel alpha blending use case.

The VPP returns MFX ERR MORE DATA for additional input until an output is ready. When the output is ready, VPP returns MFX ERR NONE. The application must process the output frame after synchronization.

Composition process is controlled by:

- mfxFrameInfo::CropXYWH in input surface- defines location of picture in the input
- InputStream[i].DstXYWH defines location of the cropped input picture in the output frame,
- mfxFrameInfo::CropXYWH in output surface defines actual part of output frame. All pixels in output frame outside this region will be filled by specified color.

If the application uses composition process on video streams with different frame sizes, the application should provide maximum frame size in mfxVideoParam during initialization, reset or query operations.

If the application uses composition process, MFXVideoVPP QueryIOSurf function returns cumulative number of input surfaces, i.e. number required to process all input video streams. The function sets frame size in the mfxFrameAllocRequest equal to the size provided by application in the mfxVideoParam.

Composition process supports all types of surfaces, but opaque type has next limitations:

- all input surfaces should have the same size,
- all input surfaces should have the same color format,
- all input surfaces should be described in one mfxExtOpaqueSurfaceAlloc structure.

All input surfaces should have the same type and color format, except per pixel alpha blending case, where it is allowed to mix NV12 and RGB surfaces.

There are three different blending use cases:

- 1. Luma keying. In this case, all input surfaces should have NV12 color format specified during VPP initialization. Part of each surface, including first one, may be rendered transparent by using LumaKeyEnable, LumaKeyMin and LumaKeyMax values.
- 2. Global alpha blending. In this case, all input surfaces should have the same color format specified during VPP initialization. It should be either NV12 or RGB. Each input surface, including first one, can be blended with underling surfaces by using GlobalAlphaEnable and GlobalAlpha Values.
- 3. Per pixel alpha blending. In this case, it is allowed to mix NV12 and RGB input surfaces. Each RGB input surface, including first one, can be blended with underling surfaces by using PixelAlphaEnable value.

It is not allowed to mix different blending use cases in the same function call.



Members

| Header.BufferId | Must be MFX EXTBUFF VPP COMPOSITE |
|---------------------------------|--|
| Y, U, V R, G, B | background color, may be changed dynamically through Reset. No default value. YUV black is (0;128;128) or (16;128;128) depending on the sample range. The SDK uses YUV or RGB triple depending on output color format. |
| NumInputStream | Number of input surfaces to compose one output. May be changed dynamically at runtime through Reset. Number of surfaces can be decreased or increased, but should not exceed number specified during initialization. Query mode 2 should be used to find maximum supported number. |
| InputStream | This array of mfxVPPCompInputStream structures describes composition of input video streams. It should consist of exactly NumInputStream elements. |
| DstX, DstY, DstW, DstH | Location of input stream in output surface. |
| LumaKeyEnable | None zero value enables luma keying for the input stream. Luma keying is used to mark some of the areas of the frame with specified luma values as transparent. It may be used for closed captioning, for example. |
| LumaKeyMin, LumaKeyMax | Minimum and maximum values of luma key, inclusive. Pixels whose luma values fit in this range are rendered transparent. |
| GlobalAlphaEnable | None zero value enables global alpha blending for this input stream. |
| GlobalAlpha | Alpha value for this stream in [0255] range. 0 – transparent, 255 – opaque. |
| PixelAlphaEnable | None zero value enables per pixel alpha blending for this input stream. The stream should have RGB color format. |

Change History

This structure is available since SDK API 1.8.

The SDK API 1.9 adds LumaKeyEnable, LumaKeyMin, LumaKeyMax, GlobalAlphaEnable, GlobalAlpha and PixelAlphaEnable fields.



mfxExtVPPVideoSignalInfo

Definition

```
/* TransferMatrix */
enum {
   MFX TRANSFERMATRIX UNKNOWN = 0,
   MFX TRANSFERMATRIX BT709
   MFX TRANSFERMATRIX BT601
};
/* NominalRange */
enum {
   MFX NOMINALRANGE_UNKNOWN
                              = 0,
   MFX NOMINALRANGE 0 255
   MFX NOMINALRANGE 16 235
};
typedef struct {
   mfxExtBuffer Header;
   mfxU16
                  reserved1[4];
    struct {
       mfxU16 TransferMatrix;
       mfxU16 NominalRange;
       mfxU16 reserved2[6];
    } In, Out;
} mfxExtVPPVideoSignalInfo;
```

Description

The mfxExtVPPVideoSignalInfo structure is used to control transfer matrix and nominal range of YUV frames. The application should provide it during initialization. It is supported for all kinds of conversion YUV->YUV, YUV->RGB, RGB->YUV.

This structure is used by VPP only and is not compatible with mfxExtVideoSignalInfo.

Members

```
Header.BufferId Must be MFX EXTBUFF VPP VIDEO SIGNAL INFO

TransferMatrix Transfer matrix

NominalRange Nominal range
```

Change History

This structure is available since SDK API 1.8.



mfxExtEncoderCapability

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU32     MBPerSec;
    mfxU16     reserved[58];
} mfxExtEncoderCapability;
```

Description

The mfxExtEncoderCapability structure is used to retrive SDK encoder capability. See description of mode 4 of the <u>MFXVideoENCODE Query</u> function for details how to use this structure.

Not all implementations of the SDK encoder support this extended buffer. The application has to use query mode 1 to determine if such functionality is supported. To do so, the application has to attach this extended buffer to mfxVideoParam structure and call mfxVideoEncode Query function. If function returns MFX_ERR_NONE then such functionality is supported.

Members

```
Header.BufferId Must be MFX EXTBUFF ENCODER CAPABILITY

MBPerSec Specify the maximum processing rate in macro blocks per second.
```

Change History

This structure is available since SDK API 1.7.

mfxExtEncoderResetOption

Definition

Description

The mfxExtEncoderResetOption structure is used to control the SDK encoder behavior during reset. By using this structure, the application instructs the SDK encoder to start new coded sequence after reset or continue encoding of current sequence.



This structure is also used in mode 3 of MFXVideoENCODE Query function to check for reset outcome before actual reset. The application should set StartNewSequence to required behavior and call query function. If query fails, see status codes below, then such reset is not possible in current encoder state. If the application sets StartNewSequence to MFX CODINGOPTION UNKNOWN then query function replaces it by actual reset type: MFX CODINGOPTION ON if the SDK encoder will begin new sequence after reset or MFX CODINGOPTION OFF if the SDK encoder will continue current sequence.

Using this structure may cause next status codes from MFXVideoENCODE Reset and MFXVideoENCODE Query functions:

- MFX ERR INVALID VIDEO PARAM if such reset is not possible. For example, the application sets StartNewSequence to off and requests resolution change.
- MFX ERR INCOMPATIBLE VIDEO PARAM if the application requests change that leads to memory allocation. For example, the application set StartNewSequence to on and requests resolution change to bigger than initialization value.
- MFX ERR NONE if such reset is possible.

There is limited list of parameters that can be changed without starting a new coded sequence:

- bitrate parameters, TargetKbps and MaxKbps in the mfxInfoMFX structure.
- number of slices, NumSlice in the mfxInfoMFX structure. Number of slices should be equal or less than number of slices during initialization.
- number of temporal layers in mfxExtAvcTemporalLayers structure. Reset should be called immediately before encoding of frame from base layer and number of reference frames should be big enough for new temporal layers structure.
- Quantization parameters, QPI, QPP and QPB in the mfxInfoMFX structure.

As it is described in Configuration Change chapter, the application should retrieve all cached frames before calling reset. When query function checks for reset outcome, it expects that this requirement be satisfied. If it is not true and there are some cached frames inside the SDK encoder, then query result may differ from reset one, because the SDK encoder may insert IDR frame to produce valid coded sequence.

Not all implementations of the SDK encoder support this extended buffer. The application has to use guery mode 1 to determine if such functionality is supported. To do so, the application has to attach this extended buffer to mfxVideoParam structure and call MFXVideoENCODE Query function. If function returns MFX_ERR_NONE then such functionality is supported.

See also Appendix C: Streaming and Video Conferencing Features.

Members

Header BufferId Must be MFX EXTBUFF ENCODER RESET OPTION

StartNewSequence Instructs encoder to start new sequence after reset. It is one of the

CodingOptionValue OptionS:

MFX CODINGOPTION ON - the SDK encoder completely reset internal state and begins new coded sequence after reset, including insertion

of IDR frame, sequence and picture headers.



MFX_CODINGOPTION_OFF - the SDK encoder continues encoding of current coded sequence after reset, without insertion of IDR frame.

MFX_CODINGOPTION_UNKNOWN – depending on the current encoder state and changes in configuration parameters the SDK encoder may or may not start new coded sequence. This value is also used to query reset outcome.

Change History

This structure is available since SDK API 1.7.

mfxExtAVCEncodedFrameInfo

Definition

```
typedef struct {
   mfxExtBuffer
                   Header;
   mfxU32
                   FrameOrder;
   mfxU16
                   PicStruct;
                   LongTermIdx;
   mfxU16
   mfxU32
                   MAD;
   mfxU16
                   BRCPanicMode;
   mfxU16
   mfxU32
                   SecondFieldOffset;
   mfxU16
                   reserved[2];
    struct {
           mfxU32
                      FrameOrder;
           mfxU16
                       PicStruct;
           mfxU16
                      LongTermIdx;
           mfxU16
                      reserved[4];
    } UsedRefListL0[32], UsedRefListL1[32];
} mfxExtAVCEncodedFrameInfo;
```

Description

The mfxExtAVCEncodedFrameInfo is used by the SDK encoder to report additional information about encoded picture. The application can attach this buffer to the mfxBitstream structure before calling MFXVideoENCODE EncodeFrameAsync function. For interlaced content the SDK encoder requires two such structures. They correspond to fields in encoded order.

Not all implementations of the SDK encoder support this extended buffer. The application has to use query mode 1 to determine if such functionality is supported. To do so, the application has to attach this extended buffer to mfxVideoParam structure and call mfxVideoENCODE_Query function. If function returns MFX_ERR_NONE then such functionality is supported.



Members

Header.BufferId Must be MFX EXTBUFF ENCODED FRAME INFO

FrameOrder Frame order of encoded picture.

PicStruct Picture structure of encoded picture.

LongTermIdx Long term index of encoded picture if applicable.

MAD Mean Absolute Difference between original pixels of the frame and

motion compensated (for inter macroblocks) or spatially predicted (for intra macroblocks) pixels. Only luma component, Y plane, is

used in calculation.

BRCPanicMode Bitrate control was not able to allocate enough bits for this frame.

Frame quality may be unacceptably low.

QP Luma QP.

SecondFieldOffset Offset to second field. Second field starts at

mfxBitstream::Data + mfxBitstream::DataOffset +
mfxExtAVCEncodedFrameInfo::SecondFieldOffset

UsedRefListL0
UsedRefListL1

Reference lists that have been used to encode picture.

FrameOrder Frame order of reference picture.

PicStruct Picture structure of reference picture.

LongTermIdx Long term index of reference picture if applicable.

Change History

This structure is available since SDK API 1.7.

The SDK API 1.8 adds MAD and BRCPanicMode fields.

The SDK API 1.9 adds SecondFieldOffset fields.

mfxExtEncoderROI

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 NumROI;
    mfxU16 reserved1[11];
```



```
struct {
    mfxU32 Left;
    mfxU32 Top;
    mfxU32 Right;
    mfxU32 Bottom;

    mfxI16 Priority;
    mfxU16 reserved2[7];
    } ROI[256];
} mfxExtEncoderROI;
```

The mfxExtEncoderROI structure is used by the application to specify different Region Of Interests during encoding. It may be used at initialization or at runtime.

Members

| Header.BufferId | Must be MFX EXTBUFF ENCODER ROI |
|-----------------------------------|---|
| NumROI | Number of ROI descriptions in array. The Query function mode 2 returns maximum supported value (set it to 256 and Query will update it to maximum supported value). |
| ROI | Array of ROIs. Different ROI may overlap each other. If macroblock belongs to several ROI, Priority from ROI with lowest index is used. |
| Left, Top, Right, Bottom | ROI location. Should be aligned to MB boundaries (should be dividable by 16). If not, the SDK encoder truncates it to MB boundaries, for example, both 17 and 31 will be truncated to 16. |
| Priority | Priority of ROI. |
| | For VBR, CBR and AVBR modes, this is relative priority of the region in the -33 range. Bigger value produces better quality. |
| | For CQP mode, this is absolute value in the -5151 range, that will be added to the MB QP. Lesser value produces better quality. |

Change History

This structure is available since SDK API 1.8.

mfxExtVPPDeinterlacing



```
typedef struct {
    mfxExtBuffer Header;
    mfxU16 Mode;
    mfxU16 TelecinePattern;
    mfxU16 TelecineLocation;
    mfxU16 reserved[9];
} mfxExtVPPDeinterlacing;
```

The mfxExtVPPDeinterlacing structure is used by the application to specify different deinterlacing algorithms.

Members

| Header.BufferId | Must be MFX EXTBUFF VPP DEINTERLACING |
|------------------|---|
| Mode | Deinterlacing algorithm. See the $\frac{\texttt{DeinterlacingMode}}{\texttt{details}}$ enumerator for details. |
| TelecinePattern | Specifies telecine pattern when <code>Mode = MFX_DEINTERLACING_FIXED_TELECINE_PATTERN</code> . See the <code>TelecinePattern</code> enumerator for details. |
| TelecineLocation | Specifies position inside a sequence of 5 frames where the artifacts start when TelecinePattern = MFX TELECINE POSITION PROVIDED. |

Change History

This structure is available since SDK API 1.8.

The SDK API 1.13 adds TelecinePattern and TelecineLocation fields.

mfxFrameAllocator

```
typedef struct {
      mfxU32
                  reserved[4];
      mfxHDL
                  pthis;
      mfxStatus
                  (*Alloc) (mfxHDL pthis, mfxFrameAllocRequest *request,
                  mfxFrameAllocResponse *response);
      mfxStatus
                  (*Lock) (mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr);
      mfxStatus
                  (*Unlock) (mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr);
                (*GetHDL) (mfxHDL pthis, mfxMemId mid, mfxHDL *handle);
      mfxStatus
      mfxStatus
                  (*Free) (mfxHDL pthis, mfxFrameAllocResponse *response);
```



} mfxFrameAllocator;

Description

The mfxFrameAllocator structure describes the callback functions Alloc, Lock, Unlock, GetHDL and Free that the SDK implementation might use for allocating internal frames. Applications that operate on OS-specific video surfaces must implement these callback functions.

Using the default allocator implies that frame data passes in or out of SDK functions through pointers, as opposed to using memory IDs.

The SDK behavior is undefined when using an incompletely defined external allocator. See the section Memory Allocation and External Allocators for additional information.

Members

| pthis | Pointer to the allocator object |
|--------|---|
| Alloc | Pointer to the function that allocates frames |
| Lock | Pointer to the function that locks a frame and obtain its pointers |
| Unlock | Pointer to the function that unlocks a frame; after unlocking, any pointers to the frame are invalid. |
| GetHDL | Pointer to the function that obtains the OS-specific handle |
| Free | Pointer to the function that de-allocates a frame |

Change History

This structure is available since SDK API 1.0.

Alloc

Syntax

```
mfxStatus (*Alloc) (mfxHDL pthis, mfxFrameAllocRequest *request,
mfxFrameAllocResponse *response);
```

Parameters

| ptnis | Pointer to the allocator object |
|---------|---|
| request | Pointer to the <pre>mfxFrameAllocRequest</pre> structure that |
| | specifies the type and number of required frames |



response

Pointer to the <u>mfxFrameAllocResponse</u> structure that

retrieves frames actually allocated

Description

This function allocates surface frames. For decoders, MEXVideoDECODE Init calls alloc only once. That call includes all frame allocation requests. For encoders, MEXVideoENCODE Init calls alloc twice: once for the input surfaces and again for the internal reconstructed surfaces.

If two SDK components must share DirectX* surfaces, this function should pass the pre-allocated surface chain to SDK instead of allocating new DirectX surfaces. See the **Error! Reference source not found.** section for additional information.

Return Status

MFX_ERR_NONE The function successfully allocated the memory block.

MFX_ERR_MEMORY_ALLOC The function failed to allocate the video frames.

MFX_ERR_UNSUPPORTED The function does not support allocating the specified type of memory.

Change History

This function is available since SDK API 1.0.

Free

Syntax

mfxStatus (*Free) (mfxHDL pthis, mfxFrameAllocResponse *response);

Parameters

pthis Pointer to the allocator object

response Pointer to the mfxFrameAllocResponse Structure

returned by the Alloc function

Description

This function de-allocates all allocated frames.

Return Status

MFX_ERR_NONE The function successfully de-allocated the memory

block.



Change History

This function is available since SDK API 1.0.

Lock

Syntax

```
mfxStatus (*Lock) (mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr);
```

Parameters

pthis Pointer to the allocator object

mid Memory block ID

ptr Pointer to the returned frame structure

Description

This function locks a frame and returns its pointer.

Return Status

MFX ERR NONE The function successfully locked the memory block.

MFX ERR LOCK MEMORY This function failed to lock the frame.

Change History

This function is available since SDK API 1.0.

Unlock

Syntax

```
mfxStatus (*Unlock) (mfxHDL pthis, mfxMemId mid, mfxFrameData *ptr);
```

Parameters

pthis Pointer to the allocator object

mid Memory block ID

ptr Pointer to the frame structure; This pointer can be



NULL.

Description

This function unlocks a frame and invalidates the specified frame structure.

Return Status

MFX_ERR_NONE The function successfully unlocked the frame.

Change History

This function is available since SDK API 1.0.

GetHDL

Syntax

mfxStatus (*GetHDL) (mfxHDL pthis, mfxMemId mid, mfxHDL *hdl);

Parameters

pthis Pointer to the allocator object

mid Memory block ID

hdl Pointer to the returned OS-specific handle

Description

This function returns the OS-specific handle associated with a video frame. If the handle is a COM interface, the reference counter must increase. The SDK will release the interface afterward.

Return Status

MFX_ERR_NONE The function successfully returned the OS-specific

handle.

MFX_ERR_UNSUPPORTED The function does not support obtaining OS-specific

handle.

Change History

This function is available since SDK API 1.0.



mfxFrameAllocRequest

Definition

```
typedef struct {
    union {
        mfxU32 AllocId;
        mfxU32 reserved[1];
    };
    mfxU32 reserved3[3];
    mfxFrameInfo Info;
    mfxU16 Type; /* decoder or processor render targets */
    mfxU16 NumFrameMin;
    mfxU16 NumFrameSuggested;
    mfxU16 reserved2;
} mfxFrameAllocRequest;
```

Description

The mfxFrameAllocRequest structure describes multiple frame allocations when initializing encoders, decoders and video preprocessors. A range specifies the number of video frames. Applications are free to allocate additional frames. In any case, the minimum number of frames must be at least NumFrameMin or the called function will return an error.

Members

| AllocId | Unique (within the session) ID of component requested the allocation. |
|-------------------|---|
| Info | Describes the properties of allocated frames |
| Туре | Allocated memory type; see the $\underbrace{\mathtt{ExtMemFrameType}}_{\texttt{details}}$ enumerator for details. |
| NumFrameMin | Minimum number of allocated frames |
| NumFrameSuggested | Suggested number of allocated frames |

Change History

This structure is available since SDK API 1.0.

The SDK API 1.16 adds AllocId field.



mfxFrameAllocResponse

Definition

Description

The mfxFrameAllocResponse structure describes the response to multiple frame allocations. The calling function returns the number of video frames actually allocated and pointers to their memory IDs.

Members

| AllocId | Unique (within the session) ID of component requested the allocation. |
|----------------|---|
| mids | Pointer to the array of the returned memory IDs; the application allocates or frees this array. |
| NumFrameActual | Number of frames actually allocated |

Change History

This structure is available since SDK API 1.0.

The SDK API 1.16 adds AllocId field.

mfxFrameData

```
typedef struct {
   union {
```



```
mfxExtBuffer **ExtParam;
   mfxU64 reserved2;
} ;
mfxU16 NumExtParam;
mfxU16 reserved[10];
mfxU16
         PitchHigh;
mfxU64
       TimeStamp;
mfxU32
          FrameOrder;
mfxU16
          Locked;
union{
  mfxU16 Pitch;
   mfxU16 PitchLow;
} ;
/* color planes */
union {
   mfxU8
           *Y;
   mfxU8
           *R;
} ;
union {
   mfxU8
           *UV;
                         /* for UV merged formats */
                         /* for VU merged formats */
   mfxU8
          *VU;
                         /* for CbCr merged formats */
   mfxU8
           *CbCr;
                         /* for CrCb merged formats */
   mfxU8
          *CrCb;
   mfxU8
           *Cb;
   mfxU8
           *U;
   mfxU8
           *G;
} ;
union {
   mfxU8
          *Cr;
   mfxU8
           *V;
   mfxU8
           *B;
};
mfxU8
           *A;
```



```
mfxMemId MemId;

/* Additional Flags */
mfxU16 Corrupted;
mfxU16 DataFlag;
} mfxFrameData;
```

The mfxFrameData structure describes frame buffer pointers.

Members

| TimeStamp | Time stamp of the video frame in units of 90KHz (divide TimeStamp by 90,000 (90 KHz) to obtain the time in seconds). A value of MFX_TIMESTAMP_UNKNOWN indicates that there is no time stamp. |
|------------------------|---|
| Pitch | Deprecated. |
| PitchHigh, PitchLow | Distance in bytes between the start of two consecutive rows in a frame. |
| FrameOrder | Current frame counter for the top field of the current frame; an invalid value of MFX_FRAMEORDER_UNKNOWN indicates that SDK functions that generate the frame output do not use this frame. |
| Locked | Counter flag for the application; if ${\tt Locked}$ is greater than zero then the application locks the frame or field pair. Do not move, alter or delete the frame. |
| Y, U, V, A; | Data pointers to corresponding color channels. The frame buffer pointers must be 16-byte aligned. The application has to specify pointers to all color channels even for packed formats. For example, for YUY2 format the application has to specify Y, U and V pointers. For RGB32 – R, G, B and A pointers. |
| R, G, B, A; | |
| Y, Cr, Cb, A; | |
| Y, CbCr; | |
| Y, CrCb; | |
| Y, UV; | |
| Y, VU; | |
| MemId | Memory ID of the data buffers; if any of the preceding data pointers is non-zero then the SDK ignores \texttt{MemId} . |
| DataFlag | Additional flags to indicate frame data properties. See the <pre>FrameDataFlag</pre> enumerator for details. |
| Corrupted | Some part of the frame or field pair is corrupted. See the corruption enumerator for details. |



NumExtParam The number of extra configuration structures attached to this structure.

ExtParam Points to an array of pointers to the extra configuration structures; see

the $\underline{\textbf{ExtendedBufferID}}$ enumerator for a list of extended

configurations.

Change History

This structure is available since SDK API 1.0.

SDK API 1.3 extended the Corrupted and DataFlag fields.

SDK 1.8 replaced Pitch by PitchHigh and PitchLow fields.

SDK API 1.11 added NumExtParam and ExtParam fields.

mfxFrameInfo

```
typedef struct {
   mfxU32 reserved[4];
   mfxU16 reserved4;
   mfxU16 BitDepthLuma;
   mfxU16 BitDepthChroma;
   mfxU16 Shift;
   mfxFrameId FrameId;
   mfxU32 FourCC;
   union {
       struct { /* Frame parameters */
           mfxU16 Width;
           mfxU16 Height;
           mfxU16 CropX;
           mfxU16 CropY;
           mfxU16 CropW;
           mfxU16 CropH;
       struct { /* Buffer parameters (for plain formats like P8) */
           mfxU64 BufferSize;
           mfxU32 reserved5;
       };
   };
   mfxU32 FrameRateExtN;
   mfxU32 FrameRateExtD;
   mfxU16 reserved3;
   mfxU16 AspectRatioW;
```



```
mfxU16 AspectRatioH;

mfxU16 PicStruct;
 mfxU16 ChromaFormat;
 mfxU16 reserved2;
} mfxFrameInfo;
```

The ${\tt mfxFrameInfo}$ structure specifies properties of video frames. See also Appendix A: Configuration Parameter Constraints.

Members

| Number of bits used to represent luma samples. Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported. |
|---|
| Number of bits used to represent chroma samples. Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported. |
| When not zero indicates that values of luma and chroma samples are shifted. Use BitDepthLuma and BitDepthChroma to calculate shift size. Use zero value to indicate absence of shift. Not all codecs and SDK implementations support this value. Use Query function to check if this feature is supported. |
| FourCC code of the color format; see the ColorFourCC enumerator for details. |
| Width and height of the video frame in pixels; Width must be a multiple of 16. Height must be a multiple of 16 for progressive frame sequence and a multiple of 32 otherwise. |
| Display the region of interest of the frame; specify the display width and height in <pre>mfxVideoParam</pre> . |
| Size of frame buffer in bytes. Valid only for plain formats (when FourCC is P8); Width, Height and crops in this case are invalid. |
| These parameters specify the sample aspect ratio. If sample aspect ratio is explicitly defined by the standards (see Table 6-3 in the MPEG-2 specification or Table E-1 in the H.264 specification), AspectRatioW and AspectRatioH should be the defined values. Otherwise, the sample aspect ratio can be derived as follows: AspectRatioW=display aspect ratio width*display height; |
| |

AspectRatioH=display_aspect_ratio_height*display_width;



For MPEG-2, the above display aspect ratio must be one of the defined values in Table 6-3. For H.264, there is no restriction on display aspect ratio values.

If both parameters are zero, the encoder uses default value of sample aspect ratio.

FrameRateExtN Specify the frame rate by the formula:

FrameRateExtD FrameRateExtD.

For encoding, frame rate must be specified. For decoding, frame rate may be unspecified (FrameRateExtN and FrameRateExtD are all zeros.)

In this case, the frame rate is default to 30 frames per second.

PicStruct Picture type as specified in the PicStruct enumerator

of ChromaFormatIdc. ChromaFormat is not defined if FourCC is zero.

Change History

This structure is available since SDK API 1.0.

SDK API 1.9 added BitDepthLuma, BitDepthChroma and Shift fields.

SDK API 1.15 adds BufferSize field.

Remarks

See Appendix A for constraints of specifying certain parameters during SDK class initialization and operation.

mfxFrameSurface1

Definition

Description

The mfxFrameSurface1 structure defines the uncompressed frames surface information and data buffers. The frame surface is in the frame or complementary field pairs of pixels



up to four color-channels, in two parts: mfxFrameInfo and mfxFrameData.

Members

Change History

This structure is available since SDK API 1.0.

mfxInfoMFX

Definition

```
typedef struct {
   mfxU32 reserved[7];
   mfxU16 LowPower;
   mfxU16 BRCParamMultiplier;
   mfxFrameInfo
                  FrameInfo;
   mfxU32 CodecId;
   mfxU16 CodecProfile;
   mfxU16 CodecLevel;
   mfxU16 NumThread;
   union {
       struct { /* MPEG-2/H.264 Encoding Options */
           mfxU16 TargetUsage;
           mfxU16 GopPicSize;
           mfxU16 GopRefDist;
           mfxU16 GopOptFlag;
           mfxU16 IdrInterval;
           mfxU16 RateControlMethod;
               mfxU16 InitialDelayInKB;
               mfxU16 QPI;
```



```
mfxU16 Accuracy;
    } ;
    mfxU16 BufferSizeInKB;
    union {
       mfxU16 TargetKbps;
       mfxU16 QPP;
       mfxU16 ICQQuality;
    };
    union {
       mfxU16 MaxKbps;
       mfxU16 QPB;
       mfxU16 Convergence;
    };
   mfxU16 NumSlice;
   mfxU16 NumRefFrame;
   mfxU16 EncodedOrder;
};
struct { /* H.264, MPEG-2 and VC-1 Decoding Options */
   mfxU16 DecodedOrder;
   mfxU16 ExtendedPicStruct;
   mfxU16 TimeStampCalc;
   mfxU16 SliceGroupsPresent;
   mfxU16 MaxDecFrameBuffering;
   mfxU16 reserved2[8];
} ;
struct { /* JPEG Decoding Options */
   mfxU16 JPEGChromaFormat;
   mfxU16 Rotation;
   mfxU16 JPEGColorFormat;
   mfxU16 InterleavedDec;
   mfxU16 reserved3[9];
} ;
struct {    /* JPEG Encoding Options */
   mfxU16 Interleaved;
   mfxU16 Quality;
   mfxU16 RestartInterval;
   mfxU16 reserved5[10];
};
```

};



} mfxInfoMFX;

Description

This structure specifies configurations for decoding, encoding and transcoding processes. A zero value in any of these fields indicates that the field is not explicitly specified.

Members

| LowPower | For encoders set this flag to ON to reduce power consumption and GPU usage. See the CodingOptionValue enumerator for values of this option. Use <a check="" feature="" function="" href="Query" if="" is="" supported.<="" th="" this="" to=""> |
|--------------------|---|
| BRCParamMultiplier | Specifies a multiplier for bitrate control parameters. Affects next four variables InitialDelayInKB, BufferSizeInKB, TargetKbps, MaxKbps. If this value is not equal to zero encoder calculates BRC parameters as value * BRCParamMultiplier. |
| FrameInfo | <pre>mfxFrameInfo</pre> structure that specifies frame parameters |
| CodecId | Specifies the codec format identifier in the FOURCC code; see the <pre>CodecFormatFourCC</pre> enumerator for details. This is a mandated input parameter for <pre>QueryIOSurf</pre> and <pre>Init</pre> functions. |
| CodecProfile | Specifies the codec profile; see the CodecProfile enumerator for details. Specify the codec profile explicitly or the SDK functions will determine the correct profile from other sources, such as resolution and bitrate. |
| CodecLevel | Codec level; see the CodecLevel enumerator for details. Specify the codec level explicitly or the SDK functions will determine the correct level from other sources, such as resolution and bitrate. |
| GopPicSize | Number of pictures within the current GOP (Group of Pictures); if GopPicSize=0, then the GOP size is unspecified. If GopPicSize=1, only I-frames are used. See Example 13 for pseudo-code that demonstrates how SDK uses this parameter. |
| GopRefDist | Distance between I- or P- key frames; if it is zero, the GOP structure is unspecified. Note: If GopRefDist = 1, there are no B-frames used. See Example 13 for pseudo-code that demonstrates how SDK uses this parameter. |
| GopOptFlag | ORs of the GopOptFlag enumerator indicate the additional flags for the GOP specification; see Example 13 for an example of pseudo-code that demonstrates how to use this parameter. |
| IdrInterval | For H.264, IdrInterval specifies IDR-frame interval in terms of I-frames; if IdrInterval=0, then every I-frame is an IDR-frame. |



If IdrInterval=1, then every other I-frame is an IDR-frame, etc.

For MPEG2, IdrInterval defines sequence header interval in terms of I-frames. If IdrInterval=N, SDK inserts the sequence header before every Nth I-frame. If IdrInterval=0 (default), SDK inserts the sequence header once at the beginning of the stream.

If GopPicSize Or GopRefDist is Zero, IdrInterval is undefined.

TargetUsage

Target usage model that guides the encoding process; see the TargetUsage enumerator for details.

RateControlMethod

Rate control method; see the RateControlMethod enumerator for details.

InitialDelayInKB
TargetKbps
MaxKbps

These parameters are for the constant bitrate (CBR), variable bitrate control (VBR) and **CQP HRD** algorithms.

The SDK encoders follow the Hypothetical Reference Decoding (HRD) model. The HRD model assumes that data flows into a buffer of the fixed size <code>BufferSizeInKB</code> with a constant bitrate <code>TargetKbps</code>. (Estimate the targeted frame size by dividing the framerate by the bitrate.)

The decoder starts decoding after the buffer reaches the initial size <code>InitialDelayInKB</code>, which is equivalent to reaching an initial delay of <code>InitialDelayInKB*8000/TargetKbps</code> ms. Note: In this context, KB is 1000 bytes and Kbps is 1000 bps.

If InitialDelayInKB or BufferSizeInKB is equal to zero, the value is calculated using bitrate, frame rate, profile, level, and so on.

TargetKbps must be specified for encoding initialization.

For variable bitrate control, the MaxKbps parameter specifies the maximum bitrate at which the encoded data enters the Video Buffering Verifier (VBV) buffer. If MaxKbps is equal to zero, the value is calculated from bitrate, frame rate, profile, level, and so on.

QPI, QPP, QPB

Quantization Parameters (QP) for I, P and B frames, respectively, for the constant QP (CQP) mode.

TargetKbps
Accuracy
Convergence

These parameters are for the average variable bitrate control (AVBR) algorithm. The algorithm focuses on overall encoding quality while meeting the specified bitrate, TargetKbps, within the accuracy range Accuracy, after a Convergence period. This method does not follow HRD and the instant bitrate is not capped or padded.

The **Accuracy** value is specified in the unit of tenth of percent.



| The Convergence value is specified in the unit of 100 frames. |
|--|
| The TargetKbps value is specified in the unit of 1000 bits per |
| second. |
| This parameter is for Intelligent Constant Quality (ICQ) bitrate |

control algorithm. It is value in the 1...51 range, where 1

corresponds the best quality.

BufferSizeInKB Represents the maximum possible size of any

compressed frames.

NumSlice Number of slices in each video frame; each slice contains one or

more macro-block rows. If ${\tt NumSlice}$ equals zero, the encoder may choose any slice partitioning allowed by the codec standard.

See also mfxExtCodingOption2::NumMbPerSlice.

NumRefFrame Number of reference frames; if NumRefFrame = 0, this parameter

is not specified.

EncodedOrder If not zero, EncodedOrder specifies that ENCODE takes the input

surfaces in the encoded order and uses explicit frame type control. Application still must provide GopRefDist and

mfxExtCodingOption2::BRefType SO SDK can pack headers and

build reference lists correctly.

NumThread Deprecated; Used to represent the number of threads the

underlying implementation can use on the host processor. Always

set this parameter to zero.

DecodedOrder Deprecated; Used to instruct the decoder to decoded output in the

decoded order. Always set this parameter to zero.

ExtendedPicStruct Instructs **DECODE** to output extended picture structure values for

additional display attributes. See the PicStruct description for

details.

TimeStampCalc Time stamp calculation method; see the TimeStampCalc

description for details.

SliceGroupsPresent Nonzero value indicates that slice groups are present in the

bitstream. Only AVC decoder uses this field.

MaxDecFrameBuffering Nonzero value specifies the maximum required size of the

decoded picture buffer in frames for AVC and HEVC decoders.

Change History

This structure is available since SDK API 1.0.

SDK API 1.1 extended the QPI, QPP, QPB fields.



```
SDK API 1.3 extended the Accuracy, Convergence, TimeStampCalc, ExtendedPicStruct and BRCParamMultiplier fields.

SDK API 1.6 added SliceGroupsPresent field.

SDK API 1.8 added ICQQuality field.

SDK API 1.15 adds LowPower field.
```

SDK API 1.16 adds MaxDecFrameBuffering field.

mfxU16 get gop sequence (...) { pos=display frame order; if $(pos == \overline{0})$ return MFX FRAMETYPE I | MFX FRAMETYPE IDR | MFX FRAMETYPE REF; /* Only I-frames */ If (GopPicSize == 1) return MFX FRAMETYPE I | MFX FRAMETYPE REF; if (GopPicSize == 0) frameInGOP = pos; //Unlimited GOP else frameInGOP = pos%GopPicSize; if (frameInGOP == 0) return MFX FRAMETYPE I | MFX FRAMETYPE REF; return MFX FRAMETYPE P | MFX FRAMETYPE REF; frameInPattern = (frameInGOP-1) %GopRefDist; if (frameInPattern == GopRefDist - 1) return MFX FRAMETYPE P | MFX FRAMETYPE REF;

Example 13: Pseudo-Code for GOP Structure Parameters

mfxInfoVPP

Definition

```
typedef struct _mfxInfoVPP {
    mfxU32     reserved[8];
    mfxFrameInfo     In;
```

return MFX FRAMETYPE B;



```
mfxFrameInfo
Out;
} mfxInfoVPP;
```

Description

The mfxInfoVPP structure specifies configurations for video processing. A zero value in any of the fields indicates that the corresponding field is not explicitly specified.

Members

In Input format for video processing

Out

Output format for video processing

Change History

This structure is available since SDK API 1.0.

mfxInitParam

Definition

```
typedef struct {
      {\tt mfxIMPL}
                         Implementation;
      mfxVersion
                         Version;
      mfxU16
                         ExternalThreads;
      union {
        struct {
            mfxExtBuffer **ExtParam;
            mfxU16 NumExtParam;
        } ;
        mfxU16 reserved2[5];
    } ;
    mfxU16
                 GPUCopy;
    mfxU16
                 reserved[21];
} mfxInitParam;
```

Description

The mfxInitParam structure specifies advanced initialization parameters. A zero value in any of the fields indicates that the corresponding field is not explicitly specified.



Members

Implementation mfxIMPL enumerator that indicates the desired SDK implementation

Version Structure which specifies minimum library version or zero, if not

specified

ExternalThreads Desired threading mode. Value 0 means internal threading, 1 -

external.

NumExtParam The number of extra configuration structures attached to this

structure.

ExtParam Points to an array of pointers to the extra configuration structures;

see the ExtendedBufferID enumerator for a list of extended

configurations.

GPUCopy Enables or disables GPU accelerated copying between video and

system memory in the SDK components. See the GPUCopy

enumerator for a list of valid values.

Change History

This structure is available since SDK API 1.14.

The SDK API 1.15 adds NumExtParam and ExtParam fields.

The SDK API 1.16 adds GPUCopy field.

mfxPayload

Definition

```
typedef struct {
    mfxu32     reserved[4];
    mfxu8     *Data;
    mfxu32     NumBit;
    mfxu16     Type;
    mfxu16     BufSize;
} mfxPayload;
```

Description

The mfxPayload structure describes user data payload in MPEG-2 or SEI message payload in H.264. For encoding, these payloads can be inserted into the bitstream. The payload



buffer must contain a valid formatted payload. For H.264, this is the sei_message() as specified in the section 7.3.2.3.1 "Supplemental enhancement information message syntax" of the ISO*/IEC* 14496-10 specification. For MPEG-2, this is the section 6.2.2.2.2 "User data" of the ISO*/IEC* 13818-2 specification, excluding the user data start_code. For decoding, these payloads can be retrieved as the decoder parses the bitstream and caches them in an internal buffer.

Members

Type MPEG-2 user data start code or H.264 SEI message type

NumBit Number of bits in the payload data

Data Pointer to the actual payload data buffer

BufSize Payload buffer size in bytes

Change History

This structure is available since SDK API 1.0.

mfxVersion

Definition

Description

The mfxVersion structure describes the version of the SDK implementation.

Members

Version SDK implementation version number

Major Major number of the SDK implementation

Minor Number of the SDK implementation



Change History

This structure is available since SDK API 1.0.

mfxVideoParam

Definition

```
typedef struct _mfxVideoParam {
     mfxU32
                 AllocId;
     mfxU32
                 reserved[2];
     mfxU16
                reserved3;
     mfxU16
                 AsyncDepth;
     union {
           mfxInfoMFX
                             mfx;
           mfxInfoVPP
                             vpp;
     }
     mfxU16
                       Protected;
     mfxU16
                       IOPattern;
     mfxExtBuffer
                       **ExtParam;
     mfxU16
                       NumExtParam;
     mfxU16
                       reserved2;
} mfxVideoParam;
```

Description

The mfxVideoParam structure contains configuration parameters for encoding, decoding, transcoding and video processing.

Members

| AllocId | Unique component ID that will be passed by SDK to mfxFrameAllocRequest. Useful in pipelines where several components of the same type share the same allocator. |
|------------|--|
| AsyncDepth | Specifies how many asynchronous operations an application performs before the application explicitly synchronizes the result. If zero, the value is not specified. |
| mfx | Configurations related to encoding, decoding and transcoding; see the |



definition of the mfxInfoMFX structure for details.

Configurations related to video processing; see the definition of the vpp

mfxInfoVPP structure for details.

Protected Specifies the content protection mechanism; this is a reserved

parameter. Its value must be zero.

IOPattern Input and output memory access types for SDK functions; see the

> enumerator IOPattern for details. The Query functions return the natively supported IOPattern if the Query input argument is NULL. This parameter is a mandated input for **QueryIOSurf** and **Init** functions. For **DECODE**, the output pattern must be specified; for **ENCODE**, the input pattern must be specified; and for **VPP**, both input

and output pattern must be specified.

NumExtParam The number of extra configuration structures attached to this structure.

ExtParam Points to an array of pointers to the extra configuration structures; see

the ExtendedBufferID enumerator for a list of extended

configurations.

The list of extended buffers should not contain duplicated entries, i.e. entries of the same type. If mfxVideoParam structure is used to query the SDK capability, then list of extended buffers attached to input and output mfxVideoParam structure should be equal, i.e. should contain

the same number of extended buffers of the same type.

Change History

This structure is available since SDK API 1.0. SDK API 1.1 extended the AsyncDepth field. SDK API 1.17 adds Allocid field.

mfxVPPStat

Definition

```
typedef struct mfxVPPStat {
     mfxU32
                  reserved[16];
     mfxU32
                  NumFrame;
     mfxU32
                  NumCachedFrame;
} mfxVPPStat;
```

Description

The mfxVPPStat structure returns statistics collected during video processing.

Members



Total number of frames processed NumFrame NumCachedFrame Number of internally cached frames

Change History

This structure is available since SDK API 1.0.

mfxENCInput

Definition

```
typedef struct mfxENCInput mfxENCInput;
struct mfxENCInput{
   mfxU32 reserved[32];
   mfxFrameSurface1 *InSurface;
   mfxU16 NumFrameL0;
   mfxFrameSurface1 **LOSurface;
   mfxU16 NumFrameL1;
   mfxFrameSurface1 **L1Surface;
   mfxU16 NumExtParam;
   mfxExtBuffer **ExtParam;
};
```

Description

The mfxENCInput structure specifies input for the **ENC** class of functions.

Members

InSurface Input surface. NumFrameL0, Number of surfaces in L0 and L1 reference lists. NumFrameL1 LOSurface, L0 and L1 reference lists L1Surface NumExtParam Number of extended buffers. ExtParam List of extended buffers.

Change History

This structure is available since SDK API 1.10.



mfxENCOutput

Definition

```
typedef struct _mfxENCOutput mfxENCOutput;
struct _mfxENCOutput{
    mfxU32    reserved[32];

    mfxU16    NumExtParam;
    mfxExtBuffer    **ExtParam;
};
```

Description

The mfxENCOutput structure specifies output of the ENC class of functions.

Members

NumExtParam Number of extended buffers.

ExtParam List of extended buffers.

Change History

This structure is available since SDK API 1.10.

mfxExtLAControl

Definition

```
typedef struct
{
    mfxExtBuffer Header;
    mfxU16 LookAheadDepth;
    mfxU16 DependencyDepth;
    mfxU16 DownScaleFactor;
    mfxU16 BPyramid;

    mfxU16 reserved1[23];

    mfxU16 NumOutStream;
    struct mfxStream{
        mfxU16 Width;
        mfxU16 Height;
        mfxU16 reserved2[14];
    } OutStream[16];
}mfxExtLAControl;
```



Description

The mfxExtLAControl structure is used to control standalone look ahead behavior. This LA is performed by **ENC** class of functions and its results are used later by **ENCODE** class of functions to improve coding efficiency.

This LA is intended for one to N transcoding scenario, where one input bitstream is transcoded to several output ones with different bitrates and resolutions. Usage of integrated into the SDK encoder LA in this scenario is also possible but not efficient in term of performance and memory consumption. Standalone LA by **ENC** class of functions is executed only once for input bitstream in contrast to the integrated LA where LA is executed for each of output streams.

This structure is used at **ENC** initialization time and should be attached to the mfxVideoParam Structure.

Members

| Header.BufferId | Must be mfx_extbuff_lookahead_ctrl. |
|-----------------|---|
| LookAheadDepth | Look ahead depth. This parameter has exactly the same meaning as LookAheadDepth in the mfxExtCodingOption2 structure. |
| DependencyDepth | Dependency depth. This parameter specifies the number of frames that SDK analyzes to calculate inter-frame dependency. It should be less than LookAheadDepth filed. |
| DownScaleFactor | Down scale factor. This parameter has exactly the same meaning as LookAheadDs in the mfxExtCodingOption2 structure. It is recommended to execute LA on downscaled image to improve performance without significant quality degradation. |
| BPyramid | Turn ON this flag to enable BPyramid feature (this mode is not supported by h264 encoder). See the CodingOptionValue enumerator for values of this option. |
| NumOutStream | Number of output streams in one to N transcode scenario. |
| OutStream | Output stream parameters. |
| Width | Output stream width. |
| Height | Output stream height. |

Change History

This structure is available since SDK API 1.10.

The SDK API 1.15 adds BPyramid field.



mfxExtLAFrameStatistics

Definition

```
typedef struct
    mfxU16 Width;
    mfxU16 Height;
    mfxU32 FrameType;
    mfxU32 FrameDisplayOrder;
    mfxU32 FrameEncodeOrder;
    mfxU32 IntraCost;
    mfxU32 InterCost;
mfxU32 DependencyCost;
    mfxU16 Layer;
    mfxU16 reserved[23];
    mfxU64 EstimatedRate[52];
}mfxLAFrameInfo;
typedef struct {
    mfxExtBuffer Header;
    mfxU16 reserved[20];
    mfxU16 NumAlloc;
    mfxU16 NumStream;
mfxU16 NumFrame;
    mfxLAFrameInfo *FrameStat;
    mfxFrameSurface1 *OutSurface;
} mfxExtLAFrameStatistics;
```

Description

The mfxExtLAFrameStatistics structure is used to pass standalone look ahead statistics to the SDK encoder in one to N transcode scenario. This structure is used at runtime and should be attached to the mfxEncoutput structure and then passed, attached, to the mfxEncodeCtrl structure.

Members

| Header.BufferId | Must be mfx_extbuff_lookahead_stat. |
|-----------------|--|
| NumAlloc | Number of allocated elements in the FrameStat array. |
| NumStream | Number of streams in the FrameStat array. |
| NumFrame | Number of frames for each stream in the FrameStat array. |



FrameStat LA statistics for each frame in output stream.

Width Output stream width.

Height Output stream height.

FrameType Output frame type.

FrameDisplayOrder Output frame number in display order.

FrameEncodeOrder Output frame number in encoding order.

IntraCost Intra cost of output frame.

InterCost Inter cost of output frame.

DependencyCost Aggregated dependency cost. It shows how this frame influences

subsequent frames.

Layer BPyramid layer number. zero if BPyramid is not used.

Estimated Rate Estimated rate for each QP.

OutSurface Output surface.

Change History

This structure is available since SDK API 1.10.

The SDK API 1.15 adds Layer field.

mfxExtVPPFieldProcessing

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 Mode;
    mfxU16 InField;
    mfxU16 OutField;
    mfxU16 reserved[25];
} mfxExtVPPFieldProcessing;
```

Description

The mfxExtVPPFieldProcessing structure configures the **VPP** field processing algorithm. The application can attach this extended buffer to the mfxVideoParam structure to configure initialization and/or to the mfxFrameData during runtime, runtime configuration has priority



over initialization configuration. If field processing algorithm was activated via mfxExtVPPDoUse structure and mfxExtVPPFieldProcessing extended buffer was not provided during initialization, this buffer must be attached to mfxFrameData of each input surface.

Members

Must be MFX EXTBUFF VPP FIELD PROCESSING.

Mode Specifies the mode of field processing algorithm. See the VPPFieldProcessingMode enumerator for values of this option

InField When Mode is MFX_VPP_COPY_FIELD specifies input field. See the PicType enumerator for values of this parameter.

OutField When Mode is MFX_VPP_COPY_FIELD specifies output field. See the PicType enumerator for values of this parameter.

Change History

This structure is available since SDK API 1.11.

mfxExtMBQP

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU32 reserved[11];
    mfxU32 NumQPAlloc;
    union {
        mfxU8 *QP;
        mfxU64 reserved2;
    };
} mfxExtMBQP;
```

Description

The mfxExtMBQP structure specifies per-macroblock QP for current frame if mfxExtCodingOption3::EnableMBQP was turned ON during encoder initialization. The application can attach this extended buffer to the mfxEncodeCtrl during runtime.

Members

Header.BufferId Must be MFX EXTBUFF MBQP.

NumQPAlloc The allocated QP array size.

QP Pointer to a list of per-macroblock QP in raster scan order. In case



of interlaced encoding the first half of QP array affects top field and the second – bottom field.

For AVC valid range is 1..51.

For MPEG2 QP corresponds to quantizer_scale of the ISO*/IEC* 13818-2 specification and have valid range 1..112.

Change History

This structure is available since SDK API 1.13.



mfxExtChromaLocInfo

Definition

Description

The mfxExtChromaLocInfo structure defines the location of chroma samples information.

Members

| Header.BufferId | Must be MFX EXTBUFF CHROMA LOC INFO. |
|--------------------------------|---|
| ChromaLocInfoPresentFlag | These parameters define the location of chroma |
| ChromaSampleLocTypeTopField | samples information. |
| ChromaSampleLocTypeBottomField | See Annex E of the ISO*/IEC* 14496-10 specification for the definition of these parameters. |

Change History

This structure is available since SDK API 1.13.

mfxExtHEVCTiles

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 NumTileRows;
    mfxU16 NumTileColumns;
    mfxU16 reserved[74];
}mfxExtHEVCTiles;
```

Description

The mfxExtHEVCTiles structure configures tiles options for the HEVC encoder. The application can attach this extended buffer to the mfxVideoParam structure to configure initialization.



Members

Header.BufferId Must be MFX EXTBUFF HEVC TILES.

NumTileRows Number of tile rows.

NumTileColumns Number of tile columns.

Change History

This structure is available since SDK API 1.13.

mfxExtMBDisableSkipMap

Definition

```
typedef struct {
   mfxExtBuffer Header;
   mfxU32 reserved[11];
   mfxU32 MapSize;
   union {
       mfxU8 *Map;
       mfxU64 reserved2;
} mfxExtMBDisableSkipMap;
```

Description

The mfxExtMBDisableSkipMap structure specifies macroblock map for current frame which forces specified macroblocks to be non skip if mfxExtCodingOption3::MBDisableSkipMap was turned ON during encoder initialization. The application can attach this extended buffer to the mfxEncodeCtrl during runtime.

Members

Header.BufferId Must be MFX EXTBUFF MB DISABLE SKIP MAP.

MapSize Macroblock map size.

Мар Pointer to a list of non-skip macroblock flags in raster

scan order. Each flag is one byte in map. Set flag to 1 to force corresponding macroblock to be non-skip. In case of interlaced encoding the first half of map affects

top field and the second - bottom field.

Change History

This structure is available since SDK API 1.13.



mfxExtDecodedFrameInfo

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 FrameType;
    mfxU16 reserved[59];
} mfxExtDecodedFrameInfo;
```

Description

This structure is used by the SDK decoders to report additional information about decoded frame. The application can attach this extended buffer to the mfxFrameSurface1::mfxFrameData structure at runtime.

Members

Header.BufferId

Must be MFX EXTBUFF DECODED FRAME INFO

FrameType

Frametype. See FrameType enumerator for the list of possible types.

Change History

This structure is available since SDK API 1.14.

mfxExtTimeCode

Definition

Description

This structure is used by the SDK to pass MPEG 2 specific timing information.

Members

Header.BufferId Must be MFX EXTBUFF TIME CODE



DropFrameFlag TimeCodeHours TimeCodeMinutes TimeCodeSeconds TimeCodePictures

These parameters define timing information.

See ISO/IEC 13818-2 and ITU-T H.262, MPEG-2 Part 2

for the definition of these parameters.

Change History

This structure is available since SDK API 1.14.

mfxExtHEVCRegion

Definition

```
enum {
   MFX HEVC REGION ENCODING ON = 0,
   MFX HEVC REGION ENCODING OFF = 1
};
typedef struct {
   mfxExtBuffer Header;
   mfxU32 RegionId;
mfxU16 RegionTyp
               RegionType;
   mfxU16
               RegionEncoding;
   mfxU16
                reserved[24];
} mfxExtHEVCRegion;
```

Description

Attached to the mfxVideoParam structure during HEVC encoder initialization, specifies the region to encode.

Members

Header.BufferId Must be MFX EXTBUFF HEVC REGION.

RegionId Id of region.

RegionType Type of region. See HEVCRegionType enumerator for

the list of possible types.

RegionEncoding Set to MFX HEVC REGION ENCODING ON to encode only

specified region.

Change History

This structure is available since SDK API 1.15.

The SDK API 1.16 adds RegionEncoding field.



mfxExtThreadsParam

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 NumThread;
    mfxI32 SchedulingType;
    mfxI32 Priority;
    mfxU16 reserved[55];
} mfxExtThreadsParam;
```

Description

Attached to the <u>mfxInitParam</u> structure during the SDK session initialization, mfxExtThreadsParam stracture specifies options for threads created by this session.

Members

```
Header.BufferId

Must be MFX EXTBUFF THREADS PARAM.

NumThread

The number of threads.

SchedulingType

Scheduling policy for all threads.

Priority

Priority for all threads.
```

Change History

This structure is available since SDK API 1.15.

mfxExtHEVCParam

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 PicWidthInLumaSamples;
    mfxU16 PicHeightInLumaSamples;
    mfxU64 GeneralConstraintFlags;
    mfxU16 reserved[118];
} mfxExtHEVCParam;
```

Description



Attached to the <u>mfxVideoParam</u> structure extends it with HEVC-specific parameters. Used by both decoder and encoder.

Members

Header.BufferId

Must be MFX EXTBUFF HEVC PARAM.

PicWidthInLumaSamples

Specifies the width of each coded picture in units of luma samples.

PicHeightInLumaSamples

Specifies the height of each coded picture in units of luma samples.

GeneralConstraintFlags

Additional flags to specify exact profile/constraints. See the GeneralConstraintFlags enumerator for values of this field.

Change History

This structure is available since SDK API 1.14.

The SDK API 1.16 adds GeneralConstraintFlags field.

mfxExtPredWeightTable

Definition

```
typedef struct {
   mfxExtBuffer Header;
                                         // 0..7
   mfxU16
               LumaLog2WeightDenom;
               ChromaLog2WeightDenom;
                                         // 0..7
   mfxU16
               LumaWeightFlag[2][32];
   mfxU16
                                         // [list] 0,1
               ChromaWeightFlag[2][32]; // [list] 0,1
   mfxU16
                                         // [list][list entry][Y, Cb,
   mfxI16
               Weights[2][32][3][2];
Cr][weight, offset]
   mfxU16
               reserved[58];
} mfxExtPredWeightTable;
```

Description

When mfxExtCodingOption3::WeightedPred was set to explicit during encoder Init or
Reset and the current frame is P-frame or mfxExtCodingOption3::WeightedBiPred was set
to explicit during encoder Init or Reset and the current frame is B-frame, attached to
mfxEncodeCtrl, this structure specifies weighted prediction table for current frame.

Members

Header.BufferId Must be MFX EXTBUFF HEVC PRED WEIGHT TABLE.



LumaLog2WeightDenom

Base 2 logarithm of the denominator for all luma weighting factors. Value shall be in the range of 0 to 7, inclusive.

ChromaLog2WeightDenom

Base 2 logarithm of the denominator for all chroma weighting factors. Value shall be in the range of 0 to 7, inclusive.

LumaWeightFlag

 $\label{lumaWeightFlag[L][R]} \begin{subarray}{ll} \tt EumaWeightFlag[L][R] & equal to 1 specifies that the weighting factors for the luma component are specified for R's entry of RefPicList L. \end{subarray}$

ChromaWeightFlag

Weights

The values of the weights and offsets used in the encoding processing. The value of

Weights[i][j][k][m] is interpreted as: i refers to reference picture list 0 or 1; j refers to reference list entry 0-31; k refers to data for the luma component when it is 0, the Cb chroma component when it is 1 and the Cr chroma component when it is 2; m refers to weight when it is 0 and offset when it is 1

Change History

This structure is available since SDK API 1.16.

mfxExtDirtyRect

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 NumRect;
    mfxU16 reserved1[11];

    struct {
        mfxU32 Left;
        mfxU32 Top;
        mfxU32 Right;
        mfxU32 Bottom;

        mfxU16 reserved2[8];
    } Rect[256];
} mfxExtDirtyRect;
```



Description

Used by the application to specify dirty regions within a frame during encoding. It may be used at initialization or at runtime

Members

NumRect

Number of dirty rectangles.

Rect

Array of dirty rectangles.

Left

Dirty region location. Should be aligned to MB boundaries (should be dividable by 16). If not, the SDK encoder truncates it to MB boundaries, for example, both 17 and 31 will be truncated to 16.

Bottom

Change History

This structure is available since SDK API 1.16.

mfxExtMoveRect

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 NumRect;
    mfxU16 reserved1[11];

    struct {
        mfxU32 DestLeft;
        mfxU32 DestRight;
        mfxU32 DestBottom;

        mfxU32 SourceLeft;
        mfxU32 SourceTop;
        mfxU16 reserved2[4];
    } Rect[256];
} mfxExtMoveRect;
```

Description

Used by the application to specify moving regions within a frame during encoding.

Members



Header.BufferId Must be MFX EXTBUFF MOVING RECTANGLES.

NumRect Number of moving rectangles.

Rect Array of moving rectangles.

DestLeft Destination rectangle location. Should be aligned to MB boundaries (should be dividable by 16). If not, the DestTop SDK encoder truncates it to MB boundaries, for DestRight example, both 17 and 31 will be truncated to 16.

DestBottom

SourceLeft Source rectangle location.

SourceTop

Change History

This structure is available since SDK API 1.16.

mfxExtCodingOptionVPS

Definition

```
typedef struct {
                    Header;
   mfxExtBuffer
    union {
        mfxU8
                    *VPSBuffer;
        mfxU64
                    reserved1;
    };
   mfxU16
                    VPSBufSize;
   mfxU16
                    VPSId;
   mfxU16
                    reserved[6];
} mfxExtCodingOptionVPS;
```

Description

Attach this structure as part of the mfxVideoParam extended buffers to configure the SDK encoder during MFXVideoENCODE Init. The sequence or picture parameters specified by this structure overwrite any such parameters specified by the mfxVideoParam structure or any other extended buffers attached therein.



If the encoder does not support the specified parameters, the encoder does not initialize and returns the status code MFX ERR INCOMPATIBLE VIDEO PARAM.

Check with the <u>MFXVideoENCODE Query</u> function for the support of this multiple segemnt encoding feature. If this feature is not supported, the query returns <u>MFX ERR UNSUPPORTED</u>.

Members

Header.BufferId Must be MFX EXTBUFF CODING OPTION VPS.

VPSBuffer Pointer to a valid bitstream that contains the VPS (video

parameter set for HEVC) buffer.

VPSBufSize Size of the VPS in bytes

VPSId VPS identifier; the value is reserved and must be zero.

Change History

This structure is available since SDK API 1.17.

mfxExtVPPRotation

Definition

```
typedef struct {
    mfxExtBuffer Header;

    mfxU16 Angle;
    mfxU16 reserved[11];
} mfxExtVPPRotation;
```

Description

The mfxExtVPPRotation structure configures the **VPP** Rotation filter algorithm.

Members

Header.BufferId Must be MFX EXTBUFF VPP ROTATION

Angle Rotation angle. See <u>Angle</u> enumerator for supported values.

Change History



This structure is available since SDK API 1.17.



Enumerator Reference

BitstreamDataFlag

Description

The BitstreamDataFlag enumerator uses bit-ORed values to itemize additional information about the bitstream buffer.

Name/Description

MFX BITSTREAM COMPLETE FRAME

The bitstream buffer contains a complete frame or complementary field pair of data for the bitstream. For decoding, this means that the decoder can proceed with this buffer without waiting for the start of the next frame, which effectively reduces decoding latency.

If this flag is set, but the bitstream buffer contains

incomplete frame or pair of field, then decoder will produce

corrupted output.

MFX BITSTREAM EOS

The bitstream buffer contains the end of the stream. For decoding, this means that the application does not have any additional bitstream data to send to decoder.

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.6 adds MFX BITSTREAM EOS definition.

ChromaFormatIdc

Description

The ChromaFormatIdc enumerator itemizes color-sampling formats.

Name/Description

MFX CHROMAFORMAT MONOCHROME Monochrome

MFX CHROMAFORMAT YUV420 4:2:0 color

MFX CHROMAFORMAT YUV422 4:2:2 color



MFX CHROMAFORMAT YUV444 4:4:4 color

MFX_CHROMAFORMAT_YUV400 equal to monochrome

MFX_CHROMAFORMAT_YUV411 4:1:1 color

MFX_CHROMAFORMAT_YUV422H 4:2:2 color, horizontal subsampling. It

is equal to 4:2:2 color.

MFX_CHROMAFORMAT_YUV422V 4:2:2 color, vertical subsampling

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.4 adds MFX_CHROMAFORMAT_YUV400, MFX_CHROMAFORMAT_YUV411, MFX CHROMAFORMAT YUV422H and MFX CHROMAFORMAT YUV422V definitions.

CodecFormatFourCC

Description

The CodecFormatFourCC enumerator itemizes codecs in the FourCC format.

Name/Description

MFX_CODEC_AVC AVC, H.264, or MPEG-4, part 10 codec

MFX CODEC MPEG2 MPEG-2 codec

MFX CODEC VC1 VC-1 codec

MFX_CODEC_HEVC HEVC codec

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.8 added MFX CODEC HEVC definition.

CodecLevel

Description



The CodecLevel enumerator itemizes codec levels for all codecs.

Name/Description

| MFX_LEVEL_UNKNOWN | Unspecified codec level |
|---|---|
| MFX_LEVEL_AVC_1 MFX_LEVEL_AVC_1b MFX_LEVEL_AVC_11 MFX_LEVEL_AVC_12 MFX_LEVEL_AVC_13 | H.264 level 1-1.3 |
| MFX_LEVEL_AVC_2 MFX_LEVEL_AVC_21 MFX_LEVEL_AVC_22 | H.264 level 2-2.2 |
| MFX_LEVEL_AVC_3 MFX_LEVEL_AVC_31 MFX_LEVEL_AVC_32 | H.264 level 3-3.2 |
| MFX_LEVEL_AVC_4 MFX_LEVEL_AVC_41 MFX_LEVEL_AVC_42 | H.264 level 4-4.2 |
| MFX_LEVEL_AVC_5 MFX_LEVEL_AVC_51 MFX_LEVEL_AVC_52 | H.264 level 5-5.2 |
| MFX_LEVEL_MPEG2_LOW MFX_LEVEL_MPEG2_MAIN MFX_LEVEL_MPEG2_HIGH MFX_LEVEL_MPEG2_HIGH1440 | MPEG-2 levels |
| MFX_LEVEL_VC1_LOW MFX_LEVEL_VC1_MEDIAN MFX_LEVEL_VC1_HIGH | VC-1 Level Low (simple & main profiles) |
| MFX_LEVEL_VC1_0 MFX_LEVEL_VC1_1 MFX_LEVEL_VC1_2 MFX_LEVEL_VC1_3 MFX_LEVEL_VC1_4 | VC-1 advanced profile levels |
| MFX_LEVEL_HEVC_1 MFX_LEVEL_HEVC_2 MFX_LEVEL_HEVC_21 MFX_LEVEL_HEVC_3 MFX_LEVEL_HEVC_31 MFX_LEVEL_HEVC_4 MFX_LEVEL_HEVC_41 MFX_LEVEL_HEVC_5 MFX_LEVEL_HEVC_5 MFX_LEVEL_HEVC_52 MFX_LEVEL_HEVC_66 MFX_LEVEL_HEVC_66 MFX_LEVEL_HEVC_61 MFX_LEVEL_HEVC_62 | HEVC levels and tiers |



```
MFX_TIER_HEVC_MAIN
MFX_TIER_HEVC_HIGH
```

Change History

This enumerator is available since SDK API 1.0. SDK API 1.8 added HEVC level and tier definitions.

CodecProfile

Description

The CodecProfile enumerator itemizes codec profiles for all codecs.

Name/Description

| MFX_PROFILE_UNKNOWN | Unspecified profile |
|--|---|
| MFX_PROFILE_AVC_BASELINE MFX_PROFILE_AVC_MAIN MFX_PROFILE_AVC_EXTENDED MFX_PROFILE_AVC_HIGH MFX_PROFILE_AVC_CONSTRAINED_BASELINE MFX_PROFILE_AVC_CONSTRAINED_HIGH MFX_PROFILE_AVC_PROGRESSIVE_HIGH | H.264 profiles |
| MFX_PROFILE_AVC_CONSTRAINT_SET0 MFX_PROFILE_AVC_CONSTRAINT_SET1 MFX_PROFILE_AVC_CONSTRAINT_SET2 MFX_PROFILE_AVC_CONSTRAINT_SET3 MFX_PROFILE_AVC_CONSTRAINT_SET4 MFX_PROFILE_AVC_CONSTRAINT_SET5 | Combined with H.264 profile these flags impose additional constrains. See H.264 specification for the list of constrains. |
| MFX_PROFILE_MPEG2_SIMPLE MFX_PROFILE_MPEG2_MAIN MFX_PROFILE_MPEG2_HIGH | MPEG-2 profiles |
| MFX_PROFILE_VC1_SIMPLE MFX_PROFILE_VC1_MAIN MFX_PROFILE_VC1_ADVANCED | VC-1 profiles |
| MFX_PROFILE_HEVC_MAIN MFX_PROFILE_HEVC_MAIN10 MFX_PROFILE_HEVC_MAINSP MFX_PROFILE_HEVC_REXT | HEVC profiles |

Change History



This enumerator is available since SDK API 1.0.

SDK API 1.3 adds MFX PROFILE AVC EXTENDED.

SDK API 1.4 adds MFX PROFILE AVC CONSTRAINED BASELINE,

MFX_PROFILE_AVC_CONSTRAINED_HIGH, MFX_PROFILE_AVC_PROGRESSIVE_HIGH and six constrained flags MFX PROFILE AVC CONSTRAINT SET.

SDK API 1.8 added HEVC profile definitions.

SDK API 1.16 adds MFX PROFILE HEVC REXT.

CodingOptionValue

Description

The CodingOptionValue enumerator defines a three-state coding option setting.

Name/Description

MFX_CODINGOPTION_UNKNOWN Unspecified

MFX_CODINGOPTION_ON Coding option set

MFX_CODINGOPTION_OFF Coding option not set

MFX CODINGOPTION ADAPTIVE Reserved

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.6 adds MFX CODINGOPTION ADAPTIVE option.

ColorFourCC

Description

The ColorFourCC enumerator itemizes color formats.

Name/Description

MFX_FOURCC_YV12 YV12 color planes

MFX_FOURCC_NV12 NV12 color planes

MFX FOURCC_NV16 4:2:2 color format with similar to NV12 layout.



MFX FOURCC RGB4 RGB4 (RGB32) color planes MFX FOURCC YUY2 YUY2 color planes MFX FOURCC P8 Internal SDK color format. The application should use one of the functions below to create such surface, depending on Direct3D version. Direct3D9 IDirectXVideoDecoderService::CreateSurface() Direct3D11 ID3D11Device::CreateBuffer() MFX_FOURCC_P8_TEXTURE Internal SDK color format. The application should use one of the functions below to create such surface, depending on Direct3D version. Direct3D9 IDirectXVideoDecoderService::CreateSurface() Direct3D11 ID3D11Device::CreateTexture2D() MFX FOURCC P010 P010 color format. This is 10 bit per sample format with similar to NV12 layout. This format should be mapped to DXGI_FORMAT_P010. MFX FOURCC P210 10 bit per sample 4:2:2 color format with similar to NV12 layout MFX FOURCC BGR4 ABGR color format. It is similar to MFX_FOURCC_RGB4 but with interchanged R and B channels. 'A' is 8 MSBs, then 8 bits for 'B' channel, then 'G' and 'R' channels. MFX FOURCC A2RGB10 10 bits ARGB color format packed in 32 bits. 'A' channel is two MSBs, then 'R', then 'G' and then 'B' channels. This format should be mapped to DXGI_FORMAT_R10G10B10A2_UNORM or D3DFMT_A2R10G10B10. MFX FOURCC ARGB16 10 bits ARGB color format packed in 64 bits. 'A' channel is 16 MSBs, then 'R', then 'G' and then 'B' channels. This format should be mapped to DXGI_FORMAT_R16G16B16A16_UINT or D3DFMT_A16B16G16R16 formats. MFX FOURCC R16 16 bits single channel color format.

This format should be mapped to



DXGI_FORMAT_R16_TYPELESS or D3DFMT_R16F.

MFX_FOURCC_ABGR16 10 bits ABGR color format packed in 64 bits. 'A' channel is

16 MSBs, then 'B', then 'G' and then 'R' channels.

This format should be mapped to

DXGI_FORMAT_R16G16B16A16_UINT or

D3DFMT_A16B16G16R16 formats.

MFX_FOURCC_AYUV YUV 4:4:4, AYUV color format.

This format should be mapped to DXGI_FORMAT_AYUV.

MFX_FOURCC_AYUV_RGB4 RGB4 stored in AYUV surface.

This format should be mapped to DXGI_FORMAT_AYUV.

MFX_FOURCC_UYVY UYVY color planes. Same as YUY2 except the byte order is

reversed.

Change History

This enumerator is available since SDK API 1.0.

The SDK API 1.1 adds MFX FOURCC P8.

The SDK API 1.6 adds MFX FOURCC P8 TEXTURE.

The SDK API 1.9 adds MFX_FOURCC_P010, MFX_FOURCC_BGR4, MFX_FOURCC_A2RGB10, MFX FOURCC ARGB16 and MFX FOURCC R16.

The SDK API 1.11 adds MFX FOURCC NV16 and MFX FOURCC P210.

The SDK API 1.17 adds MFX_FOURCC_ABGR16, MFX_FOURCC_AYUV, MFX_FOURCC_AYUV_RGB4, and MFX_FOURCC_UYVY.

Corruption

Description

The Corruption enumerator itemizes the decoding corruption types. It is a bit-OR'ed value of the following.

Name/Description

MFX CORRUPTION MINOR Minor corruption in decoding certain macro-blocks

MFX_CORRUPTION_MAJOR Major corruption in decoding the frame



| MFX_CORRUPTION_REFERENCE_LIST | The reference list information of this frame does not match what is specified in the Reference Picture Marking Repetition SEI message. |
|-------------------------------------|--|
| MFX_CORRUPTION_ABSENT_TOP_FIEL D | Top field of frame is absent in bitstream. Only bottom field has been decoded. |
| MFX_CORRUPTION_ABSENT_BOTTOM_F IELD | Bottom field of frame is absent in bitstream. Only top filed has been decoded. |

Change History

This enumerator is available since SDK API 1.3. The SDK API 1.6 added MFX_CORRUPTION_ABSENT_TOP_FIELD and MFX_CORRUPTION_ABSENT_BOTTOM_FIELD definitions.

ExtendedBufferID

Description

The ExtendedBufferID enumerator itemizes and defines identifiers (BufferId) for extended buffers or video processing algorithm identifiers.

Name/Description

| MFX_EXTBUFF_ AVC_REFLIST_ CTRL | This extended buffer defines additional encoding controls for reference list. See the <pre>mfxExtAVCRefListCtrl</pre> structure for details. The application can attach this buffer to the <pre>mfxVideoParam</pre> structure for encoding & decoding initialization, or the <pre>mfxEncodeCtrl</pre> structure for per-frame encoding configuration. |
|--|---|
| MFX_EXTBUFF_ AVC_TEMPORAL _LAYERS | This extended buffer configures the structure of temporal layers inside the encoded H.264 bitstream. See the <pre>mfxExtAvcTemporalLayers</pre> structure for details. The application can attach this buffer to the <pre>mfxVideoParam</pre> structure for encoding initialization. |
| MFX_EXTBUFF_ CODING_OPTIO N | This extended buffer defines additional encoding controls. See the <pre>mfxExtCodingOption</pre> structure for details. The application can attach this buffer to the <pre>mfxVideoParam</pre> structure for encoding initialization. |
| MFX_EXTBUFF_ CODING_OPTIO N_SPSPPS | This extended buffer defines sequence header and picture header for encoders and decoders. See the <pre>mfxExtCodingOptionSPSPPS</pre> structure for details. The application can attach this buffer to the <pre>mfxVideoParam</pre> structure for encoding initialization, and for obtaining raw headers from the decoders and encoders. |



MFX_EXTBUFF_ CODING_OPTIO This extended buffer defines additional encoding controls. See the mfxExtCodingOption2 structure for details. The application can attach this buffer to the mfxVideoParam structure for encoding initialization.

MFX_EXTBUFF_ CODING_OPTIO N3 This extended buffer defines additional encoding controls. See the mfxExtCodingOption3 structure for details. The application can attach this buffer to the mfxVideoParam structure for encoding initialization.

MFX_EXTBUFF_ ENCODED_FRAM E INFO This extended buffer is used by the SDK encoder to report additional information about encoded picture. See the mfxExtAVCEncodedFrameInfo structure for details. The application can attach this buffer to the mfxBitstream structure before calling
MFXVideoENCODE EncodeFrameAsync function.

MFX_EXTBUFF_ ENCODER_CAPA BILITY This extended buffer is used to retrive SDK encoder capability. See the mfxExtEncoderCapability structure for details. The application can attach this buffer to the mfxVideoParam structure before calling
MFXVideoENCODE Query function.

MFX_EXTBUFF_ ENCODER_RESE T OPTION This extended buffer is used to control encoder reset behavior and also to query possible encoder reset outcome. See the mfxExtEncoderResetOption structure for details. The application can attach this buffer to the mfxVideoParam structure before calling
MFXVideoENCODE Query Or MFXVideoENCODE Reset functions.

MFX_EXTBUFF_
OPAQUE_SURFA
CE_ALLOCATIO
N

This extended buffer defines opaque surface allocation information. See the mfxExtOpaqueSurfaceAlloc structure for details. The application can attach this buffer to decoding, encoding, or video processing initialization.

MFX_EXTBUFF_ PICTURE_TIMI NG_SEI This extended buffer configures the H.264 picture timing SEI message. See the <u>mfxExtPictureTimingSEI</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for encoding initialization, or the <u>mfxEncodeCtrl</u> structure for per-frame encoding configuration.

MFX_EXTBUFF_ VIDEO_SIGNAL _INFO This extended buffer defines video signal type. See the mfxExtVideoSignalInfo structure for details. The application can attach this buffer to the mfxVideoParam structure for encoding initialization, and for retrieving such information from the decoders.

MFX_EXTBUFF_ VPP AUXDATA

This extended buffer defines auxiliary information at the **VPP** output. See the <u>mfxExtVPPAuxData</u> structure for details. The application can attach this buffer to the <u>mfxEncodeCtrl</u> structure for per-frame encoding control.

MFX_EXTBUFF_ VPP DENOISE The extended buffer defines control parameters for the **VPP** denoise filter algorithm. See the <u>mfxExtVPPDenoise</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for



video processing initialization.

MFX_EXTBUFF_ VPP_DETAIL The extended buffer defines control parameters for the **VPP** detail filter algorithm. See the <u>mfxExtVPPDetail</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_DONOTUSE This extended buffer defines a list of **VPP** algorithms that applications should not use. See the <u>mfxExtVPPDoNotUse</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_DOUSE This extended buffer defines a list of **VPP** algorithms that applications should use. See the <u>mfxExtVPPDoUse</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_FRAME_RA TE_CONVERSIO N This extended buffer defines control parameters for the **VPP** frame rate conversion algorithm. See the <u>mfxExtVPPFrameRateConversion</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_IMAGE_ST ABILIZATION This extended buffer defines control parameters for the **VPP** image stabilization filter algorithm. See the <u>mfxExtVPPImageStab</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_PICSTRUC T_DETECTION Deprecated.

MFX_EXTBUFF_ VPP_PROCAMP

The extended buffer defines control parameters for the **VPP** ProcAmp filter algorithm. See the <u>mfxExtVPPProcAmp</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization.

MFX_EXTBUFF_ VPP_SCENE_CH ANGE Deprecated.

MFX_EXTBUFF_ VPP_FIELD_PR OCESSING The extended buffer defines control parameters for the **VPP** field-processing algorithm. See the <u>mfxExtVPPFieldProcessing</u> structure for details. The application can attach this buffer to the <u>mfxVideoParam</u> structure for video processing initialization or to the <u>mfxFrameData</u> structure during runtime.

MFX_EXTBUFF_ MBQP

This extended buffer defines per-macroblock QP. See the <u>mfxExtMBQP</u> structure for details. The application can attach this buffer to the <u>mfxEncodeCtrl</u> structure for per-frame encoding configuration.



| MFX_EXTBUFF_ CHROMA_LOC_I NFO | This extended buffer defines chroma samples location information. See the mfxExtChromaLocInfo structure for details. The application can attach this buffer to the mfxVideoParam structure for encoding initialization. |
|---|--|
| MFX_EXTBUFF_ HEVC_PARAM | See the mfxExtHEVCParam structure for details. |
| MFX_EXTBUFF_ HEVC_TILES | This extended buffer defines additional encoding controls for HEVC tiles. See the <pre>mfxExtHEVCTiles</pre> structure for details. The application can attach this buffer to the <pre>mfxVideoParam</pre> structure for encoding initialization. |
| MFX_EXTBUFF_ MB_DISABLE_S KIP_MAP | This extended buffer defines macroblock map for current frame which forces specified macroblocks to be non skip. See the <pre>mfxExtMBDisableSkipMap</pre> structure for details. The application can attach this buffer to the <pre>mfxEncodeCtrl</pre> structure for per-frame encoding configuration. |
| MFX_EXTBUFF_ DECODED_FRAM E_INFO | This extended buffer is used by SDK decoders to report additional information about decoded frame. See the <pre>mfxExtDecodedFrameInfo</pre> structure for more details. |
| MFX_EXTBUFF_ TIME_CODE | See the mfxExtTimeCode structure for more details. |
| MFX_HEVC_REGION_SLICE | This extended buffer instructs HEVC encoder to encode only one region. The application can attach this buffer to the mfxVideoParam structure for HEVC encoding initialization. |
| MFX_EXTBUFF_ THREADS_PARA M | See the <u>mfxExtThreadsParam</u> structure for details. |
| MFX_EXTBUFF_ PRED_WEIGHT_ TABLE | See the <pre>mfxExtPredWeightTable</pre> structure for details. |
| MFX_EXTBUFF_ DIRTY_RECTAN GLES | See the <u>mfxExtDitrtyRect</u> structure for details. |
| MFX_EXTBUFF_ MOVING_RECTA NGLES | See the <u>mfxExtMoveRect</u> structure for details. |
| MFX_EXTBUFF_ CODING_OPTIO N_VPS | See the <pre>mfxExtCodingOptionVPS</pre> structure for details. |
| MFX_EXTBUFF_ | See the <u>mfxExtVPPRotation</u> structure for details. |



VPP ROTATION

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.6 adds mfx_extbuff_vpp_image_stabilization, mfx_extbuff_vpp_picstruct_detection, mfx_extbuff_coding_option2 and deprecates mfx extbuff vpp scene change.

SDK API 1.7 adds MFX_EXTBUFF_ENCODED_FRAME_INFO, MFX EXTBUFF ENCODER CAPABILITY, MFX EXTBUFF ENCODER RESET OPTION.

SDK API 1.11 adds ${\tt MFX_EXTBUFF_CODING_OPTION3}$ and ${\tt MFX_EXTBUFF_VPP_FIELD_PROCESSING.}$

SDK API 1.13 adds MFX_EXTBUFF_MBQP, MFX_EXTBUFF_HEVC_TILES, MFX EXTBUFF MB DISABLE SKIP MAP and MFX EXTBUFF CHROMA LOC INFO.

SDK API 1.14 adds MFX_EXTBUFF_HEVC_PARAM, MFX_EXTBUFF_HEVC_TILES, MFX_EXTBUFF_MB_DISABLE_SKIP_MAP, MFX_EXTBUFF_DECODED_FRAME_INFO and MFX_EXTBUFF_TIME_CODE.

SDK API 1.15 adds MFX HEVC REGION SLICE and MFX EXTBUFF THREADS PARAM.

SDK API 1.16 adds Mfx_extbuff_pred_weight_table, Mfx_extbuff_dirty_rectangles and Mfx_extbuff_moving_rectangles.

SDK API 1.17 adds MFX_EXTBUFF_CODING_OPTION_VPS and MFX_EXTBUFF_VPP_ROTATION and deprecates MFX EXTBUFF VPP PICSTRUCT DETECTION.

See additional change history in the structure definitions.

ExtMemBufferType

Description

The <code>ExtMemBufferType</code> enumerator specifies the buffer type. It is a bit-ORed value of the following.

Name/Description

MFX MEMTYPE PERSISTENT MEMORY

Memory page for persistent use

Change History

This enumerator is available since SDK API 1.0.



ExtMemFrameType

Description

The <code>ExtMemFrameType</code> enumerator specifies the memory type of frame. It is a bit-ORed value of the following. For information on working with video memory surfaces, see the section Working with hardware acceleration.

Name/Description

| MFX_MEMTYPE_VIDEO_MEMORY_DE CODER_TARGET | Frames are in video memory and belong to video decoder render targets. |
|---|---|
| MFX_MEMTYPE_VIDEO_MEMORY_PR OCESSOR_TARGET | Frames are in video memory and belong to video processor render targets. |
| MFX_MEMTYPE_SYSTEM_MEMORY | The frames are in system memory. |
| MFX_MEMTYPE_FROM_ENCODE | Allocation request comes from an ENCODE function |
| MFX_MEMTYPE_FROM_DECODE | Allocation request comes from a DECODE function |
| MFX_MEMTYPE_FROM_VPPIN | Allocation request comes from a VPP function for input frame allocation |
| MFX_MEMTYPE_FROM_VPPOUT | Allocation request comes from a VPP function for output frame allocation |
| MFX_MEMTYPE_INTERNAL_FRAME | Allocation request for internal frames |
| MFX_MEMTYPE_EXTERNAL_FRAME | Allocation request for I/O frames |
| MFX_MEMTYPE_OPAQUE_FRAME | Allocation request for opaque frames |
| MFX_MEMTYPE_EXPORT_FRAME | Application requests frame handle export to some associated object. For Linux frame handle can be considered to be exported to DRM Prime FD, DRM FLink or DRM FrameBuffer Handle. Specifics of export types and export procedure depends on external frame allocator implementation |

Remarks

The application may use macro MFX_MEMTYPE_BASE to extract the base memory types, one of MFX_MEMTYPE_VIDEO_MEMORY_DECODER_TARGET,
MFX MEMTYPE VIDEO MEMORY PROCESSOR TARGET, and MFX MEMTYPE SYSTEM MEMORY.

Change History



This enumerator is available since SDK API 1.0. SDK API 1.3 extended the MFX_MEMTYPE_OPAQUE_FRAME definition and the MFX_MEMTYPE_BASE macro definition.

SDK API 1.17 adds MFX MEMTYPE EXPORT FRAME.

FrameDataFlag

Description

The FrameDataFlag enumerator uses bit-ORed values to itemize additional information about the frame buffer.

Name/Description

 $\begin{tabular}{ll} \tt MFX_FRAMEDATA_ORIGINAL_\\ \tt TIMESTAMP \end{tabular} Indicates the time stamp of this frame is not calculated and is a pass-through of the original time stamp. \\ \end{tabular}$

Change History

This enumerator is available since SDK API 1.3.

FrameType

Description

The ${\tt FrameType}$ enumerator itemizes frame types. Use bit-ORed values to specify all that apply.

Name/Description

| MFX_FRAMETYPE_I | This frame or the first field is encoded as an I frame/field. |
|-------------------|---|
| MFX_FRAMETYPE_P | This frame or the first field is encoded as a P frame/field. |
| MFX_FRAMETYPE_B | This frame or the first field is encoded as a B frame/field. |
| MFX_FRAMETYPE_S | This frame or the first field is either an SI- or SP-frame/field. |
| MFX_FRAMETYPE_REF | This frame or the first field is encoded as a reference. |
| MFX_FRAMETYPE_IDR | This frame or the first field is encoded as an IDR. |
| MFX_FRAMETYPE_xI | The second field is encoded as an I-field. |



| MFX_FRAMETYPE_xP | The second field is encoded as a P-field. |
|--------------------|---|
| MFX_FRAMETYPE_xB | The second field is encoded as a B-field. |
| MFX_FRAMETYPE_xS | The second field is an SI- or SP-field. |
| MFX_FRAMETYPE_xREF | The second field is encoded as a reference. |
| MFX FRAMETYPE xIDR | The second field is encoded as an IDR. |

Change History

This enumerator is available since SDK API 1.0. SDK API 1.3 extended the second field types.

FrcAlgm

Description

The FrcAlgm enumerator itemizes frame rate conversion algorithms. See description of mfxExtVPPFrameRateConversion structure for more details.

Name/Description

| MFX_FRCALGM_PRESERVE_TI MESTAMP | Frame dropping/repetition based frame rate conversion algorithm with preserved original time stamps. Any inserted frames will carry MFX_TIMESTAMP_UNKNOWN. |
|------------------------------------|---|
| MFX_FRCALGM_DISTRIBUTED _TIMESTAMP | Frame dropping/repetition based frame rate conversion algorithm with distributed time stamps. The algorithm distributes output time stamps evenly according to the output frame rate. |
| MFX_FRCALGM_FRAME_INTER POLATION | Frame rate conversion algorithm based on frame interpolation. This flag may be combined with MFX_FRCALGM_PRESERVE_TIMESTAMP or MFX_FRCALGM_DISTRIBUTED_TIMESTAMP flags. |

Change History

This enumerator is available since SDK API 1.3.



GopOptFlag

Description

The GopOptFlag enumerator itemizes special properties in the GOP (Group of Pictures) sequence.

Name/Description

MFX GOP CLOSED

The encoder generates closed GOP if this flag is set. Frames in this GOP do not use frames in previous GOP as reference.

The encoder generates open GOP if this flag is not set. In this GOP frames prior to the first frame of GOP in display order may use frames from previous GOP as reference. Frames subsequent to the first frame of GOP in display order do not use frames from previous GOP as reference.

The AVC encoder ignores this flag if IdrInterval in mfxInfoMFX structure is set to 0, i.e. if every GOP starts from IDR frame. In this case, GOP is encoded as closed.

This flag does not affect long-term reference frames. See Appendix C: <u>Long-term Reference frame</u> for more details.

MFX_GOP_STRICT

The encoder must strictly follow the given GOP structure as defined by parameter <code>GopPicSize</code>, <code>GopRefDist</code> etc in the <code>mfxVideoParam</code> structure. Otherwise, the encoder can adapt the GOP structure for better efficiency, whose range is constrained by parameter <code>GopPicSize</code> and <code>GopRefDist</code> etc. See also description of <code>AdaptiveI</code> and <code>AdaptiveB</code> fields in the <code>mfxextCodingOption2</code> structure.

Change History

This enumerator is available since SDK API 1.0.

IOPattern

Description

The IOPattern enumerator itemizes memory access patterns for SDK functions. Use bit-ORed values to specify an input access pattern and an output access pattern.

Name/Description

MFX IOPATTERN IN Input to SDK functions is a video memory surface



| VIDEO_MEMORY | |
|-------------------------------------|--|
| MFX_IOPATTERN_IN_ SYSTEM_MEMORY | Input to SDK functions is a linear buffer directly in system memory or in system memory through an external allocator |
| MFX_IOPATTERN_IN_OPAQUE_MEMORY | Input to SDK functions maps at runtime to either a system memory buffer or a video memory surface. |
| MFX_IOPATTERN_OUT _VIDEO_MEMORY | Output to SDK functions is a video memory surface |
| MFX_IOPATTERN_OUT _SYSTEM_MEMORY | Output to SDK functions is a linear buffer directly in system memory or in system memory through an external allocator |
| MFX_IOPATTERN_OUT _OPAQUE_MEMORY | Output to SDK functions maps at runtime to either a system memory buffer or a video memory surface. |

Change History

This enumerator is available since SDK API 1.0. SDK API 1.3 extended the MFX_IOPATTERN_IN_OPAQUE_MEMORY and MFX_IOPATTERN_OUT_OPAQUE_MEMORY definitions.

mfxHandleType

Description

The ${\tt mfxHandleType}$ enumerator itemizes system handle types that SDK implementations might use.

Name/Description

| MFX_HANDLE_D3D9_DEVICE_MA NAGER | See Working with Microsoft* DirectX* Applications for more details on how to use this handle. |
|---------------------------------|--|
| MFX_HANDLE_D3D11_DEVICE | Pointer to the ID3D11Device interface. See Working with Microsoft* DirectX* Applications for more details on how to use this handle. |
| MFX_HANDLE_VA_DISPLAY | Pointer to VADisplay interface. See Working with VA API Applications for more details on how to use this handle. |
| MFX_HANDLE_ENCODE_CONTEXT | Pointer to VAContextID interface. It represents encoder context. |



API Version 1.17

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.4 added MFX HANDLE D3D11 DEVICE definition.

SDK API 1.8 added MFX_HANDLE_VA_DISPLAY and MFX_HANDLE_ENCODE_CONTEXT definitions.

mfxIMPL

Description

The mfxIMPL enumerator itemizes SDK implementation types. The implementation type is a bit OR'ed value of the base type and any decorative flags.

Name/Description

| MFX_IMPL_AUTO | Find the best SDK implementation automatically. It includes either hardware-accelerated implementation on the default acceleration device or software implementation. |
|----------------------|---|
| | This value is obsolete and it is recommended to use MFX_IMPL_AUTO_ANY instead. |
| MFX_IMPL_SOFTWARE | Use the software implementation |
| MFX_IMPL_HARDWARE | Use the hardware-accelerated implementation on the default acceleration device |
| MFX_IMPL_RUNTIME | This value cannot be used for session initialization. It may be returned by MFXQueryIMPL function to show that session has been initialized in run time mode. |
| MFX_IMPL_UNSUPPORTED | Failed to locate the desired SDK implementation |

If the acceleration device is not default device, use the following values to initialize the SDK libraries on an alternative acceleration device.

| MFX_IMPL_AUTO_ANY | Find the SDK implementation on any acceleration device including the default acceleration device and the SDK software library. |
|-----------------------|--|
| MFX_IMPL_HARDWARE_ANY | Find the hardware-accelerated implementation on any acceleration device including the default acceleration device. |

179 SDK API Reference Manual



| MFX_IMPL_HARDWARE2 | Use the hardware-accelerated implementation on the second acceleration device. |
|--------------------|--|
| MFX_IMPL_HARDWARE3 | Use the hardware-accelerated implementation on the third acceleration device. |
| MFX_IMPL_HARDWARE4 | Use the hardware-accelerated implementation on the fourth acceleration device. |

Use the following decorative flags to specify the OS infrastructure that hardware acceleration should base on.

| MFX_IMPL_VIA_D3D9 | Hardware acceleration goes through the Microsoft* Direct3D9* infrastructure. |
|--------------------|--|
| MFX_IMPL_VIA_D3D11 | Hardware acceleration goes through the Microsoft* Direct3D11* infrastructure. |
| MFX_IMPL_VIA_VAAPI | Hardware acceleration goes through the Linux* VA API infrastructure. |
| MFX_IMPL_VIA_ANY | Hardware acceleration can go through any supported OS infrastructure. This is default value, it is used by the SDK if none of MFX_IMPL_VIA_xxx flag is specified by application. |
| MFX_IMPL_AUDIO | Load audio library. It can be used only together with MFX_IMPL_SOFTWARE, any other combinations lead to error. |

Change History

This enumerator is available since SDK API 1.0.

SDK API 1.1 added support of multiple devices.

SDK API 1.3 added support of OS infrastructure definitions.

SDK API 1.6 changed defauls OS infrustructure from ${\tt MFX_IMPL_VIA_D3D9}$ to MFX_IMPL_VIA_ANY.

SDK API 1.8 added support of MFX IMPL AUDIO and MFX IMPL VIA VAAPI.

Remarks

The application can use the macro MFX IMPL BASETYPE(x) to obtain the base implementation type.

It is recommended that the application use MFX IMPL VIA ANY if the application uses system memory or opaque surface for I/O exclusively.



mfxPriority

Description

The mfxPriority enumerator describes the session priority.

Name/Description

MFX_PRIORITY_LOW Low priority: the session operation halts when high priority

tasks are executing and more than 75% of the CPU is

being used for normal priority tasks.

MFX_PRIORITY_NORMAL Normal priority: the session operation is halted if there are

high priority tasks.

MFX PRIORITY HIGH High priority: the session operation blocks other lower

priority session operations.

Change History

This enumerator is available since SDK API 1.1.

mfxSkipMode

Description

The mfxSkipMode enumerator describes the decoder skip-mode options.

Name/Description

MFX_SKIPMODE_NONE Do not skip any frames.

MFX_SKIPMODE_MORE Skip more frames.

MFX SKIPMODE LESS Skip less frames.

Change History

181

This enumerator is available since SDK API 1.0.

SDK API Reference Manual API Version 1.17



mfxStatus

Description

The mfxStatus enumerator itemizes status codes returned by SDK functions.

When an SDK function returns an error status code, it generally expects a **Reset** or **Close** function to follow, (with the exception of MFX ERR MORE DATA and MFX ERR MORE SURFACE for asynchronous operation considerations) See section Decoding Procedures, section Encoding Procedures, and section Video Processing Procedures for more information about recovery procedures.

When an SDK function returns a warning status code, the function has performed necessary operations to continue the operation without interruption. In this case, the output might be unreliable. The application must check the validity of the output generated by the function.

Name/Description

Successful operation

| MFX | ERR | NONE | No erro | r |
|-----|-----|------|----------|---|
| | | - | 110 0110 | |

Reserved status code

| MFX_ERR_UNKNOWN | An unknown error occurred in the library function |
|-----------------|---|
| | operation. This is a reserved status code. |

Programming related errors

| MFX_ERR_NOT_INITIALIZED | Member functions called without initialization. |
|----------------------------|---|
| MFX_ERR_INVALID_HANDLE | Invalid session or MemId handle |
| MFX_ERR_NULL_PTR | ${\tt NULL}$ pointer in the input or output arguments |
| MFX_ERR_UNDEFINED_BEHAVIOR | The behavior is undefined. |
| MFX_ERR_NOT_ENOUGH_BUFFER | Insufficient buffer for input or output. |
| MFX_ERR_NOT_FOUND | Specified object/item/sync point not found. |

Memory related errors

182

| MFX_ERR_MEMORY_ALLOC | Failed to allocate memory. |
|----------------------|---|
| MFX_ERR_LOCK_MEMORY | Failed to lock the memory block (external allocator). |

Configuration related errors or warnings



| THE PLAN ON SOLITORITHE UNSUDDOLLED COMMUNICATIONS, DOLD MICH. | MFX ERR UNSUPPORTED | Unsupported configurations, | parameters, or features |
|--|---------------------|-----------------------------|-------------------------|
|--|---------------------|-----------------------------|-------------------------|

MFX_ERR_INVALID_VIDEO_PARA Invalid video parameters detected. Init and Reset functions return this status code to indicate either

that mandated input parameters are unspecified, or

the functions failed to correct them.

MFX_ERR_INCOMPATIBLE_VIDEO Incompatible

_PARAM

Incompatible video parameters detected. If a **Reset** function returns this status code, a component—decoder, encoder or video preprocessor—cannot process the specified configuration with existing structures and frame buffers. If the function MFXVideoDECODE DecodeFrameAsync returns this status code, the bitstream contains an incompatible video parameter configuration that the decoder cannot follow.

Carriot follow.

MFX_WRN_VIDEO_PARAM_CHANGE

D

The decoder detected a new sequence header in the bitstream. Video parameters may have changed.

MFX WRN VALUE NOT CHANGED The

The parameter has been clipped to its value range.

MFX WRN OUT OF RANGE

The parameter is out of valid value range.

MFX_WRN_INCOMPATIBLE_VIDEO

_PARAM

Incompatible video parameters detected. SDK functions return this status code to indicate that there was incompatibility in the specified parameters

and has resolved it.

MFX_WRN_FILTER_SKIPPED The SDK VPP has skipped one or more optional filters

requested by the application. To retrieve actual list of filters attach mfxExtVPPDoUse to mfxVideoParam and call MFXVideoVPP GetVideoParam. The application must ensure that enough memory is allocated for

filter list.

Asynchronous operation related errors or warnings

MFX ERR ABORTED The asynchronous operation aborted.

MFX_ERR_MORE_DATA Need more bitstream at decoding input, encoding

input, or video processing input frames.

MFX_ERR_MORE_SURFACE Need more frame surfaces at decoding or video

processing output

MFX WRN IN EXECUTION Synchronous operation still running

183 SDK API Reference Manual API Version 1.17



Hardware device related errors or warnings

| MFX_ERR_DEVICE_FAILED | Hardware device returned unexpected errors. SDK was unable to restore operation. See section Error! eference source not found. and section <i>Hardware Device Error Handling</i> for more information. |
|-------------------------------|---|
| MFX_ERR_DEVICE_LOST | Hardware device was lost; See the <i>Hardware Device Error Handling</i> section for further information. |
| MFX_WRN_DEVICE_BUSY | Hardware device is currently busy. Call this function again in a few milliseconds. |
| MFX_WRN_PARTIAL_ACCELERATI ON | The hardware does not support the specified configuration. Encoding, decoding, or video processing may be partially accelerated. Only SDK HW implementation may return this status code. |

Change History

This enumerator is available since SDK API 1.0. SDK API 1.3 added the MFX_ERR_MORE_BITSTREAM return status. SDK API 1.6 added the MFX WRN FILTER SKIPPED return status.

PicStruct

Description

The ${\tt PicStruct}$ enumerator itemizes picture structure. Use bit-OR'ed values to specify the desired picture type.

Name/Description

| MFX_PICSTRUCT_UNKNOWN | Unspecified or mixed progressive/interlaced pictures |
|------------------------------|--|
| MFX_PICSTRUCT_PROGRESSIVE | Progressive picture |
| MFX_PICSTRUCT_FIELD_TFF | Top field in first interlaced picture |
| MFX_PICSTRUCT_FIELD_BFF | Bottom field in first interlaced picture |
| MFX_PICSTRUCT_FIELD_REPEATED | <pre>First field repeated: pict_struct = 5 or 6 in H.264</pre> |

184 SDK API Reference Manual API Version 1.17



MFX_PICSTRUCT_FRAME_DOUBLING Double the frame for display: pict_struct = 7 in H.264

MFX_PICSTRUCT_FRAME_TRIPLING Triple the frame for display: pict struct = 8 in H.264

Change History

This enumerator is available since SDK API 1.0. SDK API 1.3 added support of combined display attributes.

Remarks

It is possible to combine the above picture structure values to indicate additional display attributes. If <code>ExtendedPicStruct</code> in the <code>mfxInfoMFX</code> structure is true, **DECODE** outputs extended picture structure values to indicate how to display an output frame as shown in the following table:

| Extended PicStruct Values | Description |
|--|---|
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FRAME_DOUBLING | The output frame is progressive; Display as two identical progressive frames. |
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FRAME_TRIPLING | The output frame is progressive; Display as three identical progressive frames. |
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FIELD_TFF | The output frame is progressive; Display as two fields, top field first. |
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FIELD_BFF | The output frame is progressive; Display as two fields, bottom field first |
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FIELD_TFF MFX_PICSTRUCT_FIELD_REPEATED | The output frame is progressive; Display as three fields: top, bottom, and top. |
| MFX_PICSTRUCT_PROGRESSIVE MFX_PICSTRUCT_FIELD_BFF MFX_PICSTRUCT_FIELD_REPEATED | The output frame is progressive; Display as three fields: bottom, top, bottom. |

In the above cases, **VPP** processes the frame as a progressive frame and passes the extended picture structure values from input to output. **ENCODE** encodes the frame as a progressive frame and marks the bitstream header properly according to the extended picture structure values.



RateControlMethod

Description

186

The RateControlMethod enumerator itemizes bitrate control methods.

Name/Description

| MFX_RATECONTROL_CBR | Use the constant bitrate control algorithm |
|----------------------|--|
| MFX_RATECONTROL_VBR | Use the variable bitrate control algorithm |
| MFX_RATECONTROL_CQP | Use the constant quantization parameter algorithm. |
| MFX_RATECONTROL_AVBR | Use the average variable bitrate control algorithm |
| MFX_RATECONTROL_LA | Use the VBR algorithm with look ahead. It is a special bitrate control mode in the SDK AVC encoder that has been designed to improve encoding quality. It works by performing extensive analysis of several dozen frames before the actual encoding and as a side effect significantly increases encoding delay and memory consumption. |
| | The only available rate control parameter in this mode is <pre>mfxInfoMFX::TargetKbps</pre> . Two other parameters, MaxKbps and InitialDelayInKB, are ignored. To control LA depth the application can use <pre>mfxExtCodingOption2::LookAheadDepth</pre> parameter. |
| | This method is not HRD compliant. |
| MFX_RATECONTROL_ICQ | Use the Intelligent Constant Quality algorithm. This algorithm improves subjective video quality of encoded stream. Depending on content, it may or may not decrease objective video quality. Only one control parameter is used - quality factor, specified by <pre>mfxInfoMFX::ICQQuality.</pre> |
| MFX_RATECONTROL_VCM | Use the Video Conferencing Mode algorithm. This algorithm is similar to the VBR and uses the same set of parameters <pre>mfxInfoMFX::InitialDelayInKB</pre> , <pre>TargetKbps</pre> and <pre>MaxKbps</pre> . It is tuned for IPPP GOP pattern and streams with strong temporal correlation between frames. It produces better objective and subjective video quality in these conditions than other bitrate control algorithms. It does not support interlaced content, B frames and produced stream is not HRD compliant. |

SDK API Reference Manual API Version 1.17



MFX_RATECONTROL_LA_ICQ Use intelligent constant quality algorithm with look

ahead. Quality factor is specified by

mfxInfoMFX::ICQQuality. To control LA depth the

application can use

mfxExtCodingOption2::LookAheadDepth parameter.

This method is not HRD compliant.

intended for one to N transcode scenario and requires presence of ${\tt mfxExtLAFrameStatistics}$ structure at

encoder input at runtime.

MFX_RATECONTROL_QVBR Use the variable bitrate control algorithm with constant

quality. This algorithm trying to achieve the target subjective quality with the minimum number of bits, while the bitrate constraint and HRD compliancy are satisfied. It uses the same set of parameters as VBR

and quality factor specified by

 $\underline{\texttt{mfxExtCodingOption3}} : : \texttt{QVBRQuality}.$

Change History

This enumerator is available since SDK API 1.0.

The SDK API 1.1 added the constant quantization parameter algorithm.

The SDK API 1.3 added the average variable bitrate control algorithm.

The SDK API 1.7 added the look ahead algorithm.

The SDK API 1.8 added the intelligent constant quality and video conferencing mode algorithms.

The SDK API 1.10 added the extended look ahead rate control algorithm.

The SDK API 1.11 added the HRD compliant look ahead and variable bitrate with constant quality rate control algorithms.

TimeStampCalc

Description

The TimeStampCalc enumerator itemizes time-stamp calculation methods.

Name/Description



MFX TIMESTAMPCALC UNKNOWN The time stamp calculation is to base on the input frame rate, if time stamp is not explicitly specified.

MFX TIMESTAMPCALC TELECINE Adjust time stamp to 29.97fps on 24fps

> progressively encoded sequences if telecining attributes are available in the bitstream and time stamp is not explicitly specified. (The input frame

rate must be specified.)

Change History

This enumerator is available since SDK API 1.3.

TargetUsage

Description

The TargetUsage enumerator itemizes a range of numbers from MFX TARGETUSAGE 1, best quality, to MFX TARGETUSAGE 7, best speed. It indicates trade-offs between quality and speed. The application can use any number in the range. The actual number of supported target usages depends on implementation. If specified target usage is not supported, the SDK encoder will use the closest supported value.

Name/Description

| MFX_TARGETUSAGE_1 MFX_TARGETUSAGE_2 MFX_TARGETUSAGE_3 MFX_TARGETUSAGE_4 MFX_TARGETUSAGE_5 MFX_TARGETUSAGE_6 MFX_TARGETUSAGE_7 | Target usage |
|---|---|
| MFX_TARGETUSAGE_UNKNOWN | Unspecified target usage |
| MFX_TARGETUSAGE_BEST_QUALITY | Best quality, mapped to MFX_TARGETUSAGE_1 |
| MFX_TARGETUSAGE_BALANCED | Balanced quality and speed, mapped to MFX_TARGETUSAGE_4 |
| MFX_TARGETUSAGE_BEST_SPEED | Fastest speed, mapped to MFX_TARGETUSAGE_7 |

Change History

This enumerator is available since SDK API 1.0.

The SDK API 1.7 adds MFX_TARGETUSAGE_1 .. MFX_TARGETUSAGE_7 values.



TrellisControl

Description

The TrellisControl enumerator is used to control trellis quantization in AVC encoder. The application can turn it on or off for any combination of I, P and B frames by combining different enumerator values. For example, "MFX_TRELLIS_I \mid MFX TRELLIS B" turns it on for I and B frames.

Due to performance reason on some target usages trellis quantization is always turned off and this control is ignored by the SDK encoder.

Name/Description

| MFX_TRELLIS_UNKNOWN | Default value, it is up to the SDK encoder to turn trellis quantization on or off. |
|---------------------|--|
| MFX_TRELLIS_OFF | Turn trellis quantization off for all frame types. |
| MFX_TRELLIS_I | Turn trellis quantization on for I frames. |
| MFX_TRELLIS_P | Turn trellis quantization on for P frames. |
| MFX TRELLIS B | Turn trellis quantization on for B frames. |

Change History

This enumerator is available since SDK API 1.7.

BRefControl

Description

The BRefControl enumerator is used to control usage of B frames as reference in AVC encoder.

Name/Description

| MFX_B_REF_UNKNOWN | Default value, it is up to the SDK encoder to use B frames as reference. |
|-------------------|--|
| MFX_B_REF_OFF | Do not use B frames as reference. |
| MFX_B_REF_PYRAMID | Arrange B frames in so-called "B pyramid" reference structure. |



'n

Change History

This enumerator is available since SDK API 1.8.

LookAheadDownSampling

Description

The LookAheadDownSampling enumerator is used to control down sampling in look ahead bitrate control mode in AVC encoder.

Name/Description

| MFX_LOOKAHEAD_DS_UNKNOWN | Default value, it is up to the SDK encoder what down sampling value to use. |
|--------------------------|---|
| MFX_LOOKAHEAD_DS_OFF | Do not use down sampling, perform estimation on original size frames. This is the slowest setting that produces the best quality. |
| MFX_LOOKAHEAD_DS_2x | Down sample frames two times before estimation. |
| MFX_LOOKAHEAD_DS_4x | Down sample frames four times before estimation. This option may significantly degrade quality. |

Change History

This enumerator is available since SDK API 1.8.

VPPFieldProcessingMode

Description

The VPPFieldProcessingMode enumerator is used to control VPP field processing algorithm.

Name/Description

| MFX_VPP_COPY_FRAME | Copy the whole frame. | | |
|---------------------|-----------------------------|--|--|
| MFX_VPP_COPY_FIELD | Copy only one field. | | |
| MFX_VPP_SWAP_FIELDS | Swap top and bottom fields. | | |

Change History

This enumerator is available since SDK API 1.11.



PicType

Description

The PicType enumerator itemizes picture type.

Name/Description

MFX_PICTYPE_UNKNOWN Picture type is unknown.

MFX_PICTYPE_FRAME Picture is a frame.

MFX_PICTYPE_TOPFIELD Picture is a top field.

MFX_PICTYPE_BOTTOMFIELD Picture is a bottom field.

Change History

This enumerator is available since SDK API 1.11.

SkipFrame

Description

The SkipFrame enumerator is used to define usage of mfxEncodeCtrl::SkipFrame
parameter.

Name/Description

MFX SKIPFRAME NO SKIP Frame skipping is disabled, mfxEncodeCtrl::SkipFrame is ignored MFX SKIPFRAME INSERT DUMMY Skipping is allowed, when mfxEncodeCtrl::SkipFrame is set encoder inserts into bitstream frame where all macroblocks are encoded as skipped. Only nonreference P and B frames can be skipped. If GopRefDist = 1 and mfxEncodeCtrl::SkipFrame is set for reference P frame, it will be encoded as non-reference. MFX SKIPFRAME INSERT NOTHING Similar to MFX SKIPFRAME INSERT DUMMY, but when mfxEncodeCtrl::SkipFrame is set encoder inserts nothing into bitstream. MFX SKIPFRAME BRC ONLY mfxEncodeCtrl::SkipFrame indicates number of missed frames before the current frame. Affects only BRC, current frame will be encoded as



usual.

Change History

This enumerator is available since SDK API 1.11.

The SDK API 1.13 adds MFX SKIPFRAME BRC ONLY.

DeinterlacingMode

Description

The Deinterlacing Mode enumerator itemizes VPP deinterlacing modes.

Name/Description

| MFX_DEINTERLACING_BOB | BOB deinterlacing mode. |
|---|--|
| MFX_DEINTERLACING_ADVANCED | Advanced deinterlacing mode. |
| MFX_DEINTERLACING_AUTO_DOUBLE | Auto mode with deinterlacing double framerate output. |
| MFX_DEINTERLACING_AUTO_SINGLE | Auto mode with deinterlacing single framerate output. |
| MFX_DEINTERLACING_FULL_FR_OUT | Deinterlace only mode with full framerate output. |
| MFX_DEINTERLACING_HALF_FR_OUT | Deinterlace only Mode with half framerate output. |
| MFX_DEINTERLACING_24FPS_OUT | 24 fps fixed output mode. |
| MFX_DEINTERLACING_FIXED_TELEC INE_PATTERN | Fixed telecine pattern removal mode. |
| MFX_DEINTERLACING_30FPS_OUT | 30 fps fixed output mode. |
| MFX_DEINTERLACING_DETECT_INTE RLACE | Only interlace detection. |
| MFX_DEINTERLACING_ADVANCED_NO REF | Advanced deinterlacing mode without using of reference frames. |

Change History

This enumerator is available since SDK API 1.13.



The SDK 1.17 adds MFX DEINTERLACING ADVANCED NOREF.

TelecinePattern

Description

The TelecinePattern enumerator itemizes telecine patterns.

Name/Description

```
MFX_TELECINE_PATTERN_32 3:2 telecine

MFX_TELECINE_PATTERN_2332 2:3:3:2 telecine

MFX_TELECINE_PATTERN_FRAME_R EPEAT

MFX_TELECINE_PATTERN_41 4:1 telecine

MFX_TELECINE_PATTERN_41 User must provide position inside a sequence of 5 frames where the artifacts start.
```

Change History

This enumerator is available since SDK API 1.13.

HEVCRegionType

Description

The HEVCRegionType enumerator itemizes type of HEVC region.

Name/Description

MFX HEVC REGION SLICE Slice.

Change History

This enumerator is available since SDK API 1.15.

GPUCopy

Description

The $\mathtt{GPUCopy}$ enumerator controls usage of GPU accelerated copying between video and system memory in the SDK components.



Name/Description

implementation.

MFX_GPUCOPY_ON Enable GPU accelerated copying.

MFX_GPUCOPY_OFF Disable GPU accelerated copying.

Change History

This enumerator is available since SDK API 1.16.

WeightedPred

Description

The WeightedPred enumerator itemizes weighted prediction modes.

Name/Description

MFX_WEIGHTED_PRED_UNKNOWN Allow encoder to decide.

MFX_WEIGHTED_PRED_DEFAULT Use default weighted prediction.

MFX_WEIGHTED_PRED_EXPLICIT Use explicit weighted prediction.

MFX_WEIGHTED_PRED_IMPLICIT Use implicit weighted prediction (for B-frames

only).

Change History

This enumerator is available since SDK API 1.16.

ScenarioInfo

Description

The ScenarioInfo enumerator itemizes scenarios for the encoding session.

Name/Description

MFX_SCENARIO_UNKNOWN
MFX_SCENARIO_DISPLAY_REMOTING
MFX_SCENARIO_VIDEO_CONFERENCE
MFX_SCENARIO_ARCHIVE



```
MFX_SCENARIO_LIVE_STREAMING
MFX SCENARIO CAMERA CAPTURE
```

Change History

This enumerator is available since SDK API 1.16.

ContentInfo

Description

The ContentInfo enumerator itemizes content types for the encoding session.

Name/Description

```
MFX_CONTENT_UNKNOWN
MFX_CONTENT_FULL_SCREEN_VIDEO
MFX_CONTENT_NON_VIDEO_SCREEN
```

Change History

This enumerator is available since SDK API 1.16.

PRefType

Description

The PRefType enumerator itemizes models of reference list construction and DPB management when GopRefDist=1.

Name/Description

| MFX_P_REF_DEFAULT | Allow encoder to decide. |
|-------------------|--|
| MFX_P_REF_SIMPLE | Regular sliding window used for DPB removal process. |
| MFX_P_REF_PYRAMID | Let N be the max reference list's size. Encoder treat each N's frame as "strong" reference and the others as "weak" references. Encoder uses "weak" reference only for prediction of the next frame and removes it from DPB right after. "Strong" references removed from DPB by sliding window. |

Change History



This enumerator is available since SDK API 1.16.

GeneralConstraintFlags

Description

The GeneralConstraintFlags enumerator uses bit-ORed values to itemize HEVC bitstream indications for specific profiles.

Name/Description

```
MFX_HEVC_CONSTR_REXT_MAX_12BIT

MFX_HEVC_CONSTR_REXT_MAX_10BIT

MFX_HEVC_CONSTR_REXT_MAX_8BIT

MFX_HEVC_CONSTR_REXT_MAX_422CHROMA

MFX_HEVC_CONSTR_REXT_MAX_420CHROMA

MFX_HEVC_CONSTR_REXT_MAX_MONOCHROME

MFX_HEVC_CONSTR_REXT_INTRA

MFX_HEVC_CONSTR_REXT_ONE_PICTURE_ONLY

MFX_HEVC_CONSTR_REXT_LOWER_BIT_RATE
```

Indications for format range extensions profiles.

Change History

This enumerator is available since SDK API 1.16.

Angle

Description

The Angle enumerator itemizes valid rotation angles.

Name/Description

| MFX_ANGLE_0 | 0° |
|---------------|------|
| MFX_ANGLE_90 | 90° |
| MFX_ANGLE_180 | 180° |
| MFX_ANGLE_270 | 270° |

Change History



This enumerator is available since SDK API 1.17.



Appendices

Appendix A: Configuration Parameter Constraints

The <u>mfxFrameInfo</u> structure is used by both the <u>mfxVideoParam</u> structure during SDK class initialization and the <u>mfxFrameSurface1</u> structure during the actual SDK class function. The following constraints apply:

Constraints common for **DECODE**, **ENCODE** and **VPP**:

| Parameters | During SDK initialization | During SDK operation |
|--------------|--|---|
| FourCC | Any valid value The value must be the initialization va | |
| | | The only exception is VPP in composition mode, where in some cases it is allowed to mix RGB and NV12 surfaces. See mfxExtVPPComposite for more details. |
| ChromaFormat | Any valid value | The value must be the same as the initialization value. |

Constraints for **DECODE**:

| Parameters | During SDK initialization | During SDK operation | | |
|------------------------------|--|---|--|--|
| Width Height | Aligned frame size | The values must be the equal to or larger than the initialization values. | | |
| CropX, CropY CropW, CropH | Ignored | DECODE output. The cropping values are per-frame based. | | |
| AspectRatioW AspectRatioH | Any valid values or unspecified (zero); if unspecified, values from the input bitstream will be used; see note below the table | DECODE output. | | |
| FrameRateExtN FrameRateExtD | Any valid values or unspecified (zero); | DECODE output. | | |



| | if unspecified, values from the input bitstream will be used; see note below the table | |
|-----------|--|-----------------------|
| PicStruct | Ignored | DECODE output. |

Note about priority of initialization parameters.

If application explicitly sets FrameRateExtN/FrameRateExtD or AspectRatioW/ AspectRatioH during initialization then decoder uses these values during decoding regardless of values from bitstream and does not update them on new SPS. If application sets them to 0, then decoder uses values from stream and update them on each SPS.

Constraints for **VPP**:

| Parameters | During SDK initialization | During SDK operation | | |
|------------------------------|---|--|--|--|
| Width Height | Any valid values | These values must be the same or larger than the initialization values. | | |
| CropX, CropY CropW, CropH | Ignored | These parameters specify the region of interest from input to output. | | |
| AspectRatioW AspectRatioH | Ignored | Aspect ratio values will be passed through from input to output. | | |
| FrameRateExtN FrameRateExtD | Any valid values | Frame rate values will be updated with the initialization value at output. | | |
| PicStruct | MFX_PICSTRUCT_UNKNOWN, MFX_PICSTRUCT_PROGRESSIVE, MFX_PICSTRUCT_FIELD_TFF, or | The base value must be the same as the initialization value unless MFX_PICSTRUCT_UNKNOWN is specified during initialization. | | |
| | MFX_PICSTRUCT_FIELD_BFF. | Other decorative picture structure flags are passed through or added as needed. See the PicStruct enumerator for details. | | |



Constraints for **ENCODE**:

| Parameters | During SDK initialization | During SDK operation | | |
|--------------------------------|---|---|--|--|
| Width Height | Encoded frame size | The values must be the same or larger than the initialization values | | |
| CropX, CropY CropW, CropH | H.264: Cropped frame size MPEG-2: CropW and CropH specify the real width and height (maybe unaligned) of the coded frames. CropX and CropY must be zero. | Ignored | | |
| AspectRatioW AspectRatioH | Any valid values | Ignored | | |
| FrameRateExtN FrameRateExtD | Any valid values | Ignored | | |
| PicStruct | MFX_PICSTRUCT_UNKNOWN, MFX_PICSTRUCT_PROGRESSIVE, MFX_PICSTRUCT_FIELD_TFF, or MFX_PICSTRUCT_FIELD_BFF. | The base value must be the same as the initialization value unless MFX_PICSTRUCT_UNKNOWN is specified during initialization. Add other decorative picture structure flags to indicate additional display attributes. Use MFX_PICSTRUCT_UNKNOWN during initialization for field attributes and MFX_PICSTRUCT_PROGRESSIVE for frame attributes. See the PicStruct enumerator for details. | | |

The following table summarizes how to specify the configuration parameters during initialization and during encoding, decoding and video processing:

| | | ENCODE Init Encoding | | DECODE | | VPP | |
|------|-----------|----------------------|---|--------|----------|------|------------|
| | | | | Init | Decoding | Init | Processing |
| mfxV | ideoParam | | | | | | |
| | Protected | R | - | R | - | R | - |
| | IOPattern | М | - | М | - | М | - |
| | ExtParam | 0 | - | 0 | - | 0 | - |



| | ENCODE | | DECODE | | VPP | |
|-------------------|--------|----------|--------|----------|------|------------|
| | Init | Encoding | Init | Decoding | Init | Processing |
| NumExtParam | 0 | - | 0 | - | 0 | - |
| mfxInfoMFX | 1 | | 1 | | 1 | |
| CodecId | М | - | М | - | - | - |
| CodecProfile | 0 | - | 0 | - | - | - |
| CodecLevel | 0 | - | 0 | - | - | - |
| NumThread | 0 | - | 0 | - | - | - |
| TargetUsage | 0 | - | - | - | - | - |
| GopPicSize | 0 | - | - | - | - | - |
| GopRefDist | 0 | - | _ | - | _ | - |
| GopOptFlag | 0 | - | - | - | - | - |
| IdrInterval | 0 | - | _ | - | _ | - |
| RateControlMethod | 0 | - | - | - | - | - |
| InitialDelayInKB | 0 | - | - | - | - | - |
| BufferSizeInKB | 0 | - | - | - | - | - |
| TargetKbps | М | - | - | - | - | - |
| MaxKbps | 0 | - | - | - | - | - |
| NumSlice | 0 | - | - | - | - | - |
| NumRefFrame | 0 | - | _ | - | _ | - |
| EncodedOrder | М | - | _ | - | _ | - |
| mfxFrameInfo | | | | | | |
| FourCC | М | М | М | М | М | М |
| Width | М | М | М | М | М | М |
| Height | М | М | М | М | М | М |
| CropX | М | Ign | Ign | /U | Ign | М |
| CropY | М | Ign | Ign | /U | Ign | М |
| CropW | М | Ign | Ign | /U | Ign | М |
| СторН | М | Ign | Ign | /U | Ign | М |
| FrameRateExtN | М | Ign | 0 | /U | М | /U |
| FrameRateExtD | М | Ign | 0 | /U | М | /U |
| AspectRatioW | 0 | Ign | 0 | /U | Ign | PT |
| AspectRatioH | 0 | Ign | 0 | /U | Ign | PT |



| | | | ENCODE | | DECODE | | VPP | |
|---------|--------------|----------|----------------------|----------|--------|------------------|------|------------|
| | | | Init | Encoding | Init | Decoding | Init | Processing |
| | PicStruct | | 0 | М | Ign | /U | М | M/U |
| | ChromaFormat | | М | М | М | М | Ign | Ign |
| Remarks | | | | | | | | |
| | Ign | Ignored | PT Pass Throug | | jh | - Does Not Apply | | |
| | М | Mandated | R Reserved | | | | | |
| | 0 | Optional | /U Updated at output | | | | | |
| | | | | | | | | |



Appendix B: Multiple-Segment Encoding

Multiple-segment encoding is useful in video editing applications when during production; the encoder encodes multiple video clips according to their time line. In general, one can define multiple-segment encoding as dividing an input sequence of frames into segments and encoding them in different encoding sessions with the same or different parameter sets, as illustrated in Figure 6. (Note that different encoders can also be used.)

The application must be able to:

- 1. Extract encoding parameters from the bitstream of previously encoded segment;
- 2. Import these encoding parameters to configure the encoder.

Encoding can then continue on the current segment using either the same or the similar encoding parameters.




Figure 6: Multiple-Segment Encoding

Extracting the header containing the encoding parameter set from the encoded bitstream is usually the task of a format splitter (de-multiplexer). Nevertheless, the SDK MFXVideoDECODE DecodeHeader function can export the raw header if the application attaches the mfxExtCodingOptionSPSPPS structure as part of the parameters.

The encoder can use the mfxExtCodingOptionSPSPPS structure to import the encoding parameters during MFXVideoENCODE Init. The encoding parameters are in the encoded bitstream format. Upon a successful import of the header parameters, the encoder will generate bitstreams with a compatible (not necessarily bit-exact) header. Table 9 shows all functions that can import a header and their error codes if there are unsupported parameters in the header or the encoder is unable to achieve compatibility with the imported header.

| Table | 9. | Multiple-Seament Encoding Functions | |
|-------|----|---|--|
| Iable | Э. | Multiple-Seattletti Effcoalita i afficiolis | |

| Function Name | Error Code if Import Fails |
|----------------------------|----------------------------------|
| MFXVideoENCODE Init | MFX ERR INCOMPATIBLE VIDEO PARAM |
| MFXVideoENCODE QueryIOSurf | MFX ERR INCOMPATIBLE VIDEO PARAM |
| MFXVideoENCODE_Reset | MFX_ERR_INCOMPATIBLE_VIDEO_PARAM |
| MFXVideoENCODE Query | MFX ERR UNSUPPORTED |

The encoder must encode frames to a GOP sequence starting with an IDR frame for H.264 (or I frame for MPEG-2) to ensure that the current segment encoding does not refer to any frames in the previous segment. This ensures that the encoded segment is self-contained, allowing the application to insert it anywhere in the final bitstream. After encoding, each encoded segment is HRD compliant. However, the concatenated segments may not be HRD compliant.



Example 14 shows an example of the encoder initialization procedure that imports H.264 sequence and picture parameter sets.

```
mfxStatus init encoder(...) {
      mfxExtCodingOptionSPSPPS option, *option array;
      /* configure mfxExtCodingOptionSPSPPS */
      memset(&option, 0, sizeof(option));
      option.Header.BufferId=MFX EXTBUFF CODING OPTION SPSPPS;
      option.Header.BufferSz=sizeof(option);
      option.SPSBuffer=sps buffer;
      option.SPSBufSize=sps buffer length;
      option.PPSBuffer=pps buffer;
      option.PPSBufSize=pps buffer length;
      /* configure mfxVideoParam */
      mfxVideoParam param;
      param.NumExtParam=1;
      option array=&option;
      param.ExtParam=&option array;
      /* encoder initialization */
      mfxStatus status;
      status=MFXVideoENCODE Init(session, &param);
      if (status==MFX ERR INCOMPATIBLE VIDEO PARAM) {
            printf("Initialization failed\n");
      } else {
            printf("Initialized\n");
      return status;
```

Example 14: Pseudo-code to Import H.264 SPS/PPS Parameters



Appendix C: Streaming and Video Conferencing Features

The following sections address a few aspects of additional requirements that streaming or video conferencing applications may use in the encoding or transcoding process. See also Configuration Change chapter.

Dynamic Bitrate Change

The SDK encoder supports dynamic bitrate change differently depending on bitrate control mode and HRD conformance requirement. If HRD conformance is required, i.e. if application sets NalHrdConformance Option in mfxExtCodingOption structure to ON, the only allowed bitrate control mode is VBR. In this mode, the application can change TargetKbps and MaxKbps values. The application can change these values by calling the MFXVideoENCODE Reset function. Such change in bitrate usually results in generation of a new key-frame and sequence header. There are some exceptions though. For example, if HRD Information is absent in the stream then change of TargetKbps does not require change of sequence header and as a result the SDK encoder does not insert a key frame.

If HRD conformance is not required, i.e. if application turns off NalHrdConformance option in mfxExtCodingOption structure, all bitrate control modes are available. In CBR and AVBR modes the application can change TargetKbps, in VBR mode the application can change TargetKbps and MaxKbps values. Such change in bitrate will not result in generation of a new key-frame or sequence header.

The SDK encoder may change some of the initialization parameters provided by the application during initialization. That in turn may lead to incompatibility between the parameters provided by the application during reset and working set of parameters used by the SDK encoder. That is why it is strongly recommended to retrieve the actual working parameters by MFXVideoENCODE GetVideoParam function before making any changes to bitrate settings.

In all modes, the SDK encoders will respond to the bitrate changes as quickly as the underlying algorithm allows, without breaking other encoding restrictions, such as HRD compliance if it is enabled. How soon the actual bitrate can catch up with the specified bitrate is implementation dependent.

Alternatively, the application may use the CQP (constant quantization parameter) encoding mode to perform customized bitrate adjustment on a per-frame base. The application may use any of the encoded or display order modes to use per-frame CQP.

SDK API Reference Manual

¹ HRD information is absent in the stream if both VuiVclHrdParameters and VuiNalHrdParameters options in mfxExtCodingOption structure are OFF.



Dynamic resolution change

The SDK encoder supports dynamic resolution change in all bitrate control modes. The application may change resolution by calling MFXVideoENCODE Reset function. The application may decrease or increase resolution up to the size specified during encoder initialization.

Resolution change always results in insertion of key IDR frame and new sequence parameter set header. The SDK encoder does not guarantee HRD conformance across resolution change point.

The SDK encoder may change some of the initialization parameters provided by the application during initialization. That in turn may lead to incompatibility of parameters provide by the application during reset and working set of parameters used by the SDK encoder. That is why it is strongly recommended to retrieve the actual working parameters set by MFXVideoENCODE GetVideoParam function before making any resolution change.

Forced Key Frame Generation

The SDK supports forced key frame generation during encoding. The application can set the FrameType parameter of the mfxEncodeCtrl structure to control how the current frame is encoded, as follows:

- If the SDK encoder works in the display order, the application can enforce any current frame to be a key frame. The application cannot change the frame type of already buffered frames inside the SDK encoder.
- If the SDK encoder works in the encoded order, the application must exactly specify frame type for every frame thus the application can enforce the current frame to have any frame type that particular coding standard allows.

Reference List Selection

During streaming or video conferencing, if the application can obtain feedbacks about how good the client receives certain frames, the application may need to adjust the encoding process to use or not use certain frames as reference. The following paragraphs describe how to fine-tune the encoding process based on such feedbacks.

The application can specify the reference window size by specifying the parameter mfxInfoMFX::NumRefFrame during encoding initialization. Certain platform may have limitation on how big the size of the reference window is. Use the function MFXVideoENCODE GetVideoParam to retrieve the current working set of parameters.

During encoding, the application can specify the actual reference list lengths by attaching the mfxExtAVCRefListCtrl Structure to the MFXVideoENCODE EncodeFrameAsync function. The



NumRefIdxLOActive parameter of the mfxExtAVCRefListCtrl structure specifies the length of the reference list LO and the NumRefIdxL1Active parameter specifies the length of the reference list L1. These two numbers must be less or equal to the parameter mfxInfoMFX:: NumRefFrame during encoding initialization.

The application can instruct the SDK encoder to use or not use certain reference frames. To do this, there is a prerequisite that the application must uniquely identify each input frame, by setting the mfxFrameData::FrameOrder parameter. The application then specifies the preferred reference frame list PreferredRefList and/or the rejected frame list RejectedRefList in the mfxExtAVCRefListCtrl structure, and attach the structure to the MFXVideoENCODE EncodeFrameAsync function. The two lists fine-tune how the SDK encoder chooses the reference frames of the current frame. The SDK encoder does not keep PreferredRefList and application has to send it for each frame if necessary. There are a few limitations:

- The frames in the lists are ignored if they are out of the reference window.
- If by going through the lists, the SDK encoder cannot find a reference frame for the current frame, the SDK encoder will encode the current frame without using any reference frames.
- If the GOP pattern contains B-frames, the SDK encoder may not be able to follow the mfxExtAVCRefListCtrl instructions.

Low Latency Encoding and Decoding

The application can set mfxVideoParam:: AsyncDepth=1 to disable any decoder buffering of output frames, which is aimed to improve the transcoding throughput. With AsyncDepth=1, the application must synchronize after the decoding or transcoding operation of each frame.

The application can adjust <u>mfxExtCodingOption</u>::MaxDecFrameBuffering, during encoding initialization, to improve decoding latency. It is recommended to set this value equal to number of reference frames.

Reference Picture Marking Repetition SEI message

The application can request writing the reference picture marking repetition SEI message during encoding initialization, by setting the RefPicMarkRep flag in the mfxExtCodingOption structure. The reference picture marking repetition SEI message repeats certain reference frame information in the output bitstream for robust streaming.

The SDK decoder will respond to the reference picture marking repetition SEI message if such message exists in the bitstream, and check with the reference list information specified in the sequence/picture headers. The decoder will report any mismatch of the SEI message with the reference list information in the mfxFrameData::Corrupted field.



Long-term Reference frame

The application may use long-term reference frames to improve coding efficiency or robustness for video conferencing applications. The application controls the long-term frame marking process by attaching the mfxExtAVCRefListCtrl extended buffer during encoding. The SDK encoder itself never marks frame as long-term.

There are two control lists in the mfxExtAVCRefListCtrl extended buffer. The
LongTermRefList list contains the frame orders (the FrameOrder value in the mfxFrameData structure) of the frames that should be marked as long-term frames. The RejectedRefList list contains the frame order of the frames that should be unmarked as long-term frames. The application can only mark/unmark those frames that are buffered inside encoder. Because of this, it is recommended that the application marks a frame when it is submitted for encoding. Application can either explicitly unmark long-term reference frame or wait for IDR frame, there all long-term reference frames will be unmarked.

The SDK encoder puts all long-term reference frames at the end of a reference frame list. If the number of active reference frames (the NumRefIdxLOActive and NumRefIdxLlActive values in the mfxExtAVCRefListCtrl extended buffer) is smaller than the total reference frame number (the NumRefFrame value in the mfxInfoMFX structure during the encoding initialization), the SDK encoder may ignore some or all long term reference frames. The application may avoid this by providing list of preferred reference frames in the PreferredRefList list in the mfxExtAVCRefListCtrl extended buffer. In this case, the SDK encoder reorders the reference list based on the specified list.

Temporal scalability

The application may specify the temporal hierarchy of frames by using the mfxExtAvcTemporalLayers extended buffer during the encoder initialization, in the displayorder encoding mode. The SDK inserts the prefix NAL unit before each slice with a unique
temporal and priority ID. The temporal ID starts from zero and the priority ID starts from the
BaseLayerPID value. The SDK increases the temporal ID and priority ID value by one for each
consecutive layer.

If the application needs to specify a unique sequence or picture parameter set ID, the application must use the mfxExtCodingOptionSPSPPS extended buffer, with all pointers and sizes set to zero and valid spsid/PPSId fields. The same SPS and PPS ID will be used for all temporal layers.

Each temporal layer is a set of frames with the same temporal ID. Each layer is defined by the Scale value. Scale for layer N is equal to ratio between the frame rate of subsequence consisted of temporal layers with temporal ID lower or equal to N and frame rate of base



temporal layer. The application may skip some of the temporal layers by specifying the scale value as zero. The application should use an integer ratio of the frame rates for two consecutive temporal layers.

For example, 30 frame per second video sequence typically is separated by three temporal layers, that can be decoded as 7.5 fps (base layer), 15 fps (base and first temporal layer) and 30 fps (all three layers). Scale for this case should have next values {1,2,4,0,0,0,0,0}.

Appendix D: Switchable Graphics and Multiple Monitors

The following sections address a few aspects of supporting switchable graphics and multiple monitors configurations.

Switchable Graphics

Switchable Graphics refers to the machine configuration that multiple graphic devices are available (integrated device for power saving and discrete devices for performance.) Usually at one time or instance, one of the graphic devices drives display and becomes the active device, and others become inactive. There are different variations of software or hardware mechanisms to switch between the graphic devices. In one of the switchable graphics variations, it is possible to register an application in an affinity list to certain graphic device so that the launch of the application automatically triggers a switch. The actual techniques to enable such a switch are outside the scope of this document. This document discusses the implication of switchable graphics to the SDK and the SDK applications.

As the SDK performs hardware acceleration through Intel graphic device, it is critical that the SDK can access to the Intel graphic device in the switchable graphics setting. If possible, it is recommended to add the application to the Intel graphic device affinity list. Otherwise, the application must handle the following cases:

1> By the SDK design, during the SDK library initialization, the function MFXInit searches
for Intel graphic devices. If a SDK implementation is successfully loaded, the function
MFXInit returns MFX ERR NONE and the MFXQueryIMPL function returns the actual
implementation type. If no SDK implementation is loaded, the function MFXInit returns
MFX ERR UNSUPPORTED.

In the switchable graphics environment, if the application is not in the Intel graphic device affinity list, it is possible that the Intel graphic device is not accessible during the SDK library initialization. The fact that the MFXINIT function returns

MFX ERR UNSUPPORTED does not mean that hardware acceleration is not possible permanently. The user may switch the graphics later and by then the Intel graphic device will become accessible. It is recommended that the application initialize the SDK

209 SDK API Reference Manual API Version 1.17



- library right before the actual decoding, video processing, and encoding operations to determine the hardware acceleration capability.
- 2> During decoding, video processing, and encoding operations, if the application is not in the Intel graphic device affinity list, the previously accessible Intel graphic device may become inaccessible due to a switch event. The SDK functions will return MFX ERR DEVICE LOST OF MFX ERR DEVICE FAILED, depending on when the switch occurs and what stage the SDK functions operate. The application needs to handle these errors and exits gracefully.

Multiple Monitors

Multiple monitors refer to the machine configuration that multiple graphic devices are available. Some of the graphic devices connect to a display, they become active and accessible under the Microsoft* DirectX* infrastructure. For those graphic devices not connected to a display, they are inactive. Specifically, under the Microsoft Direct3D9* infrastructure, those devices are not accessible.

The SDK uses the adapter number to access to a specific graphic device. Usually, the graphic device that drives the main desktop becomes the primary adapter. Other graphic devices take subsequent adapter numbers after the primary adapter. Under the Microsoft Direct3D9 infrastructure, only active adapters are accessible and thus have an adapter number.

The SDK extends the implementation type mfxIMPL as follows

| Implementation Type | Definition |
|---------------------|--|
| MFX_IMPL_HARDWARE | The SDK should initialize on the primary adapter |
| MFX_IMPL_HARDWARE2 | The SDK should initialize on the 2 nd graphic adapter |
| MFX_IMPL_HARDWARE3 | The SDK should initialize on the 3 rd graphic adapter |
| MFX_IMPL_HARDWARE4 | The SDK should initialize on the 4 th graphic adapter |

The application can use the above definitions to instruct the SDK library to initializes on a specific graphic device. The application can also use the following definitions for automatic detection:



| Implementation Type | Definition |
|-----------------------|--|
| MFX_IMPL_HARDWARE_ANY | The SDK should initialize on any graphic adapter |
| MFX_IMPL_AUTO_ANY | The SDK should initialize on any graphic adapter. If not successful, load the software implementation. |

If the application uses the Microsoft* DirectX* surfaces for I/O, it is critical that the application and the SDK works on the same graphic device. It is recommended that the application use the following procedure:

- 1> The application uses the MFXInit function to initialize the SDK library, with option MFX IMPL HARDWARE ANY OR MFX IMPL AUTO ANY. The MFXInit function returns MFX ERR NONE if successful.
- 2> The application uses the MFXQueryIMPL function to check the actual implementation type. The implementation type MFX IMPL HARDWARE...MFX IMPL HARDWARE4 indicates the graphic adapter the SDK works on.
- 3> The application creates the Direct3D* device on the respective graphic adapter, and passes it to the SDK through the MFXVideoCORE SetHandle function.

Finally, similar to the switchable graphics cases, it is possible that the user disconnects monitors from the graphic devices or remaps the primary adapter thus causes interruption. If the interruption occurs during the SDK library initialization, the MFXInit function may return MFX ERR UNSUPPORTED. This means hardware acceleration is currently not available. It is recommended that the application initialize the SDK library right before the actual decoding, video processing, and encoding operations to determine the hardware acceleration capability.

If the interruption occurs during decoding, video processing, or encoding operations, the SDK functions will return MFX ERR DEVICE LOST or MFX ERR DEVICE FAILED. The application needs to handle these errors and exit gracefully.

Appendix E: Working directly with VA API for Linux*

The SDK takes care of all memory and synchronization related operations in VA API. However, in some cases the application may need to extend the SDK functionality by working directly with VA API for Linux*. For example, to implement customized external allocator or USER functions (also known as "plug-in"). This chapter describes some basic memory management and synchronization techniques.



To create VA surface pool the application should call vaCreateSurfaces as it is shown in Example 15.

Example 15: Creation of VA surfaces

To destroy surface pool the application should call vaDestroySurfaces as it is shown in Example 16.

```
vaDestroySurfaces(va_display, surfaces, NUM_SURFACES);
```

Example 16: Destroying of VA surfaces

If the application works with hardware acceleration through the SDK then it can access surface data immediately after successful completion of MFXVideoCORE_SyncOperation call. If the application works with hardware acceleration directly then it has to check surface status before accessing data in video memory. This check can be done asynchronously by calling vaQuerySurfaceStatus function or synchronously by vaSyncSurface function.

After successful synchronization the application can access surface data. It is performed in two steps. At the first step VAImage is created from surface and at the second step image buffer is mapped to system memory. After mapping VAImage.offsets[3] array holds offsets to each color plain in mapped buffer and VAImage.pitches[3] array holds color plain pitches, in bytes. For packed data formats, only first entries in these arrays are valid. Example 17 shows how to access data in NV12 surface.

```
VAImage image;
unsigned char *buffer, Y, U, V;

vaDeriveImage(va_display, surface_id, &image);
vaMapBuffer(va_display, image.buf, &buffer);

/* NV12 */
Y = buffer + image.offsets[0];
U = buffer + image.offsets[1];
V = U + 1;
```

Example 17: Accessing data in VA surface



After processing data in VA surface the application should release resources allocated for mapped buffer and VAImage object. Example 18 shows how to do it.

```
vaUnmapBuffer(va display, image.buf);
vaDestroyImage(va display, image.image id);
```

Example 18: unmapping buffer and destroying VAImage

In some cases, for example, to retrieve encoded bitstream from video memory, the application has to use VABuffer to store data. Example 19 shows how to create, use and then destroy VA buffer. Note, that vaMapBuffer function returns pointers to different objects depending on mapped buffer type. It is plain data buffer for VAImage and VACodedBufferSegment structure for encoded bitstream. The application cannot use VABuffer for synchronization and in case of encoding it is recommended to synchronize by input VA surface as described above.

```
/* create buffer */
VABufferID buf id;
vaCreateBuffer(va display, va context,
               VAEncCodedBufferType, buf size,
               1, NULL, & buf id);
/* encode frame */
/* map buffer */
VACodedBufferSegment *coded buffer segment;
vaMapBuffer(va display, buf id, (void **)(& coded buffer segment));
size = coded buffer segment->size;
offset = coded buffer segment->bit offset;
    = coded buffer segment->buf;
/* retrieve encoded data*/
/* unmap and destroy buffer */
vaUnmapBuffer(va display, buf id);
vaDestroyBuffer(va display, buf id);
```

Example 19: Working with encoded bitstream buffer

Appendix F: CQP HRD mode encoding

Application can configure AVC encoder to work in CQP rate control mode with HRD model parameters. SDK will place HRD information to SPS/VUI and choose appropriate profile/level. It's responsibility of application to provide per-frame QP, track HRD conformance and insert required SEI messages to the bitstream.



Example 21 shows how to enable CQP HRD mode. Application should set RateControlMethod to CQP, VuiNalHrdParameters to ON, NalHrdConformance to OFF and set rate control parameters similar to CBR or VBR modes (instead of QPI, QPP and QPB). SDK will choose CBR or VBR HRD mode based on MaxKbps parameter. If MaxKbps is set to zero, SDK will use CBR HRD model (write cbr_flag = 1 to VUI), otherwise VBR model will be used (and cbr_flag = 0 is written to VUI).

```
mfxExtCodingOption option, *option array;
     /* configure mfxExtCodingOption */
     memset(&option, 0, sizeof(option));
     /* configure mfxVideoParam */
     mfxVideoParam param;
     param.mfx.RateControlMethod
                                     = MFX RATECONTROL CQP;
     param.mfx.FrameInfo.FrameRateExtN = <valid non zero value>;
     param.mfx.FrameInfo.FrameRateExtD = <valid_non_zero_value>;
     param.mfx.BufferSizeInKB = <valid_non_zero_value>;
param.mfx.InitialDelayInKB = <valid_non_zero_value>;
     param.mfx.TargetKbps
                                     = <valid non zero value>;
     if (<write cbr flag = 1>)
          param.mfx.MaxKbps = 0;
     else /* <write cbr flag = 0> */
          param.mfx.MaxKbps = <valid non zero value>;
     param.NumExtParam = 1;
     option array = &option;
     param.ExtParam = &option array;
     /* encoder initialization */
     mfxStatus sts;
     sts = MFXVideoENCODE Init(session, &param);
     /* encoding */
     mfxEncodeCtrl ctrl;
     memset(&ctrl, 0, sizeof(ctrl));
     ctrl.QP = <frame qp>
     sts=MFXVideoENCODE EncodeFrameAsync(session,&ctrl,surface2,bit
s, &syncp);
```

Example 21: Pseudo-code to enable CQP HRD mode