Project 1

1) MIPS Instruction Set

Use the attached cheat sheet (at the end of the assignment) in order to determine which

MIPS instructions appear in the program. Determine the instruction format for each instruction.

Determine the operands for each instruction. For registers determine both, the register number and the symbolic register name.

There are conditional branches in the function. Determine to which instructions they branch.

line	opcode	format	funct	MN	rs	rt	rd	$_{ m imm}$	traduction
0	4	I		BEQ	4	0		OxD	if $(a0 = 0)$ then $PC = PC + 4 + 4*$
4									nop
8	32	I		LB	4	5		0x0	a1 = memory[a0 + 0] as a byte
\mathbf{c}									nop
10	4	I		BEQ	5	0		0x7	if $a1 = 0$ then $PC = PC + 4 + 4*7$
14	0	\mathbf{R}	37	OR	0	0	2		v0 = 0
18	9	I		ADDIU	4	4		0x1	a0 = a0 + 1
1c	14	I		XORI	5	3		0x20	v1 = a1 XOR 0x20 : 6th byte flippe
20	32	I		LB	4	5		0x0	a1 = memory[a0] as a byte (we are
24	0	\mathbf{R}	43	SLTU	0	3	3		v1 = (0 < v1) <=> (v1 != 0) as it
28	5	I		BNE	5	0		0xFFFB	if a1 $!= 0$ then branch at PC + 4 +
2c	0	\mathbf{R}	33	ADDU	2	3	2		v0 = v0 + v1
30	0	\mathbf{R}	8	$_{ m JR}$	31				Jump Register : PC = ra
34									nop
38	0	\mathbf{R}	8	$_{ m JR}$	31				Jump Register : PC = ra
3c	9	\mathbf{R}		ADDIU	0	2		OxFFFF	v0 = 0xFFFF = -1

What is the function actually doing? What is its return value?

This function takes a string as argument and returns :

- -1 if the string is a null pointer
- The number of char different than a space in the string otherwise.

2) MIPS Tool Chain

Write a C program matching the program from above.

```
int f(char *s) {
    if(s == 0) return -1;
    char c = *s;
    if(c == 0) return 0;

    int r = 0;
    while(c != 0) {
        r += (c != ' ');
        c = *(++s);
    }
    return r;
}
```

Compile the program using the MIPS compiler installed on the lab machines using the

following command line:

```
mips-linux-gnu-gcc -mips1 -c -g -o mips-prog.o <input-file>
```

Disassemble the compiled program (mips-prog.o) with the objdump tool using the

following command line:

```
mips-linux-gnu-objdump -d mips-prog.o
```

Compare the resulting assembly code obtained from the objdump tool with the code

from above. Explain why the code looks so differently? The code contains many lw

instructions that use the register s8. What is the purpose of register s8? What are these

memory access instructions doing?

If we compile it without optimization. The assembly code is quite different, much longer and most instructions are useless. It uses register S8 which is the frame pointer. But here it is useless as we know the size of the stack. Sp could have done the job, and here sp = fp, so really it's useless. Moreover the code never uses other register than v0 and it always store it's value in the stack (thanks to s8) and load values from the stack.

Try to change the compiler options (enable/disable optimizations using the option -O0,

-O, or -O3) and see how this changes the code that you can see using the objdump tool.

With some optimization we get better results, and we no longer use S8. With -O2 optimization we have the exact same code. And with -Os we get even a shorter code (but maybe less efficient).

3) MIPS Architecture

3.1 Program Flow

Provide a full list of instructions until the function terminates by executing a jr instruction.

PC	instruction	a0	a1	v0	v1	explaination
0x0	beq a0, 0,	0x200	0x0	0x0	0x0	a0 = 0 so the branch is
	0xD					untaken
0x4	nop	0x200	0x0	0x0	0x0	no change
0x8	lb a0, a1,	0x200	0x0	0x0	0x0	read from memory $[0x200]$ to a1
	0x0					the value arrives in the next
						instruction
0xc	nop	0x200	0x61	0x0	0x0	no change wait for loading
0X10	beq a1, 0 ,	0x200	0x61	0x0	0x0	a1 $!= 0$ so the branch is
	0x7					untaken
0x14	or $v0, 0, 0$	0x200	0x61	0x0	0x0	v0 <= 0
0x18	addiu a0,	0x201	0x61	0x0	0x0	$a0 \le a0 + 1$
	a0, 0x1					
0x1c	xori v1, a1,	0x201	0x61	0x0	0x41	$v1 \le a1 \hat{0}x20$
	0x20					
0x20	lb a0, a1,	0x201	0x61	0x0	0x41	read from memory[0x201] to a1
	0x0					the value arrives in the next
0.04	1. 1.0	0 001	0.00	0.0	0.4	instruction
0x24	sltu v1, 0,	0x201	0x20	0x0	0x1	v1 <= (v1!=0)
0.00	v1	0.001	0.00	0.0	0 1	
0x28	bne a1, 0 ,	0x201	0x20	0x0	0x1	a1 $!= 0$ so the branch is taken.
	0xfffb					the next instruction is still
0.0	11 0	0.001	0.00	0 1	0 1	executed
0x2c	addu v0,	0x201	0x20	0x1	0x1	$v0 \le v0 + v1 = 1$
010	v1, v0	0202	020	01	01	20 < 20 + 1
0x18	addiu a0,	0x202	0x20	0x1	0x1	$a0 \le a0 + 1$
010	a0, 0x1	0202	020	0x1	00	$v1 \le a1 \hat{0}x20$
0x1c	xori v1, a1, 0x20	0x202	0x20	UXI	0x0	$V1 \le a1 0x20$
0x20		0202	020	01	00	mand from manager [0x202] to all
UXZU	lb a0, a1, 0x0	0x202	0x20	0x1	0x0	read from memory[0x202] to a1 the value arrives in the next
	UXU					instruction
						IIISti uction

PC	instruction	a0	a1	v0	v1	explaination
0x24	sltu v1, 0, v1	0x202	0x62	0x1	0x0	$v1 \le (v1! = 0)$
0x28	bne a1, 0, 0xfffb	0x202	0x62	0x1	0x0	a1 != 0 so the branch is taken. the next instruction is still executed
0x2c	addu v0, v1, v0	0x202	0x62	0x1	0x0	$v0 \le v0 + v1 = 1$
0x18	addiu a0, a0, 0x1	0x203	0x62	0x1	0x0	$a0 \le a0 + 1$
0x1c	xori v1, a1, 0x20	0x203	0x62	0x1	0x42	$v1 \le a1 \hat{0}x20$
0x20	lb a0, a1, 0x0	0x203	0x62	0x1	0x42	read from memory[0x203] to a1 the value arrives in the next instruction
0x24	sltu v1, 0, v1	0x203	0x0	0x1	0x1	$v1 \le (v1! = 0)$
0x28	bne a1, 0, 0xfffb	0x203	0x0	0x1	0x1	a1 == 0 so the branch is not taken
0x2c	addu v0, v1, v0	0x203	0x0	0x2	0x1	$v0 \le v0 + v1 = 2$
0x30	jr ra	0x203	0x0	0x2	0x1	end of function, returns. next instruction is still executed
0x34	nop	0x203	0x0	0x2	0x1	nop

3.2 Pipiline Diagram

Draw a pipeline diagram showing all the instructions executed by the function as determined

above. Assume a processor implementation as described above. Highlight

all forms of hazards that occur and graphically distinguish resolution mechanisms (e.g.,

forwarding, stalls, flushing).

4) Processor design

4.1 Instruction Set Architecture

Group instructions into binary formats, similar to the I-, J-, and R-format discussed for $\,$

MIPS in the lecture. Illustrate the formats using figures in your report.

The first format is ${\bf R\text{-}format}$, the 16-bits instruction is divided in 4 part of 4 bits :

03	47	811	1215
opcode	Rs	R1	R2

(There are 16 registers, so register id are on 4 bits.)

The second format is **M-format**, used for memory access. The opcode is now on 3 bits, and the immediate value is on 5 bits:

02	36	710	1115
opcode	Rs	Ra	immediate

And the last format is **I-format**. The opcode is on only 2 bits, and the immediate value is on 10 bits (register id are still on 4 bits):

01	25	615
opcode	R	immediate

Describe each instruction of your processor. Explain what the instruction is doing, how it can be written in human readable form (assembly), and how it is encoded in binary form.

Assembly code	Format	Opcode	Traduction
ADD	R	0000	Rs < -R1 + R2
AND	\mathbf{R}	0001	Rs <- R1 & R2
XOR	\mathbf{R}	0010	Rs <- R1 ^ R2
$_{ m JR}$	\mathbf{R}	0011	PC <- Rs
LB	${ m M}$	010	$Rs \leftarrow SE(Mem[Ra + SE(immediate)])$ (*)
$_{ m SB}$	${ m M}$	011	Mem[Ra + SE(immediate)] <- Rs[7:0]
MV	I	10	$R \leftarrow SE(immediate)$
BNN	I	11	If R $!= 0$, then PC = PC + 2 * immediate (**)

^{*}SE = Sign Extend.

^{**} Instructions are on 16 bits, so PC should always be an even number.

Provide a sequence of instructions in assembly form that allows to load the constant

65534 into a register using the instructions of your processor. Give a short explanation of

each instruction and each intermediate result of your code.

In order to load 65534 (= 0xFFFE) into a register with those instructions, we can do :

```
MV RO Ox3FF
ADD RO RO RO
```

The first line will set R0 to -1 = 0x3FF (on 10 bits). It means that after this instruction, R0 has 0xFFFF value due to sign extension. Then the second instruction do: R0 <= -1 + -1 = -2 (0xFFFF + 0xFFFF = 0xFFFE).

Translate the C-code from Question 1 to corresponding instructions of your processor.

Assume that the input pointer is provided in the second register of your processor and that

the result should be returned in the first register. The return address is similarly provided

in register 15. Try to use the instructions of your processor as optimal as possible in order

to minimize the number of instructions. There is no need to preserve any register values $\,$

in your code, i.e., you can overwrite any register if needed.

Translation of C-code, we assume here that there is no pipeline in the processor yet.

```
00 BNN R1 3
                        //R1 = 0 \rightarrow return -1
02
   MV RO 0x3FF
04
    JR
       R15
06
   MV
        RO O
                        //Initialization
80
   MV R3 0x20
0a
   MV
        R4 1
0с
   LB
        R2 R1 0
   BNN R2 2
                        //R2 = 0 \rightarrow return R0
0e
10
   JR R15
12
   XOR R2 R2 R3
   ADD R1 R1 R4
14
16
   BNN R2 2
   BNN R4 Ox3Fa
                        //Go back to Oc instruction
   ADD RO RO R4
   BNN R4 0x3F8
                        //Go back to Oc instruction
```

4.2 Pipelining

Which kinds of hazards (data, control, or structural) can you encounter for your processor?

Explain under which circumstances these hazards occur. How are these hazards resolved?

There are 3 types of hazards:

- data hazard
- control hazard
- structural hazard

We will treat them one by one.

Data hazard:

This hazard occure when a data is not available when it is needed for the next instruction.

The textbook exemple is when an instruction needs the result of an ALU operation. For example :

```
00 ADD R2 R3 R4
02 ADD R0 R1 R2
```

In this code the result of the first instruction is needed as an operand for the second one.

Nevertheless, in a pipelined CPU the result of an ALU operation might not be written back in

the register file as soon as it is executed.

However in our pipelined CPU we only have three stages :

- Instruction Fetch (IF)
- Instruciton Decode (ID)
- Execute (EX)

The result of a ALU operation is written during the EX stage and is directly available. So this

result can be used for the next EX. This solves without any hazard the porblem of the codes like :

```
00 ADD R2 R3 R4
02 ADD R0 R1 R2
```

But the result of a EX instruction can be needed for a ID, typically:

```
00 ADD R0 R1 R2 02 BNN R0 0x08
```

Indeed, BNN (Branch Non Null) is done during the ID stage and thus needs the value of R0.

However this is not a hazard neither because we assume that the result of the ALU is

given so quickly that we have it for the ID directly.

As says the statement of the PR1:

Assume that the processor registers are written at the beginning of the EX stage and read at the end of the ID stage, i.e., values written in the EX stage are immediately available in the ID stage.

As a result, a data hazard can only occure of there is a memory load. This hazard is solved by stalling the IF and ID stages.

Control hazard:

A control hazard occure when the next PC is not correct. This happens when a branch is mispredicted.

In our CPU we only predict untaken branch. This means this hazard occures when a branch

is taken. As a result we must flush the IF stage.

Structural hazard:

This hazard happens when a ressource is needed by several instructions at the same time. In our simple CPU, **This kind of hazard never occures**.

Does your processor need forwarding (as discussed in the lecture) for the instructions $\,$

in the EX stage? What about the conditional branch that is executed in the ID stage?

Explain for both cases why it is needed or why it is not needed.

Our CPU does not need a forwarding for the EX stage. Indeed, the result of the previous EX stage

is directly written back in the register file and available.

As for the ID stage, we assumed that the result of the EX stage is written back sufficiently quickly that it can be used in the same clock by the ID stage (for example for a branch instruction). This means that **we don't need to implement**

a forwarding for this CPU.