Computer Systems

Muchang Bahng

Spring 2024

Contents

| 1 | Enc | coding Schemes | 3 |
|---|-------------------|---|----------|
| | 1.1 | Booleans and Characters | 4 |
| | 1.2 | Integer Family | 4 |
| | | 1.2.1 Arithmetic Operations on Binary Numbers | 8 |
| | 1.3 | Float Family | 8 |
| 2 | Mei | mory | 8 |
| _ | 2.1 | | 1 |
| | 2.2 | | 1 |
| | 2.3 | | 2 |
| | $\frac{2.3}{2.4}$ | | 2 |
| | 2.4 | | 3 |
| | | v v | .3 |
| | 0.5 | | |
| | $\frac{2.5}{2.6}$ | | .7 |
| | 2.6 | , , , | |
| | 2.7 | Dynamic Memory Allocation | 20 |
| 3 | Imp | plementations of Memory Structures in C | 0 |
| | 3.1 | Arrays | 20 |
| | 3.2 | Strings | 20 |
| | 3.3 | Structs | 20 |
| | 3.4 | Functions | 20 |
| | 3.5 | Classes (for $C++$) | 20 |
| | 3.6 | | 20 |
| 4 | Con | atual Duagossing Unit | 20 |
| 4 | 4.1 | 0 | 23 |
| | 4.1 | | 23 24 |
| | 4.2 | 9 | 24 25 |
| | | ↓ 0 | |
| | 4.0 | v e | 26 |
| | 4.3 | Q . | 26 |
| | | | 27 |
| | | v 0 | 28 |
| | 4.4 | | 28 |
| | | 0 | 29 |
| | | | 29 |
| | | | 29 |
| | | 1 | 30 |
| | | | 31 |
| | | 4.4.6 ARM Instructions | 31 |

| | | 4.4.7 Buffer Overflows | 61 |
|---|-----|--|----|
| 5 | Sto | age Hierarchy | 61 |
| | 5.1 | Locality | 62 |
| | 5.2 | RAM | 63 |
| | 5.3 | Caches | 63 |
| | 5.4 | SSD | |
| | 5.5 | HDD | |
| 6 | Cor | apiling and Linking | 64 |
| | 6.1 | Precompiling Stage | 64 |
| | 6.2 | Compiling Stage | 67 |
| | 6.3 | Objdump | |
| | | 6.3.1 ELF and Mach-O Formats | 70 |
| | | 6.3.2 Objdump Commands | 71 |
| | 6.4 | Assembling Stage and Object Files | |
| | 6.5 | Linking Stage and Relocation | |
| | | 6.5.1 Relocation | |
| | | 6.5.2 Linking with One Object File | |
| | | 6.5.3 Global vs External Symbols | |
| | | 6.5.4 Linking with Multiple Object Files | |
| | 6.6 | Compiler Optimization | |
| | 6.7 | Virtual Memory Addresses | |

Before we do any coding, we must learn the theory behind how computer systems work, which all starts from memory management and CPU architecture. We will use C with the gcc compiler, along with MIPS and NASM assembler. It is imperative to learn these two since given that you know a high level language pretty well (Python in my case), you want to learn C to appreciate the things Python does for you, and you want to learn Assembly to appreciate the things C does for you.¹.

To start off, we want a big overall picture of high a computer works. We introduce this with the simplest model of the computer, the Von Nuemann architecture. It consists of a **central processing unit** (CPU), **memory**, and an **input/output** (I/O) system. We show a diagram of this first for conciseness in Figure 1.




Figure 1: von Neumann Architecture

We will go through these one by one, touching on C and Assembly along the way, but the implementation of these things can differ by the **computer architecture**, so let's list some of the basic ones.

Definition 0.1 (Computer Architecture)

The **computer architecture** is the design of the computer, which includes the CPU, memory, and I/O system. There are many different architectures, but we will focus on the most common ones.

We first go over some basic theoretical properties of basic data types, focusing on C, and then we cover all the stuff about memory and then all the stuff about the CPU. This is a natural progression since to work with data, you must first know where to store the data and how it is stored (the memory), and then you want to know how data is manipulated (the CPU).

1 Encoding Schemes

In order to get into memory, it is helpful to know the theory behind how primitive types are stored in memory.

Definition 1.1 (Collections of Bits)

There are many words that are used to talk about values of different data types:

- 1. A **bit** (b) is either 0 or 1.
- 2. A **Hex** (x) is a collection of 4 bits, with a total of $2^4 = 16$ possible values, and this is used since it is easy to read for humans.
- 3. A Byte (B) is a collection of 8 bits or 2 hex, with a total of $2^8 = 256$ possible values, and most computers will work with Bytes as the smallest unit of memory.

¹https://www.youtube.com/watch?v=XlvfHOrF26M

Definition 1.2 (Collections of Bytes)

Sometimes, we want to talk about slightly larger collections, so we group them by how many bytes they have. However, note that these may not always be the stated size, depending on what architecture or language you are using. This is more of a general term, and they may have different names in different languages. If there is a difference, we will state it explicitly.

- 1. A word (w) is 2 Bytes.
- 2. A long (l) is 4 Bytes.
- 3. A quad (q) is 8 Bytes.

Try to know which letter corresponds to which structure, since that will be useful in both C and Assembly.

1.1 Booleans and Characters

Definition 1.3 (Booleans in C)

The most basic type is the boolean, which is simply a bit. In C, it is represented as bool, and it is either true (1) or false (0).

We can manually check the size of the boolean type in C with the following code.

```
1  #include<stdio.h>
2  #include<stdbool.h>
3
4  int main() {
5    printf("%lu\n", sizeof(bool));
6    return 0;
7  }
1  1
2  .
3  .
4  int main() {
6    c.
7  .
```

Figure 2: We can verify the size of various primitive data types in C with the sizeof operator.

1.2 Integer Family

The most primitive things that we can store are integers. Let us talk about how we represent some of the simplest primitive types in C: unsigned short, unsigned int, unsigned long, unsigned long long.

Definition 1.4 (Unsigned Integer Types in C)

In C, there are several integer types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. An **unsigned short** is 2 bytes long and can be represented as a 4-digit hex or 16 bits, with values in [0:65,535]. Therefore, say that we have
- 2. An **unsigned int** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in [0:4,294,967,295].
- 3. An **unsigned long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 32 bits in other systems.
- 4. An **unsigned long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, and they are guaranteed to be stored in 64 bits in other systems.

Theorem 1.1 (Bit Representation of Unsigned Integers in C)

To encode a signed integer in bits, we simply take the binary expansion of it.




Figure 3: Unsigned encoding of 4-bit integers in C.

Example 1.1 (Bit Representation of Unsigned Integers in C)

We can see for ourselves how these numbers are represented in bits. Printing the values out in binary requires to make new functions, but we can easily convert from hex to binary.

```
int main() {
    unsigned short x = 13;
    unsigned int y = 256;
    printf("%x\n", x);
    printf("%x\n", y);
    return 0;
    }
}
```

So far, the process of converting unsigned numbers to bits seemed simple. Now let's introduce signed integers.

Definition 1.5 (Signed Integer Types in C)

In C, there are several signed integer types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. A **signed short** is 2 bytes long and can be represented as a 4-digit hex or 16 bits, with values in [-32,768:32,767].
- 2. A **signed int** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in [-2, 147, 483, 648: 2, 147, 483, 647].
- 3. A **signed long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 32 bits in other systems.
- 4. A **signed long long** is 8 bytes and can be represented as an 16-digit hex or 64 bits, and they are guaranteed to be stored in 64 bits in other systems.

To store signed integers, it is intuitive to simply take the first (left-most) bit and have that be the sign. Therefore, we lose one significant figure but gain information about the sign. However, this has some problems: first, there are two representations of zeros: -0 and +0. Second, the continuity from -1 to 0 is not natural. It is best explained through an example, which doesn't lose much insight into the general case.

Example 1.2 (Problems with the Signed Magnitude)

Say that you want to develop the signed magnitude representation for 4-bit integers in C. Then, you can imagine the following diagram to represent the numbers.




Figure 4: Signed magnitude encoding of 4-bit integers in C.

You can see that there are some problems:

- 1. There are two representations for 0, which is 0000 and 1000.
- 2. -1 (1001) plus 1 becomes -2 (1010).
- 3. The lowest number -7 (1111) plus 1 goes to 0 (0000) when it should go to -6 (1100).
- 4. The highest number 7 (0111) plus 1 goes to 0 (1000).

An alternative way is to use the two's complement representation, which solves both problems and makes it more natural.

Theorem 1.2 (Bit Representation of Signed Integers in C)

The **two's complement** representation is a way to represent signed integers in binary. It is defined as follows. Given that you want to store a decimal number p in n bits,

- 1. If p is positive, then take the binary expansion of that number, which should be at most n-1 bits (no overflow), pad it with 0s on the left.
- 2. If p is negative, then you can do two things: First, take the binary expansion of the positive number, flip all the bits, and add 1. Or second, represent $p = q 2^n$, take the binary representation of q in n 1 bits, and add a 1 to the left.

If you have a binary number $b = b_n b_{n-1} \cdots b_1$ then to convert it to a decimal number, you simply calculate

$$q = -b_n 2^{n-1} + b_{n-1} 2^{n-2} + \dots + b_1 \tag{1}$$




Figure 5: Two's complement encoding of 4-bit integers in C.

Example 1.3 (Bit Representation of Signed Integers in C)

We can see for ourselves how these numbers are represented in bits.

```
int main() {
                                                   d
                                                   ffe7
                                                   100
    short short_pos = 13;
    short short_neg = -25;
                                                   ffffffe00
    int int_pos = 256;
6
    int int_neg = -512;
    printf("%x\n", short_pos);
    printf("%x\n", short_neg);
    printf("%x\n", int_pos);
    printf("%x\n", int_neg);
    return 0;
  }
```

```
#include<stdio.h>
#include<stdbool.h>

#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdbool.h>
#include<stdboo
```

Figure 6: Size of various integer types in C with the sizeof.

1.2.1 Arithmetic Operations on Binary Numbers

Theorem 1.3 (Inversion of Binary Numbers)

Given a binary number p, to compute -p, simply invert the bits and add 1.

Theorem 1.4 (Addition and Subtraction of Binary Numbers)

Given two binary numbers p and q.

- 1. To compute p + q, simply add the numbers together as you would in base 10, but carry over when the sum is greater than 1.
- 2. To compute p-q, you can invert q to -q and compute p+(-q).

1.3 Float Family

Definition 1.6 (Floating Point Types in C)

In C, there are several floating point types. We use this hierarchical method to give flexibility to the programmer on the size of the integer and whether it is signed or not.

- 1. A **float** is 4 bytes long and can be represented as an 8-digit hex or 32 bits, with values in $[1.2 \times 10^{-38} : 3.4 \times 10^{38}]$.
- 2. A **double** is 8 bytes long and can be represented as an 16-digit hex or 64 bits, with values in $[2.3 \times 10^{-308} : 1.7 \times 10^{308}]$.
- 3. A **long double** is 8 bytes and can be represented as an 16-digit hex or 64 bits, but they are only guaranteed to be stored in 80 bits in other systems.

Theorem 1.5 (Bit Representation of Floating Point Types in C)

Floats are actually like signed magnitude. We have

$$(-1)^n \times 2^{e-127} \times 1.s$$
 (2)

where

Doubles encode 64 bits, so not we have exponent having 11 bits (so bias is not 1023) and 52 bits for mantissa.

2 Memory

Definition 2.1 (Memory)

The **memory** is where the computer stores data and instructions, which can be though of as a giant array of memory addresses, with each containing a byte. This data consists of graphical things or even instructions to manipulate other data. It can be visualized as a long array of boxes that each have an **address** (where it is located) and **contents** (what is stored in it).

Memory simply works as a bunch of bits in your computer with each bit having some memory address, which is also a bit. For example, the memory address 0b0010 (2) may have the bit value of 0b1 (1) stored in it.

| Addresses | Values |
|-----------|--------|
| 060010 | 1 |
| 060011 | (|
| 060100 | D |
| 060101 | I |
| 060110 | 0 |
| 060111 | O |
| 061000 | 0 |
| 061001 | 1 |
| 0 9 1 010 | 1 |

Figure 7: Visualization of memory as a long array of boxes of bits.

However, computers do not need this fine grained level of control on the memory, and they really work at the Byte level rather than the bit level. Therefore, we can visualize the memory as a long array of boxes indexed by Bytes, with each value being a byte as well. In short, the memory is **byte-addressable**. In certain arthitectures, some systems are **word-addressable**, meaning that the memory is addressed by words, which are 4 bytes.^a

| Byte Address | Values | Values | Word Address |
|--------------|------------------|-------------|--------------|
| 0×120 | 10010010 = 0×92 | | 0x48 |
| 0×121 | 00000000 = 0 ×00 | 0x92006FBO | |
| 0×122 | 01101111 = 0x6F | | |
| 0 x 123 | 1011 0000 = 0xB0 | | |
| 0×124 | 10010110 =0×96 | | 0×49 |
| 0 x125 | 10010111 = 0×97 | Dx 96971199 | |
| 0×126 | 00010001 = 0 11 | | |
| 0×127 | 10011001 = 0×99 | | |
| 0×128 | 11111110 : 0xFE | 0xFE | 0×4A |

Figure 8: Visualization of memory as a long array of boxes of bytes. Every address is a byte and its corresponding value at that address is also a byte, though we represent it as a 2-digit hex.

In the examples above, I listed the memory addresses as a 3 hex character (1.5 bytes) for brevity. In reality,

 $[^]a$ Note that in here the size of a word is 2 bytes rather than 4 as stated above. This is just how it is defined in some x86 architectures.

the number of bytes that a memory address takes is much longer.

Definition 2.2 (32 and 64 Bit Machines)

There are two types of machines that tend to format these boxes very differently: 32-bit and 64-bit machines.

- 1. 32 bit machines store addresses in 32 bits, so they can have 2^{32} addresses, which is about 4 GB of memory.
- 2. 64 bit machines store addresses in 64 bits, so they can have 2^{64} addresses, which is about 16 EB of memory. This does not mean that the actual RAM is 16 EB, but it means that the machine can *handle* that much memory.

The numbers typically mean the size of the type that the machine works best with, so all memory addresses will be 32 or 64 bits wide. Most machines are 64-bits, and so everything in this notes will assume that we are working with a 64 bit machine. As we will later see, this is why pointers are 8 bytes long, i.e. 64 bits. This is because the memory addresses are 64 bits long, though all of them are not used.

With this structure in mind and knowing the size of some primitive types, we can now focus on how declaring them works in the backend.

Definition 2.3 (Declaration, Initialization)

Assigning a value to a variable is a two step process, which is often not distinguished in high level languages like Python.

- 1. You must first **initialize** the variable by setting aside the correct number of bytes in memory.
- 2. You must then **assign** that variable to be some actual value.

The two step process is often called declaration.

This is the reason why C is statically, or strongly, typed. In order to set aside some memory for a variable, you must know how big that variable will be, which you know by its type. This makes sense. We can first demonstrate how to both initialize and declare a variable.

```
int main() {
    // declaring
    int x = 4;
    printf("%p\n", &x);

    // initializing and assigning
    int y;
    printf("%p\n", &y);
    y = 3;
    printf("%p\n", &y);
    return 0;
}
```

Figure 9: How to declare variables in C. As you can see, by initializing y, the memory address is already assigned and it doesn't change when you assign it. The address is only shown to be 9 hex digits long, but it is actually 16 hex digits long and simply 0 padded on the left.

One question that may come to mind is, what is the value of the variable if you just initialize it? After all the value at that address that is initialized must be either 0s or 1s. Let's find out.

```
int main() {
   int y;
   printf("%d\n", y);
   y = 3;
   printf("%d\n", y);
   for return 0;
   }
}
1 6298576

2 3
3 .
4 .
5 .
6 .
7 return 0;
8 }
```

Figure 10: The value of an uninitialized variable is some random number.

It may be interesting to see how this random unititialized value is generated. It is simply the value that was stored in that memory address before, and it is not cleared when you initialize it, so you should not use this as a uniform random number generator.

2.1 Debugging and Object Dumping

Talk about gdb, lldb, objdump, etc. These are debugging tools that allow you to parse your code line by line. However, to actually see the C code, you must compile it with the debugging flag. This adds a little bit of overhead memory to the binary, but not a lot.

2.2 Endian Architecture

It is intuitive to think that given some multi-byte object like an int (4 bytes), the beginning of the int would be the lowest address and the end of the int would be the highest address, like how consecutive integers are stored in an array. However, this is not always the case (almost always not the case since most computers are little-endian).

Definition 2.4 (Endian Architecture)

Depending on the machine architecture, computers may store these types slightly differently in their byte order. Say that we have an integer of value 0xA1B2C3D4 (4 bytes). Then,

- 1. A **big-endian architecture** (e.g. SPARC, z/Architecture) will store it so that the least significant byte has the highest address.
- 2. A little-endian architecture (e.g. x86, x86-64, RISC-V) will store it so that the least significant byte has the lowest address.
- 3. A bi-endian architecture (e.g. ARM, PowerPC) can specify the endianness as big or little.




Figure 11: The big vs little endian architectures.

We can simply print out the hex values of primitive types to see how they are stored in memory, but it does not provide the level of details that we want on which bytes are stored where. At this point, we must use certain **debuggers** to directly look at the memory. For x86 architectures, we can use gdb and for ARM architectures, we can use lldb. At this point, we need to understand assembly to look through debuggers, so we will provide the example here.

Example 2.1 (Endianness of C Int in x86-64) To do.

Example 2.2 (Endianness of C Int in ARM64)

To do.

2.3 Type Casting

2.4 Pointers

We have learned how to declare/initialize a variable, which frees up some space in the memory and possibly assigns a value to it. One great trait of C is that we can also store the memory address of a variable in another variable called a pointer. You access both the memory and the value at that memory with this pointer variable.

Definition 2.5 (Pointer Variable)

A **pointer** variable/type is a variable that stores the memory address of another variable.

- 1. You can declare a pointer in the same way that you declare a variable, but you must add a asterisk in front of the variable name.
- 2. The size of this variable is the size of the memory address, which is 8 bytes in a 64-bit architecture.
- 3. To get the value of the variable that the pointer points to, called **dereferencing**, you simply put a asterisk in front of the pointer. This is similar to how you put a ampersand in front of a variable to get its memory address.

```
int main() {
                                                    x = 4
     // declare an integer
                                                    &x = 0x16d49ae68
     int x = 4;
                                                    p = 0x16d49ae68
     printf("x = \frac{d}{n}, x);
     printf("&x = p\n, &x);
                                                    q = 0x16d49ae68
     // declare pointer
     int *p = &x;
     printf("p = p \in p, p);
     printf("*p = %d\n", *p);
     // initialize pointer
13
     int *q;
14
     q = &x;
     printf("q = p\n, q);
     printf("*q = %d\n", *q);
     return 0;
18 }
```

Figure 12

Since the size of addresses are predetermined by the architecture, it may not seem like we need to know the underlying data type of what it points to, so why do we need to write strongly type the underlying data type? Remember that to do pointer arithmetic, you need to know how large the underlying data type is so that you can know how many bytes to move when traversing down an array.

One of the reasons why pointers are so valuable is that they allow you to pass by reference, which is a way to change the value of a variable in a function.

2.4.1 Call by Value vs Call by Reference

```
Definition 2.6 (Call by Value)

Definition 2.7 (Call by Reference)
```

2.4.2 Pointer Errors

Just like for regular variables, you may be curious on the value of an unassigned pointer. Let's take a look.

Example 2.3 (Uninitialized Pointers)

```
int main() {
   int x = 4;
   int *p;
   printf("p = %p\n", p);
   printf("*p = %x\n", *p);
   return 0;
   }
}

1   p = 0x10249ff20
2   *p = d100c3ff
3   .
4   .
5   .
6   .
7   return 0;
8  }
```

Figure 13: The value of an uninitialized pointer is some random address and at a random address it would be some random byte.

This is clearly not good, especially since the program compiles correctly and runs without any errors. This kind of pointer that hasn't been initialized is called a wild pointer.

```
Definition 2.8 (Wild Pointer)
```

A wild pointer is a pointer that has not been initialized to a known value.

To fix this, we must always initialize a pointer to a known value. This may come at a disadvantage, since now we can't reap the benefits of initializing first and assigning later. A nice compromise is to initialize the pointer to a null pointer.

Definition 2.9 (Null Pointer)

A **null pointer** is a pointer that has been initialized to a known value, which is the address 0x0. You can set the type of the pointer and then initialize it to NULL.

```
int main() {
    int *p = NULL;
    printf("p = %p\n", p);

    // the code below gives seg fault
    /* printf("*p = %d\n", *p); */

    int x = 4;
    p = &x;
    p = &x;
    printf("p = %p\n", p);
    printf("p = %p\n", p);
    return 0;
    return 0;
}
```

Figure 14: Initializing a null pointer. It is a good practice to initialize a pointer to a null value.

Therefore, the null pointer allows you to set the type of the underlying data type, but the actual address will be 0x0. You cannot dereference a null pointer, and doing so will give you a segmentation fault. There may be times when you do not even know the data type of the pointer, and for this you can use the void pointer, which now doesn't know the type of the variable that it points to but it does allocate address.

Definition 2.10 (Void Pointer)

A **void pointer** is a pointer that does not know the type of the variable that it points to. We can initialize it by simply setting the underlying type to be void. This initializes the address, which should always be 8 bytes, but trying to access the value of the variable is not possible.

```
int main() {
    void *p;
    printf("p = %p\n", p);
    int x = 4;
    p = &x;
    printf("%d", *((int*)p));
    return 0;
    }
}

1    p = 0x102553f54
2    4
3    .
4    .
5    p = &x;
6    printf("%d", *((int*)p));
7    return 0;
8  }
```

Figure 15: Initialize a void pointer and then use typecasting to access the value of the variable that it points to.

2.5 Pointer Arithmetic

With pointers out of the way, we can talk about how arrays are stored in memory.

Definition 2.11 (Array)

A C array is a collection of elements of the same type, which are stored in contiguous memory locations. You can initialize and declare arrays in many ways, and access their elements with the index, e.g. arr[i].

1. You declare an array of some constant number of elements n with the elements themselves.

```
int arr[5] = {1, 2, 3, 4, 5};
```

2. You declare an array with out its size n and simply assign them. Then n is automatically determined.

```
int arr[] = {1, 2, 3, 4, 5};
```

3. You initialize an array of some constant size c, and then you assign each element of the array.

```
int arr[5];
for (int i = 0; i < 5; i++) {
    arr[i] = i + 1;
}</pre>
```

Unfortunately, C does not provide a built-in way to get the size of the array (like len in Python), so we must keep track of the size of the array ourselves. Furthermore, the address of the array is the address of where it begins at, i.e. the address of the first element.

You can literally see that the elements of the array are contiguous in memory by iterating through each element and printing out its address.

```
int main(void) {
                                                       Value at position 0 : 1
     // initialize array
                                                       Address at position 0 : 0x7ffd8636b0d0
     int arr[5];
                                                       Value at position 1: 4
     for (int val = 1; val < 6; val++) {</pre>
                                                       Address at position 1: 0x7ffd8636b0d4
       arr[val-1] = val * val;
                                                       Value at position 2:9
                                                       Address at position 2 : 0x7ffd8636b0d8
6
                                                       Value at position 3: 16
     int* p = &arr[0];
                                                       Address at position 3 : 0x7ffd8636b0dc
     for (int i = 0; i < 5; i++) {</pre>
                                                       Value at position 4: 25
9
       printf("Value at position %d : %d\n", i,
                                                    Address at position 4 : 0x7ffd8636b0e0
       arr[i]);
       printf("Address at position %d : %p\n",
       i, p + i);
     return 0;
                                                    16
  }
15
```

Figure 16: Ints are 4 bytes long, so the address of the next element is 4 bytes away from the previous element, making this a contiguous array.

The most familiar implementation of an array is a string in C.

Definition 2.12 (String)

A string is an array of characters, which is terminated by a null character $\setminus 0$. You can initialize them in two ways:

1. You can declare a string with the characters themselves, which you must make sure to end with the null character.

```
char str[6] = {'H', 'e', 'l', 'l', 'o', '\0'};
```

2. You can declare them with double quotes, which automatically adds the null character.

```
char str[] = "Hello";
```

Note that for whatever string we initialize, the size of the array is the number of characters plus 1.

To access elements of an array, you simply use the index of the element, e.g. arr[i], but in the backend, this is implemented with *pointer arithmetic*.

Definition 2.13 (Pointer Arithmetic)

Pointer arithmetic is the arithmetic of pointers, which is done by adding or subtracting an integer to a pointer.

- 1. If you add an integer n to a pointer p, e.g. p + n, then the new pointer will point to the nth element after the current element, with the next element being sizeof(type) bytes away from the pervious element.
- 2. If you subtract an integer n from a pointer, then the pointer will point to the nth element before the current element.

This is why you can access the elements of an array with the index, since the index is simply the number of elements away from the first element.

Example 2.4 (Pointer Arithmetic with Arrays of Ints and Chars)

Ints have a size of 4 bytes and chars 1 byte. You can see that using pointer arithmetic, the addresses of the elements of ints increment by 4 and those of the char array increment by 1.

```
int main() {
                                                   Array of Integers
    int integers[3] = {1, 2, 3};
                                                   0x16d39ee58
                                               3
    char characters[3] = {'a', 'b', 'c'};
                                                   0x16d39ee5c
3
    int *p = &integers[0];
                                                   0x16d39ee60
    char *q = &characters[0];
                                               5
                                                  Array of Characters
                                               7 0x16d39ee50
    printf("Array of Integers\n");
                                               8 0x16d39ee51
    for (int i = 0; i < 3; i++) {</pre>
      printf("%p\n", integers+i); }
                                               9 0x16d39ee52
    printf("Array of Characters\n");
    for (int i = 0; i < 3; i++) {</pre>
      printf("%p\n", characters+i); }
    return 0;
  }
```

Therefore, we can think of accessing the elements of an array as simply pointer arithmetic.

Theorem 2.1 (Bracket Notation is Pointer Arithmetic)

The bracket notation is simply pointer arithmetic in the backend.

```
int main() {
   int arr[3] = {1, 2, 3};
   int *p = &arr[0];

   for (int i = 0; i < 3; i++) {
      printf("%d\n", arr[i]);
      printf("%d\n", *(p+i));
      }
   return 0;
   ret
```

Figure 17: Accessing the elements of the list using both ways is indeed the same.

2.6 Global, Stack, and Heap Memory

Everything in a program is stored in memory, variables, functions, and even the code itself. However, we will find out that they are stored in different parts of the memory. When a program runs, its application memory consists of four parts, as visualized in the Figure 18.

- 1. The **code** is where the code text is stored.
- 2. The **global memory** is where all the global variables are stored.
- 3. The **stack** is where all of the functions and local variables are stored.
- 4. The **heap** is variable and can expand to as much as the RAM on the current system. We can specifically store whatever variables we want in the heap.

We provide a visual of these four parts first, and we will go into them later.




Figure 18: The four parts of memory in a C program.

Definition 2.14 (Code Memory)

This is where the code text is stored. It is read-only and is not modifiable.

In high level languages, we always talk about local and global scope. That is, variables defined within functions have a local scope in the sense that anything we modify in the local scope does not affect the global scope. We can now understand what this actually means by examining the backend. The global scope variables are stored in the global memory, and all local variables (and functions) are stored in the stack.

Definition 2.15 (Global Memory)

This is where all the global variables are stored.

Definition 2.16 (Stack Memory)

This is where all of the functions and local variables are stored. As we will see later, the compiler will always run the main function, which must exist in your file. By the main function is a function itself, and therefore it has its own local scope.

Then, when you initialize any functions or local variables within those functions (which will be the majority of your code), all these will be stored in the stack, which is an literally an implementation of the stack data structure. It is LIFO, and the first thing that goes in is the main function and its local variables, which is referred to as the **stack frame**. You can't free memory in the stack unless its in the top of the stack.

To see what happens in the stack, we can go through an example.

Example 2.5 (Going through the Stack)

Say that you have the following code:

```
int total;
int Square(int x) {
   return x*x;
}
int SquareOfSum(int x, int y) {
   int z = Square(x + y);
   return z;
}
```

```
8  }
9  int main() {
10   int a = 4, b = 8;
11   total = SquareOfSum(a, b);
12   printf("output = %d", total);
13   return 0;
14  }
```

The memory allocation of this program will run as such:

- 1. The total variable is initialized and is put into global memory.
- 2. main is called. It is put into the stack.
- 3. The local variables a=4 and b=8 are initialized and are put into the stack.
- 4. The SquareOfSum function is called and put into the stack.
- 5. The input local variables x=4, y=8, z are initialized and put into the stack.
- 6. x + y=12 is computed and put into the stack.
- 7. The Square function is called and put into the stack.
- 8. The x=12 local variable of Square is initialized and put into the stack.
- 9. The CPU computes x*x=144 and returns the output. The Square function is removed from the stack.
- 10. We assign z=144 and SquareOfSum returns it. Now SquareOfSum is removed from the stack.
- 11. total=144 is assigned in the global memory still.
- 12. The printf function is called and put into the stack.
- 13. The printf function prints the output and is removed from the stack.
- 14. The main function returns 0 and is removed from the stack, ending our application.

One limitation of the stack is that its total available memory is fixed from the start, ranging from 1MB to 8MB, and so you can't initialize arrays of billions of integers in the stack. It will cause a memory overflow. In fact, the memory of the stack, along with the global and text memory, are assigned at compile time, making it a **static memory**.

Since the stack is really just a very small portion of available memory, the heap comes into rescue, which is the pool of memory available to you in RAM.

Definition 2.17 (Heap Memory)

The **heap memory** (nothing to do with the heap data structure) is a variable length (meaning it can grow at runtime) and **dynamically allocated** (meaning that we can assign memory addresses during runtime) memory that is limited to your computer's hardware. Unlike simply initializing variables to allocate memory as in the stack, we must use the **malloc** and **free** functions in C, and **new** and **delete** operations in C++.

Definition 2.18 (malloc)

Definition 2.19 (free)

The stack can store pointer variables that point to the memory address in the heap. So the only way to access variables in the heap is through pointer reference, and the stack provides you that window to access that big pool of heap memory.

One warning: if you allocate another address, the previous address does not get deallocated off the memory.

Definition 2.20 (Memory Leak)

On the other hand, if you free an address but have a pointer still pointing to that address, this is also a problem called the dangling pointer.

Definition 2.21 (Dangling Pointer)

At this point, we might be wondering why we need both a stack and a heap. Well the benefits of heaps are clearer since you can dynamically allocate memory, and you don't have the LIFO paradigm that is blocking you from deallocating memory that has been allocated in the beginning of your program. A problem with just having heap is that stacks can be orders of magnitude times faster when allocating/deallocating from it than the heap, and the sequence of function calls is naturally represented as a stack.

2.7 Dynamic Memory Allocation

Let's talk about how malloc and free are implemented in C. If you make a for loop and simply print all the addresses that you allocate to. You will find that they can be quite random. After a program makes some calls to malloc and free, the heap memory can becomes fragmented, meaning that there are chunks of free heap space interspersed with chunks of allocated heap space. The heap memory manager typically keeps lists of different ranges of sizes of heap space to enable fast searching for a free extent of a particular size. In addition, it implements one or more policies for choosing among multiple free extents that could be used to satisfy a request.

The free function may seem odd in that it only expects to receive the address of the heap space to free without needing the size of the heap space to free at that address. That's because malloc not only allocates the requested memory bytes, but it also allocates a few additional bytes right before the allocated chunk to store a header structure. The header stores metadata about the allocated chunk of heap space, such as the size. As a result, a call to free only needs to pass the address of heap memory to free. The implementation of free can get the size of the memory to free from the header information that is in memory right before the address passed to free.

3 Implementations of Memory Structures in C

- 3.1 Arrays
- 3.2 Strings
- 3.3 Structs
- 3.4 Functions
- 3.5 Classes (for C++)
- 3.6 Input Output

We have standard in, standard out, and standard error.

4 Central Processing Unit

Now let's talk about how functions work on a deeper level. When we write a command, like int x = 4, we are manually looking for an address (in the stack, global, or heap) and rewriting the bits that are at that address. Functions are just an automated way to do this, and all these modifications and computations are done by the CPU.

Definition 4.1 (Central Processing Unit)

The CPU is responsible for taking instructions (data) from memory and executing them.

- 1. The CPU is composed of **registers** (different from the cache), which are small, fast storage locations. These registers can either be **general purpose** (can be used with most instructions) or **special purpose** (can be accessed through special instructions, or have special meanings/uses, or are simply faster when used in a specific way).
- 2. The CPU also has an **arithmetic unit** and **logic unit**, which is responsible for performing arithmetic and logical operations.
- 3. The CPU also has a **control unit**, which is responsible for fetching instructions from memory through the **databus**, which is literally a wire connecting the CPU and RAM, and executing them

It executes instructions from memory one at a time and executes them, known as the **fetch-execute cycle**. It consists of 4 main operations.

- 1. **Fetch**: The **program counter**, which holds the memory address of the next instruction to be executed, tells the control unit to fetch the instruction from memory through the databus.
- 2. **Decode**: The fetched data is passed to the **instruction decoder**, which figures out what the instruction is and what it does and stores them in the registers.
- 3. **Execute**: The arithmetic and logic unit then carries out these operations.
- 4. Store: Then it puts the results back on the databus, and stores them back into memory.

The CPU's **clock cycle** is the time it takes for the CPU to execute one instruction. More specifically, the clock cycle refers to a single oscillation of the clock signal that synchronizes the operations of the processor and the memory (e.g. fetch, decode, execute, store), and decent computers have clock cycles of at least 2.60GHz (2.6 billion clock cycles per second).

Therefore, in order to actually do computations on the data stored in the memory, the CPU must first fetch the data, perform the computations, and then store the results back into memory. This can be done in two ways.

- 1. Load and Store Operations: CPUs use load instructions to move data from memory to registers (where operations can be performed more quickly) and store instructions to move the modified data back into memory.
- 2. If the data is too big to fit into the registers, the CPU will use the **cache** to store the data, and in worse cases, the actual memory itself. Compilers optimize code by maximizing the use of registers for operations to minimize slow memory access. This is why you often see assembly code doing a lot in registers.

To clarify, let us compare registers and memory. Memory is addressed by an unsigned integer while registers have names like **%rsi**. Memory is much bigger at several GB, while the total register space is much smaller at around 128 bytes (may differ depending on the architecture). The memory is much slower than registers, which is usually on a sub-nanosecond timescale. The memory is dynamic and can grow as needed while the registers are static and cannot grow.

The specific structure/architecture of the CPU is determined by the instruction set architecture (ISA), which can be thought of as a subset of the general computer architecture.

Definition 4.2 (Instruction Set Architecture)

The **ISA** or just **architecture** of a CPU is a high level description of what it can do. Some differences are listed here:

- 1. What instructions it can execute.
- 2. The instruction length and decoding, along with its complexity.
- 3. The performance vs power efficiency.

ISAs can be classified into two types.

- 1. The **complex instruction set computer** (CISC) is characterized by a large set of complex instructions, which can execute a variety of low-level operations. This approach aims to reduce the number of instructions per program, attempting to achieve higher efficiency by performing more operations with fewer instructions.
- 2. The reduced instruction set computer (RISC) emphasizes simplicity and efficiency with a smaller number of instructions that are generally simpler and more uniform in size and format. This approach facilitates faster instruction execution and easier pipelining, with the philosophy that simpler instructions can provide greater performance when optimized.

Just like how memory addressing is different between 32 and 64 bit machines, CPUs also use these schemes. While 32-bit processors have 2^{32} possible addresses in their cache, it turns out that 64-bit processors have a 48-address space. This is because CPU manufacturers took a shortcut. They use an instruction set which allows a full 64-bit address space, but current CPUs just only use the last 48-bits. The alternative was wasting transistors on handling a bigger address space which wasn't going to be needed for many years (since 48-bits is about 256TB). Just a bit of history for you. Finally, just to briefly mention, the input/output device, as the name suggests, processes inputs and displays outputs, which is how you can see what the program does.

Example 4.1 (x86 Architecture)

The x86 architecture is a CISC architecture, which is the most common architecture for personal computers. Here are important properties:

- 1. It is a complex instruction set computer (CISC) architecture, which means that it has a large set of complex instructions a .
- 2. Byte-addressing is enabled and words are stored in little-endian format.
- 3. In the x86_64 architecture, registers are 8 bytes long (and 4 bytes in x86_32) and there are 16 total general purpose registers, for a total of only 128 bytes (very small compared to many GB of memory). Other special purpose registers are also documented in the wikipedia page, but it is not fully documented.

Example 4.2 (ARM Archiecture)

Mainly in phones, tablets, laptops.

Example 4.3 (MIPS Architecture)

MIPS is a RISC architecture, which is used in embedded systems such as digital home and networking equipment.

Definition 4.3 (Input/Output Device)

The input device can read/load/write/store data from the outside world. The output device, which has **direct memory address**, can display data to the outside world.

One final note to mention, there are many assembly languages out there and various syntaxes.

Example 4.4 (Assembly Syntax)

The two most popular syntaxes are AT&T and Intel.

1. **Intel Syntax**: Specifies memory operands without any special prefixes. Square brackets [] are used to denote memory addresses. For example, mov eax, [ebx] means move the contents of the

^ahttps://en.wikipedia.org/wiki/X86 instruction listings

- memory location pointed to by ebx into eax.
- 2. AT&T Syntax: Memory operands are denoted with parentheses () and include the % prefix for registers. An instruction moving data from a memory location into a register might look like movl (%ebx), %eax, with additional prefixes for immediate values and segment overrides.

Example 4.5 (Assembly Languages)

The various assembly languages are as follows:

- 1. **x86** Assembly: The assembly language for Intel and AMD processors using the x86 architecture. Both AT&T and Intel syntax are available. Tools or environments often allow switching between the two, with AT&T being the default in GNU tools like GDB.
- 2. **ARM Assembly**: The assembly language for ARM processors. Has its own unique syntax, not categorized as AT&T or Intel. ARM syntax is closely tied to its instruction set architecture and is distinct from the x86 conventions.
- 3. MIPS Assembly: The assembly language for MIPS processors. MIPS uses its own assembly language syntax, which is neither AT&T nor Intel. MIPS syntax is designed around the MIPS instruction set architecture.
- 4. **PowerPC Assembly**: The assembly language for PowerPC processors. PowerPC has its own syntax style, tailored to its architecture and instruction set, distinct from the AT&T and Intel syntax models.
- 5. **6502** Assembly: Used in many early microcomputers and gaming consoles. Utilizes a syntax unique to the 6502 processor, not following AT&T or Intel conventions.
- 6. **AVR Assembly**: The assembly language for Atmel's AVR microcontrollers. AVR assembly follows its own syntax style, designed specifically for AVR microcontrollers and not based on AT&T or Intel syntax.
- 7. **Z80 Assembly**: Associated with the Z80 microprocessor, used in numerous computing devices in the late 20th century. Z80 assembly language has its own syntax that does not adhere to AT&T or Intel syntax guidelines.

The most common one is the x86 64, which is the one that we will be focusing on, with the AT%T syntax.

4.1 Circuits

Let's go over some common logic gates since this is at the basis of how to construct arithmetic operations.

Definition 4.4 (AND, NOT, OR)

Definition 4.5 (XOR, NAND, NOR)

Definition 4.6 (NAND)

Talk about how to construct arithmetic operations with these gates such as adding two integers or multiplying them, and not just that, but other operations that we may need in a programming language.

Theorem 4.1 (Implementation of Moving Data in Circuits)

Theorem 4.2 (Implementation of Addition, Subtraction in Circuits)

Theorem 4.3 (Implementation of Multiplication in Circuits)

Theorem 4.4 (Implementation of Bitwise Operations in Circuits)

Theorem 4.5 (Implementation of Bitshift Operations)

We also want some sort of conditionals. This then can be used to implement loops by checking some conditional.

Theorem 4.6 (Implementation of Conditionals in Circuits)

As a bonus, we talk about the difference between volatile and non-volatile memory. We already learned that RAM is volatile, and this is simple to implement in a circuit since we can manually set all the bits to 0 or just deplete all power. If this is the case, then how does non-volatile memory like SSDs maintain their state?

Theorem 4.7 (Implementation of Volatile Memory)

Theorem 4.8 (Implementation of Non-Volatile Memory)

4.2 Registers

To understand anything that the CPU does, we must understand assembly language. In here, everything is done within registers, and we can see how the CPU fetches, decodes, and executes instructions. So what exactly are these registers?

Definition 4.7 (Register)

A register is a small, fast storage location within the CPU. It is used to store data that is being used immediately, and is the only place where the CPU can perform operations, which is why it must move data from memory to registers before it can perform operations on it. Everything in a register is in binary, at most 8 bytes, or 64 bits.

There are very specific types of registers that you should know. All of these registers are implemented for all assembly languages and are integral to the workflow of the CPU.

- 1. **parameter registers** which store the parameters of a function.
- 2. **Return registers** which store return values of functions.
- 3. stack pointers which point to the top of the stack (at the top of the current stack frame).
- 4. **frame pointers** which point to the base of the current stack frame.
- 5. **instruction pointers** which point to the next instruction to be executed.

4.2.1 x86 Assembly Registers

The specific type of registers that are available to a CPU depends on the computer architecture, or more specifically, the ISA, but here is a list of common ones for the x86-64. We have %rax, %rbx, %rcx, %rdx, %rsi, %rdi, %rbp, %rsp, %r8, %r9, %r10, %r11, %r12, %r13, %r14, %r15. Therefore, the x86-64 Intel CPU has a total of 16 registers for storing 64 bit data. However, it is important to know which registers are used for what.

Definition 4.8 (Parameter Registers)

Compilers typically store the first six parameters of a function in registers

respectively.

Definition 4.9 (Return Register)

The return value of a function is stored in the

register.

Definition 4.10 (Stack and Frame Pointers)

The %rsp register is the stack pointer, which points to the top of the stack. The %rbp register is the frame pointer, or base pointer, which points to the base of the current stack frame. In a typical function prologue, %rbp is set to the current stack pointer (%rsp) value, and then %rsp is adjusted to allocate space for the local variables of the function. This establishes a fixed point of reference (%rbp) for accessing those variables and parameters, even as the stack pointer (%rbp) moves.

Definition 4.11 (Instruction Pointer)

The %rip register is the instruction pointer, which points to the next instruction to be executed. Unlike all the registers that we have shown so far, programs cannot write directly to %rip.

Definition 4.12 (Notation for Accessing Lower Bytes of Registers)

Sometimes, we need a more fine grained control of these registers, and x86-64 provides a way to access the lower bits of the 64 bit registers. We can visualize them with the diagram below.




Figure 19: The names that refer to subsets of register %rax.

A complete list is shown below.

| 64-bit Register | 32-bit Register | Lower 16 Bits | Lower 8 Bits |
|-----------------|-----------------|---------------|--------------|
| %rax | %eax | %ax | %al |
| %rbx | %ebx | %bx | %bl |
| %rcx | %ecx | %cx | %cl |
| %rdx | %edx | %dx | %dl |
| %rdi | %edi | %di | %dil |
| %rsi | %esi | %si | %sil |
| %rsp | %esp | %sp | %spl |
| %rbp | %ebp | %bp | %bpl |
| %r8 | %r8d | %r8w | %r8b |
| %r9 | %r9d | %r9w | %r9b |
| %r10 | %r10d | %r10w | %r10b |
| %r11 | %r11d | %r11w | %r11b |
| %r12 | %r12d | %r12w | %r12b |
| %r13 | %r13d | %r13w | %r13b |
| %r14 | %r14d | %r14w | %r14b |
| %r15 | %r15d | %r15w | %r15b |

Table 1: Register mapping in x86-64 architecture

4.2.2 ARM Assembly Registers

4.3 Addressing Modes

Registers being 8 bytes mean that we can store memory addresses, and if we can store memory addresses, we can access memory, i.e. the values at those memory addresses. There are 4 ways to do this, called **addressing modes**: immediate, normal, displacement, and indexed. When we parse an instruction, its operands are either

- 1. Constant (literal) values
- 2. Registers
- 3. Memory forms

Definition 4.13 (Immediate Addressing)

Immediate addressing is when the operand is a constant value, used with a \$ sign.

Definition 4.14 (Normal Addressing)

Normal addressing is when the operand is a register, used with a % sign and the following syntax. The parentheses are used to dereference the memory address like dereferencing a pointer in C.

$$(R) = Mem[Reg[R]]$$
 (6)

where R is the register name, Reg[R] is the value in the register, and Mem[Reg[R]] is the value in the memory address pointed to by the register.

Definition 4.15 (Displacement Addressing)

When we have a memory address stored in a register, we can add an offset to it to access a different memory address.

$$D(R) = Mem[Reg[R] + D]$$
 (7)

where R is the register name and D is a constant displacement that specifies offset.

Definition 4.16 (Indexed Addressing)

Indexed addressing gives us more flexibility, allowing us to multiply the value in the register by a constant and add it to the value in another register. The general formula is shown as the top, but there are special cases:

where D is a constant displacement of 1, 2, or 4 bytes, Rb is the base register (can be any of 8 integer registers), Ri is the index register (can be any register except rsp), and S is the scale factor (1, 2, 4, or 8).

4.3.1 x86 Assembly Addressing Modes

Example 4.6 (Immediate Addressing)

movq \$0x4, %rax

Example 4.7 (Normal Addressing)

The following example shows the source operand being a memory address, with normal addressing, and the destination operand being a register.

```
movq (%rax), %rbx
```

Example 4.8 (Displacement Addressing)

The following example shows the source operand being a memory address and the destination operand being a register. They are both addressed normally.

```
movq 8(%rdi), %rdx
```

Example 4.9 (Indexed Addressing)

The following shows the source operand being a memory address and the destination operand being a register. Say that %rdx = 0xf000 and %rcx = 0x0100. Then

$$0x80(,%rdx,2) = Mem[2*0xF000 + 0x80] = Mem[0x1E080]$$
 (8)

We see that

```
movq 0x100(%rdi, %rsi, 8), %rdx
```

4.3.2 ARM Assembly Addressing Modes

4.4 Instructions

Now that we've gotten a sense of what these registers are and some commonalities between them, let's do some operations on them with instructions.

Definition 4.17 (Instruction)

An instruction is a single line of assembly code. It consists of some instruction followed by its (one or more) operands. The instruction is a mnemonic for a machine language operation (e.g. mov, add, sub, jmp, etc.). The size specifier can be appended to this instruction mnemonic to specify the size of the operands.

- 1. **b** (byte) for 1 byte
- 2. w (word) for 2 bytes
- 3. I (long) for 4 bytes
- 4. **q** (quad word) for 8 bytes

Note that due to backwards compatibility, word means 2 bytes in instruction names. Furthermore, the maximum size is 8 bytes since that is the size of each register in x86_64. An operand can be of 3 types, determined by their **mode of access**:

- 1. Immediate addressing is denoted with a \$ sign, e.g. a constant integer data \$1.
- 2. Register addressing is denoted with a % sign with the following register name, e.g. %rax.
- 3. Memory addressing is denoted with the hexadecimal address in memory, e.g. 0x034AB.

Like higher level programming languages, we can perform operations, do comparisons, and jump to different parts of the code. Instructions can be generally categorized into three types:

1. **Data Movement**: These instructions move data between memory and registers or between the registery and registery. Memory to memory transfer cannot be done with a single instruction.

```
%reg = Mem[address]  # load data from memory into register
2 Mem[address] = %reg  # store register data into memory
```

2. Arithmetic Operation: Perform arithmetic operation on register or memory data.

3. **Control Flow**: What instruction to execute next both unconditional and conditional (if statements) ones. With if statements, loops can then be defined.

```
jmp label  # jump to label
je label  # jump to label if equal
jne label  # jump to label if not equal
jg label  # jump to label if greater
jl label  # jump to label if less
call label  # call a function
ret  # return from a function
```

Now unlike compiled languages, which are translated into machine code by a compiler, assembly code is translated into machine code through a two-step process. First, we **assemble** the assembly code into an **object file** by an **assembler**, and then we **link** the object file into an executable by a **linker**. Some common assemblers are **NASM** (Netwide Assembler) and **GAS/AS** (GNU Assembler), and common linkers are **ld** (GNU Linker) and **lld** (LLVM Linker), both installable with **sudo pacman -S nasm ld**.

4.4.1 Moving and Arithmetic

Again, it is more important to have a general feel of what instructions every assembly language should and get the ideas down rather than the syntax. We list them here, beginning with simply moving.

```
Definition 4.18 (Moving)
```

Next we want to have some sort of arithmetic to do calculations and to compare values.

```
Definition 4.19 (Arithmetic Operations)
```

4.4.2 Conditionals

```
Definition 4.20 (Conditionals)
```

4.4.3 Control Transfer on Stack

These are really the three basic functions needed to do anything in assembly, but let's talk about an important implementation called the **control transfer**. Say that you want to compute a function.

1. Then we must retrieve the data from the memory.

- 2. We must load it into our registers in the CPU and perform some computation.
- 3. Then we must store the data back into memory.

Let's begin with a refresher on how the call stack is managed. Recall that %rsp is the stack pointer and always points to the top of the stack. The register %rbp represents the base pointer (also known as the frame pointer) and points to the base of the current stack frame. The stack frame (also known as the activation frame or the activation record) refers to the portion of the stack allocated to a single function call. The currently executing function is always at the top of the stack, and its stack frame is referred to as the active frame. The active frame is bounded by the stack pointer (at the top of stack) and the frame pointer (at the bottom of the frame). The activation record typically holds local variables for a function.




Figure 20: The current active frame belongs to the callee function (fname). The memory between the stack pointer and the frame pointer is used for local variables. The stack pointer moves as local values are pushed and popped from the stack. In contrast, the frame pointer remains relatively constant, pointing to the beginning (the bottom) of the current stack frame. As a result, compilers like GCC commonly reference values on the stack relative to the frame pointer. In Figure 1, the active frame is bounded below by the base pointer of fname, which is stack address 0x418. The value stored at address 0x418 is the "saved" "rbp value (0x42c), which itself is an address that indicates the bottom of the activation frame for the main function. The top of the activation frame of main is bounded by the return address, which indicates where in the main function program execution resumes once the callee function fname finishes executing.

Once we have done this we are really done. Formally, this is called Turing complete (?).

Definition 4.21 (Control Transfers)

We list some.

- 1. Push
- 2. Pop
- 3. Call to call a function
- 4. Return to return from a function
- 5. Continue
- 6. Get out of stack with leave.

Example 4.10 (Control Transfer Example)

We show this with a minimal example with psuedocode.

4.4.4 Multiple Functions

Now what happens if there are multiple functions calling each other? Take a look at the following example with two functions.

Example 4.11 (Multiple Functions Example)

There is a bit of a concern here from the previous example. The main function had two functions that returned two values. As the subfunction stack frame is removed from the stack, the return value is stored in the %rax register. If another function is called right after, then the return value of the second function will overwrite that of the previous one. This was not a problem in the previous example since the return value of the assign function was not used. However, if it was, then the return value of the adder function would have overwritten it. This is known as register saving.

1. For **caller-saved registers**, the caller function is responsible for saving the value of the register before calling a function and restoring it after the function returns. The caller should save values in its stack frame before calling the callee function, e.g. by pushing all the return values of each callee in the caller stack frame. Then it will restore values after the call.

Therefore, if we have a set of registers {%reg}, the caller must take everything and push them in the caller stack frame. Then it will restore them after the call.

2. For **callee-saved registers**, it is the callee's responsibility to save any data in these registers before using the registers.

Therefore, if we have a set of registers {%reg}, then inside the callee stack frame, the callee must take everything and push them in the callee stack frame. Once it computes the final return value, then it will restore all the saved register values from the callee stack frame back into the registers for the caller to use.

Ideally, we want *one* calling convention to simply separate implementation details between caller and callee. In general, however, neither is best. If the caller isn't using a register, then caller-save is better, and if callee doesn't need a register, then callee-save is better. If we do need to save, then callee save generally makes smaller programs, so we compromise and use a combination of both caller-save and callee-save.

4.4.5 x86-64 Instructions

Let's talk about moving instructions first.

Definition 4.22 (mov)

Let's talk about the mov instruction which copies data from the source to the destination (the data in the source still remains!) and has the syntax

- 1. The source can be a register (%rsi), a value (\$0x4), or a memory address (0x4).
- 2. The destination can be a register or a memory address.
- 3. The _ is defined to be one of the size operands, which determine how big the data is. For example, we can call movq to move 8 bytes of data (which turns about to be the maximum size of a register).

A good diagram to see is the following:

| Imm | Source | Dest | Src, Dest | C Analog |
|---|--------|------|-------------------|---------------------------------|
| | | - | | |
| Mem Reg movq (%rax), %rdx var_d = *p_a; | | | | var_d = var_a; *p_d = var_a; |
| | Mem | Reg | movq (%rax), %rdx | var_d = *p_a; |

Even with just the mov instruction, we can look at a practical implementation of a C program in Assembly.

Example 4.12 (Swap Function)

Let us take a look at a function that swaps two integers. Let's see what they do.

- 1. In C, we dereference both xp and yp (note that they are pointers to longs, so they store 8 bytes), and assign these two values to two temporary variables. Then, we assign the value of yp to xp and the value of xp to yp.
- 2. In Assembly, we first take the registers %rdi and %rsi, which are the 1st and 2nd arguments of the function, dereference them with the parantheses, and store them in the temporary registers %rax and %rdx. Then, we store the value of %rdx into the memory address of %rdi and the value of %rax into the memory address of %rsi. Note that the input values (the actual of)

Definition 4.23 (movz and movs)

The movz and movs instructions are used to move data from the source to the destination, but with zero and sign extension, respectively. It is used to copy from a smaller source value to a larger destination, with the syntax

```
movz__ src, dest
movs__ src, dest
```

where the first _ is the size of the source and the second _ is the size of the destination.

- 1. The source can be from a memory or register.
- 2. The destination must be a register.

Example 4.13 (Simple example with movz)

Take a look at the code below.

```
novzbq %al, %rbx
```

The %al represents the last byte of the %rax register. It is 1 byte long. The %rbx register is 8 bytes long, so we can fill in the rest of the 7 bytes with zeros.

```
0x??|0x??|0x??|0x??|0x??|0x??|0xFF ←%rax

0x00|0x00|0x00|0x00|0x00|0x00|0xFF ←%rbx
```

Example 4.14 (Harder example with movs)

Take a look at the code below.

```
novsbl (%rax), %ebx
```

You want to move the value at the memory address in %rax into %ebx. Since the source size is set to 1 byte, you take that byte, say it is 0x80, from the memory, and then sign extend it (by a size of 4 bytes!) into %ebx. Note that therefore, the first four bytes of %rbx will not be affected since it's not a part of %ebx. An exception to this is that in x86-64, any instruction that generates a 32-bit long word value for a register also sets the high-order 32 bits of the register to 0, so this ends up clearing the first 4 bytes to 0.

```
0x00 0x00 0x7F 0xFF 0xC6 0x1F 0xA4 0xE8 ←%rax

... 0x?? 0x?? 0x80 0x?? 0x?? 0x?? ... ← MEM

0x00 0x00 0x00 0x00 0xFF 0xFF 0xFF 0x80 ←%rbx
```

Now we can talk about control transfer. Say that you have the following C and Assembly code.

```
int add(int x) {
                                                        add:
    return x + 2;
                                                           movq %rdi, %rax
2
3
                                                           addq $2, %rax
                                                           ret
  int main() {
                                                        main:
    int a = 2;
                                                           movq $3, $rdi
    int b = add(a);
                                                           call add
                                                           movq $0, %rax
     return 0;
```

Figure 21: A simple function.

If you go through the instructions, you see that in main, you first move \$3 into the %rdi register. Then, you call the add function, and within it you also have the %rdi register. This is a conflict in the register, and we don't want to simply overwrite the value of %rdi in the main function. Simply putting it to another register isn't a great idea since we can't always guarantee that it will be free. Therefore, we must use the memory itself.

Recall the stack, which we can think of as a giant array in which data gets pushed and popped in a last-infirst-out manner. The stack is used to store data and return addresses, and is used to manage function calls. Visually, we want to think of the elements getting pushed in from the bottom (upside down) towards lower memory addresses.

Definition 4.24 (Stack Pointer)

Note that every time we want to push or pop something from the stack, we must know *where* to push or pop it. This is where the **stack pointer** comes in. It is a special register that always points to the top of the stack, and is used to keep track of the stack.

Definition 4.25 (Push and Pop)

The push and pop instructions are used to push and pop data onto and off the stack, respectively.

- 1. When we push the source, we fetch the value at the source and store it at the memory address pointed to by the stack pointer **%rsp**. Then, we decrement **%rsp** by 8.
- 2. When we pop from the stack, we fetch the value at the memory address pointed to by the stack pointer **%rsp** and store it in the destination. Then, we increment **%rsp** by 8.

Note that no matter what the size of the operand, we always subtract 8 from the stack pointer. This is because the stack grows downwards, and we want to make sure that the next element is pushed into the next available space.

Note that the register **%rsp** is the stack pointer, which points to the top of the stack. The stack is used to store data and return addresses, and is used to manage function calls.

Definition 4.26 (Push and Pop)

The push and pop instructions are used to push and pop data onto and off the stack, respectively.

The _ is a size operand, which determines how big the data is.

Definition 4.27 (Call and Ret)

The call instruction pushes the return address onto the stack and jumps to the function. The ret instruction pops the return address from the stack and jumps to it.

We also talked about how there is instruction code that is even below the stack that is stored. This is where all the machine code/assembly is stored, and we want to find out where we are currently at in this code. This is done with the program counter.

Definition 4.28 (Program Counter, Instruction Pointer)

The **program counter**, or **instruction pointer**, is a special register **rip** that points to the current instruction in the program. It is used to keep track of the next instruction to be executed.

Let's go through one long example to see in detail how this is calculated.

Example 4.15 (Evaluating a Function)

Say that we have the following C code.

```
int adder2(int a) {
   return a + 2;
}

int main() {
   int x = 40;
   x = adder2(x);
   printf("x is: %d\n", x);
   return 0;
}
```


When we compile this program, we can view its full assembly code by calling objdump -d a.out. The output is quite long, so we will focus on the instruction for the adder2 function.

```
0000000000400526 <adder2>:
400526:
               55
                                                %rbp
                                         push
400527:
               48 89 e5
                                         mov
                                                %rsp,%rbp
40052a:
               89 7d fc
                                                %edi,-0x4(%rbp)
                                         mov
40052d:
               8b 45 fc
                                                -0x4(%rbp), %eax
                                         mov
400530:
               83 c0 02
                                                $0x2, %eax
                                         add
400533:
               5d
                                                %rbp
                                         pop
400534:
               сЗ
                                         retq
```

Figure 22: The output of objdump for the adder2 function. The leftmost column represents the addresses (in hex) of where the actual instructions lie. The second column represents the machine code that is being executed. The third column represents the assembly code.

Note some things. Since adder2 is taking in an integer input value, we want to load it into the lower 32 bits (4 bytes) of the %rdi register, which is the first parameter. So we use %edi. Likewise for the return value, we want to output an int so we use %eax rather than %rax. Let's go through some of the steps.


1. By the time we get into calling adder2, we can take a look at the relevant registers.




- (a) First, the **%eax** is filled with garbage, which are leftovers from previous programs that haven't been overwritten yet.
- (b) Second, the %edi=0x28 since we have set x=40 in main, before calling adder2, so it lingers on.
- (c) %rsp=0xd28 since that is where the top of the stack is.
- (d) %rbp=0xd40
- (e) %rip=0x526 since that is where we are currently at in our instruction (we are about to do

it, but haven't done it yet).


2. When we execute the first line of code, we simply push the value at %rbp into the stack. The top of the stack gets decremented by 8 and the value at %rbp is stored there. This means that the top of the stack is at %rsp=0xd20 and the next instruction will be at %rip=0x527.




3. The reason we have pushed %rbp onto the stack is that we want to save it before it gets overwritten by this next execution. We basically move the value of %rsp into %rbp, and the %rip advances to the next instruction. %rip moves to the next instruction.




4. Now we want to take our first argument %edi and store it in memory. Note that since this is 4 bytes, we can move this value into memory that is 4 bytes below the stack (-0x4(%rbp)). Note that the storing the value of %edi into memory doesn't affect the stack pointer %rsp. As far as the program is concerned, the top of this stack is still address 0xd20.




5. The next instruction simply goes into memory 4 bytes below the stack pointer, takes the value there, and stores it into %eax. This is the value of %edi that we just stored. This may seem redundant since we are making a round trip to memory and back to ultimately move the value of %edi into %eax, but compilers are not smart and just follow these instructions.



6. Finally, we add the value \$0x2 to %eax and store it back into %eax.



7. Finally, we pop the value at the top of the stack and store it into %rbp. Note that this is not the value 0x28. It is simply the value that is stored at %rsp=0xd20, which is (%rsp)=0xd40.



Note that the final values in the registers %rsp and %rip are 0xd28 and 0x534, respectively, which are the same values as when the function started executing! This is normal and expected behavior with the call stack, which just stores temporary variable sand data of each function as it executes a program. Once a function completes executing, the stack returns to the state it was in prior to the function call. Therefore, it is common to see the following two instructions at the beginning of a function:

```
push %rbp
mov %rsp, %rbp
```

and the following two at the end of a function

```
pop %rbp retq
```

Now arithemtic operations are quite simple.

Definition 4.29 (Add, Subtract, Multiply)

The add and sub instructions are used to add and subtract data from the destination.

The **imul** instruction is used to multiply data between the source and destination and store it in the destination.

Again the _ is a size operand, which determines how big the data is.

Definition 4.30 (Increment, Decrement)

The inc and dec instructions are used to increment and decrement the value in the destination.

```
inc_ dest
dec_ dest
dest = dest + 1
dec_ dest
```

Definition 4.31 (Negative)

The **neg** instruction is used to negate the value in the destination.

```
neg_ dest = -dest
```

Example 4.16 (Basic Arithmetic Function)

The following represents the same program in C and in assembly. Let's go through each one:

- 1. In C, we first initialize a = 4, then b = 8, add them together to get c, and then return c.
- 2. In Assembly, we move the value 4 to the %rax register, then move the value 8 to the %rbx register, add the two values together to store it into %rax, and then return the value in the %rax register.

```
int main() {
   int a = 4, b = 8;
   int c = a + b;
   return c;
   }
   main:
   movq $4, %rax
   movq $8, %rbx
   addq %rbx, %rax
   ret
   ret
   ret
```

It is slightly different in Assembly since rather than storing 4 in some intermediate register, we immediately store it in the return register. In a way it is more optimized, and this is what the compiler does for you so that as few registers are used.

A shorthand way to do this is with lea, which stands for load effective address.

Definition 4.32 (Load Effective Address)

The **lea** instruction is used to load the effective address of the source into the destination. For now, we will focus on the arithmetic operations that it can do

This is useful for doing arithmetic operations on the address of a variable.

Definition 4.33 (Bitwise)

The **and**, **or**, **xor**, and **not** instructions are used to perform bitwise operations on the source and destination.

```
and src, dest dest = dest & src or src, dest dest = dest | src xor src, dest dest = dest \hat{s}rc neg dest dest = -dest not dest dest = \simdest
```

Definition 4.34 (Arithmetic and Logical Bit Shift)

The sal arithmetic instruction is used to shift the bits of the destination to the left by the number of bits specified in the source. The shr instruction is used to shift the bits of the destination to the right by the number of bits specified in the source.

```
sal src, dest dest = dest « src
shr src, dest dest = dest » src
```

The sar instruction is used to shift the bits of the destination to the right by the number of bits specified in the source, and fill the leftmost bits with the sign bit. The shl instruction is used to shift the bits of the destination to the left by the number of bits specified in the source, and fill the rightmost bits with zeros.

Example 4.17 (Harder Arithmetic Example)

The following two codes are equivalent.

```
long arith(long x, long y, long z) {
                                                    arith:
                                                      \# rax/t1 = x + y
    long t1 = x + y;
    long t2 = z + t1;
                                                      leaq (%rdi, %rsi), %rax
3
    long t3 = x + 4;
                                                      \# rax/t2 = z + t1
    long t4 = y * 48;
                                                      addq %rdx, %rax
    long t5 = t3 + t4;
                                                      \#rdx = 3 * y
                                                      leaq (%rsi, %rsi, 2), %rdx
    long rval = t2 * t5;
    return rval;
                                                      \#rdx/t4 = (3*y) * 16
  }
                                                      salq $4, %rdx
9
                                                      \#rcx/t5 = x + t4 + 4
                                                      leag 4(%rdi, %rdi), %rcx
12
                                                      \# rax/rval = t5 * t2
                                                      imulg %rcx, %rax
                                                      ret
```

The final thing in our list is condition codes.

Sometimes, we want to move (really copy) some value to another register if some condition is met. This is where we use conditional moves. These conditions are met by the flags register, which is a special register that stores the status of the last operation. It is the value of these flags that determine whether all future conditional statements are met in assembly.

Definition 4.35 (Condition Code Flags)

The flags register in the x86 CPU keeps 4 condition code flag bits internally. Think of these as status flags that are *implicitly* set by the most recent arithmetic operation (think of it as side effects). Note that condition codes are NOT set by lea or mov instructions!

- 1. **Zero Flag**: if the last operation resulted in a zero value.
- 2. Sign Flag: if the last operation resulted in a negative value (i.e. the most significant bit is 1).
- 3. **Overflow Flag**: if the last operation resulted in a signed overflow.
- 4. Carry Flag: if the last operation resulted in a carry out of the most significant bit, i.e. an unsigned overflow.

Every operation may or may not changes these flags to test for zero or nonzero, positive or negative,

or overflow conditions, and combinations of these flags express the full range of conditions and cases, e.g. for signed and unsigned values.

Example 4.18 (Zero Flag)

If the code below was just run, then ZF would be set to 1.

```
1 movq $2, %rax
2 subq $2, %rax
```

Example 4.19 (Sign Flag)

If the code below was just run, then SF would be set to 1.

```
1 movq $2, %rax
2 subq $4, %rax
```

Example 4.20 (Overflow Flag)

If either code below was just run, then OF would be set to 1.

Example 4.21 (Carry Flag)

If the code below was just run, then CF would be set to 1.

```
movq $0xffffffffffffff, %rax addq $1, %rax
```

This is because the result is 0x0, which is a carry out of the most significant bit and an unsigned overflow.

It would be tedious to always set these flags manually, so there are two methods that can be used to *explicitly* set these flags.

Definition 4.36 (Compare)

The **cmp** instruction is used to perform a subtraction between the source and destination, and set the flags accordingly, but it does not store the result.

```
cmp_ src, dest dest - src
```

The following flags are set if the conditions are met:

- 1. $\mathbf{ZF} = \mathbf{1}$ if dest == src
- 2. SF = 1 if dest < src (MSB is 1)
- 3. $\mathbf{OF} = \mathbf{1}$ if signed overflow

4. $\mathbf{CF} = \mathbf{1}$ if unsigned overflow

Definition 4.37 (Test)

The **test** instruction is used to perform a bitwise AND operation between the source and destination, and set the flags accordingly.

dest & src

The following flags are set if the conditions are met. Note that you can't have carry out (CF) or overflow (OF) if these flags are set.

- 1. $\mathbf{ZF} = \mathbf{1}$ if dest & src == 0
- 2. SF = 1 if dest & src < 0 (MSB is 1)

Example 4.22 (Compare)

Assuming that %al = 0x80 and %bl = 0x81, which flags are set when we execute cmpb %al, %bl? Well we must first compute

%bl - %al =
$$0x81$$
 - $0x80$ = $0x81$ + $\sim 0x80$ + 1 = $0x81$ + $0x7F$ + 1 = $0x101$ = $0x01$ (10)

- 1. CF=1 since the result is greater than 0xFF (i.e. larger than byte)
- 2. ZF=0 since the result is not 0
- 3. SF=0 since the MSB is 0, i.e. there is unsigned overflow
- 4. OF=0 since there is no signed overflow

For conditional moves and jumps later shown, it basically uses these explicit sets and always compares them to 0. We will see what this means later.

Finally, we can actually set a byte in a register to 1 or 0 based on the value of a flag.

Definition 4.38 (Set)

We can then talk about conditional moves and jumps.

Definition 4.39 (Equality with 0)

The test instruction is used to perform a bitwise AND operation between the source and destination, and set the flags accordingly.

dest & src

The sete instruction is used to set the destination to 1 if the zero flag is set, and 0 otherwise.

$$dest = (ZF == 1) ? 1 : 0$$

The cmovne instruction is used to move the source to the destination if the zero flag is not set.

$$dest = (ZF == 0)$$
 ? $src : dest$

Definition 4.40 (Jump)

There are several jump instructions, but essentially they are used to jump to another part of the code. We can use the following mnemonic to jump to a label.

| Letter | Word |
|--------|---------------------------------|
| j | jump |
| n | not |
| e | equal |
| s | signed |
| g | greater (signed interpretation) |
| 1 | less (signed interpretation) |
| a | above (unsigned interpretation) |
| b | below (unsigned interpretation) |

Table 2: Letter to Word Mapping

Figure 23: Mnemonic for Jump Instructions

For completeness, we include all the jump instructions.

| Signed Comparison | Unsigned Comparison | Description |
|-------------------|---------------------|------------------------------------|
| je (jz) | | jump if equal (==) or jump if zero |
| jne (jnz) | | jump if not equal (!=) |
| js | | jump if negative |
| jns | | jump if non-negative |
| jg (jnle) | ja (jnbe) | jump if greater (>) |
| jge (jnl) | jae (jnb) | jump if greater than or equal (>=) |
| jl (jnge) | jb (jnae) | jump if less (<) |
| jle (jng) | jbe (jna) | jump if less than or equal (<=) |

Table 3: Comparison Instructions in Assembly

Figure 24: All jump instructions

Definition 4.41 (int)

The int instruction is used to generate a software interrupt. It is often used to invoke a system call.

Definition 4.42 (ret)

The ret instruction is used to return from a function. It returns the value in the %rax register.

Now we can have a basic idea of how if statements can be used as a sequence of conditionals and jump operators. Let's first look at the **goto** version of C.

Definition 4.43 (Goto Syntax)

The goto version processes instructions sequentially as long as there is no jump. This is useful because compilers translating code into assembly designate a jump when a condition is true. Contrast this behavior with the structure of an if statement, where a "jump" (to the else) occurs when conditions are not true. The goto form captures this difference in logic.

```
int getSmallest(int x, int y) {
                                                        int getSmallest(int x, int y) {
     int smallest;
                                                           int smallest;
     if (x > y) \{ //if (conditional) \}
                                                           if (x \le y) \{ //if (!conditional) \}
       smallest = y; //then statement
                                                             goto else_statement;
       smallest = x; //else statement
                                                           smallest = y; //then statement
                                                           goto done;
     return smallest;
9
                                                        else statement:
                                                           smallest = x; //else statement
                                                     12
                                                     13
                                                        done:
                                                     14
                                                           return smallest;
14
                                                        }
```

Figure 25: C vs GoTo code of the same function. While GoTo code allows us to view C more like assmebly, it is generally not readable and is not considered best practice.

Now let's see how if statements are implemented by taking a look at this function straight up in assembly.

```
int getSmallest(int x, int y) {
                                            Dump of assembler code for function getSmallest:
                                                                    %edi,-0x14(%rbp)
    int smallest;
                                            0x40059a <+4>:
                                                             mov
    if (x > y ) { //if (conditional)
                                            0x40059d <+7>:
                                                                    %esi,-0x18(%rbp)
                                                             mov
       smallest = y; //then statement
                                            0x4005a0 <+10>: mov
                                                                     -0x14(%rbp), %eax
    }
                                                                     -0x18(%rbp),%eax
                                            0x4005a3 <+13>:
                                                             cmp
    else {
                                            0x4005a6 <+16>:
                                                             jle
                                                                     0x4005b0 <getSmallest+26>
                                                                     -0x18(%rbp), %eax
      smallest = x; //else statement
                                            0x4005a8 <+18>:
                                            0x4005ae <+24>:
                                                                     0x4005b9 <getSmallest+35>
                                                             jmp
                                                                     -0x14(%rbp), %eax
    return smallest;
                                            0x4005b0 <+26>:
                                                             mov
                                         9
9
                                            0x4005b9 <+35>:
                                                                     %rbp
  }
                                                             pop
                                            0x4005ba <+36>: retq
```

Figure 26: Assembly code of a simple if statement

Again, note that since we are working with int types, the respective parameter registers are %edi and %esi, the respective lower 32-bits of the registers %rdi and %rsi. Let's walk through this again.

- 1. The first mov instruction copies the value located in register %edi (the first parameter, x) and places it at memory location %rbp-0x14 on the call stack. The instruction pointer (%rip) is set to the address of the next instruction, or 0x40059d.
- 2. The second mov instruction copies the value located in register %esi (the second parameter, y) and places it at memory location %rbp-0x18 on the call stack. The instruction pointer (%rip) updates to point to the address of the next instruction, or 0x4005a0.

- 3. The third mov instruction copies x to register %eax. Register %rip updates to point to the address of the next instruction in sequence.
- 4. The cmp instruction compares the value at location %rbp-0x18 (the second parameter, y) to x and sets appropriate condition code flag registers. Register %rip advances to the address of the next instruction, or 0x4005a6.
- 5. The jle instruction at address 0x4005a6 indicates that if x is less than or equal to y, the next instruction that should execute should be at location <getSmallest+26> and that %rip should be set to address 0x4005b0. Otherwise, %rip is set to the next instruction in sequence, or 0x4005a8.

With the cmov instruction, this can be a lot shorter. With the gcc compiler with level 1 optimizations turned on, we can see that a lot of redundancies are turned off.

Figure 27: Compiled with gcc -O1 -o getSmallest getSmallest.c

Like if statements, loops in assembly can be implementing using jump functions that revisit some instruction address based on the result on an evaluated condition. Let's take a look at a basic loop function.

```
int sumUp(int n) {
                                                         Dump of assembler code for function sumUp:
     int total = 0;
                                                         0x400526 <+0>:
                                                                           push
                                                                                   %rbp
     int i = 1;
                                                         0x400527 <+1>:
                                                                                   %rsp,%rbp
                                                                           mov
                                                         0x40052a <+4>:
                                                                                   \%edi,-0x14(\%rbp)
                                                                           mov
                                                                                   $0x0,-0x8(%rbp)
     while (i <= n) {
                                                         0x40052d <+7>:
                                                                           mov
       total += i;
                                                                                   $0x1,-0x4(%rbp)
                                                         0x400534 <+14>:
                                                                           mov
                                                                                   0x400547 < sumUp+33>
       i++;
                                                         0x40053b <+21>:
                                                                           jmp
     }
                                                         0x40053d <+23>:
                                                                                   -0x4(\%rbp), %eax
                                                                           mov
                                                                                   %eax,-0x8(%rbp)
     return total;
                                                         0x400540 <+26>:
                                                                           add
9
                                                         0x400543 <+29>:
                                                                                   $0x1,-0x4(%rbp)
                                                                           add
                                                         0x400547 <+33>:
                                                                                   -0x4(\%rbp),\%eax
                                                                           mov
                                                         0x40054a <+36>:
                                                                                   -0x14(\%rbp), \%eax
                                                                           cmp
                                                         0x40054d <+39>:
                                                                                   0x40053d < sumUp+23>
                                                                           jle
                                                         0x40054f <+41>:
                                                                                   -0x8(\%rbp),\%eax
                                                         0x400552 <+44>:
                                                                                   %rbp
                                                                           gog
                                                         0x400553 <+45>:
                                                                           retq
16
```

Figure 28: Simple loop function in C and assembly.

Finally, we want to let the reader know the convention of calle and caller saved registers. The compiler tries to pick these registers, and by convention in x86, we have the following.

| %rax | Return value - Caller saved | %r8 | Argument #5 - Caller saved |
|------|-----------------------------|------|----------------------------|
| %rbx | Callee saved | %r9 | Argument #6 - Caller saved |
| %rcx | Argument #4 - Caller saved | %r10 | Caller saved |
| %rdx | Argument #3 - Caller saved | %r11 | Caller Saved |
| %rsi | Argument #2 - Caller saved | %r12 | Callee saved |
| %rdi | Argument #1 - Caller saved | %r13 | Callee saved |
| %rsp | Stack pointer | %r14 | Callee saved |
| %rbp | Callee saved | %r15 | Callee saved |

Figure 29: Caller save and callee save registers.

So far, we've traced through simple functions in assembly. In this section, we discuss the interaction between multiple functions in assembly in the context of a larger program. We also introduce some new instructions involved with function management.

Definition 4.44 (Leave)

The **leave** instruction is used to deallocate the current stack frame. For example, the leaveq instruction is a shorthand that the compiler uses to restore the stack and frame pointers as it prepares to leave a function. When the callee function finishes execution, leaveq ensures that the frame pointer is restored to its previous value. It is equivalent to the following two instructions:

leaveq movq %rbp, %rsp popq %rbp

Definition 4.45 (Call and Return)

The **call** instruction is used to call a function and the **ret** to return from a function. The callq and retq instructions play a prominent role in the process where one function calls another. Both instructions modify the instruction pointer (register %rip).

1. When the caller function executes the callq instruction, the current value of %rip is saved on the stack to represent the return address, or the program address at which the caller resumes executing once the callee function finishes. The callq instruction also replaces the value of %rip with the address of the callee function.

callq addr <fname> push %rip mov addr, %rip

2. The retq instruction restores the value of %rip to the value saved on the stack, ensuring that the program resumes execution at the program address specified in the caller function. Any value returned by the callee is stored in %rax or one of its component registers (e.g., %eax). The retq instruction is usually the last instruction that executes in any function.

retq pop %rip

Let's work through an example to solidify our knowledge.

Example 4.23 (Calling Functions in Assembly)


Let's take the following code and trace through main.

```
0000000000400526 <assign>:
   #include <stdio.h>
                                                                        push
                               400526:
                                              55
                                                                               %rbp
   int assign(void) {
                               400527:
                                              48 89 e5
                                                                               %rsp,%rbp
                                                                        mov
       int y = 40;
                               40052a:
                                              c7 45 fc 28 00 00 00
                                                                               $0x28,-0x4(%rbp)
                                                                        movl
                               400531:
                                              8b 45 fc
                                                                               -0x4(%rbp),%eax
       return y;
                                                                        mov
                               400534:
                                              5d
                                                                               %rbp
6
                                                                        pop
                               400535:
                                              сЗ
                                                                        retq
   int adder(void) {
                             0000000000400536 <adder>:
       int a;
9
                               400536:
                                              55
       return a + 2;
                                                                        push
                                                                               %rbp
                               400537:
                                              48 89 e5
   }
                                                                               %rsp,%rbp
                                                                        mov
                               40053a:
                                              8b 45 fc
                                                                               -0x4(\%rbp), \%eax
                                                                        mov
   int main(void) {
                               40053d:
                                              83 c0 02
                                                                        add
                                                                               $0x2, %eax
                               400540:
       int x;
                                              5d
                                                                               %rbp
14
                                                                        pop
       assign();
                               400541:
                                              сЗ
                                                                        retq
       x = adder();
       printf("x is:
                             0000000000400542 <main>:
        d\n'', x);
                               400542:
                                              55
                                                                               %rbp
                                                                        push
       return 0;
                               400543:
                                              48 89 e5
                                                                               %rsp,%rbp
                                                                        mov
   }
                               400546:
                                              48 83 ec 10
                                                                        sub
                                                                               $0x10, %rsp
                               40054a:
                                              e8 e3 ff ff ff
                                                                               400526 <assign>
                                                                        callq
                                                                               400536 <adder>
                               40054f:
                                              e8 d2 ff ff ff
                                                                        callq
                               400554:
                                              89 45 fc
                                                                               %eax,-0x4(%rbp)
                                                                        mov
                               400557:
                                              8b 45 fc
                                                                               -0x4(%rbp), %eax
                                                                        mov
                               40055a:
                                              89 c6
                                                                               %eax,%esi
                                                                        mov
                               40055c:
                                              bf 04 06 40 00
                                                                               $0x400604, %edi
                                                                        mov
                               400561:
                                              ъ8 00 00 00 00
                                                                               $0x0, %eax
                                                                        mov
                                              e8 95 fe ff ff
                               400566:
                                                                        callq
                                                                               400400
                                  cprintf@plt>
                               40056b:
                                              ъ8 00 00 00 00
                                                                               $0x0, %eax
                                                                        mov
                               400570:
                                              с9
                                                                        leaveq
                               400571:
                                              с3
                                                                        retq
```


Figure 30: C code and its assembly equivalent. Main function calls two other functions.

Let's trace through what happens here in detail. This will be long.


1. %rbp is the base pointer that is initialized to something. Before we even begin main, say that we have the following initializations, where %eax, %edi is garbage. %rsp denotes where on the stack we are right before calling to main, %rbp is the base pointer to the current program, and %rip should be the address of the first instruction in main. Again since we work with integers we use the lower 32-bits of the registers. %rip now points to the next instruction.




2. Now we start the main function. By calling main, the base pointer **%rbp** of the stack outside of the main frame will be overwritten by the base of the main stack frame, so we must save it for when main is done. Therefore, we push it onto the stack where **%rsp** is pointing. **%rip** now points to the next instruction.




3. Then we actually change the location of the base pointer to the top of the stack, which now includes the first instruction in main.




4. Now we manually change the stack pointer and have it grow by two bytes (0x10). Therefore, %rsp is decremented by 0x10 and %rip points to the next instruction at 0x54a.




5. Now the next instruction pointed at by %rip is the callq instruction, which tells to go to the address of the assign function. We by default first update %rip to point to the next instruction at 0x55f. However, this should not be the actual next instruction that we execute since we are calling another function. Rather, we want to update %rip to address 0x526 where assign is located at, but after completion we also want to know that we want to execute the instruction after it at address 0x55f. Therefore, we should save address 0x55f onto the stack and then update %rip to point to 0x526. This is what we refer to as a return address.




6. %rip is incremented to the next address. We step into the assign function, which is now a new stack frame, so the first thing we do is save the base pointer of the main stack frame onto the stack since we must immediately update it with the base pointer of the assign stack frame, which is where %rsp is pointing to.




7. %rip is incremented to the next address. We then update the base pointer to the top of the stack.




8. Now we want to move the number 0x28 (40) into the memory location -0x4(%rbp) of the stack, which is 4 bytes above the frame pointer, which is also the stack pointer. It is common that the frame pointer is used to reference locations on the stack. Note that this does not update the stack pointer.



9. Now we take the same address where we stored 0x28 to and move it into %eax, effectively loading 40 onto the return value.




10. We see that we will return this value soon, but before we do, we want to make sure that when the assign stack frame gets deleted (not really, but overwritten), we want to restore the base pointer of the main stack frame. We have already saved this before at "rsp, which hasn't changed since we only worked with displacements from the base pointer. We retrieve the main stack pointer data and load it back into "rbp. Note that this increments "rsp by 8 bytes, shrinking the stack, and we are technically out of the assign stack frame.




11. Note that at this point, since "rbp was popped off, the next value that is at the top of the stack


is the address %rip that we store earlier, which points to the next execution in main. When retq executes, this value at the top of the stack is popped into %rip, allowing main to continue executing within the main stack frame. Note that the return value is stored in %eax.




12. Now we execute the next instruction in %rip which is a call to the adder function. %rip is automatically updated to the next address at 0x554, but since this is a callq instruction, we first want to store this %rip into the stack so we can come back to it, and then update %rip to the first instruction in adder, which is address 0x536.




13. Since we are in the adder function, this creates a new stack frame and we must update %rbp. Again, we don't want to overwrite the base pointer of main, so we save it onto the stack by pushing %rbp.




14. Then we update %rbp to the current stack pointer.




15. This part is a bit tricky. Note that the value of 0x28 still lives at 0xd1c, which is conveniently at address -0x4(%rbp). Therefore, when we call int a; in that corresponding line in adder, we can actually add 2 to it, though it seems like there was no value assigned to it. This is just a trick though. So, we can take these remnant value and store it into %eax.




17. Now we are almost done, so we pop the base pointer of the main stack frame, at 0xd40, back into %rbp.




18. We now return the value in <code>%eax</code> and pop the base pointer of the adder stack frame, which simply updates the instruction pointer <code>%rip</code> back to the next instruction in main. This is equivalent to pop <code>%rip</code>, which is equivalent to moving the stack pointer <code>%rsp</code> into <code>%rip</code> and then shrinking the stack by 8 bytes <code>subq \$8, %rsp</code>.




19. Now it is relatively straightforward since we do the rest in main (except for the print statement). The current value in <code>%eax</code> represents the return value of adder. We want to put this in the variable x, which we have already allocated some memory for right above the base pointer in the main stack frame. We move it there. Note that right after, it places this right back into




20. the mov instruction at address 0x55a copies the value in %eax (or 0x2A) to register %esi, which is the 32-bit component register associated with %rsi and typically stores the second parameter to a function. We can see why since this will be put into a print statement, which is a function, and x = %esi is the second argument of printf.




21. Now we want to retrieve the first argument of the print function. The address at \$0x400604 is some address in the code segment memory that holds the string "x is %d\n".






24. The print function might have returned something, but we don't care. We want to main function to return 0, so we move 0 into %eax.



25. Finally we execute leaveq, which prepares the stack for returning from the function call. It essentially moves the base pointer back to the stack pointer and then pops the base pointer off the stack. The new %rbp is the original base pointer of whatever was outside the main function, 0x830.



We have omitted the details of caller and callee saved registers, but they do exist and are important for the general implementations.

For arrays, there's not anything new here. Let's go over some code and follow through it.

```
int sumArray(int *array, int length) {
   int i, total = 0;
   for (i = 0; i < length; i++) {
      total += array[i];
   }
   return total;
   }
}</pre>
```

This function takes the address of an array and the length of it and sums up all the elements in the array.

```
0x400686 <+0>: push %rbp
                                             # save %rbp
  0x400687 <+1>: mov %rsp,%rbp
                                             # update %rbp (new stack frame)
  0x40068a <+4>: mov %rdi,-0x18(%rbp)
                                             # copy array to %rbp-0x18
  0x40068e <+8>: mov %esi,-0x1c(%rbp)
                                             # copy length to %rbp-0x1c
5 \text{ 0x400691} < +11>: \text{ movl } $0x0, -0x4(\%rbp)
                                                # copy 0 to %rbp-0x4 (total)
                   movl $0x0,-0x8(%rbp)
6 0x400698 <+18>:
                                                # copy 0 to %rbp-0x8 (i)
7  0x40069f <+25>: jmp  0x4006be <sumArray+56> # goto <sumArray+56>
8 0x4006a1 <+27>:
                   mov -0x8(%rbp),%eax
                                                # copy i to %eax
9 0x4006a4 <+30>:
                                                # convert i to a 64-bit integer
                   cltq
0x4006a6 <+32>: lea 0x0(,%rax,4),%rdx
                                                # copy i*4 to %rdx
0x4006ae <+40>: mov -0x18(%rbp),%rax
                                                # copy array to %rax
12 0x4006b2 <+44>:
                   add %rdx,%rax
                                                # compute array+i*4, store in %rax
13 0x4006b5 <+47>:
                   mov (%rax), %eax
                                                # copy array[i] to %eax
                    add %eax,-0x4(%rbp)
                                                # add %eax to total
14 0x4006b7 <+49>:
                    addl $0x1,-0x8(%rbp)
                                                # add 1 to i (i+=1)
15 0x4006ba <+52>:
                                                # copy i to %eax
  0x4006be <+56>:
                    mov -0x8(%rbp),%eax
```

```
0x4006c1 <+59>:
                     cmp
                          -0x1c(%rbp),%eax
                                                 # compare i to length
                     jl
  0x4006c4 <+62>:
                          0x4006a1 <sumArray+27> # if i<length goto <sumArray+27>
                          -0x4(%rbp), %eax
  0x4006c6 <+64>:
                                                 # copy total to %eax
                     mov
                                                  # prepare to leave the function
  0x4006c9 <+67>:
                          %rbp
                     pop
21 0x4006ca <+68>:
                                                 # return total
                     retq
```

4.4.6 ARM Instructions

4.4.7 Buffer Overflows

5 Storage Hierarchy

There are different types of memory, with three key components that we should think about:

- 1. The **capacity**, i.e. amount of data, it can store (how large the water tank is).
- 2. The **latency**, i.e. amount of time it takes for a device to respond with data after it has been instructed to perform a data retrieval operation (how fast the data flows).
- 3. The **transfer rate**, i.e. amount of data that can be moved between the device and main memory (how wide the pipe is).

We must provide a good balance of these three qualities, and also note that there are some physical limitations (i.e. latency cannot be faster than speed of light). The highest level categorization of memory is between primary and secondary storage devices, which simply distinguishes the memory that is directly accessible by the CPU and memory that is not.

Definition 5.1 (Primary Storage)

Primary storage devices are directly accessible by the CPU and are used to store data that is currently being processed. This includes CPU registers, cache memory, and RAM. There are two primary ways:

- 1. **Static RAM (SRAM)** stores data in small electrical circuits (e.g. latches) and is typically the fastest type of memory. However, it is more expensive to build, consumers more power, and occupies more space, limiting the SRAM storage.
- 2. **Dynamic RAM (DRAM)** stores data using electrical components (e.g. capacitors) that hold an electrical charge. It is called *dynamic* because a DRAM system must frequently refresh the charge of its capacitors to maintain a stored value.

| Device | Capacity | Approx. latency | RAM type |
|-------------|------------------|-----------------|----------|
| Register | 4 - 8 bytes | < 1 ns | SRAM |
| CPU cache | 1 - 32 megabytes | 5 ns | SRAM |
| Main memory | 4 - 64 gigabytes | 100 ns | DRAM |

Table 4: Memory hierarchy characteristics

Definition 5.2 (Secondary Storage)

Secondary storage devices are not directly accessible by the CPU and are used to store data that is not currently being processed. This includes hard drives, SSDs, and magnetic tapes.

The figure overviews the different types of memory.




Figure 31: Memory hierarchy.

5.1 Locality

So far, we have abstracted away most of these memory types as a single entity with nearly instantaneous access, but in practice this is not the case. The most simple way is to simply have RAM and our CPU registers, but by introducing more intermediate memory types, we can achieve greater efficiency.

Definition 5.3 (Locality)

Locality is a principle that generally states that a program that accesses a memory location n at time t is likely to access memory location $n + \epsilon$ at time $t + \epsilon$. This principle motivates the design of efficient caches.

- 1. **Temporal locality** is the idea that if you access a memory location, you are likely to access it again soon.
- 2. **Spatial locality** is the idea that if you access a memory location, you are likely to access nearby memory locations soon.

This generally means that if you access some sort of memory, the values around that address is also likely to be accessed and therefore it is wise to store it closer to your CPU.

Example 5.1 (Locality)

Consider the following code.

```
int sum_array(int *array, int len) {
   int i;
   int sum = 0;

for (i = 0; i < len; i++) {
   sum += array[i];
   }
}</pre>
```

```
9 return sum;
10 }
```

- 1. The repetitive nature of the for loop exploits temporal locality. More specifically, the CPU accesses the same memory (stored in variables i, len, sum, array) within each iteration and therefore at similar times.
- 2. The spatial locality is exploited when the CPU accesses memory locations from each element of the array, which are contiguous in memory. Even though the program accesses each array element only once, a modern system loads more than one int at a time from memory to the CPU cache. That is, accessing the first array index fills the cache with not only the first integer but also the next few integers after it too. Exactly how many additional integers get moved depends on the cache's block size. For example, a cache with a 16 byte block size will store array[i] and the elements in i+1, i+2, i+3.

We can see the differences in spatial locality in the following example.

Example 5.2 ()

One may find that simply changing the order of loops can cause a significant speed up in your program. Consider the following code.

```
float averageMat_v1(int **mat, int n) {
                                                  float averageMat_v2(int **mat, int n) {
  int i, j, total = 0;
                                                     int i, j, total = 0;
  for (i = 0; i < n; i++) {</pre>
                                                     for (j = 0; j < n; j++) {
    for (j = 0; j < n; j++) {
                                                       for (i = 0; i < n; i++) {</pre>
      // Note indexing: [i][j]
                                                         total += mat[i][j];
      total += mat[i][j];
    }
                                                     }
  }
                                                     return (float) total / (n * n);
  return (float) total / (n * n);
}
```

Figure 32: Two implementations of taking the total sum of all elements in a matrix.

It turns out that the left hand side of the code executes about 5 times faster than the second version. Consider why. When we iterate through the i first and then the j, we access the values array[i][j] and then by spatial locality, the next few values in the array, which are array[i][j+1], ... are stored in the cache.

- 1. In the left hand side of the code, these next stored values are exactly what is being accessed, and the CPU can access them in the cache rather than having to go into memory.
- 2. In the right hand side of the code, these next values are *not* being accessed since we want to access array[i+1][j], Unfortunately, this is not stored in the cache and so for every n^2 loops we have to go back to the memory to retrieve it.

5.2 RAM

5.3 Caches

Valgrind's cachegrind mode.

5.4 SSD

5.5 HDD

6 Compiling and Linking

Now let's talk about how this compiling actually happens. *Compiling* is actually an umbrella term that is misused. Turning at C file into an executable file consists of multiple intermediate steps, one of which is actually compiling, but the whole series is sometimes referred to as compiling. A more accurate term would be *building*. Before we get onto it, there are two types of compilers.

Definition 6.1 (GCC, CLang)

The two mainstream compilers used is GCC (with the gdb debugger) and Clang (with lldb). For now, the difference is that

- 1. gcc is more established.
- 2. clang is newer and has more features.

A useful flag to know is that we can always specify the name of the (final or intermediary) output file with the -o flag.

Definition 6.2 (Complete Build Process)

To actually turn a C file into an executable file, we need to go through a series of steps. We start off with the C code, which are the .c, .cpp, or .h files.

1. **Preprocessing**: The precompiler step expands the *preprocessor directives* (all the #include and #define statements) and removes comments. This results in a .i file. The preprocessor will replace these macros with the actual code. This results in a .i file.

```
clang/gcc -E main.c -o main.i
```

2. Compiling: We take these and generate assembly code. This results in a .asm or .s file.

```
clang/gcc -S main.c -o main.s
```

3. **Assembler**: We take the assembly code and generate machine code in the form of relocatable binary object code (this is machine code, not assembly). This results in a .o or .obj file.

```
clang/gcc -c main.c -o main.o
```

4. **Linking**: We take these object files and link them together to form an executable file. This results in a .exe or .out file.

The GCC or CLang compiler automates this process for us. For example, gcc -c hello.c generates an object file, taking care of the preprocessing, compiling, and assembling code. Then, gcc hello.o links the object file to generate an executable file.

There are a lot of questions to be asked here, and we will go through them step by step.

6.1 Precompiling Stage

Just like how Python package managers like conda have specific directories that they find package in, the C library also has a certain directory.

Definition 6.3 (Standard Library Directory)

In Linux systems, there are two main directories you look at:

- 1. /usr/include contains the standard C library headers.
- 2. /usr/local/include contains the headers for libraries that you install yourself.

In Mac Silicon, these directories are a little bit more involved. You must first install the xcode command line developer tools, which will then create these directories.

1. The standard C library headers are in

/Library/Developer/CommandLineTools/SDKs/MacOSX*.sdk/usr/include.

In here, we can find all the relevant import files like stdio.h and such. When we precompile, the output .i file represents a precompiled C file. It still has C code, but it has been optimized to

- 1. Remove comments.
- 2. Replace all the #include statements with the actual code.
- 3. Replace all the global variables declared in #define with the actual value.

Between x86 and ARM, there are no significant differences in how C files are precompiled.

Example 6.1 ()

Take a look at the following minimal example.

Figure 33: I have included a main.c file that imports statements from a second.h file.

Now, I run gcc -E main.c -o main.i to generate the precompiled file, which gives me the following.

```
# 1 "main.c"
   # 1 "<built-in>" 1
   # 1 "<built-in>" 3
   # 418 "<built-in>" 3
   # 1 "<command line>" 1
   # 1 "<built-in>" 2
   # 1 "main.c" 2
   # 1 "./second.h" 1
   int subtract(int a, int b) {
     return a - b;
12
   # 2 "main.c" 2
   int add(int x, int y) {
     return x + y;
   }
   int main() {
     int b = 5;
     int c = add(3, b);
     int d = subtract(3, b);
     return 0;
24
   }
```

Figure 34: The precompiled file.

Notice a few things:

- 1. The header file **second.h** has been replaced with the actual code.
- 2. The comments have indeed been removed.
- 3. The global variable a has been replaced with the actual value 3.

This leaves us with the question of what all the rest of the lines that start with a # are for. They are called preprocessor directives.

Definition 6.4 (Preprocessor Directives)

Preprocessor directives are commands that are executed before the actual compilation begins. These directives allow additional actions to be taken on the C source code before it is compiled into object code. Directives are not part of the C language itself, and they are always prefixed with a # symbol.

- 1. #include is used to include the contents of a file into the source file. It selects portions of the file to include based on the file name.
- 2. #define is used to define a macro, which is a way to give a name to a constant value or a piece of code.
- 3. #ifdef, #ifndef, #else, and #endif are used for conditional compilation.
- 4. #error is used to generate a compilation error.
- 5. #pragma is used to give the compiler specific instructions.

6.2 Compiling Stage

Once we have precompiled, we can compile the code into assembly code. For the following two examples, we will parse through the general syntax of assembly code. It is quite different between x86 and ARM, so we will use the minimal C code

```
int add(int x, int y) {
   return x + y;
}

int main() {
   int a = 3;
   int b = 5;
   int c = add(a, b);
   return 0;
}
```

for both examples.

Example 6.2 (x86 Compiled Assembly Language)

```
The assmebly code is shown.
      .file "main.c"
     .text
     .globl add
     .type add, @function
 6 add:
   .LFB0:
     .cfi_startproc
     endbr64
     pushq %rbp
     .cfi_def_cfa_offset 16
     .cfi_offset 6, -16
12
     movq %rsp, %rbp
     .cfi_def_cfa_register 6
14
     movl %edi, -4(%rbp)
     movl %esi, -8(%rbp)
     movl
            -4(%rbp), %edx
     movl
            -8(%rbp), %eax
     addl %edx, %eax
19
     popq
           %rbp
     .cfi_def_cfa 7, 8
     ret
     .cfi_endproc
   .LFEO:
     .size add, .-add
     .globl main
26
     .type main, @function
28 main:
29
   .LFB1:
     .cfi_startproc
30
     endbr64
31
     pushq %rbp
32
     .cfi_def_cfa_offset 16
      .cfi_offset 6, -16
```

```
movq %rsp, %rbp
     .cfi_def_cfa_register 6
     subq $16, %rsp
     movl
           $3, -12(%rbp)
     movl
           $5, -8(%rbp)
40
     movl
           -8(%rbp), %edx
41
     movl
           -12(%rbp), %eax
     movl
           %edx, %esi
42
     movl
           %eax, %edi
43
     call
           add
44
     movl %eax, -4(%rbp)
45
     movl $0, %eax
46
47
    leave
   .cfi_def_cfa 7, 8
48
49
   ret
    .cfi_endproc
51 .LFE1:
    .size main, .-main
     .ident "GCC: (Ubuntu 9.4.0-1ubuntu1~20.04.2) 9.4.0"
     .section .note.GNU-stack,"",@progbits
    .section .note.gnu.property, "a"
    .align 8
     .long 1f - 0f
    .long 4f - 1f
     .long 5
59
60 0:
                "GNU"
61
     .string
62 1:
63
     .align 8
    .long
           0xc0000002
64
            3f - 2f
65
    .long
  2:
     .long
            0x3
69
    .align 8
   4:
```

Example 6.3 (ARM Compiled Assembly Language)

The assembly code is shown.

```
.section __TEXT,__text,regular,pure_instructions
   .build_version macos, 14, 0 sdk_version 14, 4
  .globl _add
                                          ; -- Begin function add
    .p2align 2
6 _add:
                                         ; @add
    .cfi_startproc
8 ; %bb.0:
   sub sp, sp, #16
   .cfi_def_cfa_offset 16
  str w0, [sp, #12]
   str w1, [sp, #8]
    ldr w8, [sp, #12]
13
    ldr w9, [sp, #8]
```

```
add w0, w8, w9
     add sp, sp, #16
     ret
     .cfi_endproc
                                             ; -- End function
19
     .globl _main
                                             ; -- Begin function main
     .p2align 2
                                             ; @main
   _main:
     .cfi_startproc
   ; %bb.0:
24
     sub sp, sp, #48
     .cfi_def_cfa_offset 48
26
     stp x29, x30, [sp, #32]
                                         ; 16-byte Folded Spill
     add x29, sp, #32
28
     .cfi_def_cfa w29, 16
     .cfi_offset w30, -8
30
     .cfi_offset w29, -16
     mov w8, #0
32
     str w8, [sp, #12]
                                          ; 4-byte Folded Spill
     stur wzr, [x29, #-4]
     mov w8, #3
     stur w8, [x29, #-8]
36
     mov w8, #5
     stur w8, [x29, #-12]
38
     ldur w0, [x29, #-8]
39
     ldur w1, [x29, #-12]
40
     bl _add
     mov x8, x0
     ldr w0, [sp, #12]
                                          ; 4-byte Folded Reload
     str w8, [sp, #16]
44
     ldp x29, x30, [sp, #32]
45
                                          ; 16-byte Folded Reload
46
     add sp, sp, #48
48
     .cfi_endproc
                                             ; -- End function
   .subsections_via_symbols
```

We can see that in both examples, there are generally two types of codes.

- 1. The regular CPU operations with registers and memory.
- 2. Some code starts off with some code that starts with a .. Every line that starts with a . are called assembler directives.

Let's elaborate more on what these directives are.

Definition 6.5 (Assembler Directives)

An assembler directives are instructions in assembly language programming that that give commands to the assembler (which then converts this to an object file) about various aspects of the assembly process, but they do not represent actual CPU instructions that execute in the program. Unlike typical assembly language instructions that directly manipulate registers and execute arithmetic or logical operations, directives are used to organize, control, and provide necessary information for the assembly and linking of binary programs. They can manage memory allocation, define symbols, control compilation settings, and much more.

There are general types of directives that are common in both x86 and ARM that we should be aware

about:

- 1. Section directives.
- 2. Data allocation directives.
- 3. Symbol definition directives.
- 4. Macro and Include directives.
- 5. Debugging and error handling directives.

Example 6.4 (x86 Assembly Directives)

Let us elaborate on the specific directives in the x86 assembly code, some of which are in the example above.

- 1. .file "main.c" is a directive that tells the assembler that the following code is from the file main.c. It is a form of metadata.
- 2. .text is a directive that tells the assembler that the following code is the text section (the text/code portion of memory) of the program. This is where the actual code is stored.
- 3. .glob1 add is a directive that tells the assembler that the following code is a global function called add.
- 4. .type add, Ofunction is a directive that tells the assembler that the following code is a function.

Example 6.5 (ARM Assembly Directives)

You also see that there are symbols that represent memory addresses. Let's elaborate on what symbols mean.

Definition 6.6 (Symbol)

A **symbol** is a name that is used to refer to a memory location. It can be a function name, a global variable, or a local variable.

- 1. Global symbols are symbols that can be referenced by other object files, e.g. non-static functions and global variables.
- 2. Local symbols are symbols that are only visible within the object file, e.g. static functions and local variables. The linker won't know about these types.
- 3. External symbols are referenced by this object file but defined in another object file.

6.3 Objdump

Since we will be using the objdump package quite a lot, it is worth mentioning the different commands you will use and store them here as a reference. For first readers, don't expect to know what each of them do, but rather look back at this for a reference.

6.3.1 ELF and Mach-O Formats

Objdump is a command line utility that is used to display information about object files, which are often outputted in a specific format. The two main output file types are called ELF (Executable and Linkable Format) and Mach-O (Mach Object).

Definition 6.7 (ELF)

The **Executable and Linkable Format** (ELF) is a common standard file format for executables, object code, shared libraries, and core dumps. It is analogous to a book, with the following parts:

- 1. **Header**, which is like the cover of the book. It contains metadata about the file, such as the architecture, the entry point, and the sections.
- 2. Sections, which are like chapters. Each section contains the content for some given purpose or use wthin the program. e.g. .binary is just a block of bytes, .text contains the machine code, .data contains initialized data, and .bss contains uninitialized data.
- 3. **Symbol Table**, is like a detailed table of contents of all defined symbols such as functions, external (global) variables, local maps, etc.
- 4. **Relocation records**, which is like the index of the book that lists references to symbols. The format is generally as such when you run objdump -d -r hello.o (d represents disassembly and r represents relocation entries).

```
ELF header
                      # file type
   .text section
     - code goes here
   .rodata section
     - read only data
   .data section
    - initialized global variables
  .bss section
13
     - uninitialized global variables
  .symtab section
     - symbol table (symbol name, type, address)
   .rel.text section
     - relocation entries for .text section
19
     - addresses of instructions that will need to be modified in the executable.
   .rel.data section
     - relocation info for .data section
23
     - addresses of pointer data that will need to be modified in the merged executable.
  .debug section
26
     - info for symbolic debugging (gcc -g)
```

Definition 6.8 (Mach-O)

6.3.2 Objdump Commands

Theorem 6.1 (File Headers with Objdump)

Given that you have an object file, the first thing you might want to do is see the file header. You do with this objdump -f main.o.

Theorem 6.2 (Section with Objdump)

To look at the section headers to get a closer overview, you use objdump -h main.o.

```
main.o:
        file format elf64-x86-64
2
 Sections:
 Idx Name
           Size
                 VMA
                           LMA
                                     File off Algn
           00000040
  0 .text
                                           2**0
           CONTENTS, ALLOC, LOAD, RELOC, READONLY, CODE
           0000008b 2**0
  1 .data
           CONTENTS, ALLOC, LOAD, DATA
           0000008b 2**0
  2 .bss
9
            ALLOC
           0000008b 2**0
  3 .comment
           CONTENTS, READONLY
12
  CONTENTS, READONLY
14
  CONTENTS, ALLOC, LOAD, READONLY, DATA
16
           00000058 00000000000000 0000000000000 00000d8 2**3
   6 .eh_frame
           CONTENTS, ALLOC, LOAD, RELOC, READONLY, DATA
```

Theorem 6.3 (Disassembly with Objdump)

Now you might actually want to look at the disassembly of the code, which is what we often use it for. To do this, you use objdump -D main.o to get the entire output.

- 1. The leftmost column represents the address of the instruction.
- 2. The next column represents the machine code of the instruction.
- 3. The next column represents the assembly code of the instruction.

```
main.o:
               file format elf64-x86-64
   Disassembly of section .text:
3
   0000000000000000 <add>:
      0: f3 Of 1e fa
                                  endbr64
     17: c3
                                  retq
   0000000000000018 <main>:
     18: f3 Of 1e fa
                                  endbr64
     . . .
     4a: c3
                                  retq
   Disassembly of section .comment:
16
   0000000000000000 <.comment>:
      0: 00 47 43
                                         %al,0x43(%rdi)
                                  add
18
19
     2a: 30 00
                                         %al,(%rax)
                                  xor
  Disassembly of section .note.gnu.property:
   0000000000000000 <.note.gnu.property>:
```

If you just want to look at the contents of the executable sections, then you can use objdump -d main.o.

```
main.o:
               file format elf64-x86-64
   Disassembly of section .text:
   000000000000000 <add>:
      0: f3 Of 1e fa
                                 endbr64
      4: 55
                                 push
                                        %rbp
      5: 48 89 e5
                                        %rsp,%rbp
                                 mov
      8: 89 7d fc
                                        %edi,-0x4(%rbp)
                                 mov
     b: 89 75 f8
                                        %esi,-0x8(%rbp)
                                 mov
     e: 8b 55 fc
                                 mov
                                        -0x4(%rbp),%edx
12
     11: 8b 45 f8
                                 mov
                                        -0x8(%rbp), %eax
     14: 01 d0
                                 add
                                        %edx,%eax
    16: 5d
                                 pop
                                        %rbp
14
     17: c3
15
                                 retq
  000000000000018 <main>:
    18: f3 Of 1e fa
                                 endbr64
18
     1c: 55
                                 push
                                        %rbp
19
     1d: 48 89 e5
                                 mov
                                        %rsp,%rbp
     20: 48 83 ec 10
                                 sub
                                        $0x10,%rsp
     24: c7 45 f4 03 00 00 00
                                 movl
                                        $0x3,-0xc(%rbp)
     2b: c7 45 f8 05 00 00 00
                                 movl
                                        $0x5,-0x8(%rbp)
     32: 8b 55 f8
                                 mov
                                        -0x8(%rbp),%edx
     35: 8b 45 f4
                                 mov
                                        -0xc(%rbp), %eax
     38: 89 d6
                                        %edx,%esi
                                 mov
     3a: 89 c7
                                        %eax,%edi
                                 mov
     3c: e8 00 00 00 00
                                 callq 41 < main + 0x29 >
     41: 89 45 fc
                                        %eax,-0x4(%rbp)
                                 mov
     44: b8 00 00 00 00
                                        $0x0, %eax
                                 mov
     49: c9
                                 leaveq
     4a: c3
                                 retq
```

If you want to see the source code intermixed with disassembly, then you can use the -S flag, but make sure that the object file is a generated with debugging information, i.e. use gcc -c -g main.c -o main.o.

```
main.o:
               file format elf64-x86-64
   Disassembly of section .text:
   0000000000000000 <add>:
   int add(int x, int y) {
      0: f3 Of 1e fa
                                  endbr64
      4: 55
                                  push
                                         %rbp
      5: 48 89 e5
                                  mov
                                         %rsp,%rbp
      8: 89 7d fc
                                  mov
                                         %edi,-0x4(%rbp)
      b: 89 75 f8
                                  mov
                                         %esi,-0x8(%rbp)
     return x + y;
      e: 8b 55 fc
                                  mov
                                         -0x4(\%rbp), %edx
     11: 8b 45 f8
                                  mov
                                         -0x8(%rbp), %eax
     14: 01 d0
                                         %edx,%eax
                                  add
17 }
     16: 5d
                                         %rbp
                                  pop
19
     17: c3
                                  retq
  000000000000018 <main>:
  int main() {
    18: f3 Of 1e fa
                                  endbr64
24
     1c: 55
                                  push
                                         %rbp
    1d: 48 89 e5
                                  mov
                                         %rsp,%rbp
     20: 48 83 ec 10
                                  sub
                                         $0x10, %rsp
     int a = 3;
28
     24: c7 45 f4 03 00 00 00
                                         $0x3,-0xc(%rbp)
                                  movl
     int b = 5;
     2b: c7 45 f8 05 00 00 00
                                         $0x5,-0x8(%rbp)
                                  movl
     int c = add(a, b);
     32: 8b 55 f8
                                         -0x8(%rbp), %edx
                                  mov
     35: 8b 45 f4
                                  mov
                                         -0xc(%rbp),%eax
     38: 89 d6
                                         %edx,%esi
                                  mov
     3a: 89 c7
                                         %eax,%edi
                                  mov
36
     3c: e8 00 00 00 00
                                  callq 41 < main + 0x29 >
     41: 89 45 fc
                                         %eax,-0x4(%rbp)
38
                                  mov
     return 0;
     44: b8 00 00 00 00
                                         $0x0, %eax
41 }
     49: c9
                                  leaveg
     4a: c3
                                  retq
```

Figure 35: Disassembly of the object file back into assembly using objdump -d -S main.o.

Note that you can always see this disassembly with debuggers like gdb or lldb, but objdump generally works for all architectures.

Theorem 6.4 (Symbol Table)

If you want to look at all the symbols existing within the object file, you use objdump -t main.o (t for table of symbols).

1. The leftmost column represents the address of the symbol.

- 2. The next column represents the type of the symbol. The g and 1 represent global and local symbols, respectively. The O and F represent object and function symbols, while the UND and ABS represent undefined and absolute symbols.
- 3. The next column represents the section that the symbol is in.
- 4. The next column represents the size of the symbol.
- 5. The last column represents the name of the symbol.

```
file format elf64-x86-64
main.o:
SYMBOL TABLE:
00000000000000000001
                                 0000000000000000 main.c
                      df *ABS*
00000000000000000001
                      d .text
                                 000000000000000 .text
00000000000000000001
                      d
                         .data
                                 00000000000000 .data
00000000000000000001
                         .bss 00000000000000 .bss
00000000000000000001
                      d .note.GNU-stack 00000000000000 .note.GNU-stack
00000000000000000001
                      d .note.gnu.property 0000000000000 .note.gnu.property
000000000000000000001
                      d .eh_frame 00000000000000 .eh_frame
                                    000000000000000 .comment
000000000000000000001
                      d .comment
000000000000000 g
                                 000000000000018 add
                       F .text
0000000000000018 g
                                 000000000000033 main
                       F .text
```

Theorem 6.5 (Relocation Table)

If you want to look then at the relocation table, then you use objdump -r main.o.

- 1. The leftmost column represents the offset of the relocation (i.e. the location within the section where this relocation needs to be applied).
- 2. The second column represents the type of relocation.
- 3. The third column represents the symbol that this relocation references.

6.4 Assembling Stage and Object Files

Now, once you have gotten the object file, you cannot simply open it up in a text edit as it is in machine code. To actually interpret anything from it, you must **disassmble** it, meaning that you convert the machine code back into assembly code. The main software that you use to do this is objdump. Let's take a look again at the object file.

```
Disassembly of section .text:
0000000000000000 <add>:
   0: f3 Of 1e fa
                                endbr64
   4: 55
                                push
                                       %rbp
   5: 48 89 e5
                                       %rsp,%rbp
                               mov
   8: 89 7d fc
                                       %edi,-0x4(%rbp)
                               mov
   b: 89 75 f8
                                       %esi,-0x8(%rbp)
                               mov
   e: 8b 55 fc
                                       -0x4(%rbp), %edx
                               mov
  11: 8b 45 f8
                                       -0x8(%rbp), %eax
                                mov
  14: 01 d0
                                       %edx,%eax
                                add
  16: 5d
                                       %rbp
                                pop
  17: c3
                                retq
0000000000000018 <main>:
  18: f3 Of 1e fa
                                endbr64
  1c: 55
                                push
                                       %rbp
  1d: 48 89 e5
                                mov
                                       %rsp,%rbp
  20: 48 83 ec 10
                                       $0x10, %rsp
                                sub
  24: c7 45 f4 03 00 00 00
                                       $0x3,-0xc(%rbp)
                               movl
  2b: c7 45 f8 05 00 00 00
                               movl
                                       $0x5,-0x8(%rbp)
  32: 8b 55 f8
                                       -0x8(%rbp), %edx
                               mov
  35: 8b 45 f4
                                       -0xc(%rbp), %eax
                                mov
  38: 89 d6
                                       %edx,%esi
                                mov
  3a: 89 c7
                                       %eax,%edi
  3c: e8 00 00 00 00
                                       41 <main+0x29>
                                callq
  41: 89 45 fc
                                       \%eax, -0x4(\%rbp)
                               mov
  44: b8 00 00 00 00
                                       $0x0, %eax
                               mov
  49: c9
                                leaveg
  4a: c3
                                retq
```

Figure 36: Disassembly of the object file back into assembly using objdump -d main.o.

Let's note a couple things.

1. The functions are organized by their starting address followed by their name, e.g.

```
1 00000000000000 <add>:
```

Within each function, each line of assembly code is shown. To find the total memory the function takes up, you can just take the address of the last line and subtract it from the address of the first line. Or you can literally count the number of bytes in each line (remember 2 hex is 1 byte).

- 2. The line that calls the add function is 0x0 (00 00 00), with is the *relative target address* intended to be filled in by the linker. The actual assembly line just says that the function continues on to the next line at address 0x41. This is because the object file is not aware of where it will be loaded into memory, and all lines with this opcode e8 00 00 00 00 is intended to be filled in by the linker.
- 3. Look at address 0x3c. It is calling another function, but the values starting from address 0x3d is 00 00 00, which is not the actual address of the function but also a dummy address. This is because the object file is not aware of where the function is located in memory.

6.5 Linking Stage and Relocation

6.5.1 Relocation

If the object file is already in machine code, then why do we need a separate linking stage that converts main.o into main the binary? The reason is stated in the previous section: because the object files uses relative memory addressing and does not know about which memory is accessed in other object files, we need to relocate the symbols in the object file to their proper addresses. So how does the linker actually know how to relocate these symbols into their proper addresses? It uses the relocation table, which contains information about the addresses that need to be modified in the object file.

```
file format elf64-x86-64
main.o:
RELOCATION RECORDS FOR [.text]:
OFFSET
                  TYPF.
                                     VALUE
000000000000003d R_X86_64_PLT32
                                     add-0x0000000000000004
RELOCATION RECORDS FOR [.eh_frame]:
OFFSET
                  TYPF.
                                     VALUE.
000000000000000 R_X86_64_PC32
                                     .text
00000000000000040 R_X86_64_PC32
                                     .text+0x0000000000000018
```

Figure 37: Relocation table for main.o object file.

Let's talk about how to actually read this table. We can look at the first entry, which shows an offset of 0x3d. This represents the offset from the beginning of the .text section where the relocation needs to be applied. Looking back at the disassembly file, this address 0x3d is precisely where there was a dummy address 00 00 00. We want to replace this with the actual address defined in the VALUE column, which is add (with a slight offset of 0x4, which is typically used to compensate for the PC-relative addressing mode where the CPU might be adding the length of the instruction to the program counter (PC) before the relocation value is applied). The type of relocation won't be covered in our scope. Let's go through each relocation entry:

1. The first entry is for the add function. If we look at the disassembly, within the main function, the address 0x3d is where the add function is called. The linker will replace the dummy address with the actual address of the add function.

```
Disassembly of section .text:
   0000000000000000 <add>:
3
      0: f3 Of 1e fa
                                    endbr64
      4: 55
                                    push
                                           %rbp
      5: 48 89 e5
                                           %rsp,%rbp
                                    mov
      8: 89 7d fc
                                           %edi,-0x4(%rbp)
                                    mov
      b: 89 75 f8
                                           %esi,-0x8(%rbp)
                                    mov
      e: 8b 55 fc
                                           -0x4(\%rbp), %edx
                                    mov
     11: 8b 45 f8
                                            -0x8(%rbp), %eax
                                    mov
     14: 01 d0
                                    add
                                           %edx,%eax
     16: 5d
                                           %rbp
                                    pop
     17: c3
                                    retq
   000000000000018 <main>:
     18: f3 Of 1e fa
                                    endbr64
17
     1c: 55
                                    push
                                           %rbp
                                           %rsp,%rbp
     1d: 48 89 e5
                                    mov
     20: 48 83 ec 10
                                           $0x10, %rsp
                                    sub
```

```
24: c7 45 f4 03 00 00 00
                                     $0x3,-0xc(%rbp)
                             movl
2b: c7 45 f8 05 00 00 00
                             movl
                                     $0x5,-0x8(%rbp)
32: 8b 55 f8
                                     -0x8(%rbp), %edx
                             mov
35: 8b 45 f4
                                     -0xc(%rbp),%eax
                             mov
38: 89 d6
                                     %edx,%esi
                             mov
3a: 89 c7
                                     %eax, %edi
3c: e8 00 00 00 00
                              callq
                                     41 <main+0x29>
                                                          <-- here
                                     %eax,-0x4(%rbp)
41: 89 45 fc
                             mov
44: b8 00 00 00 00
                                     $0x0, %eax
                             mov
49: c9
                              leaveq
4a: c3
                              retq
```

2. The second and third entries are for the .eh_frame section. We can see that the offset of 0x20 and 0x40 represents the following lines below. They also have dummy addresses that need to be replaced. They are replaced by the address .text, which represents the first address in the .text section, i.e. the address of the add function, and the address .text+0x18, which represents the address of the main function.

```
Disassembly of section .eh_frame:
2
   0000000000000000 <.eh_frame>:
                                           $0x0,%al
      0: 14 00
                                   adc
      2: 00 00
                                           %al,(%rax)
                                   add
      4: 00 00
                                           %al,(%rax)
                                   add
      6: 00 00
                                           %al,(%rax)
                                   add
      8: 01 7a 52
                                   add
                                           %edi,0x52(%rdx)
      b: 00 01
                                   add
                                           %al,(%rcx)
      d: 78 10
                                   js
                                           1f <.eh_frame+0x1f>
      f: 01 1b
                                   add
                                           %ebx,(%rbx)
     11: 0c 07
                                           $0x7,%al
                                   or
     13: 08 90 01 00 00 1c
                                           %dl,0x1c000001(%rax)
13
                                   or
     19: 00 00
                                           %al,(%rax)
                                   add
     1b: 00 1c 00
                                   add
                                           %bl,(%rax,%rax,1)
     1e: 00 00
                                           %al,(%rax)
                                   add
                                           %al,(%rax)
     20: 00 00
                                   add
                                                           <-- here for 2nd entry
     22: 00 00
                                   add
                                           %al,(%rax)
     24: 18 00
                                           %al,(%rax)
                                   sbb
     26: 00 00
                                           %al,(%rax)
                                   add
     28: 00 45 0e
                                   add
                                           %al,0xe(%rbp)
     2b: 10 86 02 43 0d 06
                                   adc
                                           %al,0x60d4302(%rsi)
     31: 4f 0c 07
                                   rex.WRXB or $0x7,%al
     34: 08 00
                                           %al,(%rax)
                                   or
     36: 00 00
                                   add
                                           %al,(%rax)
     38: 1c 00
                                   sbb
                                           $0x0,%al
     3a: 00 00
                                           %al,(%rax)
                                   add
                                           $0x0,%al
     3c: 3c 00
                                   cmp
     3e: 00 00
                                           %al,(%rax)
                                   add
     40: 00 00
                                           %al,(%rax)
                                   add
                                                           <-- here for 3rd entry
     42: 00 00
                                   add
                                           %al,(%rax)
     44: 33 00
                                           (%rax),%eax
                                   xor
```

Therefore, we can see that the object file generates a "skeleton" code that contains all the instructions, with some dummy addresses that need to be replaced. The relocation table T tells us exactly where these dummy addresses are in the code and what they need to be replaced with. Therefore, if we want to call a function printf that is in the text section at address 0x30, then we can actually look at the value at T[30] to see where the actual address is. At this point, note that we still do not know the actual memory address of add. This is determined by the linker.

6.5.2 Linking with One Object File

Now let's see what happens once we link the object file main.o into the final executable main. If we disassemble it, then we can see a few things:

- 1. The addresses of all the functions have been changed. add starts on address 0x1129 rather than 0x0 and main starts on address 0x1141 rather than 0x18.
- 2. The dummy address 0x0 of the call to function add in main have been replaced with the actual addresses 0x1129.

```
000000000001129 <add>:
  1129: f3 Of 1e fa
                                  endbr64
                                 push
  112d:
         55
                                         %rbp
  112e: 48 89 e5
                                         %rsp,%rbp
                                 mov
  1131: 89 7d fc
                                         %edi,-0x4(%rbp)
                                 mov
                                         %esi,-0x8(%rbp)
  1134: 89 75 f8
                                 mov
  1137: 8b 55 fc
                                         -0x4(\%rbp), %edx
                                 mov
  113a:
         8b 45 f8
                                         -0x8(%rbp), %eax
                                 mov
         01 d0
                                         %edx,%eax
  113d:
                                  add
  113f: 5d
                                         %rbp
                                 pop
  1140: c3
                                 retq
000000000001141 <main>:
  1141: f3 Of 1e fa
                                  endbr64
  1145:
         55
                                 push
                                         %rbp
         48 89 e5
  1146:
                                         %rsp,%rbp
                                 mov
  1149:
         48 83 ec 10
                                         $0x10, %rsp
                                  sub
                                         $0x3,-0xc(%rbp)
  114d:
         c7 45 f4 03 00 00 00
                                 movl
  1154: c7 45 f8 05 00 00 00
                                         $0x5,-0x8(%rbp)
                                 movl
  115b:
         8b 55 f8
                                         -0x8(%rbp), %edx
                                 mov
  115e:
         8b 45 f4
                                         -0xc(\%rbp), \%eax
                                 mov
         89 d6
                                         %edx,%esi
  1161:
                                 mov
  1163:
         89 c7
                                         %eax,%edi
                                 mov
                                         1129 <add>
  1165:
         e8 bf ff ff ff
                                                        <-- replaced with actual address
                                  callq
  116a:
         89 45 fc
                                         %eax,-0x4(%rbp)
                                 mov
  116d: b8 00 00 00 00
                                 mov
                                         $0x0, %eax
  1172:
         с9
                                  leaveq
                                 retq
  1173:
         сЗ
         66 2e Of 1f 84 00 00
  1174:
                                         %cs:0x0(%rax, %rax, 1)
                                 nopw
  117b:
         00 00 00
         66 90
  117e:
                                 xchg
                                         %ax,%ax
```

6.5.3 Global vs External Symbols

So far, we have talked about using the **#include** as a precompiling command that says "put all the text from this other file right here." Take the following code for instance.

```
// file1.c
                                                          // sum.h
  #include "sum.h"
                                                          int sum(int *a, int n) {
                                                            int i, s = 0;
  int array[2] = {1, 2};
                                                            for (i = 0; i < n; i++) {</pre>
                                                                += a[i];
  int main() {
6
     int val = sum(array, 2);
                                                            return s:
                                                          }
     return val:
  }
9
```

Figure 38: Including a header file in file1.c to import functions and variables.

However, there is another way to do this. We can use *external symbols* to access. Rather than simply copying and pasting the code into the file, the **extern** keyword marks that the variable or function exists externally to this source file and does not allocate storage for it.

```
1  // main.c
2  extern int sum(int *array, int n);
3
4  int array[2] = {1, 2};
6  int main(void) {
7   int val = sum(array, 2);
8   return val;
9  }

1   // sum.c
2  int sum(int *array, int n) {
3   int i, s = 0;
4   for (int i = 0; i < n; i++) {
5       s += array[i];
6   }
7   return s;
8  }
9  .</pre>
```

Figure 39: Using external symbols to access functions and variables.

One is not a replacement for the other, so what advantage does this have? Well, as we will see, if we have multiple object (source) files, say A.c, B.c, and C.c, that need to reference the same function or variable var in ext.c, then how would we do this? If we simply put #include "ext.h" in all the files, then we would have multiple copies of the same code. This means that for each source there would be its own copy of var created and the linker would be unable to resolve this symbol. However, if we put extern int var; at the top of each source file, then only one copy of var would be created (in ext.c), which creates a single instance of var for the linker to resolve. ²

Therefore, there are three types of symbols (variables, functions, etc.) that we need to consider:

- 1. Global symbols that are defined in the global scope of a C file.
- 2. Local symbols that are defined in the local scope of a C file, e.g. within functions, loops, etc.
- 3. External symbols that are defined in another C file referenced by the extern keyword.

Linkers will only know about global and external symbols, and will have no idea that any local symbols exist. With the information of these two types of symbols and the relocation tables of each object file, the linker can then resolve the addresses of all the symbols in the final binary.

The two types of symbols that the linker will know about are the global and external symbols. We can see that external symbols can be problematic if the object files don't know about each other.

²https://stackoverflow.com/questions/1330114/whats-the-difference-between-using-extern-and-including-header-files

Example 6.6 (Global and Local Symbols)

Consider the following code where the left file includes the right file.

In the left file,

- 1. We define the global symbol main().
- 2. Inside main, val is a local symbol so the linker knows nothing about it.
- 3. The sum function is an external symbol, and it references a global symbol that's defined in sum the right file.
- 4. The array is a global symbol that is defined in the right file.

In the right file, the linker knows nothing of the local symbols i or s.

6.5.4 Linking with Multiple Object Files

We have seen the case of linking when we simply have one object file. The relocation was simple since the .text section is contiguous and so we needed simple translations of addresses to relocate add and main, along with whatever other sections and files. Now let's consider the case where we have multiple object files.

```
// main.c
                                                        // sum.c
  extern int sum(int *array, int n);
                                                        int sum(int *array, int n) {
                                                          int i, s = 0;
                                                          for (int i = 0; i < n; i++) {</pre>
  int array[2] = {1, 2};
4
                                                              s += array[i];
  int main(void) {
                                                            }
    int val = sum(array, 2);
                                                          return s;
                                                        }
    return val;
9
  }
```

Now they have their own object files shown below, where I also put the source code lines to make it easier to parse. Note that again, in main.o the call to function sum is a dummy address that needs to be replaced. Furthermore, in both main.o and sum.o, the .text section is at address 0x0, where the addresses of the function main and sum are, respectively. This causes an overload in the address space.

To demonstrate what happens, we look at how the disassembly, symbol tables, and relocation tables are updated before (with the object files) and after (in the binary) linking.

Example 6.7 (Disassembly of Object Files)

In here, note that both the array and sum are not initialized and are therefore set to dummy addresses.

```
main.o: file format elf64-x86-64
plisassembly of section .text:

0000000000000000000 <main>:
extern int sum(int *array, int n);
```

```
int array[2] = {1, 2};
   int main(void) {
      0: f3 Of 1e fa
                                 endbr64
      4: 55
                                 push
                                        %rbp
     5: 48 89 e5
                                 mov
                                        %rsp,%rbp
     8: 48 83 ec 10
                                 sub
                                        $0x10,%rsp
     int val = sum(array, 2);
14
     c: be 02 00 00 00
                                 mov
                                        $0x2, %esi
     11: 48 8d 3d 00 00 00 00
                                 lea
                                        0x0(%rip),%rdi
                                                            # 18 <main+0x18> <-- dummy
       address
     18: e8 00 00 00 00
                                 callq 1d <main+0x1d>
                                                                                <-- dummy
      address
     1d: 89 45 fc
                                 mov
                                        %eax,-0x4(%rbp)
     return val;
     20: 8b 45 fc
                                        -0x4(%rbp), %eax
                                 mov
21 }
     23: c9
                                 leaveq
     24: c3
                                 retq
              file format elf64-x86-64
```

```
Disassembly of section .text:
   0000000000000000 <sum>:
   int sum(int *array, int n) {
      0: f3 Of 1e fa
                                  endbr64
      4: 55
                                  push
                                         %rbp
      5: 48 89 e5
                                         %rsp,%rbp
                                  mov
      8: 48 89 7d e8
                                  mov
                                         %rdi,-0x18(%rbp)
      c: 89 75 e4
                                  mov
                                         %esi,-0x1c(%rbp)
     int i, s = 0;
     f: c7 45 f8 00 00 00 00
                                  movl
                                         $0x0,-0x8(%rbp)
     for (int i = 0; i < n; i++) {</pre>
     16: c7 45 fc 00 00 00 00
                                  movl
                                         $0x0,-0x4(%rbp)
14
     1d: eb 1d
                                         3c < sum + 0x3c >
                                  jmp
      s += array[i];
16
                                  mov
     1f: 8b 45 fc
                                         -0x4(%rbp), %eax
17
     22: 48 98
                                  cltq
     24: 48 8d 14 85 00 00 00
                                  lea
                                         0x0(,%rax,4),%rdx
     2b: 00
     2c: 48 8b 45 e8
                                         -0x18(%rbp), %rax
                                  mov
     30: 48 01 d0
                                  add
                                         %rdx,%rax
     33: 8b 00
                                          (%rax), %eax
                                  mov
     35: 01 45 f8
                                         %eax,-0x8(%rbp)
                                  add
     for (int i = 0; i < n; i++) {</pre>
     38: 83 45 fc 01
                                  addl
                                         $0x1,-0x4(%rbp)
     3c: 8b 45 fc
                                  mov
                                         -0x4(\%rbp), %eax
     3f: 3b 45 e4
                                  cmp
                                          -0x1c(%rbp),%eax
     42: 7c db
                                         1f < sum + 0x1f >
                                  jl
     return s;
31
     44: 8b 45 f8
                                         -0x8(%rbp), %eax
32
                                  mov
33 }
     47: 5d
                                         %rbp
                                  pop
     48: c3
                                  retq
```

- 1. In main.o at address 0x0, we have the main function and this is because everything is stored relatively to the start of main. Once we have linked, main shows the absolute addresses of all the instructions.
- 2. In instruction 11 in main. o we can see that 48 8d 3d is the lea instruction, which is the same as that in main. However, the address that is was acting on is 0x0 since the array has not been initialized yet. We can see in main that the address is now 0x00002ecf.
- 3. The comment in main indicates that the final relocated address used to access the array is 0x4010. To see relocated addresses in general, just look for the comments and shift them accordingly.

```
file format elf64-x86-64
   main:
   000000000001129 <main>:
3
       1129:
                f3 Of 1e fa
                                         endbr64
       112d:
                55
                                                 %rbp
                                         push
                                                 %rsp,%rbp
       112e:
                48 89 e5
                                         mov
       1131:
                48 83 ec 10
                                                 $0x10,%rsp
                                         sub
                be 02 00 00 00
                                                 $0x2, %esi
       1135:
                                         mov
       113a:
                48 8d 3d cf 2e 00 00
                                         lea
                                                 0x2ecf(%rip),%rdi
                                                                           # 4010 <array>
       1141:
                e8 08 00 00 00
                                         callq
                                                 114e <sum>
       1146:
                89 45 fc
                                         mov
                                                 %eax,-0x4(%rbp)
       1149:
                8b 45 fc
                                         mov
                                                 -0x4(%rbp), %eax
       114c:
                с9
                                         leaveq
       114d:
                сЗ
                                         retq
   00000000000114e <sum>:
                f3 Of 1e fa
       114e:
                                         endbr64
18
       1152:
                55
                                         push
                                                 %rbp
                                                 %rsp,%rbp
19
       1153:
                48 89 e5
                                         mov
       1156:
                48 89 7d e8
                                                 %rdi,-0x18(%rbp)
                                         mov
       115a:
                89 75 e4
                                         mov
                                                 %esi,-0x1c(%rbp)
```

Example 6.8 (Symbol Tables of Object Files)

Let's take a look at the symbol table of each file as well. Again, all of the addresses of each symbol are 0s since they are using relative addressing. The array and main are global symbols since they reside in the global scope, while the sum function is an external and undefined symbol.

```
main.o:
            file format elf64-x86-64
SYMBOL TABLE:
                                 0000000000000000 main.c
                      df *ABS*
0000000000000000001
0000000000000000001
                      d .text
                                 000000000000000 .text
00000000000000000001
                                 000000000000000 .data
                      d
                         .data
0000000000000000001
                      d
                         .bss 00000000000000 .bss
000000000000000000001
                      d
                         .note.GNU-stack 00000000000000 .note.GNU-stack
                         .note.gnu.property 0000000000000 .note.gnu.property
00000000000000000001
                      d
                         .eh_frame 0000000000000 .eh_frame
000000000000000000001
00000000000000000001
                      d .comment
                                    000000000000000 .comment
0000000000000000 g
                       O .data
                                 0000000000000008 array
0000000000000000 g
                       F .text
                                 0000000000000025 main
0000000000000000
                         *UND*
                                 000000000000000 _GLOBAL_OFFSET_TABLE_
000000000000000
                         *UND*
                                 000000000000000 sum
```

```
sum.o:
           file format elf64-x86-64
SYMBOL TABLE:
00000000000000000001
                       df *ABS*
                                  000000000000000 sum.c
00000000000000000001
                       d .text
                                  000000000000000 .text
00000000000000000001
                         .data
                                  000000000000000 .data
0000000000000000001
                       d
                         .bss 000000000000000 .bss
                          .note.GNU-stack 00000000000000 .note.GNU-stack
000000000000000000001
                       d
                          .note.gnu.property 0000000000000 .note.gnu.property
00000000000000000001
                       d
                                     000000000000000 .eh_frame
00000000000000000001
                          .eh_frame
                          .comment
00000000000000000001
                                      000000000000000 .comment
0000000000000000 g
                        F .text
                                  0000000000000049 \text{ sum}
```

When we have the linked binary, note a few things.

- 1. In main.o, the numbers on the left represents the address of the symbol (all 0s since we haven't linked yet and their final addresses aren't known), while the addresses in a.out are all known.
- 2. In main.o, the sum function is an external symbol and is undefined. The linker will need to know where this is. In main, note that the sum function is now a global symbol and is defined, along with the size. We can now see that all the final addresses of each symbol is known, along with their sizes, and the UND marker is now gone as well.
- 3. Only the size of the global variable is known in main.o since we have defined it within the code. However, in main, the linker has now assigned an address to it.
- 4. To see the size in bytes of the array, you can look at the address and how much size it takes up.

```
file format elf64-x86-64
  main:
  SYMBOL TABLE:
  0000000000004008 g
                                       0000000000000000
                          0 .data
                                                                      .hidden __dso_handle
  00000000000114e g
                          F .text
                                       0000000000000049
                                                                      sum
6
  0000000000002000 g
                                       00000000000000004
                                                                      _IO_stdin_used
                          0 .rodata
  0000000000011a0 g
                                       0000000000000065
                                                                      __libc_csu_init
                          F .text
  000000000004020 g
                            .bss
                                       000000000000000
                                                                      _end
  000000000001040 g
                          F .text
                                       000000000000002f
                                                                      _start
  0000000000004018 g
                                       0000000000000000
                            .bss
                                                                      __bss_start
  000000000001129 g
                          F .text
                                       0000000000000025
                                                                      main
  0000000000004018 g
                          0 .data
                                       000000000000000
                                                                      .hidden __TMC_END__
```

Example 6.9 (Relocation Tables)

Ignoring the .eh_frame, in main.o the relocation table contains entries for array and sum that must be relocated.

We can see a couple things. Namely, there is nothing to be relocated in a.out since everything has been relocated already by the linker. So let's focus on the relocation for main.o. In here, we can see that in the .text section, there are two things being relocated:

- 1. The reference to the global variable array is being relocated. In this object file, we look at the offset 0x14 from the beginning of the .text section, which contains the instruction that needs to access array. This relocation record tells the linker to calculate the 32-bit offset from the instruction (at offset 0x14) to the start of array, then adjust it by subtracting 4 bytes.
- 2. The reference to the sum function is being relocated. In this object file, we look at the offset 0x19 from the beginning of the .text section, which contains the instruction that needs to access sum. This relocation record tells the linker to calculate the 32-bit offset from the instruction (at offset 0x19) to the start of the .plt section, then adjust it by subtracting 4 bytes.

```
nain: file format elf64-x86-64
```

6.6 Compiler Optimization

We have learned the complete process of compilers, but compilers can be a little smarter than just translating code line by line. They also come with flags that can optimize the code.

Definition 6.9 (gcc Optimization)

The gcc compiler can optimize the code with the -0 flag. To run level 1 optimization, we can write

```
gcc -01 -o main main.c
```

The level of optimizations are listed:

- 1. Level 1 perform basic optimizations to reduce code size and execution time while attempting to keep compile time to a minimum.
- 2. Level 2 optimizations include most of GCC's implemented optimizations that do not involve a space-performance trade-off.
- 3. Level 3 performs additional optimizations (such as function inlining) and may cause the program to take significantly longer to compile.

Let's see what common implementation are.

Definition 6.10 (Constant Folding)

Constants in the code are evaluated at compile time to reduce the number of resulting instructions. For example, in the code snippet that follows, macro expansion replaces the statement int debug = N-5 with int debug = 5-5. Constant folding then updates this statement to int debug = 0.

```
#define N 5
int debug = N - 5; //constant folding changes this statement to debug = 0;
```

Definition 6.11 (Constant Propagation)

Constant propagation replaces variables with a constant value if such a value is known at compile time. Consider the following code segment, where the if (debug) statement is replaced with if (0).

```
int debug = 0;

int doubleSum(int *array, int length){
   int i, total = 0;
   for (i = 0; i < length; i++){
       total += array[i];
       if (debug) {
            printf("array[%d] is: %d\n", i, array[i]);
       }
    }

   return 2 * total;
}</pre>
```

Definition 6.12 (Dead Code Elimination)

Dead code elimination removes code that is never executed. For example, in the code snippet that follows, the if (debug) statement and its body is removed since the value of debug is known to be 0.

```
int debug = 0;

int doubleSum(int *array, int length){
    int i, total = 0;
    for (i = 0; i < length; i++){
        total += array[i];
        if (debug) {
            printf("array[%d] is: %d\n", i, array[i]); // remove
        }
        // remove
    }

return 2 * total;
}</pre>
```

Definition 6.13 (Simplifying Expressions)

Some instructions are more expensive than others, so things like

- 1. 2 * total may be replaced with total + total because addition instruction is less expensive than multiplication.
- 2. total * 8 may be replaced with total « 3
- 3. total % 8 may be replaced with total & 7

Note that these optimization techniques are in no way a guarantee that the code will run faster since there are many factors and always edge cases (for example, maybe some localities are lost). Furthermore, compiler optimization will never be able to improve runtime complexity (e.g. by replacing bubble sort with quicksort).

6.7 Virtual Memory Addresses

Memory addresses are actual virtual. There exists a hashmap from a virtual address to a physical address for each process. If we used physical addresses only to begin with, another application that uses the same physical address would overwrite the data, so there needs to be some sort of isolation. Note that every process has its own mapping, that's completely different! It's not one mapping for all processes. These