CMSC 330: Organization of Programming Languages

Reference Counting and Interior Mutability

Rust Ownership and Mutation


- Recall Rust ownership rules
 - Each value in Rust has a variable that's called its owner; there can be only one
 - When the owner goes out of scope, the value will be dropped
- Recall Rust mutability rules
 - Mutation can occur only through mutable variables (e.g., the owner) or references
 - Rust permits only one borrowed mutable reference (and no immutable ones at the same time)

But: Mutation and Sharing is Useful

Example: a simple spreadsheet

```
struct CellStyle { fontSize: f64 }
struct Cell { style: CellStyle }
struct Table { cells: [Cell; 128] }
- S0: a Table Owns its CellS
```

- But: a format inspector needs to read and write the cell data
 - Ensuring only one borrowed mutable reference would be awkward
 - Easier if the inspector has its own reference



Another Example

- Suppose you have a multiplayer chess game
 - Local data structures record the board state
 - Maybe the board is owned by the window that contains it
- What happens when a new move comes in from the network?
 - That's handled by a different software component, not the window
- Simplest design is to have multiple (mutable) references to the board
 - But Rust doesn't allow that

Relaxing Rust's Restrictions

- Architecturally, designating one owner that all accesses must go through can be awkward
 - We might end up wanting shared mutable access to the owner!
- Rust provides APIs by which you can get around the compilerenforced restrictions against multiple mutable references
 - Use reference counting to manage lifetimes safely
 - Track borrows at run-time to overcome limited compiler analysis
 - Discipline is called interior mutability
 - But: extra checks at space and time overhead; some previous compiletime failures now occur at run-time
 - Also a pain to program: Experimental GcRef to ease this

Multiple Pointers to a Value

What's wrong with this code?

```
fn main() {
  let a = Cons(5,
    Box::new(Cons(10,
    Box::new(Nil))));
  let b = Cons(3, Box::new(a));
  let c = Cons(4, Box::new(a));//fails
}
Nil,
Cons(i32,Box<List>)
}
```

enum List {

- Box::new takes ownership of its argument, so the second Box::new (a) call fails since a is no longer the owner
- How to allow something like this code?
 - Problem: Managing lifetime

```
enum List {
  Nil,
  Cons(i32,Box<List>)
}
```

Managing Lifetimes Dynamically

Benefit of ownership: compiler knows when to free memory

```
let nil_box = Box::new(List::Nil);
// free memory HERE (nil_box is going out of scope)
```

Suppose Box didn't own its data:


(Box does own its data so the above pattern is not allowed.)

Rc<T>: Multiple Owners, Dynamically

- This is a smart pointer that associates a counter with the underlying reference
- Calling clone copies the pointer, not the pointed-to data, and bumps the counter by one
 - By convention, call Rc::clone(&a) rather than a.clone(), as a visual marker for future performance debugging
 - In general, calls to x.clone() are possible issues
- Calling drop reduces the counter by one
- When the counter hits zero, the data is freed

Rc::clone "Shares" Ownership

Rc associates a refCount with the value



Lists with Sharing

```
enum List {
 Nil,
  Cons(i32,Rc<List>)
use List::{Cons, Nil};
fn main() {
  let a = Rc::new(Cons(5,
    Rc::new(Cons(10,
      Rc::new(Nil))));
  let b = Cons(3, Rc::clone(&a));
  let c = Cons(4, Rc::clone(&a));//ok
```

Nb. Rc::strong_count returns the current ref count

Reference Counting: Summary

- To create: let r = Rc::new(...);
 To copy a pointer: let s = Rc::clone(&r);
 Increments the reference count
- To move a reference: let t = s;
 - Does not increment reference count; s no longer the owner
- To *free* is automatic: **drop** is called when variables go out of scope, reducing the count; freed when 0
- See docs:
 - https://doc.rust-lang.org/book/ch15-04-rc.html
 - https://doc.rust-lang.org/std/rc/index.html

C. 2

D. This code doesn't compile

```
fn print refcount(r: Rc<i32>) {
    println!("{}", Rc::strong_count(&r));
 fn main() {
     let forty_two = Rc::new(42);
    print refcount(forty two);
         let v = Rc::clone(&forty_two);
        print refcount(v); // What does this print?
A. 0
B. 1
```

```
fn print refcount(r: Rc<i32>) {
    println!("{}", Rc::strong count(&r));
 fn main() {
     let forty_two = Rc::new(42);
    print refcount(forty two);
         let v = Rc::clone(&forty two);
        print refcount(v); // What does this print?
                                  error[E0382]: borrow of moved value: `forty two`
                                    --> src/main.rs:46:27
A. 0
                                   43 |
                                           let forty_two = Rc::new(42);
B. 1
                                               ---- move occurs because
                                   `forty two` has type `std::rc::Rc<i32>`, which
C. 2
                                  does not implement the `Copy` trait
D. This code doesn't compile
```

```
fn print refcount(r: &Rc<i32>) {
    println!("{}", Rc::strong count(r));
 fn main() {
     let forty two = Rc::new(42);
         let v = Rc::clone(&forty_two);
     print_refcount(&forty_two); // What does this print?
A. 0
B. 1
C. 2
D. This code doesn't compile
```

```
fn print refcount(r: &Rc<i32>) {
    println!("{}", Rc::strong count(r));
fn main() {
     let forty two = Rc::new(42);
         let v = Rc::clone(&forty_two);
     print_refcount(&forty_two); // What does this print?
A. 0
            v went out of scope, so the reference count is 1 (once again).
B. 1
C. 2
D. This code doesn't compile
```

Risks of Reference Counts

- Cyclic data is problematic
 - Suppose the arrows are Rc references



- Reference counts are always positive; will never be deallocated!
- Can fix by using weak references (see docs)
 - App must be prepared for referent to be revoked
 - These are not required for project 5

Rc References: Mutation?

 With Rc I can now make multiple references and safely manage lifetimes. Great! Let's see if I can mutate the reference's contents

```
let mut b = Rc::new(42);
 *b = 43;
                     warning: variable does not need to be mutable
                      --> src/main.rs:4:9
                             let mut b = Rc::new(42);
                                help: remove this `mut`
                       = note: `#[warn(unused_mut)]` on by default
                     error[E0594]: cannot assign to data in an `Rc`
                      --> src/main.rs:5:5
                     5
                             *b = 43;
                             ^^^^^ cannot assign
                       = help: trait `DerefMut` is required to modify through a dereference,
                     but it is not implemented for `Rc<i32>`
```

Rc References: No Mutation!

Rc only allows immutable contents

```
let mut b = Rc::new(42);
b = Rc::new(43); // fresh heap alloc
```

mut b means that I can reassign b, but not the object it references!

Digression: Cells are Mutable

```
• Cell<T>: like Box<T> but with mutable contents
   pub fn set(&self, val: T)

    moves the data in

   pub fn get(&self) -> T

    copies the data out

   pub fn take(&self) -> T

    moves the data out, leaving Default::default()

   pub fn get mut(&mut self) -> &mut T

    requires a &mut self
```

Cell example (from Rust book)

```
use std::cell::Cell;
struct SomeStruct {
    regular field: u8,
    special field: Cell<u8>,
let my struct = SomeStruct {
    regular field: 0,
    special field: Cell::new(1),
};
let new value = 100;
// ERROR: `my struct` is immutable
// my struct.regular field = new value;
// WORKS: although `my struct` is immutable, `special field` is a `Cell`,
// which can always be mutated
my struct.special field.set(new value);
assert eq!(my struct.special field.get(), new value);
```

Cell Limitations

- Cell is great if
 - you can copy the contents in and out
 - and you have mutable references to the cell whenever you want to modify the cell's contents
 - and you can reason statically about lifetimes
- But what if you can't or don't?
 - e.g., you want to access contents of cell without copying it out (maybe it's a struct that's not Copy)
- Enter: RefCell

RefCell<T>

```
pub const fn new(value: T) -> RefCell<T>
```

Looks similar...

```
pub fn borrow(&self) -> Ref<' , T>
```

- This is a dynamic borrow
- "The borrow lasts until the returned **Ref** exits scope. Multiple immutable borrows can be taken out at the same time...Panics if the value is currently mutably borrowed."

```
pub fn borrow_mut(&self) -> RefMut<'_, T>
```

- Note &self, not &mut self!
- "The borrow lasts until the returned RefMut or all RefMuts derived from it exit scope. The value cannot be borrowed while this borrow is active."

Ref and RefMut are only for use with RefCell

Ref<T> vs. &T

- Both Ref<T>, returned by borrow*, and &T, implement Deref
 - Code that uses them will be similar

ET

let x = 42;

```
let r = &x;
assert_eq!(*r, 42);

Ref<T>
let cell = RefCell::new(42);
let cell_ref : Ref<i32> = cell.borrow();
assert_eq!(*cell_ref, 42);
```

Static vs. Dynamic Borrow Tracking

- &T and &mut T: static (compile-time) tracked of borrows
- RefCell<T>::borrow*: dynamic (run-time) tracked of borrows
 pub fn borrow(&self) -> Ref<'_, T>
 pub fn borrow_mut(&self) -> RefMut<'_, T>
 - Ref<'_, T>, RefMut<'_, T> implement dynamic tracking
 of outstanding, borrowed references
 - If borrow mut() with an outstanding Ref, panic!
- Static tracking is better if you can make it work
 - no run time overhead; earlier bug detection

How Does Dynamic Borrowing Work?

- Each RefCell has a borrow count to track outstanding Refs and RefMuts for that RefCell
 - RefCell borrow and borrow_mut increment the count
 - When a Ref (or RefMut) goes out of scope, Rust calls drop(),
 which decrements the borrow count

```
use std::cell::RefCell;
let c = RefCell::new(5); // imm_count=0
let m = c.borrow(); // imm_count=1
let b = c.borrow_mut(); // panic!
```

Shared Mutable Data

- Back to the beginning: We were looking for a way to have shared, mutable data. How do we do it? Use Rc<RefCell<T>>
 - The RefCell permits mutating T (at risk of run-time borrow errors)
 - Rc permits sharing, e.g., within a data structure
- Note: Rc<RefCell<u32>> has two counts:
 - Reference count for Rc (should this RefCell be deallocated?)
 - Incremented via Rc::clone()
 - Dynamic version of lifetime
 - Borrow count for RefCell (are borrow(), borrow_mut() safe?)
 - Incremented via RefCell borrow and borrow mut
 - Dynamic version of borrow checking

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
let m = (*r1).borrow mut();
*m = 43;
println!("{:?}", *r2.borrow());
A. "42"
B. "43"
C. panic
D. Compiler error
```

D. Compiler error

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
let m = (*r1).borrow mut();
*m = 43;
println!("{:?}", *r2.borrow());
                 error[E0596]: cannot borrow `m` as mutable, as it is not declared as mutable
                  --> src/main.rs:10:10
A. "42"
                 9
                          let m = (*r1).borrow_mut();
                             - help: consider changing this to be mutable: `mut m`
B. "43"
                 10
                          *m = 43;
                           ^ cannot borrow as mutable
C. panic
```

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
let m = (*r1).borrow mut();
*m = 43;
println!("{:?}", *r2.borrow());
borrow_mut() returns a DerefMut
DerefMut:
  pub fn deref_mut(&mut self) -> &mut Self::Target
To mutate the referenced value, we need a mutable DerefMut
```

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
let mut m = (*r1).borrow mut();
*m = 43;
println!("{:?}", *r2.borrow());
A. "42"
B. "43"
C. panic
D. Compiler error
```

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
let mut m = (*r1).borrow mut();
*m = 43;
println!("{:?}", *r2.borrow());
A. "42"
B. "43"
C. panic
D. Compiler error
```

m's mutable borrow of the RefCell is still outstanding when borrow() is invoked.

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
   let mut m = (*r1).borrow mut();
   *m = 43;
println!("{:?}", *r2.borrow());
A. "42"
B. "43"
C. panic
```

```
let r1 = Rc::new(RefCell::new(42));
let r2 = r1.clone();
   let mut m = (*r1).borrow mut();
   *m = 43;
println!("{:?}", *r2.borrow());
A. "42"
B. "43"
C. panic
```

Summary

- From the book [1]:
 - Rc<T> enables multiple owners of the same data; Box<T> and RefCell<T> have single owners.
 - Box<T> allows immutable or mutable borrows checked at compile time; Rc<T> allows only immutable borrows checked at compile time; RefCell<T> allows immutable or mutable borrows checked at runtime.
 - Because RefCell<T> allows mutable borrows checked at runtime, you can mutate the value inside the RefCell<T> even when the RefCell<T> is immutable.

A Quick Summary

- &mut: use when you only need one mutable reference
- Rc: reference-counted, shared reference to the heap
- RefCell/Cell: mutable contents even when immutable
 - Borrowing via a special Ref value, which ensures that Rust's borrow checking rules are followed dynamically
 - Combine with Rc for shared mutability
- Ref/RefMut: only used for accessing RefCell.

Conclusions

- Ideally, design Rust programs so each value has one owner
 - But that's not always possible
 - Even when it is, those designs may have other costs
- When necessary, use **Rc**, **RefCell** to relax Rust's static constraints
 - Part of a programming discipline called interior mutability.
 - With great power comes great responsibility!