# C++ Programming - Advanced

Author: Peter Tse (mcreng)

Most of you may find this section less useful than the previous ones. Note that this section is target to those who wish to have a better understanding the smart car libraries (*libsccc*) since previous members have use the following skills to construct them. This section would be revolving around the concept of *class* we introduced in *Intermediate* tutorial and build upon it.

## Class

This is an example of a class in C++. Throughout this tutorial, we will build upon this class.

```
1
   class Motor{
2
   public:
3
     Motor(){} // constructor
      void SetPower(uint16 t power){
4
5
        OnSetPower(power); // the actions to really change the power in real life
6
       m power = power;
      } // setter of power
8
     uint16 t GetPower() { return m power; } // getter of power
9
      void SetClockwise(bool flag) {
        OnSetClockwise(flag); // the actions to really change the direction in real life
10
11
       m_is_clockwise = flag;
      } // setter of direction
12
13
      bool IsClockwise() { return m is clockwise; } // getter of direction
14
15
   private:
    bool m_is_clockwise;
16
17
     uint16_t m_power;
      void OnSetPower(const uint16 t power);
18
19
      void OnSetClockwise(const bool flag);
20
   };
```

## **Class Construction**

As you may remember from previous tutorial, you may either initialize the parameters through assignment or member initialization list. We prefer using member initialization list, so the code looks like this.

```
1
   class Motor{
2
    public:
      Motor(bool is_clockwise, uint16_t power) :
3
4
        m_is_clockwise(is_clockwise),
 5
        m_power(power){} // constructor
      void SetPower(uint16_t power){
 6
 7
        OnSetPower(power); // the actions to really change the power in real life
8
        m_power = power;
9
      } // setter of power
10
      uint16 t GetPower() { return m power; } // getter of power
      void SetClockwise(bool flag) {
11
12
        OnSetClockwise(flag); // the actions to really change the direction in real life
13
       m_is_clockwise = flag;
14
      } // setter of direction
15
      bool IsClockwise() { return m_is_clockwise; } // getter of direction
16
   private:
17
     bool m_is_clockwise;
18
19
      uint16_t m_power;
20
      void OnSetPower(const uint16_t power);
21
      void OnSetClockwise(const bool flag);
22
   };
```

The parameters of the constructor may look very clumsy as it may get a lot of initialization values for certain modules, so we prefer using a configuration struct to store all the settings.

```
1
    class Motor{
2
    public:
3
4
      struct Config{
5
        bool is_clockwise = true;
        uint16_t power = 0;
6
7
      };
8
9
      Motor(const Config& config):
10
        m is clockwise(config.is clockwise),
11
        m power(config.power){} // constructor
12
13
      void SetPower(uint16_t power){
14
        OnSetPower(power); // the actions to really change the power in real life
15
        m power = power;
16
      } // setter of power
      uint16_t GetPower() { return m_power; } // getter of power
17
      void SetClockwise(bool flag) {
18
19
        OnSetClockwise(flag); // the actions to really change the direction in real life
20
        m_is_clockwise = flag;
21
      } // setter of direction
      bool IsClockwise() { return m is clockwise; } // getter of direction
22
23
24
   private:
      bool m_is_clockwise;
25
      uint16 t m power;
26
      void OnSetPower(const uint16 t power);
27
28
      void OnSetClockwise(const bool flag);
29
   };
```

There will be different <code>Config</code> for different modules in libsccc, and for you to not confuse yourself when you do your code, we should limit you to explicitly construct the class (i.e. implicit type conversion is not allowed).

```
1
   class Motor{
2
    public:
3
      struct Config{
4
5
        bool is_clockwise = true;
        uint16_t power = 0;
6
7
8
9
      explicit Motor(const Config& config):
10
        m is clockwise(config.is clockwise),
11
        m power(config.power){} // constructor
12
      void SetPower(uint16_t power){
13
        OnSetPower(power); // the actions to really change the power in real life
14
15
        m power = power;
      } // setter of power
16
      uint16_t GetPower() { return m_power; } // getter of power
17
18
      void SetClockwise(bool flag) {
        OnSetClockwise(flag); // the actions to really change the direction in real life
19
20
        m is clockwise = flag;
      } // setter of direction
21
22
      bool IsClockwise() { return m is clockwise; } // getter of direction
23
24
   private:
25
      bool m_is_clockwise;
26
      uint16 t m power;
27
      void OnSetPower(const uint16 t power);
28
      void OnSetClockwise(const bool flag);
29
   };
```

This would be the results.

```
Motor::Config config;
Motor bad_motor = config; // invalid due to explicit specifier
Motor motor(config); // valid
```

# **Inheritance**

Let's say now we wish to implement a *proportional* controller (part of *PID*) to the motor, hopefully in mechanical tutorials it has been covered, but nevertheless here is the recap. Suppose we have an encoder to read the motor output and found that there is an error to the target output *error*, using the proportional controller we can tell the motor to correct its power output in next duty cycle with new power  $k_p \cdot error$ .

To do so, we can *inherit* the original class and add the controllers upon it.

```
1
   class MotorController : Motor{
2
    public:
3
      struct Config : Motor::Config{ // inherited the Config inside Motor
4
5
        float kp;
        float target;
6
7
8
9
      MotorController(const Config& config) : // constructor
10
         m kp(config.kp),
11
         m target(config.target),
         Motor(config){} // to specify the Motor object constructor for inheritance
12
13
      void SetKp(float kp) { m kp = kp; } // setter for Kp
14
15
      float GetKp() { return m_kp; } // getter for Kp
16
17
      void SetTarget(float target) { m_target = target; } // setter for target
18
      float GetTarget() { return m_target; } // getter for target
19
20
      void Control(float actual){ SetPower(Calc(actual)); } // controller
21
22
    private:
23
     float m_target;
     float m_kp;
24
25
     float m_p;
     float Calc(float actual){ // P controller
26
27
        float error = m target - actual;
28
       m_p = m_k p * error;
29
       return m_p;
30
     }
31
   };
```

Here you may see two inheritance (specified with the : operator), one is for struct and one is for class. The meaning of inheritance is to copy the original class or struct and add things into it. For example, for MotorController::Config , it is different from Motor::Config by two members, kp and target. Both would also have the members is\_clockwise and power. For MotorController, it would also keep the functions SetPower(), GetPower(), etc. Some terminologies, after inheritance, we may call Motor the base class and MotorController the derived class.

Inside the member initialization list, Motor(config) is specified for the compiler to call its corresponding constructor for Motor. If it is not specified, it would try to call Motor() as the constructor, and since there is no definition for it in class Motor, the compiler returns an error.

#### **Public Inheritance vs Private Inheritance**

As you may remember from Intermediate tutorial, the default visibility for the members in struct is public and that of class is private. Here we also have the same difference, in config it is defaulted to have public inheritance while for class it is private. From the table below you may understand the difference between the two.

Publicity in base class	Public	Private
Public Inheritance	Public	Private
Private Inheritance	Private	Private

That means, for MotorController::Config, all its members from its bass class would still be publicly accessible, and for MotorController, the members from its base class would all be private. This allows the Config to just extend itself and the MotorController to not use the original functions to mess up the setup. For the example above, only inside MotorController we can access the function SetPower(). If we wish to access it outside the class, we can force it to be a public inheritance.

```
class MotorController : public Motor{ // now public inheritance
    /* ... */
};
```

#### **Overload**

You may also wish to overload some functions in the base class.

```
class MotorContoller : public Motor{
    /* ... */
    void SetPower(uint16_t power); // overload of base class, objects of derived class will use this instead
    /* ... */
};
```

# **Polymorphism**

In real life, we have two types of motor: alternate motors and direction motors, and they each work different in terms of how we change their directions and powers. So, they should have similar structures when representing both of them in C++ class syntax. Therefore, it is good to have some sort of *template* for both of the class, and let both of the class somehow inherit from the template. This is a concept of *polymorphism*, that we can build some classes with similar features with an *abstract class*.

Here we rewrite the class Motor to serve this exact purpose.

```
1
    class Motor{
2
    public:
3
4
      struct Config{
5
        bool is_clockwise = true;
        uint16_t power = 0;
6
7
      };
8
9
      explicit Motor(const Config& config):
10
        m is clockwise(config.is clockwise),
11
        m power(config.power){} // constructor
12
      void SetPower(uint16_t power){
13
        OnSetPower(power); // the actions to really change the power in real life
14
15
        m power = power;
      } // setter of power
16
      uint16_t GetPower() { return m_power; } // getter of power
17
      void SetClockwise(bool flag) {
18
        OnSetClockwise(flag); // the actions to really change the direction in real life
19
20
        m_is_clockwise = flag;
      } // setter of direction
21
      bool IsClockwise() { return m_is_clockwise; } // getter of direction
22
23
24
   private:
25
      bool m_is_clockwise;
26
      uint16 t m power;
27
      virtual void OnSetPower(const uint16 t power) = 0; // pure virtual function
      virtual void OnSetClockwise(const bool flag) = 0; // pure virtual function
28
29
   };
```

When marking some certain functions in a class with virtual keyword and declare it being 0, we have an abstract class in place. We cannot construct abstract classes.

```
Motor::Config config;
Motor motor(config); // illegal
```

Then, we can inherit this abstract class and overload the functions <code>OnSetPower()</code> and <code>OnSetClockwise()</code> since they work differently in both types of motor.

```
1 class AlternateMotor : public Motor{
 2
   public:
     AlternateMotor(const Motor::Config& config) : Motor(config){}
 3
     void OnSetPower(const uint16_t power) { /* ... */ }
    void OnSetClockwise(const bool flag) { /* ... */ }
 6
7
   };
8
9 class DirMotor : public Motor{
10 public:
    DirMotor(const Motor::Config& config) : Motor(config){}
11
12 private:
    void OnSetPower(const uint16_t power) { /* ... */ }
13
    void OnSetClockwise(const bool flag) { /* ... */ }
14
15 };
```

Both of them would have all the functions defined in Motor, with each has different implementations of OnSetPower() and OnSetClockwise().

### **Abstract Class Pointer**

For the MotorController() class, inheritance is no longer an option since Motor is now an abstract class. If you really wish to use inheritance for this, you can inherit once for each type of motor. Yet, it is actually better include a pointer to the motor objects and control the motor through this.

```
class MotorController{
public:
    /* ... */
private:
    /* ... */
Motor* p_motor = nullptr;
};
```

Here we can just use Motor\* to represent all possible types of motor class that inherit Motor.

```
Motor::Config config;
AlternateMotor m1(config);
DirMotor m2(config);
// note that m1 and m2 have different type
Motor* p_motor = nullptr;
p_motor = &m1; // valid, Motor* can point towards AlternateMotor
p_motor = &m2; // also valid, Motor* can point towards DirMotor
```

# **Generic Programming**

Inside MotorController, we used float to store all  $k_P$ , error and target value. However, sometimes we may require double, and sometimes int would do. To make the class as easy to alter as it could, we may use *generic programming* for this. In short, generic programming is about making the variable types changeable.

```
template <typename T> // or template <class T>, here we define some type T, and we can
    replace all float with T
   class MotorController{
2
   public:
3
4
     /* ··· */
5
      void SetKp(T kp) { m_kp = kp; } // setter for Kp
6
7
      T GetKp() { return m kp; } // getter for Kp
8
9
      void SetTarget(T target) { m_target = target; } // setter for target
10
      T GetTarget() { return m_target; } // getter for target
11
12
      void Control(T actual){ SetPower(Calc(actual)); } // controller
13
14
   private:
15
     T m_target;
16
     T m kp;
17
      T m p;
     T Calc(T actual){ // P controller
18
19
        T error = m_target - actual;
       m_p = m_k p * error;
20
21
       return m_p;
22
     }
23
      /* · · · */
24
25
   };
```

Codes that are related to template (generic programming) are sometimes stored in .tcc files under \inc (same place with .h files).

For the MotorController that we just updated, we can construct one of these objects with syntax

```
1 | MotorController<float> motor_controller(...);
```

In fact, you can define more than two types.

```
1 | template <typename T, typename U>
```

and the types that we feed in will be in order.

You may define default type for the template with

```
1 | template <typename T = int>
```

and you may construct the class with

```
1 | MotorController<>> motor_controller(...); // <> must be present
```

to specify it is constructed under default type.

You may even apply the concept of generic programming into the definition of functions.

```
1
   #include <iostream>
2
  template <typename T>
3
  T max(T a, T b) { return a > b ? a : b; }
4
5
  int main() {
6
       std::cout << max(1, 2) << " " << max('a', 'S');
7
       return 0;
8
   } // output: 2 a
9
```