Programming Language—Common Lisp

9. Conditions

9.1 Condition System Concepts

Common Lisp constructs are described not only in terms of their behavior in situations during which they are intended to be used (see the "Description" part of each *operator* specification), but in all other situations (see the "Exceptional Situations" part of each *operator* specification).

A situation is the evaluation of an expression in a specific context. A condition is an object that represents a specific situation that has been detected. Conditions are generalized instances of the class condition. A hierarchy of condition classes is defined in Common Lisp. A condition has slots that contain data relevant to the situation that the condition represents.

An error is a situation in which normal program execution cannot continue correctly without some form of intervention (either interactively by the user or under program control). Not all errors are detected. When an error goes undetected, the effects can be *implementation-dependent*, *implementation-defined*, unspecified, or undefined. See Section 1.4 (Definitions). All detected errors can be represented by *conditions*, but not all *conditions* represent errors.

Signaling is the process by which a *condition* can alter the flow of control in a program by raising the *condition* which can then be *handled*. The functions **error**, **cerror**, **signal**, and **warn** are used to signal *conditions*.

The process of signaling involves the selection and invocation of a *handler* from a set of *active handlers*. A *handler* is a *function* of one argument (the *condition*) that is invoked to handle a *condition*. Each *handler* is associated with a *condition type*, and a *handler* will be invoked only on a *condition* of the *handler*'s associated *type*.

Active handlers are established dynamically (see handler-bind or handler-case). Handlers are invoked in a dynamic environment equivalent to that of the signaler, except that the set of active handlers is bound in such a way as to include only those that were active at the time the handler being invoked was established. Signaling a condition has no side-effect on the condition, and there is no dynamic state contained in a condition.

If a handler is invoked, it can address the situation in one of three ways:

Decline

It can decline to handle the condition. It does this by simply returning rather than transferring control. When this happens, any values returned by the handler are ignored and the next most recently established handler is invoked. If there is no such handler and the signaling function is **error** or **cerror**, the debugger is entered in the dynamic environment of the signaler. If there is no such handler and the signaling function is either **signal** or **warn**, the signaling function simply returns **nil**.

Handle

It can *handle* the *condition* by performing a non-local transfer of control. This can be done either primitively by using **go**, **return**, **throw** or more abstractly by using a function such as **abort** or **invoke-restart**.

Defer

It can put off a decision about whether to *handle* or *decline*, by any of a number of actions, but most commonly by signaling another condition, resignaling the same condition, or forcing entry into the debugger.

9.1.1 Condition Types

Figure 9–1 lists the *standardized condition types*. Additional *condition types* can be defined by using **define-condition**.

arithmetic-error	floating-point-overflow	${f simple-type-error}$
cell-error	floating-point-underflow	simple-warning
condition	package-error	${f storage} ext{-condition}$
control-error	parse-error	stream-error
division-by-zero	print-not-readable	style-warning
end-of-file	program-error	type-error
error	reader-error	${f unbound-slot}$
file-error	serious-condition	unbound-variable
floating-point-inexact	${f simple-condition}$	undefined-function
floating-point-invalid-operation	simple-error	warning

Figure 9-1. Standardized Condition Types

All condition types are subtypes of type condition. That is,

(typep c 'condition) ightarrow true

if and only if c is a condition.

Implementations must define all specified subtype relationships. Except where noted, all subtype relationships indicated in this document are not mutually exclusive. A condition inherits the structure of its supertypes.

The metaclass of the *class* condition is not specified. *Names* of *condition types* may be used to specify *supertype* relationships in **define-condition**, but the consequences are not specified if an attempt is made to use a *condition type* as a *superclass* in a **defclass** *form*.

Figure 9–2 shows operators that define $condition\ types$ and creating conditions.

define-condition	make-condition	

Figure 9-2. Operators that define and create conditions.

Figure 9–3 shows operators that read the value of condition slots.

arithmetic-error-operands	simple-condition-format-arguments
arithmetic-error-operation	simple-condition-format-control
cell-error-name	stream-error-stream
file-error-pathname	type-error-datum
package-error-package	type-error-expected-type
print-not-readable-object	unbound-slot-instance

Figure 9-3. Operators that read condition slots.

9.1.1.1 Serious Conditions

A serious condition is a condition serious enough to require interactive intervention if not handled. Serious conditions are typically signaled with **error** or **cerror**; non-serious conditions are typically signaled with **signal** or **warn**.

9.1.2 Creating Conditions

The function **make-condition** can be used to construct a *condition object* explicitly. Functions such as **error**, **cerror**, **signal**, and **warn** operate on *conditions* and might create *condition objects* implicitly. Macros such as **ccase**, **ctypecase**, **ecase**, **etypecase**, **check-type**, and **assert** might also implicitly create (and *signal*) *conditions*.

9.1.2.1 Condition Designators

A number of the functions in the condition system take arguments which are identified as **condition designators**. By convention, those arguments are notated as

datum &rest arguments

Taken together, the *datum* and the *arguments* are "*designators* for a *condition* of default type *default-type*." How the denoted *condition* is computed depends on the type of the *datum*:

• If the *datum* is a *symbol* naming a *condition type* . . .

The denoted *condition* is the result of

(apply #'make-condition datum arguments)

• If the datum is a format control ...

The denoted *condition* is the result of

where the *defaulted-type* is a *subtype* of *default-type*.

• If the *datum* is a *condition* . . .

The denoted *condition* is the *datum* itself. In this case, unless otherwise specified by the description of the *operator* in question, the *arguments* must be *null*; that is, the consequences are undefined if any *arguments* were supplied.

Note that the *default-type* gets used only in the case where the *datum string* is supplied. In the other situations, the resulting condition is not necessarily of *type default-type*.

Here are some illustrations of how different *condition designators* can denote equivalent *condition objects*:

9.1.3 Printing Conditions

If the :report argument to define-condition is used, a print function is defined that is called whenever the defined *condition* is printed while the *value* of *print-escape* is *false*. This function is called the *condition reporter*; the text which it outputs is called a *report message*.

When a *condition* is printed and ***print-escape*** is *false*, the *condition reporter* for the *condition* is invoked. *Conditions* are printed automatically by functions such as **invoke-debugger**, **break**, and **warn**.

When ***print-escape*** is *true*, the *object* should print in an abbreviated fashion according to the style of the implementation (*e.g.*, by **print-unreadable-object**). It is not required that a *condition* can be recreated by reading its printed representation.

No function is provided for directly accessing or invoking condition reporters.

9.1.3.1 Recommended Style in Condition Reporting

In order to ensure a properly aesthetic result when presenting *report messages* to the user, certain stylistic conventions are recommended.

There are stylistic recommendations for the content of the messages output by *condition reporters*, but there are no formal requirements on those *programs*. If a *program* violates the recommendations for some message, the display of that message might be less aesthetic than if the guideline had been observed, but the *program* is still considered a *conforming program*.

The requirements on a program or implementation which invokes a condition reporter are somewhat stronger. A conforming program must be permitted to assume that if these style guidelines are followed, proper aesthetics will be maintained. Where appropriate, any specific requirements on such routines are explicitly mentioned below.

9.1.3.1.1 Capitalization and Punctuation in Condition Reports

It is recommended that a *report message* be a complete sentences, in the proper case and correctly punctuated. In English, for example, this means the first letter should be uppercase, and there should be a trailing period.

```
(error "This is a message") ; Not recommended
(error "this is a message.") ; Not recommended
(error "This is a message.") ; Recommended instead
```

9.1.3.1.2 Leading and Trailing Newlines in Condition Reports

It is recommended that a *report message* not begin with any introductory text, such as "Error: " or "Warning: " or even just *freshline* or *newline*. Such text is added, if appropriate to the context, by the routine invoking the *condition reporter*.

It is recommended that a *report message* not be followed by a trailing *freshline* or *newline*. Such text is added, if appropriate to the context, by the routine invoking the *condition reporter*.

```
(error "This is a message.~%") ; Not recommended
(error "~&This is a message.") ; Not recommended
(error "~&This is a message.~%") ; Not recommended
(error "This is a message.") ; Recommended instead
```

9.1.3.1.3 Embedded Newlines in Condition Reports

Especially if it is long, it is permissible and appropriate for a *report message* to contain one or more embedded *newlines*.

If the calling routine conventionally inserts some additional prefix (such as "Error: " or ";; Error: ") on the first line of the message, it must also assure that an appropriate prefix

will be added to each subsequent line of the output, so that the left edge of the message output by the *condition reporter* will still be properly aligned.

9.1.3.1.4 Note about Tabs in Condition Reports

Because the indentation of a report message might be shifted to the right or left by an arbitrary amount, special care should be taken with the semi-standard character $\langle Tab \rangle$ (in those implementations that support such a character). Unless the implementation specifically defines its behavior in this context, its use should be avoided.

9.1.3.1.5 Mentioning Containing Function in Condition Reports

The name of the containing function should generally not be mentioned in *report messages*. It is assumed that the *debugger* will make this information accessible in situations where it is necessary and appropriate.

9.1.4 Signaling and Handling Conditions

The operation of the condition system depends on the ordering of active applicable handlers from most recent to least recent.

Each handler is associated with a type specifier that must designate a subtype of type condition. A handler is said to be applicable to a condition if that condition is of the type designated by the associated type specifier.

Active handlers are established by using handler-bind (or an abstraction based on handler-bind, such as handler-case or ignore-errors).

Active handlers can be established within the dynamic scope of other active handlers. At any point during program execution, there is a set of active handlers. When a condition is signaled,

the most recent active applicable handler for that condition is selected from this set. Given a condition, the order of recentness of active applicable handlers is defined by the following two rules:

- 1. Each handler in a set of active handlers H_1 is more recent than every handler in a set H_2 if the handlers in H_2 were active when the handlers in H_1 were established.
- 2. Let h_1 and h_2 be two applicable active handlers established by the same form. Then h_1 is more recent than h_2 if h_1 was defined to the left of h_2 in the form that established them.

Once a handler in a handler binding form (such as handler-bind or handler-case) has been selected, all handlers in that form become inactive for the remainder of the signaling process. While the selected handler runs, no other handler established by that form is active. That is, if the handler declines, no other handler established by that form will be considered for possible invocation.

Figure 9–4 shows operators relating to the handling of conditions.

handler-bind handler-case	ignore-errors
---------------------------	---------------

Figure 9-4. Operators relating to handling conditions.

9.1.4.1 Signaling

When a *condition* is signaled, the most recent applicable *active handler* is invoked. Sometimes a handler will decline by simply returning without a transfer of control. In such cases, the next most recent applicable active handler is invoked.

If there are no applicable handlers for a *condition* that has been signaled, or if all applicable handlers decline, the *condition* is unhandled.

The functions **cerror** and **error** invoke the interactive *condition* handler (the debugger) rather than return if the *condition* being signaled, regardless of its *type*, is unhandled. In contrast, **signal** returns **nil** if the *condition* being signaled, regardless of its *type*, is unhandled.

The *variable* *break-on-signals* can be used to cause the debugger to be entered before the signaling process begins.

Figure 9–5 shows defined names relating to the signaling of conditions.

break-on-signals	error	warn	
cerror	\mathbf{signal}		

Figure 9-5. Defined names relating to signaling conditions.

9.1.4.1.1 Resignaling a Condition

During the *dynamic extent* of the *signaling* process for a particular *condition object*, **signaling** the same *condition object* again is permitted if and only if the *situation* represented in both cases are the same.

For example, a handler might legitimately signal the condition object that is its argument in order to allow outer handlers first opportunity to handle the condition. (Such a handlers is sometimes called a "default handler.") This action is permitted because the situation which the second signaling process is addressing is really the same situation.

On the other hand, in an *implementation* that implemented asynchronous keyboard events by interrupting the user process with a call to **signal**, it would not be permissible for two distinct asynchronous keyboard events to *signal identical condition objects* at the same time for different situations.

9.1.4.2 Restarts

The interactive condition handler returns only through non-local transfer of control to specially defined *restarts* that can be set up either by the system or by user code. Transferring control to a restart is called "invoking" the restart. Like handlers, active *restarts* are *established* dynamically, and only active *restarts* can be invoked. An active *restart* can be invoked by the user from the debugger or by a program by using **invoke-restart**.

A restart contains a function to be called when the restart is invoked, an optional name that can be used to find or invoke the restart, and an optional set of interaction information for the debugger to use to enable the user to manually invoke a restart.

The name of a *restart* is used by **invoke-restart**. *Restarts* that can be invoked only within the debugger do not need names.

Restarts can be established by using **restart-bind**, **restart-case**, and **with-simple-restart**. A restart function can itself invoke any other restart that was active at the time of establishment of the restart of which the function is part.

The restarts established by a restart-bind form, a restart-case form, or a with-simple-restart form have dynamic extent which extends for the duration of that form's execution.

Restarts of the same name can be ordered from least recent to most recent according to the following two rules:

- 1. Each restart in a set of active restarts R_1 is more recent than every restart in a set R_2 if the restarts in R_2 were active when the restarts in R_1 were established.
- 2. Let r_1 and r_2 be two active *restarts* with the same name established by the same *form*. Then r_1 is more recent than r_2 if r_1 was defined to the left of r_2 in the *form* that established them.

If a *restart* is invoked but does not transfer control, the values resulting from the *restart* function are returned by the function that invoked the restart, either **invoke-restart** or **invoke-restart-interactively**.

9.1.4.2.1 Interactive Use of Restarts

For interactive handling, two pieces of information are needed from a *restart*: a report function and an interactive function.

The report function is used by a program such as the debugger to present a description of the action the *restart* will take. The report function is specified and established by the :report-function keyword to restart-bind or the :report keyword to restart-case.

The interactive function, which can be specified using the :interactive-function keyword to restart-bind or :interactive keyword to restart-case, is used when the *restart* is invoked interactively, such as from the debugger, to produce a suitable list of arguments.

invoke-restart invokes the most recently *established restart* whose name is the same as the first argument to **invoke-restart**. If a *restart* is invoked interactively by the debugger and does not transfer control but rather returns values, the precise action of the debugger on those values is *implementation-defined*.

9.1.4.2.2 Interfaces to Restarts

Some restarts have functional interfaces, such as abort, continue, muffle-warning, store-value, and use-value. They are ordinary functions that use find-restart and invoke-restart internally, that have the same name as the restarts they manipulate, and that are provided simply for notational convenience.

Figure 9–6 shows defined names relating to restarts.

abort compute-restarts continue	invoke-restart-interactively muffle-warning restart-bind	store-value use-value with-simple-restart
find-restart	restart-case	
invoke-restart	restart-name	

Figure 9–6. Defined names relating to restarts.

9.1.4.2.3 Restart Tests

Each restart has an associated test, which is a function of one argument (a condition or nil) which returns true if the restart should be visible in the current situation. This test is created by the :test-function option to restart-bind or the :test option to restart-case.

9.1.4.2.4 Associating a Restart with a Condition

A restart can be "associated with" a condition explicitly by with-condition-restarts, or implicitly by restart-case. Such an association has dynamic extent.

A single restart may be associated with several conditions at the same time. A single condition may have several associated restarts at the same time.

Active restarts associated with a particular *condition* can be detected by *calling* a *function* such as **find-restart**, supplying that *condition* as the *condition* argument. Active restarts can also be detected without regard to any associated *condition* by calling such a function without a *condition* argument, or by supplying a value of **nil** for such an argument.

9.1.5 Assertions

Conditional signaling of *conditions* based on such things as key match, form evaluation, and *type* are handled by assertion *operators*. Figure 9–7 shows *operators* relating to assertions.

assert	check-type	ecase	
ccase	ctypecase	etypecase	

Figure 9-7. Operators relating to assertions.

9.1.6 Notes about the Condition System's Background

For a background reference to the abstract concepts detailed in this section, see *Exceptional Situations in Lisp*. The details of that paper are not binding on this document, but may be helpful in establishing a conceptual basis for understanding this material.

condition Condition Type

Class Precedence List:

condition, t

Description:

All types of *conditions*, whether error or non-error, must inherit from this *type*.

No additional *subtype* relationships among the specified *subtypes* of *type* **condition** are allowed, except when explicitly mentioned in the text; however implementations are permitted to introduce additional *types* and one of these *types* can be a *subtype* of any number of the *subtypes* of *type* **condition**.

Whether a user-defined condition type has slots that are accessible by with-slots is implementation-dependent. Furthermore, even in an implementation in which user-defined condition types would have slots, it is implementation-dependent whether any condition types defined in this document have such slots or, if they do, what their names might be; only the reader functions documented by this specification may be relied upon by portable code.

Conforming code must observe the following restrictions related to conditions:

- define-condition, not defclass, must be used to define new condition types.
- make-condition, not make-instance, must be used to create *condition objects* explicitly.
- The :report option of define-condition, not defmethod for print-object, must be used to define a condition reporter.
- slot-value, slot-boundp, slot-makunbound, and with-slots must not be used on *condition objects*. Instead, the appropriate accessor functions (defined by define-condition) should be used.

warning Condition Type

Class Precedence List:

warning, condition, t

Description:

The type warning consists of all types of warnings.

See Also:

style-warning

style-warning

Condition Type

Class Precedence List:

style-warning, warning, condition, t

Description:

The type style-warning includes those conditions that represent situations involving code that is conforming code but that is nevertheless considered to be faulty or substandard.

See Also:

muffle-warning

Notes:

An *implementation* might signal such a *condition* if it encounters *code* that uses deprecated features or that appears unaesthetic or inefficient.

An 'unused variable' warning must be of type style-warning.

In general, the question of whether *code* is faulty or substandard is a subjective decision to be made by the facility processing that *code*. The intent is that whenever such a facility wishes to complain about *code* on such subjective grounds, it should use this *condition type* so that any clients who wish to redirect or muffle superfluous warnings can do so without risking that they will be redirecting or muffling other, more serious warnings.

serious-condition

Condition Type

Class Precedence List:

serious-condition, condition, t

Description:

All *conditions* serious enough to require interactive intervention if not handled should inherit from the *type* **serious-condition**. This condition type is provided primarily so that it may be included as a *superclass* of other *condition types*; it is not intended to be signaled directly.

Notes:

Signaling a *serious condition* does not itself force entry into the debugger. However, except in the unusual situation where the programmer can assure that no harm will come from failing to *handle*

a serious condition, such a condition is usually signaled with **error** rather than **signal** in order to assure that the program does not continue without handling the condition. (And conversely, it is conventional to use **signal** rather than **error** to signal conditions which are not serious conditions, since normally the failure to handle a non-serious condition is not reason enough for the debugger to be entered.)

error Condition Type

Class Precedence List:

error, serious-condition, condition, t

Description:

The type error consists of all conditions that represent errors.

cell-error Condition Type

Class Precedence List:

cell-error, error, serious-condition, condition, t

Description:

The type cell-error consists of error conditions that occur during a location access. The name of the offending cell is initialized by the :name initialization argument to make-condition, and is accessed by the function cell-error-name.

See Also:

cell-error-name

cell-error-name

Function

Syntax:

 $\textbf{cell-error-name} \,\, \textit{condition} \,\,\, \rightarrow \textit{name}$

Arguments and Values:

condition—a condition of type cell-error.

name—an object.

Description:

Returns the name of the offending cell involved in the situation represented by condition.

The nature of the result depends on the specific type of condition. For example, if the condition is of type unbound-variable, the result is the name of the unbound variable which was being accessed, if the condition is of type undefined-function, this is the name of the undefined function which was being accessed, and if the condition is of type unbound-slot, this is the name of the slot which was being accessed.

See Also:

 $\begin{array}{lll} \textbf{cell-error}, \textbf{ unbound-slot}, \textbf{ unbound-variable}, \textbf{ undefined-function}, Section \ 9.1 \ (Condition \ System \ Concepts) \end{array}$

parse-error

Condition Type

Class Precedence List:

parse-error, error, serious-condition, condition, t

Description:

The type parse-error consists of error conditions that are related to parsing.

See Also:

parse-namestring, reader-error

storage-condition

Condition Type

Class Precedence List:

storage-condition, serious-condition, condition, t

Description:

The type storage-condition consists of serious conditions that relate to problems with memory management that are potentially due to *implementation-dependent* limits rather than semantic errors in *conforming programs*, and that typically warrant entry to the debugger if not handled. Depending on the details of the *implementation*, these might include such problems as stack overflow, memory region overflow, and storage exhausted.

Notes:

While some Common Lisp operations might signal *storage-condition* because they are defined to create *objects*, it is unspecified whether operations that are not defined to create *objects* create them anyway and so might also signal **storage-condition**. Likewise, the evaluator itself might create *objects* and so might signal **storage-condition**. (The natural assumption might be that such *object* creation is naturally inefficient, but even that is *implementation-dependent*.) In general, the entire question of how storage allocation is done is *implementation-dependent*, and so any operation might signal **storage-condition** at any time. Because such a *condition* is indicative of a limitation of the *implementation* or of the *image* rather than an error in a *program*, *objects* of type **storage-condition** are not of type **error**.

assert

Syntax:

```
assert test-form [(\{place\}^*) [datum-form \{argument-form\}^*]]
```

Arguments and Values:

test-form—a form; always evaluated.

place—a place; evaluated if an error is signaled.

datum-form—a form that evaluates to a datum. Evaluated each time an error is to be signaled, or not at all if no error is to be signaled.

argument-form—a form that evaluates to an argument. Evaluated each time an error is to be signaled, or not at all if no error is to be signaled.

datum, arguments—designators for a condition of default type error. (These designators are the result of evaluating datum-form and each of the argument-forms.)

assert

Description:

assert assures that test-form evaluates to true. If test-form evaluates to false, assert signals a correctable error (denoted by datum and arguments). Continuing from this error using the continue restart makes it possible for the user to alter the values of the places before assert evaluates test-form again. If the value of test-form is non-nil, assert returns nil.

The *places* are *generalized references* to data upon which *test-form* depends, whose values can be changed by the user in attempting to correct the error. *Subforms* of each *place* are only evaluated if an error is signaled, and might be re-evaluated if the error is re-signaled (after continuing without actually fixing the problem). The order of evaluation of the *places* is not specified; see Section 5.1.1.1 (Evaluation of Subforms to Places). If a *place form* is supplied that produces more values than there are store variables, the extra values are ignored. If the supplied *form* produces fewer values than there are store variables, the missing values are set to nil.

Examples:

```
(setq x (make-array '(3 5) :initial-element 3))
\rightarrow #2A((3 3 3 3 3) (3 3 3 3) (3 3 3 3))
 (setq y (make-array '(3 5) :initial-element 7))
\rightarrow #2A((7 7 7 7 7) (7 7 7 7 7) (7 7 7 7 7))
 (defun matrix-multiply (a b)
   (let ((*print-array* nil))
     (assert (and (= (array-rank a) (array-rank b) 2)
                   (= (array-dimension a 1) (array-dimension b 0)))
              "Cannot multiply ~S by ~S." a b)
             (\texttt{really-matrix-multiply a b))) \ \to \ \texttt{MATRIX-MULTIPLY}
 (matrix-multiply x y)
▷ Correctable error in MATRIX-MULTIPLY:

    Cannot multiply #<ARRAY ...> by #<ARRAY ...>.
▷ Restart options:
▷ 1: You will be prompted for one or more new values.
▷ 2: Top level.
▷ Debug> :continue 1
\triangleright Value for A: \underline{x}

    ▷ Value for B: (make-array '(5 3) :initial-element 6)

\rightarrow #2A((54 54 54 54 54)
       (54 54 54 54 54)
       (54 54 54 54 54)
       (54 54 54 54 54)
       (54 54 54 54 54))
 (defun double-safely (x) (assert (numberp x) (x)) (+ x x))
 (double-safely 4)
→ 8
```

```
(double-safely t)
▷ Correctable error in DOUBLE-SAFELY: The value of (NUMBERP X) must be non-NIL.
▷ Restart options:
▷ 1: You will be prompted for one or more new values.
▷ 2: Top level.
▷ Debug> :continue 1
▷ Value for X: 7
→ 14
```

Affected By:

break-on-signals

The set of active condition handlers.

See Also:

check-type, error, Section 5.1 (Generalized Reference)

Notes:

The debugger need not include the *test-form* in the error message, and the *places* should not be included in the message, but they should be made available for the user's perusal. If the user gives the "continue" command, the values of any of the references can be altered. The details of this depend on the implementation's style of user interface.

error Function

Syntax:

error datum &rest arguments \rightarrow

Arguments and Values:

datum, arguments—designators for a condition of default type simple-error.

Description:

error effectively invokes signal on the denoted condition.

If the *condition* is not handled, (invoke-debugger *condition*) is done. As a consequence of calling invoke-debugger, error cannot directly return; the only exit from error can come by non-local transfer of control in a handler or by use of an interactive debugging command.

Examples:

error

```
(t (* x (factorial (- x 1))))))

ightarrow FACTORIAL
(factorial 20)

ightarrow 2432902008176640000
(factorial -1)
▷ Error: -1 is not a valid argument to FACTORIAL.
> To continue, type :CONTINUE followed by an option number:

hd \ 	ext{1: Return to Lisp Toplevel.}
▷ Debug>
 (setq a 'fred)

ightarrow FRED
 (if (numberp a) (1+ a) (error "~S is not a number." A))
▷ Error: FRED is not a number.
\triangleright To continue, type :CONTINUE followed by an option number:
▷ 1: Return to Lisp Toplevel.
\triangleright Debug> :Continue 1
▷ Return to Lisp Toplevel.
 (define-condition not-a-number (error)
                    ((argument :reader not-a-number-argument :initarg :argument))
   (:report (lambda (condition stream)
               (format stream "~S is not a number."
                        (not-a-number-argument condition)))))

ightarrow NOT-A-NUMBER
 (if (numberp a) (1+ a) (error 'not-a-number :argument a))
▷ Error: FRED is not a number.

hd To continue, type :CONTINUE followed by an option number:
▷ 1: Return to Lisp Toplevel.
▷ Debug> :Continue 1
▷ Return to Lisp Toplevel.
```

Side Effects:

Handlers for the specified condition, if any, are invoked and might have side effects. Program execution might stop, and the debugger might be entered.

Affected By:

Existing handler bindings.

break-on-signals

Signals an error of type type-error if datum and arguments are not designators for a condition.

See Also:

cerror, signal, format, ignore-errors, *break-on-signals*, handler-bind, Section 9.1 (Condition

9–18 Programming Language—Common Lisp

System Concepts)

Notes:

Some implementations may provide debugger commands for interactively returning from individual stack frames. However, it should be possible for the programmer to feel confident about writing code like:

```
(defun wargames:no-win-scenario ()
  (if (error "pushing the button would be stupid."))
  (push-the-button))
```

In this scenario, there should be no chance that error will return and the button will get pushed.

While the meaning of this program is clear and it might be proven 'safe' by a formal theorem prover, such a proof is no guarantee that the program is safe to execute. Compilers have been known to have bugs, computers to have signal glitches, and human beings to manually intervene in ways that are not always possible to predict. Those kinds of errors, while beyond the scope of the condition system to formally model, are not beyond the scope of things that should seriously be considered when writing code that could have the kinds of sweeping effects hinted at by this example.

cerror Function

Syntax:

cerror continue-format-control datum &rest arguments ightarrow nil

Arguments and Values:

Continue-format-control—a format control.

datum, arguments—designators for a condition of default type simple-error.

Description:

cerror effectively invokes **error** on the *condition* named by *datum*. As with any function that implicitly calls **error**, if the *condition* is not handled, (invoke-debugger *condition*) is executed. While signaling is going on, and while in the debugger if it is reached, it is possible to continue code execution (*i.e.*, to return from **cerror**) using the **continue** restart.

If datum is a condition, arguments can be supplied, but are used only in conjunction with the continue-format-control.

Examples:

```
(defun real-sqrt (n)
  (when (minusp n)
        (setq n (- n))
```

cerror

```
(\texttt{cerror "Return sqrt(\tilde{\ }D) instead." "Tried to take sqrt(\tilde{\ }D)." n)})
   (sqrt n))
 (real-sqrt 4)

ightarrow 2.0
 (real-sqrt -9)
\triangleright Correctable error in REAL-SQRT: Tried to take sqrt(-9).
▷ Restart options:
\triangleright 1: Return sqrt(9) instead.
▷ 2: Top level.
▷ Debug> :continue 1

ightarrow 3.0
 (define-condition not-a-number (error)
   ((argument :reader not-a-number-argument :initarg :argument))
   (:report (lambda (condition stream)
                (format stream "~S is not a number."
                         (not-a-number-argument condition)))))
 (defun assure-number (n)
   (loop (when (numberp n) (return n))
          (cerror "Enter a number."
                   'not-a-number :argument n)
          (format t "~&Type a number: ")
          (setq n (read))
          (fresh-line)))
 (assure-number 'a)
\,\vartriangleright\, Correctable error in ASSURE-NUMBER: A is not a number.
▷ Restart options:
\triangleright 1: Enter a number.
▷ 2: Top level.
▷ Debug> :continue 1
\triangleright Type a number: 1/2
\rightarrow 1/2
 (defun assure-large-number (n)
   (loop (when (and (numberp n) (> n 73)) (return n))
          (cerror "Enter a number":["; a bit larger than "D"]."
                   "~*~A is not a large number."
                   (numberp n) n)
          (format t "~&Type a large number: ")
          (setq n (read))
          (fresh-line)))
```

```
(assure-large-number 10000)
\rightarrow 10000
 (assure-large-number 'a)
\triangleright Correctable error in ASSURE-LARGE-NUMBER: A is not a large number.
▷ Restart options:
\triangleright 1: Enter a number.
▷ 2: Top level.
\triangleright Debug> \underline{:}continue 1
\triangleright Type a large number: <u>88</u>
\rightarrow 88
(assure-large-number 37)
\triangleright Correctable error in ASSURE-LARGE-NUMBER: 37 is not a large number.
▷ Restart options:
▷ 1: Enter a number a bit larger than 37.
▷ 2: Top level.
\triangleright Debug> \underline{:continue\ 1}
\triangleright Type a large number: \underline{259}
\rightarrow 259
 (define-condition not-a-large-number (error)
   ((argument :reader not-a-large-number-argument :initarg :argument))
   (:report (lambda (condition stream)
                (format stream "~S is not a large number."
                          (not-a-large-number-argument condition)))))
 (defun assure-large-number (n)
   (loop (when (and (numberp n) (> n 73)) (return n))
          (cerror "Enter a number~3*~:[~; a bit larger than ~*~D~]."
                    'not-a-large-number
                    :argument n
                    :ignore (numberp n)
                    :ignore n
                   :allow-other-keys t)
          (format t "~&Type a large number: ")
          (setq n (read))
          (fresh-line)))
 (assure-large-number 'a)
\triangleright Correctable error in ASSURE-LARGE-NUMBER: A is not a large number.
▷ Restart options:
▷ 1: Enter a number.
```

Affected By:

break-on-signals.

Existing handler bindings.

See Also:

 $error,\,format,\,handler\text{-}bind,\,*break\text{-}on\text{-}signals*,\,simple\text{-}type\text{-}error$

Notes:

If datum is a condition type rather than a string, the format directive ** may be especially useful in the continue-format-control in order to ignore the keywords in the initialization argument list. For example:

check-type

Macro

Syntax:

```
\mathbf{check\text{-}type} \ \mathit{place} \ \mathit{typespec} \ [\mathit{string}] \quad \rightarrow \mathbf{nil}
```

Arguments and Values:

```
place—a place.
typespec—a type specifier.
string—a string; evaluated.
```

Description:

check-type signals a *correctable error* of *type* **type-error** if the contents of *place* are not of the type *typespec*.

check-type can return only if the **store-value** restart is invoked, either explicitly from a handler or implicitly as one of the options offered by the debugger. If the **store-value** restart is invoked, **check-type** stores the new value that is the argument to the restart invocation (or that is prompted for interactively by the debugger) in place and starts over, checking the type of the new value and signaling another error if it is still not of the desired type.

The first time *place* is *evaluated*, it is *evaluated* by normal evaluation rules. It is later *evaluated* as a *place* if the type check fails and the **store-value** *restart* is used; see Section 5.1.1.1 (Evaluation of Subforms to Places).

string should be an English description of the type, starting with an indefinite article ("a" or "an"). If string is not supplied, it is computed automatically from typespec. The automatically generated message mentions place, its contents, and the desired type. An implementation may choose to generate a somewhat differently worded error message if it recognizes that place is of a particular form, such as one of the arguments to the function that called check-type. string is allowed because some applications of check-type may require a more specific description of what is wanted than can be generated automatically from typespec.

Examples:

```
(setq aardvarks '(sam harry fred))

ightarrow (SAM HARRY FRED)
 (check-type aardvarks (array * (3)))
▷ Error: The value of AARDVARKS, (SAM HARRY FRED),
         is not a 3-long array.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Specify a value to use instead.
▷ 2: Return to Lisp Toplevel.
▷ Debug> :CONTINUE 1

▷ Use Value: #(SAM FRED HARRY)

ightarrow NIL
aardvarks
\rightarrow #<ARRAY-T-3 13571>
(map 'list #'identity aardvarks)

ightarrow (SAM FRED HARRY)
(setq aardvark-count 'foo)
 (check-type aardvark-count (integer 0 *) "A positive integer")
▷ Error: The value of AARDVARK-COUNT, FOO, is not a positive integer.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Specify a value to use instead.
▷ 2: Top level.
```

check-type

```
▷ Debug> :CONTINUE 2
            (defmacro define-adder (name amount)
              (check-type name (and symbol (not null)) "a name for an adder function")
              (check-type amount integer)
               '(defun ,name (x) (+ x ,amount)))
            (macroexpand '(define-adder add3 3))
           \rightarrow (defun add3 (x) (+ x 3))
            (macroexpand '(define-adder 7 7))
           \triangleright Error: The value of NAME, 7, is not a name for an adder function.
           \triangleright To continue, type :CONTINUE followed by an option number:
           ▷ 1: Specify a value to use instead.
           ▷ 2: Top level.
           ▷ Debug> :Continue 1
           \, \triangleright \, Specify a value to use instead.

    ▷ Type a form to be evaluated and used instead: 'ADD7

           \rightarrow (defun add7 (x) (+ x 7))
            (macroexpand '(define-adder add5 something))
           ▷ Error: The value of AMOUNT, SOMETHING, is not an integer.
           \triangleright To continue, type :CONTINUE followed by an option number:
           ▷ 1: Specify a value to use instead.
           ▷ 2: Top level.
           ▷ Debug> :Continue 1
           \triangleright Type a form to be evaluated and used instead: \underline{5}
           \rightarrow (defun add5 (x) (+ x 5))
           Control is transferred to a handler.
Side Effects:
           The debugger might be entered.
Affected By:
           *break-on-signals*
           The implementation.
See Also:
           Section 9.1 (Condition System Concepts)
            (check-type place typespec)
```

Notes:

simple-error

Condition Type

Class Precedence List:

simple-error, simple-condition, error, serious-condition, condition, t

Description:

The *type* simple-error consists of *conditions* that are signaled by error or cerror when a *format* control is supplied as the function's first argument.

invalid-method-error

Function

Syntax:

invalid-method-error method format-control &rest args $\rightarrow implementation-dependent$

Arguments and Values:

method—a method.

 $\textit{format-control} \\ - \\ \text{a} \ \textit{format control}.$

args—format arguments for the format-control.

Description:

The function invalid-method-error is used to signal an error of type error when there is an applicable method whose qualifiers are not valid for the method combination type. The error message is constructed by using the format-control suitable for format and any args to it. Because an implementation may need to add additional contextual information to the error message, invalid-method-error should be called only within the dynamic extent of a method combination function.

The function invalid-method-error is called automatically when a method fails to satisfy every qualifier pattern and predicate in a define-method-combination form. A method combination function that imposes additional restrictions should call invalid-method-error explicitly if it encounters a method it cannot accept.

Whether invalid-method-error returns to its caller or exits via throw is implementation-dependent.

Side Effects:

The debugger might be entered.

Affected By:

break-on-signals

See Also:

define-method-combination

method-combination-error

Function

Syntax:

 $\textbf{method-combination-error} \ \textit{format-control} \ \texttt{\&rest} \ \textit{args} \ \rightarrow implementation-dependent$

Arguments and Values:

format-control—a format control.

args—format arguments for format-control.

Description:

The function method-combination-error is used to signal an error in method combination.

The error message is constructed by using a *format-control* suitable for **format** and any *args* to it. Because an implementation may need to add additional contextual information to the error message, **method-combination-error** should be called only within the dynamic extent of a method combination function.

Whether **method-combination-error** returns to its caller or exits via **throw** is *implementation-dependent*.

Side Effects:

The debugger might be entered.

Affected By:

break-on-signals

See Also:

define-method-combination

signal Function

Syntax:

 $signal\ datum\ \&rest\ arguments\
ightarrow nil$

Arguments and Values:

datum, arguments—designators for a condition of default type simple-condition.

Description:

Signals the condition denoted by the given datum and arguments. If the condition is not handled, signal returns nil.

Examples:

```
(defun handle-division-conditions (condition)
   (format t "Considering condition for division condition handling~%")
   (when (and (typep condition 'arithmetic-error)
              (eq '/ (arithmetic-error-operation condition)))
     (invoke-debugger condition)))
HANDLE-DIVISION-CONDITIONS
 (defun handle-other-arithmetic-errors (condition)
   (format t "Considering condition for arithmetic condition handling~%")
   (when (typep condition 'arithmetic-error)
     (abort)))
HANDLE-OTHER-ARITHMETIC-ERRORS
 (define-condition a-condition-with-no-handler (condition) ())
A-CONDITION-WITH-NO-HANDLER
 (signal 'a-condition-with-no-handler)
NTI.
 (handler-bind ((condition #'handle-division-conditions)
                  (condition #'handle-other-arithmetic-errors))
   (signal 'a-condition-with-no-handler))
Considering condition for division condition handling
Considering condition for arithmetic condition handling
 (handler-bind ((arithmetic-error #'handle-division-conditions)
                  (arithmetic-error #'handle-other-arithmetic-errors))
   (signal 'arithmetic-error :operation '* :operands '(1.2 b)))
Considering condition for division condition handling
Considering condition for arithmetic condition handling
Back to Lisp Toplevel
```

Side Effects:

The debugger might be entered due to *break-on-signals*.

Handlers for the condition being signaled might transfer control.

Affected By:

Existing handler bindings.

break-on-signals

See Also:

break-on-signals, error, simple-condition, Section 9.1.4 (Signaling and Handling Conditions)

Notes:

If (typep datum *break-on-signals*) yields true, the debugger is entered prior to beginning the signaling process. The continue restart can be used to continue with the signaling process. This is also true for all other functions and macros that should, might, or must signal conditions.

simple-condition

Condition Type

Class Precedence List:

simple-condition, condition, t

Description:

The type simple-condition represents conditions that are signaled by signal whenever a formatcontrol is supplied as the function's first argument. The format control and format arguments are initialized with the initialization arguments named :format-control and :format-arguments to make-condition, and are accessed by the functions simple-condition-format-control and simple-condition-format-arguments. If format arguments are not supplied to make-condition, nil is used as a default.

See Also:

simple-condition-format-control, simple-condition-format-arguments

${\bf simple-condition-format-control, simple-condition-format-arguments}$

Function

Syntax:

simple-condition-format-control condition $o ext{format-control}$ simple-condition-format-arguments condition $o ext{format-arguments}$

Arguments and Values:

condition—a condition of type simple-condition.

format-control—a format control.

format-arguments— $a\ list.$

Description:

simple-condition-format-control returns the *format control* needed to process the *condition*'s *format arguments*.

simple-condition-format-arguments returns a *list* of *format arguments* needed to process the *condition*'s *format control*.

Examples:

See Also:

simple-condition, Section 9.1 (Condition System Concepts)

warn Function

Syntax:

warn datum &rest arguments \rightarrow nil

Arguments and Values:

datum, arguments—designators for a condition of default type simple-warning.

warn

Description:

Signals a condition of type warning. If the condition is not handled, reports the condition to error output.

The precise mechanism for warning is as follows:

The warning condition is signaled

While the warning condition is being signaled, the muffle-warning restart is established for use by a handler. If invoked, this restart bypasses further action by warn, which in turn causes warn to immediately return nil.

If no handler for the warning condition is found

If no handlers for the warning condition are found, or if all such handlers decline, then the *condition* is reported to *error output* by **warn** in an *implementation-dependent* format.

nil is returned

The value returned by warn if it returns is nil.

Examples:

```
(defun foo (x)
    (let ((result (* x 2)))
      (if (not (typep result 'fixnum))
          (warn "You're using very big numbers."))
     result))
\rightarrow F00
  (foo 3)
\rightarrow 6
  (foo most-positive-fixnum)
\rightarrow~4294967294
  (setq *break-on-signals* t)
  (foo most-positive-fixnum)
▷ Break: Caveat emptor.
▷ To continue, type :CONTINUE followed by an option number.
▷ 1: Return from Break.
▷ 2: Abort to Lisp Toplevel.
▷ Debug> :continue 1
```

 $\,\vartriangleright\,$ Warning: You're using very big numbers.

 $\rightarrow~4294967294$

Side Effects:

A warning is issued. The debugger might be entered.

Affected By:

Existing handler bindings.

break-on-signals, *error-output*.

Exceptional Situations:

If *datum* is a *condition* and if the *condition* is not of *type* **warning**, or *arguments* is *non-nil*, an error of *type* **type-error** is signaled.

If datum is a condition type, the result of (apply #'make-condition datum arguments) must be of type warning or an error of type type-error is signaled.

See Also:

break-on-signals, muffle-warning, signal

simple-warning

Condition Type

Class Precedence List:

simple-warning, simple-condition, warning, condition, t

Description:

The *type* simple-warning represents *conditions* that are signaled by warn whenever a *format* control is supplied as the function's first argument.

invoke-debugger

Function

Syntax:

invoke-debugger condition \rightarrow

Arguments and Values:

condition—a condition object.

Description:

invoke-debugger attempts to enter the debugger with condition.

If *debugger-hook* is not nil, it should be a function (or the name of a function) to be called prior to entry to the standard debugger. The function is called with *debugger-hook* bound to nil, and the function must accept two arguments: the condition and the value of *debugger-hook* prior to binding it to nil. If the function returns normally, the standard debugger is entered.

The standard debugger never directly returns. Return can occur only by a non-local transfer of control, such as the use of a restart function.

Examples:

```
(ignore-errors ;Normally, this would suppress debugger entry
    (handler-bind ((error #'invoke-debugger)) ;But this forces debugger entry
        (error "Foo.")))
Debug: Foo.
To continue, type :CONTINUE followed by an option number:
1: Return to Lisp Toplevel.
Debug>
```

Side Effects:

debugger-hook is bound to nil, program execution is discontinued, and the debugger is entered.

Affected By:

debug-io and *debugger-hook*.

See Also:

error, break

break

Syntax:

break &optional format-control &rest format-arguments ightarrow nil

Arguments and Values:

format-control—a format control. The default is implementation-dependent.

format-arguments—format arguments for the format-control.

Description:

break formats format-control and format-arguments and then goes directly into the debugger without allowing any possibility of interception by programmed error-handling facilities.

If the **continue** restart is used while in the debugger, **break** immediately returns **nil** without taking any unusual recovery action.

break binds *debugger-hook* to nil before attempting to enter the debugger.

Examples:

```
(break "You got here with arguments: ~:S." '(F00 37 A))
▷ BREAK: You got here with these arguments: F00, 37, A.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Return from BREAK.
▷ 2: Top level.
▷ Debug> :CONTINUE 1
▷ Return from BREAK.
→ NIL
```

Side Effects:

The debugger is entered.

Affected By:

debug-io.

See Also:

error, invoke-debugger.

Notes:

break is used as a way of inserting temporary debugging "breakpoints" in a program, not as a way of signaling errors. For this reason, **break** does not take the *continue-format-control argument* that **cerror** takes. This and the lack of any possibility of interception by *condition handling* are the only program-visible differences between **break** and **cerror**.

The user interface aspects of **break** and **cerror** are permitted to vary more widely, in order to accommodate the interface needs of the *implementation*. For example, it is permissible for a *Lisp read-eval-print loop* to be entered by **break** rather than the conventional debugger.

break could be defined by:

debugger-hook

Variable

Value Type:

a designator for a function of two arguments (a condition and the value of *debugger-hook* at the time the debugger was entered), or nil.

Initial Value:

nil.

Description:

When the *value* of *debugger-hook* is *non-nil*, it is called prior to normal entry into the debugger, either due to a call to **invoke-debugger** or due to automatic entry into the debugger from a call to **error** or **cerror** with a condition that is not handled. The *function* may either handle the *condition* (transfer control) or return normally (allowing the standard debugger to run). To minimize recursive errors while debugging, *debugger-hook* is bound to nil by **invoke-debugger** prior to calling the *function*.

Examples:

```
(defun one-of (choices & optional (prompt "Choice"))
  (let ((n (length choices)) (i))
      (do ((c choices (cdr c)) (i 1 (+ i 1)))
            ((null c))
            (format t "~&[~D] ~A~%" i (car c)))
      (do () ((typep i '(integer 1 ,n)))
            (format t "~&~A: " prompt)
            (setq i (read))
```

```
(fresh-line))
     (nth (- i 1) choices)))
 (defun my-debugger (condition me-or-my-encapsulation)
   (format t "~&Fooey: ~A" condition)
   (let ((restart (one-of (compute-restarts))))
     (if (not restart) (error "My debugger got an error."))
     (let ((*debugger-hook* me-or-my-encapsulation))
       (invoke-restart-interactively restart))))
 (let ((*debugger-hook* #'my-debugger))
   (+ 3 'a))
\triangleright Fooey: The argument to +, A, is not a number.
  [1] Supply a replacement for A.
▷ [2] Return to Cloe Toplevel.
▷ Choice: 1
▷ Form to evaluate and use: (+ 5 'b)
▷ [1] Supply a replacement for B.
\triangleright [2] Supply a replacement for A.
\triangleright [3] Return to Cloe Toplevel.
▷ Choice: 1
▷ Form to evaluate and use: 1
```

Affected By:

invoke-debugger

Notes:

When evaluating code typed in by the user interactively, it is sometimes useful to have the hook function bind *debugger-hook* to the function that was its second argument so that recursive errors can be handled using the same interactive facility.

break-on-signals

Variable

Value Type:

a type specifier.

Initial Value:

nil.

break-on-signals

Description:

When (typep condition *break-on-signals*) returns true, calls to signal, and to other operators such as error that implicitly call signal, enter the debugger prior to signaling the condition.

The **continue** restart can be used to continue with the normal signaling process when a break occurs process due to *break-on-signals*.

Examples:

```
*break-on-signals* \rightarrow NIL
 (ignore-errors (error 'simple-error :format-control "Fooey!"))

ightarrow NIL, #<SIMPLE-ERROR 32207172>
 (let ((*break-on-signals* 'error))
   (ignore-errors (error 'simple-error :format-control "Fooey!")))
▷ Break: Fooey!
▷ BREAK entered because of *BREAK-ON-SIGNALS*.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Continue to signal.
▷ 2: Top level.
▷ Debug> :CONTINUE 1
▷ Continue to signal.

ightarrow NIL, #<SIMPLE-ERROR 32212257>
 (let ((*break-on-signals* 'error))
   (error 'simple-error :format-control "Fooey!"))
▷ Break: Fooey!
\triangleright BREAK entered because of *BREAK-ON-SIGNALS*.
\triangleright To continue, type :CONTINUE followed by an option number:
▷ 1: Continue to signal.
▷ 2: Top level.
▷ Debug> :CONTINUE 1
\triangleright Continue to signal.
▷ Error: Fooey!
\,\vartriangleright\, To continue, type :CONTINUE followed by an option number:
▷ 1: Top level.
▷ Debug> :CONTINUE 1
▷ Top level.
```

See Also:

break, signal, warn, error, typep, Section 9.1 (Condition System Concepts)

Notes:

break-on-signals is intended primarily for use in debugging code that does signaling. When setting *break-on-signals*, the user is encouraged to choose the most restrictive specification

that suffices. Setting *break-on-signals* effectively violates the modular handling of *condition* signaling. In practice, the complete effect of setting *break-on-signals* might be unpredictable in some cases since the user might not be aware of the variety or number of calls to signal that are used in code called only incidentally.

break-on-signals enables an early entry to the debugger but such an entry does not preclude an additional entry to the debugger in the case of operations such as **error** and **cerror**.

handler-bind

Macro

Syntax:

```
handler-bind (\{\downarrow \textit{binding}\}^*) \{\textit{form}\}^* \rightarrow \{\textit{result}\}^*
```

binding::=(type handler)

Arguments and Values:

type—a type specifier.

handler—a form; evaluated to produce a handler-function.

handler-function—a designator for a function of one argument.

forms—an implicit progn.

results—the values returned by the forms.

Description:

Executes forms in a dynamic environment where the indicated handler bindings are in effect.

Each *handler* should evaluate to a *handler-function*, which is used to handle *conditions* of the given *type* during execution of the *forms*. This *function* should take a single argument, the *condition* being signaled.

If more than one *handler binding* is supplied, the *handler bindings* are searched sequentially from top to bottom in search of a match (by visual analogy with **typecase**). If an appropriate *type* is found, the associated handler is run in a *dynamic environment* where none of these *handler* bindings are visible (to avoid recursive errors). If the *handler declines*, the search continues for another *handler*.

If no appropriate *handler* is found, other *handlers* are sought from dynamically enclosing contours. If no *handler* is found outside, then **signal** returns or **error** enters the debugger.

Examples:

In the following code, if an unbound variable error is signaled in the body (and not handled by an intervening handler), the first function is called.

If any other kind of error is signaled, the second function is called. In either case, neither handler is active while executing the code in the associated function.

Note that "Foo." is not printed because the condition made by **signal** is a *simple condition*, which is not of *type* **error**, so it doesn't trigger the handler for **error** set up by **trap-errors**.

See Also:

handler-case

handler-case Macro

Syntax:

```
handler-case expression [\{\downarrow error-clause\}^* \mid \downarrow no-error-clause\} \rightarrow \{result\}^*

clause::=\downarrow error-clause \mid \downarrow no-error-clause

error-clause::=(typespec ([var]) \{declaration\}^* \{form\}^*)

no-error-clause::=(:no-error lambda-list \{declaration\}^* \{form\}^*)
```

Arguments and Values:

```
expression—a form.

typespec—a type specifier.
```

9–38 Programming Language—Common Lisp

```
var—a variable name.
```

lambda-list—an ordinary lambda list.

declaration—a declare expression; not evaluated.

form—a form.

results—In the normal situation, the values returned are those that result from the evaluation of expression; in the exceptional situation when control is transferred to a clause, the value of the last form in that clause is returned.

Description:

handler-case executes expression in a dynamic environment where various handlers are active. Each error-clause specifies how to handle a condition matching the indicated typespec. A no-error-clause allows the specification of a particular action if control returns normally.

If a condition is signaled for which there is an appropriate error-clause during the execution of expression (i.e., one for which (typep condition 'typespec) returns true) and if there is no intervening handler for a condition of that type, then control is transferred to the body of the relevant error-clause. In this case, the dynamic state is unwound appropriately (so that the handlers established around the expression are no longer active), and var is bound to the condition that had been signaled. If more than one case is provided, those cases are made accessible in parallel. That is, in

```
(handler-case form
  (typespec1 (var1) form1)
  (typespec2 (var2) form2))
```

if the first clause (containing form1) has been selected, the handler for the second is no longer visible (or vice versa).

The *clauses* are searched sequentially from top to bottom. If there is *type* overlap between *typespecs*, the earlier of the *clauses* is selected.

If var is not needed, it can be omitted. That is, a clause such as:

```
(typespec (var) (declare (ignore var)) form)
```

can be written (typespec () form).

If there are no forms in a selected clause, the case, and therefore handler-case, returns nil. If execution of expression returns normally and no no-error-clause exists, the values returned by expression are returned by handler-case. If execution of expression returns normally and a no-error-clause does exist, the values returned are used as arguments to the function described by constructing (lambda-list {form}*) from the no-error-clause, and the values of that function call are returned by handler-case. The handlers which were established around the expression are no longer active at the time of this call.

handler-case

Examples:

```
(defun assess-condition (condition)
              (handler-case (signal condition)
                (warning () "Lots of smoke, but no fire.")
                ((or arithmetic-error control-error cell-error stream-error)
                   (condition)
                  (format nil "~S looks especially bad." condition))
                (serious-condition (condition)
                  (format nil "~S looks serious." condition))
                (condition () "Hardly worth mentioning.")))

ightarrow ASSESS-CONDITION
           (assess-condition (make-condition 'stream-error :stream *terminal-io*))
          \rightarrow "#<STREAM-ERROR 12352256> looks especially bad."
           (define-condition random-condition (condition) ()
              (:report (lambda (condition stream)
                         (declare (ignore condition))
                         (princ "Yow" stream))))

ightarrow RANDOM-CONDITION
           (assess-condition (make-condition 'random-condition))

ightarrow "Hardly worth mentioning."
See Also:
          handler-bind, ignore-errors, Section 9.1 (Condition System Concepts)
Notes:
            (handler-case form
              (type1 (var1) . body1)
              (type2 (var2) . body2) ...)
          is approximately equivalent to:
            (block #1=#:g0001
              (let ((#2=#:g0002 nil))
                (tagbody
                  (handler-bind ((type1 #'(lambda (temp)
                                                   (setq #1# temp)
                                                   (go #3=#:g0003)))
                                  (type2 #'(lambda (temp)
                                                   (setq #2# temp)
                                                   (go #4=#:g0004))) ...)
                  (return-from #1# form))
                    #3# (return-from #1# (let ((var1 #2#)) . body1))
                    #4# (return-from #1# (let ((var2 #2#)) . body2)) ...)))
```

(handler-case form

ignore-errors

Macro

Syntax:

```
\mathbf{ignore\text{-}errors}\ \{\mathit{form}\}^* \ \to \{\mathit{result}\}^*
```

Arguments and Values:

forms—an implicit progn.

results—In the normal situation, the values of the forms are returned; in the exceptional situation, two values are returned: nil and the condition.

Description:

ignore-errors is used to prevent *conditions* of *type* **error** from causing entry into the debugger.

Specifically, **ignore-errors** executes forms in a dynamic environment where a handler for conditions of type **error** has been established; if invoked, it handles such conditions by returning two values, **nil** and the condition that was signaled, from the **ignore-errors** form.

If a normal return from the forms occurs, any values returned are returned by ignore-errors.

Examples:

```
(load-init-file "no-such-program")

▷ Init file failed to load.

NTI.
```

See Also:

handler-case, Section 9.1 (Condition System Concepts)

Notes:

```
(ignore-errors . forms)
is equivalent to:
  (handler-case (progn . forms)
      (error (condition) (values nil condition)))
```

Because the second return value is a *condition* in the exceptional case, it is common (but not required) to arrange for the second return value in the normal case to be missing or **nil** so that the two situations can be distinguished.

define-condition

Macro

Syntax:

```
define-condition name ({parent-type}*) ({\pm slot-spec}*) {option}* \rightarrow name

slot-spec::=slot-name \mid (slot-name \downarrow slot-option)
slot-option::=[[{:reader symbol}* \mid {:writer \downarrow function-name}* \mid {:accessor symbol}* \mid {:allocation \downarrow allocation-type} \mid {:initarg symbol}* \mid {:initarg symbol}* \mid {:initform form} \mid {:type type-specifier} ]]
option::=[[(:default-initargs . initarg-list) \mid {:documentation string}) \mid {:report report-name}]
```

```
function-name::={symbol | (setf symbol)}

allocation-type::=:instance | :class

report-name::=string | symbol | lambda expression

Arguments and Values:

name—a symbol.

parent-type—a symbol naming a condition type. If no parent-types are supplied, the parent-types default to (condition).

default-initargs—a list of keyword/value pairs.

Slot-spec - the name of a slot or a list consisting of the slot-name followed by zero or more slot-options.

Slot-name - a slot name (a symbol), the list of a slot name, or the list of slot name/slot form
```

Option – Any of the following:

:reader

pairs.

:reader can be supplied more than once for a given slot and cannot be nil.

:writer

:writer can be supplied more than once for a given slot and must name a $generic\ function$.

:accessor

:accessor can be supplied more than once for a given slot and cannot be nil.

:allocation

:allocation can be supplied once at most for a given *slot*. The default if :allocation is not supplied is :instance.

:initarg

:initarg can be supplied more than once for a given slot.

:initform

:initform can be supplied once at most for a given slot.

:type

:type can be supplied once at most for a given slot.

:documentation

:documentation can be supplied once at most for a given slot.

:report

:report can be supplied once at most.

Description:

define-condition defines a new condition type called *name*, which is a *subtype* of the *type* or *types* named by *parent-type*. Each *parent-type* argument specifies a direct *supertype* of the new *condition*. The new *condition* inherits *slots* and *methods* from each of its direct *supertypes*, and so on.

If a slot name/slot form pair is supplied, the slot form is a *form* that can be evaluated by **make-condition** to produce a default value when an explicit value is not provided. If no slot form is supplied, the contents of the *slot* is initialized in an *implementation-dependent* way.

If the *type* being defined and some other *type* from which it inherits have a slot by the same name, only one slot is allocated in the *condition*, but the supplied slot form overrides any slot form that might otherwise have been inherited from a *parent-type*. If no slot form is supplied, the inherited slot form (if any) is still visible.

Accessors are created according to the same rules as used by defclass.

A description of *slot-options* follows:

:reader

The :reader slot option specifies that an unqualified method is to be defined on the generic function named by the argument to :reader to read the value of the given slot.

• The :initform slot option is used to provide a default initial value form to be used in the initialization of the slot. This form is evaluated every time it is used to initialize the slot. The lexical environment in which this form is evaluated is the lexical environment in which the define-condition form was evaluated. Note that the lexical environment refers both to variables and to functions. For local slots, the dynamic environment is the dynamic environment in which make-condition was called; for shared slots, the dynamic environment is the dynamic environment in which the define-condition form was evaluated.

No implementation is permitted to extend the syntax of **define-condition** to allow (*slot-name form*) as an abbreviation for (*slot-name*:initform form).

:initarg

The :initarg slot option declares an initialization argument named by its symbol ar-

gument and specifies that this initialization argument initializes the given *slot*. If the initialization argument has a value in the call to **initialize-instance**, the value is stored into the given *slot*, and the slot's :initform slot option, if any, is not evaluated. If none of the initialization arguments specified for a given *slot* has a value, the *slot* is initialized according to the :initform slot option, if specified.

:type

The :type slot option specifies that the contents of the *slot* is always of the specified *type*. It effectively declares the result type of the reader generic function when applied to an *object* of this *condition* type. The consequences of attempting to store in a *slot* a value that does not satisfy the type of the *slot* is undefined.

:default-initargs

This option is treated the same as it would be defclass.

:documentation

The :documentation slot option provides a documentation string for the slot.

:report

Condition reporting is mediated through the **print-object** method for the condition type in question, with ***print-escape*** always being nil. Specifying (:report report-name) in the definition of a condition type C is equivalent to:

```
(defmethod print-object ((x c) stream)
  (if *print-escape* (call-next-method) (report-name x stream)))
```

If the value supplied by the argument to :report (report-name) is a symbol or a lambda expression, it must be acceptable to function. (function report-name) is evaluated in the current lexical environment. It should return a function of two arguments, a condition and a stream, that prints on the stream a description of the condition. This function is called whenever the condition is printed while *print-escape* is nil.

If report-name is a string, it is a shorthand for

```
(lambda (condition stream)
  (declare (ignore condition))
  (write-string report-name stream))
```

This option is processed after the new *condition* type has been defined, so use of the *slot* accessors within the :report function is permitted. If this option is not supplied, information about how to report this type of *condition* is inherited from the *parent-type*.

The consequences are unspecifed if an attempt is made to *read* a *slot* that has not been explicitly initialized and that has not been given a default value.

The consequences are unspecified if an attempt is made to assign the *slots* by using **setf**.

If a **define-condition** form appears as a top level form, the compiler must make name recognizable as a valid type name, and it must be possible to reference the condition type as the parent-type of another condition type in a subsequent **define-condition** form in the file being compiled.

Examples:

The following form defines a condition of *type* peg/hole-mismatch which inherits from a condition type called blocks-world-error:

The new type has slots peg-shape and hole-shape, so make-condition accepts :peg-shape and :hole-shape keywords. The *readers* peg/hole-mismatch-peg-shape and peg/hole-mismatch-hole-shape apply to objects of this type, as illustrated in the :report information.

The following form defines a condition type named machine-error which inherits from error:

Building on this definition, a new error condition can be defined which is a subtype of machine-error for use when machines are not available:

This defines a still more specific condition, built upon machine-not-available-error, which provides a slot initialization form for machine-name but which does not provide any new slots or report information. It just gives the machine-name slot a default initialization:

```
({\tt define-condition}\ {\tt my-favorite-machine-not-available-error}
                   (machine-not-available-error)
  ((machine-name :initform "mc.lcs.mit.edu")))
Note that since no :report clause was given, the information inherited from
machine-not-available-error is used to report this type of condition.
 (define-condition ate-too-much (error)
     ((person :initarg :person :reader ate-too-much-person)
      (weight :initarg :weight :reader ate-too-much-weight)
      (kind-of-food :initarg :kind-of-food
                     :reader :ate-too-much-kind-of-food)))

ightarrow ATE-TOO-MUCH
 (define-condition ate-too-much-ice-cream (ate-too-much)
   ((kind-of-food :initform 'ice-cream)
    (flavor
                  :initarg :flavor
                   : \verb"reader" ate-too-much-ice-cream-flavor"
                   :initform 'vanilla ))
   (:report (lambda (condition stream)
               (format stream "~A ate too much ~A ice-cream"
                       (ate-too-much-person condition)
                       (ate-too-much-ice-cream-flavor condition)))))
→ ATE-TOO-MUCH-ICE-CREAM
 (make-condition 'ate-too-much-ice-cream
                  :person 'fred
                  :weight 300
                  :flavor 'chocolate)
\rightarrow #<ATE-T00-MUCH-ICE-CREAM 32236101>
 (format t "~A" *)
▷ FRED ate too much CHOCOLATE ice-cream

ightarrow NIL
```

See Also:

make-condition, defclass, Section 9.1 (Condition System Concepts)

make-condition

Function

Syntax:

make-condition type &rest slot-initializations ightarrow condition

Arguments and Values:

type—a type specifier (for a subtype of condition).

 ${\it slot-initializations} {\it --} an {\it initialization argument list}.$

condition—a condition.

Description:

Constructs and returns a *condition* of type *type* using *slot-initializations* for the initial values of the slots. The newly created *condition* is returned.

Examples:

Affected By:

The set of defined condition types.

See Also:

define-condition, Section 9.1 (Condition System Concepts)

restart System Class

Class Precedence List:

restart, t

Description:

An *object* of *type* **restart** represents a *function* that can be called to perform some form of recovery action, usually a transfer of control to an outer point in the running program.

An *implementation* is free to implement a *restart* in whatever manner is most convenient; a *restart* has only *dynamic extent* relative to the scope of the binding *form* which *establishes* it.

compute-restarts

Function

Syntax:

 ${f compute-restarts}$ &optional ${f condition}$ o ${f restarts}$

Arguments and Values:

```
condition—a condition object, or nil.
restarts—a list of restarts.
```

Description:

compute-restarts uses the dynamic state of the program to compute a *list* of the *restarts* which are currently active.

The resulting list is ordered so that the innermost (more-recently established) restarts are nearer the head of the list.

When *condition* is *non-nil*, only those *restarts* are considered that are either explicitly associated with that *condition*, or not associated with any *condition*; that is, the excluded *restarts* are those that are associated with a non-empty set of *conditions* of which the given *condition* is not an *element*. If *condition* is nil, all *restarts* are considered.

compute-restarts returns all *applicable restarts*, including anonymous ones, even if some of them have the same name as others and would therefore not be found by **find-restart** when given a *symbol* argument.

Implementations are permitted, but not required, to return distinct lists from repeated calls to **compute-restarts** while in the same dynamic environment. The consequences are undefined if the list returned by **compute-restarts** is every modified.

Examples:

```
(return t))
              (format t "~&Option: ")
              (setq n (read))
              (fresh-line))
        (invoke-restart-interactively (nth n restarts)))))
 (restart-case (invoke-a-restart)
   (one () 1)
   (two () 2)
   (nil () :report "Who knows?" 'anonymous)
   (one () 'I)
   (two () 'II))
▷ O: ONE
▷ 1: TWO
▷ 2: Who knows?
▷ 3: ONE
> 4: TWO
▷ 5: Return to Lisp Toplevel.
\triangleright Option: \underline{4}
\rightarrow \, \text{II}
 ;; Note that in addition to user-defined restart points, COMPUTE-RESTARTS
 ;; also returns information about any system-supplied restarts, such as
 ;; the "Return to Lisp Toplevel" restart offered above.
```

Affected By:

Existing restarts.

See Also:

find-restart, invoke-restart, restart-bind

find-restart

Function

Syntax:

find-restart identifier &optional condition

restart

Arguments and Values:

```
identifier—a non-nil symbol, or a restart.
condition—a condition object, or nil.
```

9-50 Programming Language—Common Lisp

restart—a restart or nil.

Description:

find-restart searches for a particular restart in the current dynamic environment.

When *condition* is *non-nil*, only those *restarts* are considered that are either explicitly associated with that *condition*, or not associated with any *condition*; that is, the excluded *restarts* are those that are associated with a non-empty set of *conditions* of which the given *condition* is not an *element*. If *condition* is nil, all *restarts* are considered.

If *identifier* is a *symbol*, then the innermost (most recently established) *applicable restart* with that *name* is returned. **nil** is returned if no such restart is found.

If identifier is a currently active restart, then it is returned. Otherwise, nil is returned.

Examples:

```
(restart-case
        (let ((r (find-restart 'my-restart)))
            (format t "~S is named ~S" r (restart-name r)))
        (my-restart () nil))
> #<RESTART 32307325> is named MY-RESTART
→ NIL
        (find-restart 'my-restart)
→ NIL
```

Affected By:

Existing restarts.

 ${\bf restart\text{-}case,\ restart\text{-}bind,\ with\text{-}condition\text{-}restarts}.$

See Also:

compute-restarts

Notes:

Although anonymous restarts have a name of **nil**, the consequences are unspecified if **nil** is given as an *identifier*. Occasionally, programmers lament that **nil** is not permissible as an *identifier* argument. In most such cases, **compute-restarts** can probably be used to simulate the desired effect.

invoke-restart

invoke-restart

Function

Syntax:

```
invoke-restart restart &rest arguments \rightarrow \{result\}^*
```

Arguments and Values:

```
restart—a restart designator.
argument—an object.
```

results—the values returned by the function associated with restart, if that function returns.

Description:

Calls the function associated with restart, passing arguments to it. Restart must be valid in the current dynamic environment.

Examples:

```
(defun add3 (x) (check-type x number) (+ x 3))

(foo 'seven)
▷ Error: The value SEVEN was not of type NUMBER.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Specify a different value to use.
▷ 2: Return to Lisp Toplevel.
▷ Debug> (invoke-restart 'store-value 7)
→ 10
```

Side Effects:

A non-local transfer of control might be done by the restart.

Affected By:

Existing restarts.

Exceptional Situations:

If restart is not valid, an error of type control-error is signaled.

See Also:

find-restart, restart-bind, restart-case, invoke-restart-interactively

Notes:

The most common use for **invoke-restart** is in a *handler*. It might be used explicitly, or implicitly through **invoke-restart-interactively** or a *restart function*.

Restart functions call **invoke-restart**, not vice versa. That is, *invoke-restart* provides primitive functionality, and *restart functions* are non-essential "syntactic sugar."

invoke-restart-interactively

Function

Syntax:

invoke-restart-interactively restart $\rightarrow \{result\}^*$

Arguments and Values:

restart—a restart designator.

results—the values returned by the function associated with restart, if that function returns.

Description:

invoke-restart-interactively calls the *function* associated with *restart*, prompting for any necessary arguments. If *restart* is a name, it must be valid in the current *dynamic environment*.

invoke-restart-interactively prompts for arguments by executing the code provided in the :interactive keyword to restart-case or :interactive-function keyword to restart-bind.

If no such options have been supplied in the corresponding **restart-bind** or **restart-case**, then the consequences are undefined if the *restart* takes required arguments. If the arguments are optional, an argument list of **nil** is used.

Once the arguments have been determined, invoke-restart-interactively executes the following:

(apply #'invoke-restart restart arguments)

Examples:

```
(defun add3 (x) (check-type x number) (+ x 3))

(add3 'seven)
▷ Error: The value SEVEN was not of type NUMBER.
▷ To continue, type :CONTINUE followed by an option number:
▷ 1: Specify a different value to use.
▷ 2: Return to Lisp Toplevel.
▷ Debug> (invoke-restart-interactively 'store-value)
▷ Type a form to evaluate and use: 7
→ 10
```

Side Effects:

If prompting for arguments is necessary, some typeout may occur (on query I/O).

A non-local transfer of control might be done by the restart.

Affected By:

query-io, active restarts

Exceptional Situations:

If restart is not valid, an error of type control-error is signaled.

See Also:

find-restart, invoke-restart, restart-case, restart-bind

Notes:

invoke-restart-interactively is used internally by the debugger and may also be useful in implementing other portable, interactive debugging tools.

restart-bind Macro

Syntax:

```
restart-bind (\{(name\ function\ \{\downarrow key-val-pair\}^*)\}) \{form\}^* \rightarrow \{result\}^*

key-val-pair::=:interactive-function interactive-function |
:report-function report-function |
:test-function test-function
```

Arguments and Values:

```
name—a symbol; not evaluated.

function—a form; evaluated.

forms—an implicit progn.

interactive-function—a form; evaluated.

report-function—a form; evaluated.

test-function—a form; evaluated.

results—the values returned by the forms.
```

Description:

restart-bind executes the body of *forms* in a *dynamic environment* where *restarts* with the given *names* are in effect.

restart-bind

If a *name* is nil, it indicates an anonymous restart; if a *name* is a *non-nil symbol*, it indicates a named restart.

The function, interactive-function, and report-function are unconditionally evaluated in the current lexical and dynamic environment prior to evaluation of the body. Each of these forms must evaluate to a function.

If **invoke-restart** is done on that restart, the *function* which resulted from evaluating *function* is called, in the *dynamic environment* of the **invoke-restart**, with the *arguments* given to **invoke-restart**. The *function* may either perform a non-local transfer of control or may return normally.

If the restart is invoked interactively from the debugger (using **invoke-restart-interactively**), the arguments are defaulted by calling the *function* which resulted from evaluating *interactive-function*. That *function* may optionally prompt interactively on *query* I/O, and should return a *list* of arguments to be used by **invoke-restart-interactively** when invoking the restart.

If a restart is invoked interactively but no *interactive-function* is used, then an argument list of **nil** is used. In that case, the *function* must be compatible with an empty argument list.

If the restart is presented interactively (e.g., by the debugger), the presentation is done by calling the function which resulted from evaluating report-function. This function must be a function of one argument, a stream. It is expected to print a description of the action that the restart takes to that stream. This function is called any time the restart is printed while *print-escape* is nil.

In the case of interactive invocation, the result is dependent on the value of :interactive-function as follows.

:interactive-function

Value is evaluated in the current lexical environment and should return a function of no arguments which constructs a list of arguments to be used by **invoke-restart-interactively** when invoking this restart. The function may prompt interactively using query I/O if necessary.

:report-function

Value is evaluated in the current lexical environment and should return a function of one argument, a stream, which prints on the stream a summary of the action that this restart takes. This function is called whenever the restart is reported (printed while *print-escape* is nil). If no :report-function option is provided, the manner in which the restart is reported is implementation-dependent.

:test-function

Value is evaluated in the current lexical environment and should return a function of one argument, a condition, which returns true if the restart is to be considered visible.

Affected By:

query-io.

See Also:

restart-case, with-simple-restart

Notes:

restart-bind is primarily intended to be used to implement restart-case and might be useful in implementing other macros. Programmers who are uncertain about whether to use restart-case or restart-bind should prefer restart-case for the cases where it is powerful enough, using restart-bind only in cases where its full generality is really needed.

restart-case Macro

Syntax:

```
\mathbf{restart\text{-}case} \ \textit{restartable\text{-}form} \ \{ \downarrow \textit{clause} \} \quad \rightarrow \{ \textit{result} \}^*
```

Arguments and Values:

restartable-form—a form.

case-name—a symbol or nil.

lambda-list—an ordinary lambda list.

interactive-expression—a symbol or a lambda expression.

report-expression—a string, a symbol, or a lambda expression.

test-expression—a symbol or a lambda expression.

declaration—a declare expression; not evaluated.

form—a form.

results—the values resulting from the evaluation of restartable-form, or the values returned by the last form executed in a chosen clause, or nil.

Description:

restart-case evaluates restartable-form in a dynamic environment where the clauses have special meanings as points to which control may be transferred. If restartable-form finishes executing and returns any values, all values returned are returned by restart-case and processing has completed. While restartable-form is executing, any code may transfer control to one of the clauses (see invoke-restart). If a transfer occurs, the forms in the body of that clause is evaluated and any values returned by the last such form are returned by restart-case. In this case, the dynamic state is unwound appropriately (so that the restarts established around the restartable-form are no longer active) prior to execution of the clause.

If there are no forms in a selected clause, restart-case returns nil.

If *case-name* is a *symbol*, it names this restart.

It is possible to have more than one clause use the same *case-name*. In this case, the first clause with that name is found by **find-restart**. The other clauses are accessible using **compute-restarts**.

Each arglist is an ordinary lambda list to be bound during the execution of its corresponding forms. These parameters are used by the restart-case clause to receive any necessary data from a call to invoke-restart.

By default, **invoke-restart-interactively** passes no arguments and all arguments must be optional in order to accommodate interactive restarting. However, the arguments need not be optional if the :interactive keyword has been used to inform **invoke-restart-interactively** about how to compute a proper argument list.

Keyword options have the following meaning.

:interactive

The value supplied by :interactive value must be a suitable argument to function. (function value) is evaluated in the current lexical environment. It should return a function of no arguments which returns arguments to be used by invoke-restart-interactively when it is invoked. invoke-restart-interactively is called in the dynamic environment available prior to any restart attempt, and uses $query\ I/O$ for user interaction.

If a restart is invoked interactively but no :interactive option was supplied, the argument list used in the invocation is the empty list.

:report

If the *value* supplied by :report *value* is a *lambda expression* or a *symbol*, it must be acceptable to function. (function *value*) is evaluated in the current lexical environment. It should return a *function* of one argument, a *stream*, which prints on the *stream* a description of the restart. This *function* is called whenever the restart is printed while *print-escape* is nil.

restart-case

If value is a string, it is a shorthand for

```
(lambda (stream) (write-string value stream))
```

If a named restart is asked to report but no report information has been supplied, the name of the restart is used in generating default report text.

When *print-escape* is nil, the printer uses the report information for a restart. For example, a debugger might announce the action of typing a "continue" command by:

```
(format t "~&~S -- ~A~%" ':continue some-restart)
```

which might then display as something like:

```
:CONTINUE -- Return to command level
```

The consequences are unspecified if an unnamed restart is specified but no :report option is provided.

:test

The *value* supplied by :test *value* must be a suitable argument to function. (function *value*) is evaluated in the current lexical environment. It should return a *function* of one *argument*, the *condition*, that returns *true* if the restart is to be considered visible.

The default for this option is equivalent to (lambda (c) (declare (ignore c)) t).

If the restartable-form is a list whose car is any of the symbols signal, error, cerror, or warn (or is a macro form which macroexpands into such a list), then with-condition-restarts is used implicitly to associate the indicated restarts with the condition to be signaled.

Examples:

restart-case

restart-case

```
(defun verify-or-fix-perfect-sundae (ice-cream sauce topping)
               (do ()
                  ((all-start-with-same-letter ice-cream sauce topping))
                 (restart-case
                   (error 'bad-tasting-sundae
                           :ice-cream ice-cream
                           :sauce sauce
                           :topping topping)
                   (use-new-ice-cream (new-ice-cream)
                     :report "Use a new ice cream."
                     :interactive read-new-value
                     (setq ice-cream new-ice-cream))
                   (use-new-sauce (new-sauce)
                     :report "Use a new sauce."
                     :interactive read-new-value
                     (setq sauce new-sauce))
                   (use-new-topping (new-topping)
                     :report "Use a new topping."
                     :interactive read-new-value
                     (setq topping new-topping))))
              (values ice-cream sauce topping))
           \rightarrow \ \mathtt{VERIFY-OR-FIX-PERFECT-SUNDAE}
            (verify-or-fix-perfect-sundae 'vanilla 'caramel 'cherry)
           ▷ Error: Bad tasting sundae with VANILLA, CARAMEL, and CHERRY.
           > To continue, type :CONTINUE followed by an option number:
           ▷ 1: Use a new ice cream.
           \triangleright 2: Use a new sauce.
           \triangleright 3: Use a new topping.
           \triangleright 4: Return to Lisp Toplevel.
           \triangleright Debug> \underline{:}continue 1
           \triangleright Use a new ice cream.
           ▷ Enter a new ice cream: 'chocolate

ightarrow CHOCOLATE, CARAMEL, CHERRY
See Also:
           restart-bind, with-simple-restart.
            (restart-case expression
                (name1 \ arglist1 \dots options1 \dots \ body1)
                (name2 \ arglist2 \dots options2 \dots \ body2))
           is essentially equivalent to
```

Notes:

```
(block #1=#:g0001
  (let ((#2=#:g0002 nil))
       (tagbody
       (restart-bind ((name1 #'(lambda (&rest temp)
                                 (setq #2# temp)
                                 (go #3=#:g0003))
                          \dots slightly-transformed-options 1\dots)
                       (name2 #'(lambda (&rest temp)
                                 (setq #2# temp)
                                 (go #4=#:g0004))
                          \dots slightly-transformed-options2\dots))
       (return-from #1# expression))
         #3# (return-from #1#
                  (apply #'(lambda arglist1 . body1) #2#))
         #4# (return-from #1#
                  (apply #'(lambda arglist2 . body2) #2#)))))
```

Unnamed restarts are generally only useful interactively and an interactive option which has no description is of little value. Implementations are encouraged to warn if an unnamed restart is used and no report information is provided at compilation time. At runtime, this error might be noticed when entering the debugger. Since signaling an error would probably cause recursive entry into the debugger (causing yet another recursive error, etc.) it is suggested that the debugger print some indication of such problems when they occur but not actually signal errors.

restart-name

Function

Syntax:

restart-name restart \rightarrow name

Arguments and Values:

```
restart—a restart.
name—a symbol.
```

Description:

Returns the name of the *restart*, or **nil** if the *restart* is not named.

Examples:

See Also:

compute-restarts find-restart

with-condition-restarts

Macro

Syntax:

```
with-condition-restarts condition-form restarts-form \{form\}^* \rightarrow \{result\}^*
```

Arguments and Values:

```
{\it condition-form} {\it --} a \ {\it form}; \ {\it evaluated} \ to \ produce \ a \ {\it condition}.
```

condition—a condition object resulting from the evaluation of condition-form.

restart-form—a form; evaluated to produce a restart-list.

restart-list—a list of restart objects resulting from the evaluation of restart-form.

forms—an $implicit\ progn;$ evaluated.

results—the values returned by forms.

Description:

First, the *condition-form* and *restarts-form* are *evaluated* in normal left-to-right order; the *primary* values yielded by these *evaluations* are respectively called the *condition* and the *restart-list*.

Next, the *forms* are *evaluated* in a *dynamic environment* in which each *restart* in *restart-list* is associated with the *condition*. See Section 9.1.4.2.4 (Associating a Restart with a Condition).

See Also:

restart-case

Notes:

Usually this *macro* is not used explicitly in code, since **restart-case** handles most of the common cases in a way that is syntactically more concise.

with-simple-restart

Macro

Syntax:

```
with-simple-restart (name format-control \{format-argument\}^*) \{form\}^* \rightarrow \{result\}^*
```

Arguments and Values:

name—a symbol.

format-control—a format control.

format-argument—an object (i.e., a format argument).

forms—an implicit progn.

results—in the normal situation, the values returned by the forms; in the exceptional situation where the restart named name is invoked, two values—nil and \mathbf{t} .

Description:

with-simple-restart establishes a restart.

If the restart designated by *name* is not invoked while executing *forms*, all values returned by the last of *forms* are returned. If the restart designated by *name* is invoked, control is transferred to **with-simple-restart**, which returns two values, **nil** and **t**.

If *name* is **nil**, an anonymous restart is established.

The format-control and format-arguments are used report the restart.

with-simple-restart

Examples:

```
(defun read-eval-print-loop (level)
   (with-simple-restart (abort "Exit command level ~D." level)
     (loop
       (with-simple-restart (abort "Return to command level ~D." level)
          (let ((form (prog2 (fresh-line) (read) (fresh-line))))
            (prin1 (eval form))))))

ightarrow READ-EVAL-PRINT-LOOP
 (read-eval-print-loop 1)
 (+ 'a 3)
▷ Error: The argument, A, to the function + was of the wrong type.
         The function expected a number.
	riangle To continue, type :CONTINUE followed by an option number:
\triangleright 1: Specify a value to use this time.
▷ 2: Return to command level 1.
▷ 3: Exit command level 1.

▷ 4: Return to Lisp Toplevel.

 (defun compute-fixnum-power-of-2 (x)
   (with-simple-restart (nil "Give up on computing 2^{\tilde{D}}." x)
     (let ((result 1))
       (dotimes (i x result)
         (setq result (* 2 result))
         (unless (fixnump result)
            (error "Power of 2 is too large."))))))
COMPUTE-FIXNUM-POWER-OF-2
 (defun compute-power-of-2 (x)
   (or (compute-fixnum-power-of-2 x) 'something big))
COMPUTE-POWER-OF-2
 (compute-power-of-2 10)
1024
 (compute-power-of-2 10000)
▷ Error: Power of 2 is too large.
\triangleright To continue, type :CONTINUE followed by an option number.
\triangleright 1: Give up on computing 2^{10000}.
▷ 2: Return to Lisp Toplevel
▷ Debug> :continue 1

ightarrow SOMETHING-BIG
```

See Also:

restart-case

Notes:

with-simple-restart is shorthand for one of the most common uses of restart-case.

with-simple-restart could be defined by:

Because the second return value is t in the exceptional case, it is common (but not required) to arrange for the second return value in the normal case to be missing or nil so that the two situations can be distinguished.

abort

Data Arguments Required:

None.

Description:

The intent of the **abort** restart is to allow return to the innermost "command level." Implementors are encouraged to make sure that there is always a restart named **abort** around any user code so that user code can call **abort** at any time and expect something reasonable to happen; exactly what the reasonable thing is may vary somewhat. Typically, in an interactive listener, the invocation of **abort** returns to the *Lisp reader* phase of the *Lisp read-eval-print loop*, though in some batch or multi-processing situations there may be situations in which having it kill the running process is more appropriate.

See Also:

Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), **invoke-restart**, **abort** (function)

continue

Data Arguments Required:

None.

Description:

The **continue** restart is generally part of protocols where there is a single "obvious" way to continue, such as in **break** and **cerror**. Some user-defined protocols may also wish to incorporate it for similar reasons. In general, however, it is more reliable to design a special purpose restart with a name that more directly suits the particular application.

Examples:

See Also:

Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), invoke-restart, continue (function), assert, cerror

muffle-warning

Restart

Data Arguments Required:

None.

Description:

This restart is established by warn so that handlers of warning conditions have a way to tell warn that a warning has already been dealt with and that no further action is warranted.

Examples:

```
\label{eq:continuous} \begin{tabular}{ll} (defvar *all-quiet* nil) $\rightarrow$ *ALL-QUIET* \\ (defvar *saved-warnings* '()) $\rightarrow$ *SAVED-WARNINGS* \\ (defun quiet-warning-handler (c) \\ (when *all-quiet* \\ (let ((r (find-restart 'muffle-warning c))) \\ \end{tabular}
```

```
(when r
          (push c *saved-warnings*)
          (invoke-restart r)))))

ightarrow CUSTOM-WARNING-HANDLER
 (defmacro with-quiet-warnings (&body forms)
   '(let ((*all-quiet* t)
           (*saved-warnings* '()))
      (handler-bind ((warning #'quiet-warning-handler))
         ,@forms
         *saved-warnings*)))

ightarrow WITH-QUIET-WARNINGS
 (setq saved
   (with-quiet-warnings
     (warn "Situation #1.")
     (let ((*all-quiet* nil))
        (warn "Situation #2."))
     (warn "Situation #3.")))
▷ Warning: Situation #2.

ightarrow (#<SIMPLE-WARNING 42744421> #<SIMPLE-WARNING 42744365>)
 (dolist (s saved) (format t "~&~A~%" s))

⊳ Situation #3.

⊳ Situation #1.

ightarrow NIL
```

See Also:

Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), **invoke-restart**, **muffle-warning** (function), **warn**

store-value Restart

Data Arguments Required:

a value to use instead (on an ongoing basis).

Description:

The **store-value** restart is generally used by handlers trying to recover from errors of types such as **cell-error** or **type-error**, which may wish to supply a replacement datum to be stored permanently.

Examples:

```
(defun type-error-auto-coerce (c)
  (when (typep c 'type-error)
      (let ((r (find-restart 'store-value c)))
```

```
(\text{handler-case (let ((v (coerce (type-error-datum c) \\ (type-error-expected-type c))))} \\ (\text{invoke-restart r v))} \\ (\text{error ()))))) \rightarrow \text{TYPE-ERROR-AUTO-COERCE} \\ (\text{let ((x 3))} \\ (\text{handler-bind ((type-error #'type-error-auto-coerce))} \\ (\text{check-type x float)} \\ \text{x))} \rightarrow 3.0
```

See Also:

Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), invoke-restart, store-value (function), ccase, check-type, ctypecase, use-value (function and restart)

use-value Restart

Data Arguments Required:

a value to use instead (once).

Description:

The use-value restart is generally used by handlers trying to recover from errors of types such as cell-error, where the handler may wish to supply a replacement datum for one-time use.

See Also:

Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), invoke-restart, use-value (function), store-value (function and restart)

abort, continue, muffle-warning, store-value, usevalue Function

Syntax:

```
abort & optional condition \rightarrow | continue & optional condition \rightarrow nil muffle-warning & optional condition \rightarrow | store-value value & optional condition \rightarrow nil use-value value & optional condition \rightarrow nil
```

Arguments and Values:

```
value—an object.
condition—a condition object, or nil.
```

Description:

Transfers control to the most recently established applicable restart having the same name as the function. That is, the function abort searches for an applicable abort restart, the function continue searches for an applicable continue restart, and so on.

If no such *restart* exists, the functions **continue**, **store-value**, and **use-value** return **nil**, and the functions **abort** and **muffle-warning** signal an error of *type* **control-error**.

When *condition* is *non-nil*, only those *restarts* are considered that are either explicitly associated with that *condition*, or not associated with any *condition*; that is, the excluded *restarts* are those that are associated with a non-empty set of *conditions* of which the given *condition* is not an *element*. If *condition* is nil, all *restarts* are considered.

Examples:

```
;;; Example of the ABORT retart
 (defmacro abort-on-error (&body forms)
   '(handler-bind ((error #'abort))
      ,@forms)) 
ightarrow ABORT-ON-ERROR
 (abort-on-error (+ 3 5)) 
ightarrow 8
 (abort-on-error (error "You lose."))
▷ Returned to Lisp Top Level.
;;; Example of the CONTINUE restart
 (defun real-sqrt (n)
   (when (minusp n)
     (setq n (- n))
     (cerror "Return sqrt(~D) instead." "Tried to take sqrt(-~D)." n))
   (sqrt n))
 (real-sqrt 4) 
ightarrow 2
 (real-sqrt -9)
▷ Error: Tried to take sqrt(-9).

hd To continue, type :CONTINUE followed by an option number:
▷ 1: Return sqrt(9) instead.
▷ 2: Return to Lisp Toplevel.
▷ Debug> (continue)
▷ Return sqrt(9) instead.
```

```
(handler-bind ((error #'(lambda (c) (continue))))
   \texttt{(real-sqrt -9))} \, \rightarrow \, 3
;;; Example of the MUFFLE-WARNING restart
 (defun count-down (x)
   (do ((counter x (1- counter)))
       ((= counter 0) 'done)
     (when (= counter 1)
       (warn "Almost done"))
     (format t "~&~D~%" counter)))

ightarrow COUNT-DOWN
 (count-down 3)
▷ Warning: Almost done
⊳ 1

ightarrow DONE
 (defun ignore-warnings-while-counting (x)
   (handler-bind ((warning #'ignore-warning))
     (count-down x)))

ightarrow IGNORE-WARNINGS-WHILE-COUNTING
 (defun ignore-warning (condition)
   (declare (ignore condition))
   (muffle-warning))

ightarrow IGNORE-WARNING
 (ignore-warnings-while-counting 3)
⊳ 3
⊳ 2
⊳ 1

ightarrow DONE
;;; Example of the STORE-VALUE and USE-VALUE restarts
 (defun careful-symbol-value (symbol)
   (check-type symbol symbol)
   (restart-case (if (boundp symbol)
                       (return-from careful-symbol-value
                                     (symbol-value symbol))
                       (error 'unbound-variable
                              :name symbol))
     (use-value (value)
       :report "Specify a value to use this time."
       value)
```

```
(store-value (value)
        :report "Specify a value to store and use in the future."
        (setf (symbol-value symbol) value))))
 (setq a 1234) 
ightarrow 1234
 (careful-symbol-value 'a) 
ightarrow 1234
 (makunbound 'a) 
ightarrow A
 (careful-symbol-value 'a)
▷ Error: A is not bound.
	riangle To continue, type :CONTINUE followed by an option number.
▷ 1: Specify a value to use this time.
\triangleright 2: Specify a value to store and use in the future.
▷ 3: Return to Lisp Toplevel.
▷ Debug> (use-value 12)
\rightarrow 12
 (careful-symbol-value 'a)
▷ Error: A is not bound.
> To continue, type :CONTINUE followed by an option number.
▷ 1: Specify a value to use this time.
\triangleright 2: Specify a value to store and use in the future.

⇒ 3: Return to Lisp Toplevel.

▷ Debug> (store-value 24)
\rightarrow 24
 (careful-symbol-value 'a)
;;; Example of the USE-VALUE restart
 (defun add-symbols-with-default (default &rest symbols)
   (handler-bind ((sys:unbound-symbol
                      #'(lambda (c)
                          (declare (ignore c))
                          (use-value default))))
     (apply #'+ (mapcar #'careful-symbol-value symbols))))

ightarrow ADD-SYMBOLS-WITH-DEFAULT
 (setq x 1 y 2) \rightarrow 2
 (add-symbols-with-default 3 'x 'y 'z) \rightarrow 6
```

Side Effects:

A transfer of control may occur if an appropriate *restart* is available, or (in the case of the *function* **abort** or the *function* **muffle-warning**) execution may be stopped.

Affected By:

Each of these functions can be affected by the presence of a *restart* having the same name.

Exceptional Situations:

If an appropriate abort restart is not available for the function abort, or an appropriate muffle-warning restart is not available for the function muffle-warning, an error of type control-error is signaled.

See Also:

invoke-restart, Section 9.1.4.2 (Restarts), Section 9.1.4.2.2 (Interfaces to Restarts), assert, ccase, cerror, check-type, ctypecase, use-value, warn

Notes:

```
(abort condition) \equiv (invoke-restart 'abort)
(muffle-warning) \equiv (invoke-restart 'muffle-warning)
                  \equiv (let ((r (find-restart 'continue))) (if r (invoke-restart r)))
(use-value X) \equiv (let ((r (find-restart 'use-value))) (if r (invoke-restart r X)))
(store-value x) \equiv (let ((r (find-restart 'store-value))) (if r (invoke-restart r x)))
```

No functions defined in this specification are required to provide a use-value restart.