### Typesetting dropped capitals with LaTeX

Daniel Flipo daniel.flipo@free.fr

### 1 Introduction

The file lettrine.sty<sup>1</sup>, provides a command \lettrine which requires two mandatory arguments, and an optional one.

Adding \usepackage{lettrine} in the preamble of a document defines the command \lettrine, the simplest use of which is \lettrine{<\letter>}{<\text>}. It produces a dropped capital <\letter> (2 lines high), followed by <\text> typeset in small caps, and the rest of the paragraph is wrapped around the dropped capital.

The \lettrine[<options>]{<letter>}{<text>} command accepts various optional arguments to control the size and layout of the dropped capital and match the requirements described in the books

- + "Lexique des règles typographiques en usage à l'Imprimerie nationale" troisième édition (1994), ISBN-2-11-081075-0,
- + "Mise en page et impression" Yves Perrousseaux, ISBN-2-911220-01-3.

The parameters can be set using the key=value syntax:

- lines=<integer> sets how many lines the dropped capital will occupy (default=2);
- + depth=<integer> sets the number of lines to be reserved under the baseline, this is meant for dropped capital with positive depth, like Q (default=0);
- + lhang=<decimal> (0 ≤ lhang ≤ 1) sets how much of the dropped capital's width should hang into the margin (default=0);
- + loversize=<decimal> (-1 < loversize ≤ 1) enlarges the dropped capital's height: with loversize=0.1 its height is enlarged by 10% so that it raises above the top paragraph's line (default=0);
- + lraise=<decimal> does not affect the dropped capital's height, but moves it up (if positive), down (if negative); useful with capitals like J or Q which have a positive depth, (default=0);
- + findent=<dimen> (positive or negative) controls the horizontal gap between the dropped capital and the indented block of text (default=0pt);
- + nindent=<dimen> shifts all indented lines, starting from the second one, horizontally by <dimen> (this shift is relative to the first line, default=0.5em);
- + slope=<dimen> can be used with dropped capitals like A or V to add <dimen> (positive or negative) to the indentation of each line starting from the third one (no effect if lines=2, default=0pt);

<sup>&</sup>lt;sup>1</sup>The file described in this section has version number v2.80 and was last revised on 2025-01-30.

- + ante=<*string*> can be used to typeset <*string*> *before* the dropped capital (typical use is for French guillemets starting the paragraph).
- + image[=true] will force \lettrine to replace the letter normally used as dropped capital by an image in eps format (latex) or in pdf, jpg, png, etc. format (pdflatex, xelatex, lualatex); this requires the graphicx package to be loaded in the preamble. \lettrine[image=true]{A}{n exemple} or just \lettrine[image]{A}{n exemple} will load A.eps, A.jpg, A.png or A.pdf instead of letter A.
- + viewport=<*llx lly urx ury*> is passed to \includegraphics (same four dimen parameters); when present, \lettrine only considers the contents of the rectangle defined by its lower left and upper right corners to compute the scaling ratio (which will apply to the whole image). It's up to the user to ensure that the rest of the image will not overwrite the surrounding text, f.i. providing a \vspace\*{...} in case a significant part sticks out on top of the defined rectangle. This option may be useful in case the letter covers only a limited part of the image, see https://tex.stackexchange.com/questions/693270/ for an example, or when the image's bounding box is inaccurate.
- + grid[=true] will force the vertical skip added above the paragraph starting with \lettrine to be rounded up to an integer number of \baselineskip. This option is meant for grid typesetting.
- + nextpage[=true]; if a paragraph starting with a dropped cap begins too low on a page to fit in, a warning is issued; this flag controls whether the whole paragraph should be moved to the top of next page or not. This option is not recommended, there are often better fixes for such situations: reducing the dropped cap's height, shortening some previous paragraph, enlarging the page...
- + novskip=<*dimen>* overrides \DiscardVskip (default=1pt). In some cases (see options lraise, loversize or accentuated dropped capitals,...) the top of the dropped capital will raise above the top of following text (usually in small caps), this will trigger a corresponding vertical skip above the paragraph starting with \lettrine, *only if* this skip exceeds \DiscardVskip. Consider enlarging novskip (or \DiscardVskip) to prevent small vertical skips from being rounded up to \baselineskip when using the 'grid' option.
- + realheight[=true] will compute the default height of the initial so that the top of it is exactly aligned with the top of the text entered as second mandatory argument of \lettrine taking possible accents into account. Otherwise, the default height is computed using a customisable string \LettrineSecondString instead of the real argument. For backward compatibility, option realheight defaults to false and \LettrineSecondString to 'x'.

You probably don't need this option if you choose to typeset the second mandatory argument of \lettrine in small caps (the default). If you change \LettrineTextFont to \relax or \upshape, consider these two examples:

\lettrine{H}{ello} you might like the top of the 'H' to be aligned with the top of the 'll' rather than with the top of the 'e', adding option realheight does the trick: \lettrine[realheight]{H}{ello}.

Global variants: \LettrineRealHeighttrue or (without the realheight option) \renewcommand\*{\LettrineSecondString}{1}.

\lettrine{L}{a misere} option realheight=true would align with the top of the 'L' with the top of the grave accent, the default is probably better (top of the 'L' aligned with the top of the non accented letters).

+ refstring with no value, is meant for fancy initials with irregular heights (i.e. taken in fonts like Yinit (OpenType), cfr-initials,...). Option refstring forces the \fontsize computations to be run on the initial given as \lettrine's first mandatory argument instead of the reference string \LettrineTestString. In most cases, this option should *not* be used: think of accentuated initials or capitals with optical correction.

refstring=<*string*> can be used to override \LettrineTestString, the default reference string (option *seldom useful*).

Coloured initials are available in conjonction with package color, examples:

see package color for the syntax of colour commands. Another possibility to colour initials globally is described below, see \LettrineFontHook.

Three dimensions,  $\LettrineHeight$ ,  $\LettrineDepth$  and  $\LettrineWidth$  hold the final size of the initial (*height* and *depth* being measured from the paragraph's n-th baseline if  $\LettrineHeight$ ).

Have a look at files lettrine-demo-fr. tex and lettrine-demo-lua. tex and at the resulting PDFs in the doc folder to see the possible usage of these parameters.

Starting with version 2.30, the default settings can easily be specified as options passed to the lettrine package. These options are the same as those of the \lettrine command previously described <sup>2</sup>: f.i. \usepackage[lines=3]{lettrine} will set the default to three lines of text. Options passed to the lettrine package override the defaults set in the lettrine.cfg file (see below) and will be overriden by options passed to the \lettrine command.

The default settings can also be customized in a config file lettrine.cfg (backward compatibility). The following list shows the syntax to set them and their default values:

- + \setcounter{DefaultLines}{2},
- + \setcounter{DefaultDepth}{0},
- + \renewcommand\*{\DefaultLoversize}{0},
- + \renewcommand\*{\DefaultLraise}{0},
- + \renewcommand\*{\DefaultLhang}{0},
- + \setlength{\DefaultFindent}{Opt},
- + \setlength{\DefaultNindent}{0.5em},

<sup>&</sup>lt;sup>2</sup>With the exception of ante and viewport which do not make sense for a global usage.

- + \setlength{\DefaultSlope}{Opt}.
- + \setlength{\DiscardVskip}{1pt},
- + \LettrineImagefalse,
- + \LettrineOnGridfalse,
- + \LettrineMoveAtEOPfalse,
- + \LettrineRealHeightfalse.

Instead of giving optional parameters to the \lettrine command, it is possible to set them on a per character basis in a second config file (suggested by Pascal Kockaert): \renewcommand{\DefaultOptionsFile}{<filename>} in the preamble will force this file to be read 'AtBeginDocument'. Alternatively, \usepackage[optionsfile=<filename>]{lettrine} produces the same effect. See examples of such config files in the subdirectory contrib.

The idea is to provide settings for specific fonts, or to define suitable parameters for some initials like A or V, for instance

\LettrineOptionsFor{A}{slope=0.5em, findent=-1.5em, nindent=.7em}

Options passed this way are meant to fine tune how the text will be wrapped around the initial; for convenience  $inside \ \ LettrineOptionsFor \ only$ , \LettrineWidth can be used instead of em as a unit length.

Since version 2.70, these commands are also allowed in the document's preamble. Mixing \LettrineOptionsFor commands in the preamble and in an external config file is not recommended: remember that if an options file is declared, the settings it holds will be taken into account 'AtBeginDocument' thus possibly overriding \LettrineOptionsFor commands in the preamble.

Anyway, the settings read from this file will be overridden by the optional arguments eventually given to the **\lettrine** command.

More customisation possibilities are offered by the next four commands:

- + \renewcommand\*{\LettrineFontHook}{},
- + \renewcommand\*{\LettrineTextFont}{\scshape},
- + \renewcommand\*{\LettrineTestString}{EFTZ},
- + \renewcommand\*{\LettrineSecondString}{x},

\LettrineTextFont sets the font used for the second argument of \lettrine, its default definition is \newcommand{\LettrineTextFont}{\scshape} (second argument in small caps), this can be changed using \renewcommand.

\LettrineTestString and \LettrineSecondString provide reasonable defaults for Latin scripts (EFTZ and x). For other scripts they *should be changed* respectively to uppercase and lowercase letters of the given script, as the dropped cap's height computation is based on these strings; another possibility is to use the previously described refstring and realheight options.

\LettrineFont is not customisable see \LettrineFontHook below, it sets the font used for the dropped capital, usually the current font in a (large) size, computed

automatically from the number of lines it will fill: the font size is computed so that, a *standard* dropped capital (say Z, not  $\grave{A}$ ) when sitting on its baseline, gets its top aligned with the top of the following text (provided loversize = 0 and lines  $\geq$  2). When lines=1, size is computed as if lines was 2.

A hook \LettrineFontHook is provided to change the font used for the dropped capital, syntax follows LaTeX's low-level font interface (see LaTeX Companion III, section I-9.3), the \selectfont command is issued by \LettrineFont:

selects Palatino bold expanded slanted for the dropped capital.

With LuaLaTeX or XeLaTeX changing the lettrine's font is even easier, simply use the \fontspec command:

\renewcommand{\LettrineFontHook}{\fontspec{LinLibertine\_I.otf}}
will switch to Linux Libertine Initials.

\LettrineFontHook can also be used to change the colour of all initials in a (part of) document: \renewcommand{\LettrineFontHook}{\color[gray]{0.5}} will colour the initials following this command in grey. A \color command can be added in \LettrineTextHook if the text following the dropped cap requires the same or another colour.

Important notice: the sizing works fine with *fully scalable* fonts (like the standard Post-Script or OpenType fonts), but might not work well with CM/EC fonts which have two limitations: only a limited number of sizes is available by default (precise adjustments are impossible), and the largest size (25pt or 35pt) is often too small. The CM fonts are available in PostScript type1 format for free (courtesy of BlueSky/Y&Y), to make them fully scalable, it is mandatory to add \usepackage{type1cm} in the preamble of your document. The EC fonts are also available in type1 format for free (thanks to Vladimir Volovich, they are called cm-super), and adding \usepackage{type1ec} in the preamble will make them fully scalable too. So, if you want lettrine.sty to work properly with CM or EC fonts, you will need *PostScript versions* of these fonts *and* one of the packages type1cm.sty or type1ec.sty.

You can also consider using one of the standard PostScript fonts (Palatino, Times, Utopia...), or any OpenType font, they are fully scalable too!

Breaking change in version 2.50: in order to improve the alignment of side by side parboxes starting with a dropped cap, the internals of the \lettrine{} command have changed. Formerly, the initial was completely smashed (height=0, depth=0) and a \vskip was added in case the initial sticked out too much above the paragraph's first baseline. From version 2.50 on, the initial gets a null depth and its proper height (measured from the paragraph's first baseline, please note that it is different from \LettrineHeight). This change has the following side effect: in multicolumn type-setting, when a dropped cap starts a column and sticks out significantly above the baseline, it might be necessary to 'smash' the dropped cap and eventually to add a

<sup>&</sup>lt;sup>3</sup>This package, available on CTAN, was first released on 2002/07/30.

\vspace{} before the multicolumn environment. See lettrine-demo-fr.pdf p. 4 for an example. Using the rollback mechanism to switch back to version 2.40 is another option: \usepackage{lettrine}[=v2.4].

New in version 2.60: the \lettrine command is now compatible with right to left typesetting, with LuaLaTeX and XeLaTeX (+babel or polyglossia). With XeLaTeX, file lettrine-xetex-bidi.def (v0.8 [2022/11/06]) is automatically loaded by the bidi package; it redefines the \@lettrine command based on version 2.30 of lettrine. This code is *incompatible* with versions 2.50 and newer, you can safely remove lettrine-xetex-bidi.def when installing v2.60 of lettrine.

#### **Known issues:**

- + Starting with version 2.80, the lettrine package issues a warning in case a paragraph starting with a dropped capital occurs at the end of some page thus requiring manual page-breaking; it's up to the user to figure out how to best fix the issue (enlarging the page, shortening some previous paragraph...). A new option nextpage has also been added, when set to true, the whole paragraph is moved to the top of next page... leaving a blank at the end of the previous page.
- + \lettrine works within 'quote' 'quotation', 'abstract' environments but does not work within 'verse' environments. It doesn't work either in 'center' environments except with option [lines=1].
- + \lettrine does not work within lists.
- + If \lettrine is used inside any environment, it is *mandatory* to end the paragraph starting with the dropped capital *inside* the environment; adding a \parcommand before the end of environment usually fixes placement issues.
- + The LaTeX \raggedright command doesn't work well with the TeX \parshape command used internally by \lettrine. Please use the \RaggedRight command from the ragged2e package together with appropriate settings, f.i. \setlength{\RaggedRightRightskip}{0pt plus .1\hsize}. See https://tex.stackexchange.com/questions/97808/ for details.
- + If a *list* has to be included in a paragraph starting with \lettrine, it is necessary to add the command \parshape=0 just after the end of the list (starting a new paragraph just before or just after the list works too). Remember that 'quote', 'quotation', 'abstract' environments are implemented as *lists* in LaTeX.
- + If you are facing some slight height inaccuracy for a dropped capital, you can try option refstring; this option is meant for fancy (unaccented) initials. Informations about targeted and effective initial's height are available in the .log file. Using LuaTeX or XeTeX engines with OpenType fonts may be an option (some TFM files for Type1 fonts are slightly inaccurate).
- + \LettrineTestString's value has changed over the time; these changes may result in slight size differences for the initial. Starting with version 2.2, the lettrine package takes advantage of the rollback facilities recently introduced by the LaTeX Team<sup>4</sup>. Three rollback versions are provided in order to produce exactly the same output as with former versions: you can request

 $<sup>^4</sup>$ A LaTeX kernel dated 2018-04-01 or newer is required.

<sup>&</sup>lt;sup>5</sup>Don't forget the = sign!

# 2 TEXnical details

The lettrine package uses the rollback mechanism introduced by the LaTeX Team to provide easier backward compatibility. The current release requires a LaTeX version not older than 2022-06-01 (kernel packages ltkeys and xfp are required).

Default initializations: define the necessary counters, lengths, and commands to hold the default settings and set these default settings. They can be overwritten in file lettrine.cfg.

```
8 \newcounter{DefaultLines}
9\setcounter{DefaultLines}{2}
10 \newcounter{DefaultDepth}
11 \newcommand*{\DefaultOptionsFile}{\relax}
12 \newcommand*{\DefaultLoversize}{0}
13 \newcommand*{\DefaultLraise}{0}
14 \newcommand*{\DefaultLhang}{0}
15 \newdimen\DefaultFindent
16\setlength{\DefaultFindent}{\z@}
17 \newdimen\DefaultNindent
18 \setlength{\DefaultNindent}{0.5em}
19 \newdimen\DefaultSlope
20 \setlength{\DefaultSlope}{\z@}
21 \newdimen\DiscardVskip
22 \setlength{\DiscardVskip}{1\p@}
23 \newif\ifLettrineImage
24 \newif\ifLettrineOnGrid
25 \newif\ifLettrineRealHeight
26 \newif\ifLettrineMoveAtEOP
```

Then let's define the necessary internal counters, lengths, and commands.

```
27 \newsavebox{\L@lettrine}
28 \newsavebox{\L@lbox}
29 \newsavebox{\L@lbox}
30 \newcounter{L@lines}
31 \newcounter{L@depth}
32 \newdimen\L@Pindent
33 \newdimen\L@Findent
34 \newdimen\L@Nindent
35 \newdimen\L@Iraise
36 \newdimen\L@Iraise
36 \newdimen\L@Iraise
37 \newdimen\L@next
38 \newdimen\L@next
38 \newdimen\L@lope
39 \newdimen\L@lope
40 \newdimen\L@novskip
41 \newdimen\L@target@ht
```

```
42 \newdimen\L@target@dp
43 \newdimen\L@target@tht
44 \newdimen\LettrineWidth
45 \newdimen\LettrineHeight
46 \newdimen\LettrineDepth
47 \newdimen\L@finalht
48 \newdimen\L@finaldp
49 \newcommand*{\L@file}{}
50 \newcommand*{\L@hang}{}
51 \newcommand*{\L@oversize}{}
52 \newcommand*{\L@raise}{}
53 \newcommand*{\L@ante}{}
54 \newif\ifL@image
55 \newif\ifL@grid
56 \newif\ifL@nextpage
57 \newif\ifL@realh
58 \let\ifL@RTL\iffalse
59 \newcommand*{\L@viewport}{}
```

\LettrineTestString As some font designers apply optical correction to capitals C, G, O, or Q (they are slightly taller than 'T' or 'Z'), they are better left out of \LettrineTestString. EFTZ should be a good default for most fonts.

```
60 \newcommand*{\LettrineTestString}{EFTZ}
```

Load a local config file if present in LaTeX's search path.

```
61\InputIfFileExists{lettrine.cfg}
62 {\typeout{Loading lettrine.cfg}}
63 {\typeout{lettrine.cfg not found, using default values}}
```

Global package options enable to override the default values given above to generic parameters. These may be overriden again by options passed to the \lettrine[]{}{} command. This code is based on ltkeys.dtx.

```
64 \DeclareKeys[LettrineGlobal]
65
  {
66
     lines.code
                     = \setcounter{DefaultLines}{#1}
                   = \setcounter{DefaultDepth}{#1}
     depth.code
67
     depth.code = \setcounter{Def}
lhang.store = \DefaultLhang
68
     loversize.store = \DefaultLoversize
69
     lraise.store = \DefaultLraise
70
     findent.code = \setlength{\DefaultFindent}{#1} ,
71
     72
73
74
     image.if
                    = LettrineImage
75
     grid.if
                    = LettrineOnGrid
76
     nextpage.if
                    = LettrineMoveAtEOP
77
     realheight.if = LettrineRealHeight
78
     refstring.default:n = \L@initial
79
     refstring.store = \LettrineTestString
80
     optionsfile.store = \DefaultOptionsFile
81
82 }
83 \ProcessKeyOptions[LettrineGlobal]
```

Ditto for the \lettrine command's options.

```
84 \DeclareKeys[LettrineLocal]
85
  {
86
     lines.code
                    = \setcounter{L@lines}{#1}
                    = \setcounter{L@depth}{#1}
87
     depth.code
     lhang.store = \L@hang
88
     loversize.store = \L@oversize
89
     lraise.store
                    = \L@raise
90
                    = \L@ante
91
     ante.store
     92
93
94
95
                  = L@image
     image.if
96
     viewport.store = \L@viewport
97
     grid.if
                   = L@grid
98
     nextpage.if
                   = L@nextpage
99
     realheight.if = L@realh
100
101
     refstring.default:n = \L@initial
     refstring.store = \L@refstring
102
103 }
```

Read the per letter options file 'AtBeginDocument'.

```
104 \AtBeginDocument{%
105 \if\DefaultOptionsFile\relax
106 \else
107 \InputIfFileExists{\DefaultOptionsFile}%
108 {}%
109 {\PackageWarning{lettrine.sty}%
110 {File \DefaultOptionsFile\space not found}%
111 }%
112 \fi}
```

\LettrineOptionsFor This command sets the values of parameters on a per character basis, for instance:

\LettrineOptionsFor{A}{slope=0.6em, findent=-1em, nindent=0.6em}

```
113 \newtoks\Lettrine@tweaks
114 \newcommand*{\LettrineOptionsFor}[2]{%
115 \Lettrine@tweaks=\expandafter{\the\Lettrine@tweaks
116 \@lettrine@optionsfor{#1}{#2,}}}
```

The internal \@lettrine@optionsfor checks if its first argument matches the current initial, if so it passes the options (second argument) to \SetKeys.

```
117 \newcommand*{\@lettrine@optionsfor}[2]{%
118 \edef\L@tmpa{#1}%
```

Gobble potential color commands for the initial.

```
119 \begingroup
120 \def\color##1##{\L@color{##1}}%
121 \let\L@color\@gobbletwo
122 \def\textcolor##1##{\L@textcolor{##1}}%
123 \def\L@textcolor##1##2##3{##3}%
```

```
\xdef\L@tmpb{\L@initial}%
124
    \endgroup
125
    \ifx\L@tmpa\L@tmpb \SetKeys[LettrineLocal]{#2}\fi
126
127
```


\LettrineTextFont In French, small caps usually follow the initial.

```
128 \newcommand*{\LettrineTextFont}{\scshape}
129 \newcommand*{\LettrineSecondString}{x}
```

\LettrineFontHook \LettrineFontHook enables to select another font for the dropped capital. Its default definition is empty (the current text font is used).

```
130 \newcommand*{\LettrineFontHook}{}
```

\computeL@height The default size for the dropped capital is computed so that the top of it is exactly aligned with the top of the following text; an extra height (positive or negative) may be added globally by redefining \Defaultloversize or locally using optional argument loversize=. If lines=1, the default size for the dropped capital is computed as if lines=2.



\computeL@height first computes the targeted height for the dropped capital and stores it into \L@target@tht. This height only depends on L@lines and on the height of \L@tbox (see fig. 1). So options must be read and \L@tbox must be properly initialised before executing \computeL@height (see below in \@lettrine code).

\L@height is set to \L@target@tht raised by the \L@oversize factor.

```
131 \def\computeL@height{%
    \setlength{\L@target@ht}{\ht\L@tbox}%
```

As \baselineskip might be a rubber length, let's convert it into a 'dimen' using \@tempdima.

```
\@tempdima=\baselineskip
133
    \setlength{\L@target@dp}{\value{L@lines}\@tempdima}%
134
    \ifnum\value{L@lines}>1
135
      \addtolength{\L@target@dp}{-\@tempdima}%
136
137
      \addtolength{\L@target@ht}{\L@target@dp}%
138
```

```
\setlength{\L@target@dp}{\z@}%
139
    \fi
140
    \setlength{\L@target@tht}{\L@target@ht}%
141
    \addtolength{\L@target@tht}{\L@target@dp}%
142
    \setlength{\L@height}{\L@target@tht}%
143
    \addtolength{\L@height}{\L@oversize\L@target@tht}%
144
145 }
```

\compute@fontsize After executing \computeL@height, \L@height holds the exact height required for the dropped capital, nothing more is needed if the initial is a picture, otherwise we need to compute the matching \fontsize's value. This is done by measuring the height of a "reference" capital (i.e. either listed in \LettrineTestString or the initial itself). This command compares the height of a "reference" capital scaled by \fontsize with argument \L@height, to \L@height (the required height for the initial); both are converted into integers (in sp), to compute a ratio \L@factor (decimal number). Then, the initial will be scaled by \L@factor\L@height. Starting with v2.40, \L@factor is computed by \fpeval from xfp.sty.

> If the option refstring is set in the \lettrine command the initial itself is taken as reference to compute \fontsize, this can be handy when working with fancy fonts (i.e. cfr-initials, Yinit). In most cases, the default is a better choice.

```
146 \def\compute@fontsize{%
    \ifx\L@refstring\@empty
147
148
       \def\Lettrine@RefString{\LettrineTestString}%
149
    \else
150
       \def\Lettrine@RefString{\L@refstring}%
151
    \sbox{\@tempboxa}{\LettrineFontHook
152
                        \fontsize{\L@height}{\L@height}\selectfont
153
                        \Lettrine@RefString}%
154
    \@tempcnta=\ht\@tempboxa
155
    \ifnum\@tempcnta=0
156
       \PackageWarning{lettrine}{Unable to compute \protect\fontsize!%
157
       \MessageBreak \protect\LettrineTestString\space empty? reported}
158
       \def\L@factor{1}%
159
    \else
160
161
       \@tempcntb=\L@height
162
       \def\L@factor{\fpeval{\the\@tempcntb/\the\@tempcnta}}%
163
    \fi
164 }
```

\LettrineFont \fontsize's argument providing the requested \L@height is \L@factor\L@height.

```
165 \newcommand*{\LettrineFont}{%
      \LettrineFontHook
      \fontsize{\L@factor\L@height}{\L@factor\L@height}%
167
168
      \selectfont
169 }
```

\setupL@lbox The next (internal) command computes the requested size for the initial (letter or image) and prepares a box \L@lbox holding it.

```
170 \def\setupL@lbox{%
171 \computeL@height
```

```
\ifL@image
172
       \ifx\L@viewport\@empty
173
         \sbox{\L@lbox}{\includegraphics[height=\L@height]{\L@initial}}%
174
175
         \sbox{\L@lbox}{%
176
           \expanded{\noexpand\includegraphics%
177
                      [viewport=\L@viewport, height=\L@height]{\L@initial}%
178
179
       \fi
180
    \else
181
       \compute@fontsize
182
       \sbox{\L@lbox}{\LettrineFont \L@initial}%
183
184
     \fi
185 }
```

\lettrine Now let's define the \lettrine command.

```
186 \def\lettrine{\@ifnextchar[\@lettrine[]}}
187 \def\@lettrine[#1]#2#3{%
188 \def\L@initial{#2}\def\L@refstring{}\def\L@viewport{}%
```

#### First reset the parameters to their default values:

```
\setcounter{L@lines}{\value{DefaultLines}}%
189
    \setcounter{L@depth}{\value{DefaultDepth}}%
190
    \renewcommand*{\L@hang}{\DefaultLhang}%
191
    \renewcommand*{\L@oversize}{\DefaultLoversize}%
192
    \renewcommand*{\L@raise}{\DefaultLraise}%
193
    \renewcommand*{\L@ante}{}%
194
195
    \setlength{\L@Findent}{\DefaultFindent}%
    \setlength{\L@Nindent}{\DefaultNindent}%
196
    \setlength{\L@slope}{\DefaultSlope}%
197
    \setlength{\L@novskip}{\DiscardVskip}%
198
    \ifLettrineImage\L@imagetrue\else\L@imagefalse\fi
199
    \ifLettrineOnGrid\L@gridtrue\else\L@gridfalse\fi
200
    \ifLettrineMoveAtEOP\L@nextpagetrue\else\L@nextpagefalse\fi
201
    \ifLettrineRealHeight\L@realhtrue\else\L@realhfalse\fi
```

Then take the local options passed to \lettrine into account. The content of \L@tbox depends on option realheight, so we have to initialise the \L@tbox content now <sup>6</sup>.

```
\SetKeys[LettrineLocal]{#1}%
204
     \sbox{\L@tbox}{\LettrineTextFont{\LettrineSecondString}}%
205
     \ifL@realh
206
       \def\ensuremath{\$}%
       \ifx\@tempa\@empty
207
         \PackageWarning{lettrine.sty}%
208
           {Empty second argument, \MessageBreak
209
            ignoring option `realheight';}%
210
211
       \else
212
         \sbox{\L@tbox}{{\LettrineTextFont{#3}}}%
213
       \fi
214
     \fi
```

 $<sup>^6\</sup>mathrm{Now}$  means before eventually reading the per character config file.

Take the per character options into account if any. For these options some parameters' values findent, nindent and slope —which do not influence the initial's size— may be given relative to \LettrineWidth, the \L@lbox has to be set up first to evaluate \LettrineWidth.

```
215 \setupL@lbox
216 \setlength{\LettrineWidth}{\wd\L@lbox}%
217 \the\Lettrine@tweaks
```

As local options always prevail, read again the optionnal argument of \lettrine.

```
218 \SetKeys[LettrineLocal]{#1}%
```

Store the initial's final dimensions,

```
219 \setupL@lbox
220 \setlength{\LettrineWidth}{\wd\L@lbox}%
221 \setlength{\LettrineHeight}{\ht\L@lbox}%
222 \setlength{\LettrineDepth}{\dp\L@lbox}%
```

and reset \L@tbox's content (mandatory in case realheight=false):

```
223 \sbox{\L@tbox}{{\LettrineTextFont{#3}}}%
```

Start a new paragraph and compute in \L@finalht the height of the top part of the dropped capital which finally raises above the paragraph's first baseline and in \L@finaldp the final depth of the dropped capital.

The basis for  $\ensuremath{\texttt{L@oversize}}$ , see  $\ensuremath{\texttt{LettrineFont}}$  is  $\ensuremath{\texttt{L@target@tht}}$ .

```
\par
224
     \setlength{\L@finalht}{\LettrineHeight}%
225
     \setlength{\L@lraise}{\L@raise\L@target@tht}%
226
     \addtolength{\L@finalht}{\L@lraise}%
227
     \ifnum\value{L@lines}>\@ne
228
       \@tempcnta=\value{L@lines}%
230
       \advance\@tempcnta \m@ne
231
       \@tempdima=\@tempcnta\baselineskip
232
       \addtolength{\L@finalht}{-\@tempdima}%
       \setlength{\L@finaldp}{\@tempdima}%
233
       \addtolength{\L@finaldp}{-\L@lraise}%
234
       \addtolength{\L@finaldp}{\LettrineDepth}%
235
       \addtolength{\L@lraise}{-\@tempdima}%
236
237
```

When \L@finalht is larger than \baselineskip - \L@novskip and the grid option is true, let's skip an integer number of \baselineskip (and smash the dropped cap, see below).

```
\@tempdima=\L@finalht
     \advance\@tempdima \L@novskip
239
    \@tempdimb=\baselineskip
    \ifdim\@tempdima>\@tempdimb
241
      \ifL@grid
242
         \@tempcnta=\z@
243
         \loop\ifdim\@tempdima>\@tempdimb
244
            \advance\@tempcnta \@ne
245
246
            \advance\@tempdima -\@tempdimb
```

```
247 \repeat
248 \vskip\@tempcnta\baselineskip
249 \fi
250 \fi
```

Print some informations about accuracy to the log file,

```
\begingroup
252
     \def\IeC##1{##1}%
     \@tempdima=\L@oversize pt\relax
254
     \PackageInfo{lettrine.sty}%
       {Targeted height = \the\L@target@tht\MessageBreak
255
        (for loversize=0, accent excluded),\MessageBreak
256
       Lettrine height = \the\LettrineHeight\space (#2)%
257
        \ifdim\@tempdima>\z@\space loversize=\L@oversize\fi;%
258
        \MessageBreak reported}%
259
     \endgroup
260
```

We (mis)use the length \L@first to compute the width of the text eventually coming before the dropped capital. It is reset later on to hold the first line's length.

```
261 \setlength{\L@Pindent}{\wd\L@lbox}%
262 \addtolength{\L@Pindent}{-\L@hang\wd\L@lbox}%
263 \settowidth{\L@first}{\L@ante}%
264 \addtolength{\L@Pindent}{\L@first}%
265 \addtolength{\L@Pindent}{\L@Findent}%
266 \setlength{\L@first}{\linewidth}%
267 \addtolength{\L@first}{-\L@Pindent}%
```

Now let's compute \L@Nindent and \L@next for the next lines.

```
268 \addtolength{\L@Nindent}{\L@Pindent}%
269 \setlength{\L@next}{\linewidth}%
270 \addtolength{\L@next}{-\L@Nindent}%
```

This is for quotation, quote, abstract... environments: \linewidth is set by these environments, all we have to do is to shift our text left by \@totalleftmargin.

```
271 \addtolength{\L@Pindent}{\@totalleftmargin}%
272 \addtolength{\L@Nindent}{\@totalleftmargin}%
```

Now, set up the shape of the new paragraph (designed by \parshape). It obiously depends on the text direction, the code previously available in lettrine-xetex-bidi.def for right to left scripts is integrated here now.

```
\addtocounter{L@lines}{1}%
273
     \addtocounter{L@lines}{\value{L@depth}}%
274
     \ifL@RTL
275
       \def\L@parshape{\c@L@lines \z@ \the\L@first}%
276
277
     \else
       \def\L@parshape{\c@L@lines \the\L@Pindent \the\L@first}%
278
279
280
     \@tempcnta=\tw@
281
     \@whilenum \@tempcnta<\c@L@lines\do{%
282
        \ifL@RTL
          \edef\L@parshape{\L@parshape \z@ \the\L@next}%
283
        \else
284
```

```
\edef\L@parshape{\L@parshape \the\L@Nindent \the\L@next}%
285
        \fi
286
        \addtolength{\L@Nindent}{\L@slope}%
287
        \addtolength{\L@next}{-\L@slope}%
288
        \advance\@tempcnta\@ne}%
289
    \ifL@RTL
290
       \edef\L@parshape{\L@parshape \z@ \the\linewidth}%
291
292
       \edef\L@parshape{\L@parshape \@totalleftmargin \the\linewidth}%
293
    \fi
294
```

Compute the remaining vertical space left on the current page using TeX lengths \pagetotal and \pagegoal; always warn if the remaining space is less than the depth of the dropped cap' depth \L@finaldp. Move the whole paragraph to next page if nextpage=true (default is false).

```
\@tempdima=\pagegoal
295
    \advance\@tempdima by -\pagetotal
296
     \advance\@tempdima by -\baselineskip
297
     \ifdim\@tempdima < \L@finaldp</pre>
298
       \@tempdimb=\L@finaldp
299
       \advance\@tempdimb by -\@tempdima
300
       \PackageWarning{lettrine}{%
301
         *** ATTENTION REQUIRED ***\MessageBreak
302
         The dropped cap #2 doesn't fit on page \thepage.%
303
304
         \MessageBreak Missing vertical space: \the\@tempdimb.
305
         \MessageBreak
306
         \ifL@nextpage The whole paragraph will be moved to
307
                        next page.\MessageBreak \fi
         Reported}%
308
       \ifL@nextpage \newpage \fi
309
    \fi
310
     \noindent
311
     \parshape=\L@parshape\relax
```

Write the dropped capital into the left margin, and wrap the rest of paragraph around it.

```
313 \llap{\smash{\mbox{\L@ante}\raisebox{\L@lraise}{\usebox{\L@lbox}}}%
314 \ifL@grid\else\rule{0pt}{\L@finalht}\fi
315 \hskip \the\L@Findent}%
316 \unhcopy\L@tbox\relax
```

A \parshape reset is required in abstract, quote and quotation environments beginning with \lettrine and spreading over several paragraphs. When the list ends, \parshape returns to 0.

```
317 \ifnum\@listdepth>0 \Lreset@listparshape \fi
318 }
```

This ends the definition of \lettrine; \Lreset@listparshape adds the parshape reset to the first occurence of \everypar following the \lettrine command.

```
319 \newtoks\Llist@everypar
320 \def\Lreset@listparshape{%
321 \let\Lnew@everypar\everypar
```

## 3 Configuration file

```
331 %% lettrine.cfg: configuration file for lettrine.sty
333 %% If you want to customize lettrine, please *do not* hack into the
334 %% code, copy this file to your working directory and customize the
335 %% copy as you like.
336 %%
337 %% Uncomment any of these lines and change the parameters' values
338 %% to fit your needs (see lettrine.dtx).
340 %%\setcounter{DefaultLines}{2}
341 %%\setcounter{DefaultDepth}{0}
342 %%
343 %% These are *decimal* numbers:
344 %%\renewcommand*{\DefaultLoversize}{0}
345 %%\renewcommand*{\DefaultLraise}{0}
346%%\renewcommand*{\DefaultLhang}{0}
347 %%
348 %% These are *lengths* (don't forget the unit):
349 %%\setlength{\DefaultFindent}{Opt}
350 %%\setlength{\DefaultNindent}{0.5em}
351 %%\setlength{\DefaultSlope}{Omm}
352 %%\setlength{\DiscardVskip}{1pt}
354 %% Theses are *flags* (value=true/false):
355 %%\LettrineImagefalse
356 %%\LettrineOnGridfalse
357 %%\LettrineRealHeightfalse
358 %%\LettrineMoveAtEOPfalse
359 %%
360\,\% This is a *command*, define it as \relax if you dont want the second
361%% mandatory argument of \lettrine[]{}{} to be typset in small caps.
362 %%\renewcommand*{\LettrineTextFont}{\scshape}|
364 %% Theses are *commands* (value=string, only height matters):
365 %%\renewcommand*{\LettrineTestString}{EFTZ}
366 %%\renewcommand*{\LettrineSecondString}{x}
367 %%
368 %% In case you want to set parameters for some letters
369 %% in file `optfile.cfl'
```

# 4 Change History

Changes are listed in reverse order (latest first) from version 1.0

v2.80	v2.23
General: New keyval option:	General: Documentation cleanup 1
'nextpage' (true/false), default is	v2.22
false 2	\compute@fontsize: Warn if
\lettrine: Move the paragraph to	\fontsize computation fails due
next page if the dropped cap	to division by 0 12
doesn't fit in the current one $16$	\lettrine: \@totalleftmargin is
v2.70	the correct indentation for quote,
General: Read the config file only	quotation and abstract
once, its content is added to token	environments 15
register \Lettrine@tweaks 10	\parshape reset added in lists 16
v2.61	v2.21
\lettrine: Include the 'ante' box into	General: Code clean up, new
the \smash command in case it is	<pre>commands \computeL@height,</pre>
shifted down 16	\compute@fontsize,
v2.60	\setupL@lbox 11
\lettrine: \L@parshape compatible	v2.2
with xetex bidi RTL typesetting 15	General: Rollback mechanism used
v2.52	for recovering older versions $8$
General: New option'viewport' to be	v2.1
passed to \includegraphics 2	General: New option 'refstring' 8
v2.50	Newif \ifLettrineVone and new
General: \DiscardVskip default	option 'Vone' (removed in v2.2,
value enlarged from 0.2pt to 1pt 8	rollback prefered) 8
\lettrine: Remove the top \vskip,	\compute@fontsize: Computation of
smash the dropped cap, add a	\L@factor for \fontsize done by
\rule to mimic its height above	the minifp package 12
the baseline instead 16	\computeL@height: Height
v2.40	computations moved out of
General: lettrine.dtx auto-generates	\LettrineFont: \global settings
lettrine.sty and lettrine.cfg	no longer required 11
(lettrine.ins deleted) 8	v2.0
Package options and \lettrine	\computeL@height: Store targeted
options no longer depend on	dimensions of the dropped
xkeyval, they are based on ltkeys.dtx 9	capital (ht, dp, tht) for further use. 11
\compute@fontsize: Computation of	\lettrine: Add informations about
\L@factor for \fontsize done by	targeted and actual height of the
the xfp package 12	initial to the .log file 15
\lettrine: Options from the per	\LettrineTestString: changed from 'ABCDEFGHIJKLMNOQ-
letter config file are now handled	PRSTUVWXYZ' to 'EFTZ' as some
by LaTeX command \SetKeys 14	capitals like C, G, O, Q or X might
Replace \usebox by \unhcopy for	be slightly taller (possible optical
box \L@tbox to allow footnote	correction) 9
calls and microtype action 16	v1.9
v2.30	General: New customisable string
General: Added global options to	\LettrineSecondString to tune
package lettrine 9	the initial's height 3

New keyval option: 'realheight'	FGHIJKLMNOQPRSTUVWXYZ'.
(true/false) and new global flag	In previous versions height
\ifLettrineRealHeight 2	computations were based on
\computeL@height: \theL@lines	letter 'X' which might not exist in
changed to \value{L@lines}.	some (rare) fonts. Pointed out by
Needed for babel-hebrew which	Raphaël Pinson 9
redefines \@arabic 11	-
\lettrine: \theDefaultLines	General: Add a flag to switch to
changed to	images in eps or pdf format.
\value{DefaultLines}, same	Suggested by Bill Jetzer 2
with \theDefaultDepth. Needed for babel-hebrew which redefines	Added newif \if L@grid 8
	Added newif \ if L@image 8
\@arabic. Thanks to Ulrike	Added newif \ifLettrineImage 8
Fischer for providing the fix 13	\lettrine: Add braces around #3 to
\theL@depth changed to	allow commands taking an
\value{L@depth} 15	argument (such as
Use the second mandatory	\MakeLowercase) in
argument of \lettrine or	\LettrineTextFont. Suggested
\LettrineSecondString(which	by Philipp Lehman 14
defaults to 'x') to compute	v1.5
\L@height. This is controlled by	General: \LettrineOptionsFor and
the 'realheight' flag 13	\LettrineWidth added 10
v1.8	v1.4
General: Added newif	\lettrine: \lettrine still didn't
\ifLettrineOnGrid and new	work properly in quote, quotation,
dimen \DiscardVskip, default	abstract environments, pointed
(0.2pt) set for compatibility with	out by Matthias C. Schmidt.
previous releases 8	\rightmargin was added too
Added two keyval options: 'grid'	early to \L@Nindent, thus making
(true/false) and 'novskip' to	\L@next too short by
override \DiscardVskip 2	\rightmargin 15
\lettrine: The 0.2pt limit for	v1.3
discarded vskips is now	General: Correct the documentation
customisable through	to mention the cm-super fonts
\DiscardVskip and option	and the typelec package by
'novskip'	Vladimir Volovich 5
v1.7	v1.2
General: New counter to add lines for	General: \newlength changed to
dropped capitals with positive	\newdimen, to correct a bug with
depth, like Q 1	seminar.cls (pointed out by Peter
v1.65	Münster)
\lettrine: Measure and store the	\computeL@height:\baselineskip
initial's final dimensions 14	may be a rubber length, we
v1.64	convert it to a dimen
\lettrine: Remove \$ around \smash	v1.1
and add \relax. Bug pointed out	\lettrine: Add \rightmargin to
	\L@Pindent for \Lettrine to
by David Monniaux. Correction by Enrico Gregorio 16	
	work properly in quote, quotation,
v1.63	abstract environments but do
\LettrineTestString: (new) it	not change \linewidth which is
defaults to 'ABCDE-	set by these environments 15