Transmission Control Protocol

Reliable Transport & Congestion Control

Introduction to Computer Networks CSC358

Dr. Michael A. Galle

January 24, 2025

Objective

By the end of this class, you will understand:

- Reliable Transport and how it is implemented in TCP
- The need for Congestion Control and its implementation in TCP
- Enhancements and special overhead reduction algorithms in TCP


All materials for this lecture are available in the course repo


• git clone https://github.com/michaelgalle/ComputerNetworks.git

Overview


- 1. Bridge-in
- 2. Reliable Transport
- 3. Congestion Control
- 4. Flipped-classroom Exercise
 - TCP overhead reduction
 - TCP congestion control enhancements


- ✓ Layered communication
- ✓ Routing
- ✓ Addressing
- ✓ Transport layer protocols
- ☐ Reliable transport
- ☐ Congestion control





tcpipguide.com 5







```
C:\Users\micha>route print
IPv4 Route Table
Active Routes:
Network Destination
                                             Gateway
                           Netmask
          0.0.0.0
                           0.0.0.0
                                        192.168.50.1
        127.0.0.0
                         255.0.0.0
                                            On-link
                                            On-link
        127.0.0.1
                   255.255.255.255
  127.255.255.255
                   255.255.255.255
                                            On-link
     192.168.50.0
                     255.255.255.0
                                            On-link
```


```
C:\Users\micha>arp -a
Interface: 192.168.52.1 --- 0x3
  Internet Address
                        Physical Address
                                              Type
                        ff-ff-ff-ff-ff
  192.168.52.255
                                              static
  224.0.0.22
                        01-00-5e-00-00-16
                                              static
                        01-00-5e-00-00-fb
  224.0.0.251
                                              static
  224.0.0.252
                        01-00-5e-00-00-fc
                                              static
  239.255.255.250
                        01-00-5e-7f-ff-fa
                                              static
```

tcpipguide.com







tcpipguide.com




UDP packet structure



TCP packet structure





Connection-oriented transport

If your network is not reliable, what can happen to your packets?

Loss

Corruption (bit error)

What can you do when this happens?

Retransmit them

Reliable transport is the ability to recover from packet loss and corruption

- TCP achieves this by retransmitting these packets
- This is a type of Automatic Repeat Request (ARQ) scheme

How can we keep track of the packets that got lost?


Number them

How will we know they got lost?


Ask the receiver

What numbers can we use?

Transmitters sent packet



Receiver's response (to transmitter)



I got up to 10, expecting 11 next ...

Data Communications and Networking, By Forouzan, McGraw-Hill

Let's see one way this could work ...

- 1. Send message to recipient
- 2. Stop-and-wait for acknowledgement (ACK) from receiver
- 3. Send next packet on successful ACK

What is wrong with this?

Waiting period slows throughput

How could we improve throughput?

Send a group of packets at a time

Let's allow up to N packets to be sent before requiring an ACK

What can we do when some of the N packets are lost?

Resend all N

(Go-back-to-N retransmission scheme)

What's wrong with this?

Resends even the successful packets \rightarrow wastes bandwidth


Can we do better?

Resend *only* the lost packets

Can we actually do this?

Yes, but this is a TCP enhancement Selective Acknowledgement (SACK), will be discussed later in the lecture

So, the transmitter gets an ACK for successful packets, but how does it know that a packet was lost or corrupted in the first place?









Flow control

- 1. Receiver alerts sender about the **capacity in its buffer**
- 2. Sender **adjusts Tx rate** accordingly

Congestion control


- 1. Intermediate routers to **drop packets** on congestion
- 2. Sender monitors for lost packets and adjusts Tx rate






Why do we need flow control?

- If the inflow rate is higher than the outflow rate the Rx buffer will overflow.
- The capacity of the Rx buffer is called the send window




How does the receiver tell the sender how big its buffer is?



Data Communications and Networking, By Forouzan, McGraw-Hill

How does the Tx know how much room it has left at any given time?

It must keep track of sent (but not yet ACK'd) packets



$$\begin{bmatrix} Usable \\ Window \end{bmatrix} = \begin{bmatrix} Send \\ Window \end{bmatrix} - \begin{bmatrix} Window \ Already \\ Sent, no \ ACK \end{bmatrix}$$

Flow control



- 1. Receiver alerts sender about the capacity in its buffer
- 2. Sender **adjusts Tx rate** accordingly

Congestion control (next)







Why do we need congestion control?

Congestion Collapse

- On congestion routers drop packets
- Tx timeout expires or duplicate ACK
- Tx retransmits dropped packet → More congestion



Prevent me



How can we avoid congestion collapse?

Negative feedback

How?

Restrict the Send Window on packet drop to slow transmission

 $Send\ Window = RcvWin$

Currently the Send Window is only determined by the receiver's window

2. Congestion Control – TCP Tahoe

How can we restrict the Send Window?

Define a Congestion Window (CongWin) so that:

 $Send\ Window = min\ (RcvWin, CongWin)$

If we assume that most of the time $RcvWin \gg CongWin$ then:

 $Send\ Window = CongWin$

Send Window is mainly determined by the congestion window

• CongWin is an integer multiple (w) of the max segment size (MSS)

$$CongWin = w \times MSS$$


536 bytes by default

- The main variable we will change is w
- This congestion control method is known as TCP Tahoe (Slow Start) Algorithm

$$CongWin = w \times MSS$$

Phase	w	threshold
Slow start (w < threshold)	w = 1, then $w = 2 \times w$ (exponential growth)	threshold initialized to some value on first run, then reset in loss phase
Congestion Avoidance (w >= threshold)	w = w + 1 (linear growth)	
Loss (Timeout expires, no ACK – packet drop)	w = 1 (return to slow start)	threshold = w / 2

w increments with every sent packet



http://www.cs.emory.edu/~cheung/Cours es/455/Syllabus/A1-congestion/tcp2.html

Great, so we can prevent congestion collapse, but how does this affect our transmission rate?

$$Send\ Window = CongWin = w \times MSS \quad [bytes]$$

Unit analysis: Transmission rate has units of [bytes / s], so we need something for the denominator in seconds


If the transmitter sends all *w* segments in **one burst**, how long must it wait before it can send more?


- The burst must reach the receiver, and the ACK must travel back
- This is the Round-Trip Time (RTT)
- So, we have $w \times MSS$ bytes sent every RTT seconds
- For an *instantaneous* bit rate:

$$R(w) = \frac{w \times MSS}{RTT} \quad [bytes/s]$$

But what we really care about is the average bit rate Need to find the average value of w (w_{avg})


• We can approximate w_{avg} by ignoring the slow start phase and considering only the linear phase where w grows from M/2 to M and then returns to 1 in M/2 + 1 steps





http://www.cs.emory.edu/~cheung/Courses/455/Syllabus/A1-congestion/tcp2.html

• Approximate w_{avg} in terms of M via the **trapezoid rule**




$$Area \approx (last - first) \times \frac{1}{2}(f(first) + f(last))$$

$$w_{avg} \approx \frac{Area}{width} = \frac{\left(\frac{M}{2} + 1 - 0\right) \times \frac{1}{2} \left(\frac{M}{2} + M\right)}{\left(\frac{M}{2} + 1 - 0\right)} = \frac{3M}{4}$$

• And the Average Transmission Rate is:

$$R(w_{avg}) \approx \frac{w_{avg} \times MSS}{RTT} = \frac{3M}{4} \times \frac{MSS}{RTT}$$

Alt.: Approximate using Gauss's formula for the sum of n consecutive integers



$$Area \approx \frac{n}{2}(first + last),$$
 $n is # of integers (i.e., M/2 + 1)$

$$w_{avg} \approx \frac{Area}{width} = \frac{(M/2 + 1)}{2} (M/2 + M) = \frac{3M}{4}$$

• And the Average Transmission Rate is:

$$R(w_{avg}) \approx \frac{w_{avg} \times MSS}{RTT} = \frac{3M}{4} \times \frac{MSS}{RTT}$$

Summary

- Reliable transport is the ability to recover from packet loss & corruption.
- TCP achieves this by retransmitting these packets in an ARQ scheme that numbers the packets and asks the receiver to acknowledge (ACK) them.
- TCP implements flow and congestion control techniques to prevent overflow of the receiver's buffer and prevent congestion collapse on the network.
- Flow and congestion control techniques regulate the transmission rate

3. Flipped Classroom

In this active learning exercise, the class is divided into 4 groups to present one of the TCP topics (below):


- 1. Explicit Congestion Notification (ECN)
- 2. Selective Acknowledgement (SACK)
- 3. Small Packet Problem (solution Nagle's Algorithm)
- 4. Silly Window Syndrome (solution Clark's Algorithm)

Resources include

- Editable <u>flipped classroom slides</u> (originals follow)
- Section 3 of the <u>notes</u> that accompany this lecture

- A TCP protocol enhancement that enables congestion reporting
- Source, destination and intermediate routers to be ECN aware
- Instead of dropping a packet on congestion an ECN aware router will set a flag in its IP header to notify the receivers TCP
- Receivers TCP will signal the senders TCP to slow its Tx rate

- An ECN aware router signals congestion using two reserved bits in the type-ofservice field of the IP header
- Routers operate at the 'internet' layer so they can only see and modify the IP header



The two CE bits can be set

00 – ECN not implemented

10 – ECN Capable Transport, ECT(0)

01 - ECN Capable Transport, ECT(1)

11 - Congestion Encountered, CE


Endpoints negotiate which bit is used by either side during the TCP handshake

Congestion signaled by setting the other reserved bit to '1' so the field becomes '11'

Congestion can only be handled by TCP by reducing the Send (Congestion) Window

On Congestion Encountered, CE bits '11' must be handled by **TCP**

- The receivers IP layer notifies its TCP layer
- Receiver's TCP signals congestion to sender's TCP by using bit 5 and 6 of the reserved bits of the TCP header
 - Bit 6 signals congestion
 - Bit 5 tells sender to reduce its Congestion Window



3. Selective Acknowledgment (SACK)

Problem

- Traditional TCP acknowledges the value of the highest byte received before a lost segment.
- Any lost packet requires retransmissions of all segments up to that point (wastes bandwidth).

Solution:

• Selective Acknowledgement (SACK) allows a receiver to inform the sender about specific segments in the send window that have been successfully received, so only the lost packets are retransmitted.

3. Selective Acknowledgment (SACK)

Example:

Suppose a sender transmits data in the byte range 0–10,000, and packets corresponding to byte ranges 2,000–3,000 and 6,001–7,000 are lost.

Bytes	No SACK	SACK
0-1,999	ACK	ACK
2,000 – 3,000 (lost)	Retransmit	Retransmit
3,001 – 6,000	Retransmit	ACK
6,001 – 7,000 (lost)	Retransmit	Retransmit
7001 – 10,000	Retransmit	ACK

3. Small packet – Nagle's Algorithm

Problem:

- Sender transmits TCP segments with large header compared to payload
 - wastes bandwidth (high overhead), creates congestion (many small packets)
 - e.g. Telnet apps that send one TCP segment per keystroke

Solution

- Nagle's Algorithm: Sender side strategy
 - 1. Send first byte and accumulate new bytes while waiting for ACK
 - 2. On ACK send accumulated bytes
 - 3. Repeat
- Trade-off: Increased latency for lower overhead and congestion

3. Silly Window Syndrome – Clark's Algorithm

Problem:

- A slow receiver sends ACK with a small window size
- Sender can only send small TCP segment

 Small Packet Problem (again)

Solution:

- Clark's Algorithm: Receiver side strategy
 - 1. Wait for a minimum window size to be available in Rx buffer before sending ACK
 - 2. Process data (freeing up buffer space) while waiting
- Trade-off: Increased latency for lower overhead and congestion

References

- INFO73180 Data Communications and Networks, Michael Galle, Lecture slides and handouts
- Computer Networks A Top-Down Approach, Kurose and Ross
- CSC358 Introduction to Computer Networks, Peter Marbach lectures, <u>https://www.cs.toronto.edu/~marbach/csc358_F19.html</u>, accessed Dec. 2024.
- http://www.tcpipguide.com/
- Data Communications and Networking, Forouzan, McGraw-Hill