Introduction Making better nodes Managing system complexity) Configuring Slurm policies

OpenHPC: Beyond the Install Guide for PEARC24

Tennessee Tech University

2024-07-22

Acknowledgments and shameless plugs

- OpenHPC especially Tim Middelkoop (Internet2) and Chris Simmons (Massachusetts Green High Performance Computing Center). They have a BOF at 1:30 Wednesday. You should go to it.
- Jetstream2 especially Jeremy Fischer, Mike Lowe, and Julian Pistorius. Jetstream2 has a tutorial at the same time as this one. Please stay here.
 - NSF CC* for the equipment that led to some of the lessons we're sharing today (award #2127188).
 - ACCESS current maintainers of the project formerly known as the XSEDE Compatible Basic Cluster.

Where we're starting from




Figure 1: Two example HPC networks

31 HPC clusters (2 shown) with:

- 1. Rocky Linux 9
- 2. OpenHPC 3
- 3. Warewulf 3
- 4. Slurm
- 5. 2 non-GPU nodes
- 6. 2 GPU nodes (currently without GPU drivers, so: expensive non-GPU nodes)
- 7. 1 management node (SMS)
- 8. 1 unprovisioned login node

Where we're starting from

We used the OpenHPC automatic installation script from Appendix A with a few variations:

- 1. Installed s-nail to have a valid MailProg for slurm.conf.
- 2. Created user1 and user2 accounts with password-less sudo privileges.
- 3. Changed CHROOT from /opt/ohpc/admin/images/rocky9.3 to /opt/ohpc/admin/images/rocky9.4.
- 4. Enabled slurmd and munge in CHROOT.
- 5. Added nano and yum to CHROOT.
- 6. Removed a redundant ReturnToService line from /etc/slurm/slurm.conf.
- 7. Stored all nodes' SSH host keys in /etc/ssh/ssh_known_hosts.

Where we're going

- 1. A login node that's practically identical to a compute node (except for where it needs to be different)
- 2. A slightly more secured SMS
- 3. GPU drivers on the GPU nodes
- 4. Using node-local storage for the OS and/or scratch
- 5. De-coupling the SMS and the compute nodes (e.g., independent kernel versions)
- 6. Easier management of node differences (GPU or not, diskless/single-disk/multi-disk, Infiniband or not, etc.)
- 7. Slurm configuration to match some common policy goals (fair share, resource limits, etc.)

Assumptions

- 1. We have a VM named login, with no operating system installed.
- 2. The eth0 network interface for login is attached to the internal network, and eth1 is attached to the external network.
- 3. The eth0 MAC address for login is known—check the **Login server** section of your handout for that. It's of the format aa:bb:cc:dd:ee:ff.
- 4. We're logged into the SMS as user1 or user2 that has sudo privileges.

Creating a new login node

Working from section 3.9.3 of the install guide:

```
[user1@sms-0 ~] $ sudo wwsh -y node new login --netdev eth0 \
    --ipaddr=172.16.0.2 --hwaddr=__:__:__:__:__:
[user1@sms-0 ~] $ sudo wwsh -y provision set login \
    --vnfs=rocky9.4 --bootstrap=`uname -r` \
    --files=dynamic_hosts, passwd, group, shadow, munge.key, network
```

Make sure to replace the __ with the characters from your login node's MAC address!

Ever since login was powered on, it's been stuck in a loop trying to PXE boot. What's the usual PXE boot process for a client in an OpenHPC environment?

1. The client network card tries to get an IP address from a DHCP server (the SMS) by broadcasting its MAC address.

- 1. The client network card tries to get an IP address from a DHCP server (the SMS) by broadcasting its MAC address.
- 2. The SMS responds with the client's IP and network info, a next-server IP (the SMS again), and a filename option (a bootloader from the iPXE project).

- 1. The client network card tries to get an IP address from a DHCP server (the SMS) by broadcasting its MAC address.
- 2. The SMS responds with the client's IP and network info, a next-server IP (the SMS again), and a filename option (a bootloader from the iPXE project).
- 3. The network card gets the bootloader over TFTP and executes it.

- 1. The client network card tries to get an IP address from a DHCP server (the SMS) by broadcasting its MAC address.
- 2. The SMS responds with the client's IP and network info, a next-server IP (the SMS again), and a filename option (a bootloader from the iPXE project).
- 3. The network card gets the bootloader over TFTP and executes it.
- 4. iPXE makes a second DHCP request and this time, it gets a URL (by default, http://SMS_IP/WW/ipxe/cfg/\${client_mac}) for an iPXE config file.

- 1. The client network card tries to get an IP address from a DHCP server (the SMS) by broadcasting its MAC address.
- 2. The SMS responds with the client's IP and network info, a next-server IP (the SMS again), and a filename option (a bootloader from the iPXE project).
- 3. The network card gets the bootloader over TFTP and executes it.
- 4. iPXE makes a second DHCP request and this time, it gets a URL (by default, http://SMS_IP/WW/ipxe/cfg/\${client_mac}) for an iPXE config file.
- 5. The config file contains the URL of a Linux kernel and initial ramdisk, plus multiple kernel parameters available after initial bootup for getting the node's full operating system contents.

1. The node name, --hwaddr, and --ipaddr parameters go into the SMS DHCP server settings.

- 1. The node name, --hwaddr, and --ipaddr parameters go into the SMS DHCP server settings.
- 2. The --bootstrap parameter defines the kernel and ramdisk for the iPXE configuration.

- 1. The node name, --hwaddr, and --ipaddr parameters go into the SMS DHCP server settings.
- 2. The --bootstrap parameter defines the kernel and ramdisk for the iPXE configuration.
- 3. The node name, --netdev, --ipaddr, --hwaddr parameters all go into kernel parameters accessible from the provisioning software.

- 1. The node name, --hwaddr, and --ipaddr parameters go into the SMS DHCP server settings.
- 2. The --bootstrap parameter defines the kernel and ramdisk for the iPXE configuration.
- 3. The node name, --netdev, --ipaddr, --hwaddr parameters all go into kernel parameters accessible from the provisioning software.
- 4. During the initial bootup, the --hwaddr parameter is passed to a CGI script on the SMS to identify the correct VNFS for the provisioning software to download (set by the --vnfs parameter).

- 1. The node name, --hwaddr, and --ipaddr parameters go into the SMS DHCP server settings.
- 2. The --bootstrap parameter defines the kernel and ramdisk for the iPXE configuration.
- 3. The node name, --netdev, --ipaddr, --hwaddr parameters all go into kernel parameters accessible from the provisioning software.
- 4. During the initial bootup, the --hwaddr parameter is passed to a CGI script on the SMS to identify the correct VNFS for the provisioning software to download (set by the --vnfs parameter).
- 5. After downloading the VNFS, the provisioning software will also download files from the SMS set by the --files parameter.

A dedicated login node A bit more security for the

A bit more security for the SMS Semi-stateful node provisioning Management of GPU drivers

Did it work? So far, so good.

```
[user1@sms-0 ~] $ sudo ssh login
[root@login ~] # df -h
Filesystem
...
172.16.0.1:/home
172.16.0.1:/opt/ohpc/pub
```

Did it work? Not entirely.

```
[root@login ~]# sinfo
sinfo: error: resolve_ctls_from_dns_srv: res_nsearch error:
   Unknown host
sinfo: error: fetch_config: DNS SRV lookup failed
sinfo: error: _establish_config_source: failed to fetch config
sinfo: fatal: Could not establish a configuration source
```

systemctl status slurmd is more helpful, with

fatal: Unable to determine this slurmd's NodeName. So how do we fix this one?

A dedicated login node

A bit more security for the SMS Semi-stateful node provisioning Management of GPU drivers

Option 1: take the error message literally

So there's no entry for login in the SMS slurm.conf. To fix that:

1. Run slurmd -C on the login node to capture its correct CPU specifications. Copy that line to your laptop's clipboard.

- 1. Run slurmd -C on the login node to capture its correct CPU specifications. Copy that line to your laptop's clipboard.
- 2. On the SMS, run nano /etc/slurm/slurm.conf and make a new line of all the slurmd -C output from the previous step (pasted from your laptop clipboard).

- 1. Run slurmd -C on the login node to capture its correct CPU specifications. Copy that line to your laptop's clipboard.
- On the SMS, run nano /etc/slurm/slurm.conf and make a new line of all the slurmd -C output from the previous step (pasted from your laptop clipboard).
- 3. Save and exit nano by pressing Ctrl-X and then Enter.

- 1. Run slurmd -C on the login node to capture its correct CPU specifications. Copy that line to your laptop's clipboard.
- 2. On the SMS, run nano /etc/slurm/slurm.conf and make a new line of all the slurmd -C output from the previous step (pasted from your laptop clipboard).
- 3. Save and exit nano by pressing Ctrl-X and then Enter.
- 4. Reload the new Slurm configuration everywhere (well, everywhere functional) with sudo scontrol reconfigure on the SMS.

- 1. Run slurmd -C on the login node to capture its correct CPU specifications. Copy that line to your laptop's clipboard.
- On the SMS, run nano /etc/slurm/slurm.conf and make a new line of all the slurmd -C output from the previous step (pasted from your laptop clipboard).
- 3. Save and exit nano by pressing Ctrl-X and then Enter.
- 4. Reload the new Slurm configuration everywhere (well, everywhere functional) with sudo scontrol reconfigure on the SMS.
- 5. ssh back to the login node and restart slurmd, since it wasn't able to respond to the scontrol reconfigure from the previous step (sudo ssh login systemctl restart slurmd on the SMS).

A dedicated login node

A bit more security for the SMS Semi-stateful node provisioning Management of GPU drivers

Option 1: take the error message literally

Now an sinfo should work on the login node:

```
[root@login ~]# sinfo
PARTITION AVAIL TIMELIMIT NODES STATE NODELIST
normal* up 1-00:00:00 1 idle c1
```

Option 2: why are we running slurmd anyway?

The slurmd service is really only needed on systems that will be running computational jobs, and the login node is not in that category.

Running slurmd like the other nodes means the login node can get all its information from the SMS, but we can do the same thing with a very short customized slurm.conf with two lines from the SMS' slurm.conf:

```
ClusterName=cluster
SlurmctldHost=sms-0
```

(where sms-0 should be **your** SMS hostname from your handout) and stopping/disabling the slurmd service.

Interactive testing

- 1. On the login node as root, temporarily stop the slurmd service with systemctl stop slurmd
- On the login node as root, edit /etc/slurm/slurm.conf with nano /etc/slurm/slurm.conf
- 3. Add the two lines to the right.
- 4. Save and exit nano by pressing Ctrl-X and then Enter.

/etc/slurm/slurm.conf on login node

ClusterName=cluster SlurmctldHost=sms-0

Verify that sinfo still works without slurmd and with the custom /etc/slurm/slurm.conf.

```
[root@login ~]# sinfo
PARTITION AVAIL TIMELIMIT NODES STATE NODELIST
normal* up 1-00:00:00 1 idle c1
```

Making permanent changes from the SMS

Let's reproduce the changes we made interactively on the login node in the Warewulf settings on the SMS.

For the customized slurm.conf file, we can keep a copy of it on the SMS and add it to the Warewulf file store.

We've done that previously for files like the shared munge.key for all cluster nodes (see section 3.8.5 of the OpenHPC install guide).

We also need to make sure that file is part of the login node's provisioning settings.

Making permanent changes from the SMS

On the SMS:

Now the file is available, but we need to ensure the login node gets it. That's handled with wwsh provision.

A quick look at wwsh provision

What are the provisioning settings for compute node c1?

```
[user1@sms-0 ~]$ wwsh provision print c1
   c1: MASTER
                  = UNDEF
c1: BOOTSTRAP
                  = 6.1.96-1.el9.elrepo.x86 64
c1: VNFS
                  = rocky9.4
c1: VALIDATE
                  = FALSE
c1: FILES
                  = dynamic_hosts,group,munge.key,network,
  passwd, shadow
. . .
c1: KARGS
                  = "net.ifnames=0 biosdevname=0 quiet"
c1: BOOTLOCAL
                  = FALSE
```

A quick look at wwsh provision

What are the provisioning settings for node login?

```
[user10sms-0 ~]$ wwsh provision print login
login: MASTER
                  = UNDEF
login: BOOTSTRAP = 6.1.96-1.el9.elrepo.x86.64
login: VNFS
                  = rocky9.4
login: VALIDATE
                  = FALSE
login: FILES
                  = dynamic_hosts,group,munge.key,network,
  passwd, shadow
login: KARGS
                  = "net.ifnames=0 biosdevname=0 quiet"
login: BOOTLOCAL
                  = FALSE
```

A quick look at wwsh provision

The provisioning settings for c1 and login are identical, but there's a lot to read in there to be certain about it.

We could run the two outputs through diff, but every line contains the node name, so no lines are literally identical.

Let's simplify and filter the wwsh provision output to make it easier to compare.

A dedicated login node

A bit more security for the SMS Semi-stateful node provisioning Management of GPU drivers

Filtering wwsh provision output

▶ I only care about the lines containing = signs, so

```
wwsh provision print c1 | grep =
```

is a start.

Filtering wwsh provision output

▶ I only care about the lines containing = signs, so

```
wwsh provision print c1 | grep =
```

is a start.

▶ Now all the lines are prefixed with c1:, and I want to keep everything after that, so

```
wwsh provision print c1 | grep = | cut -d: -f2-
```

will take care of that.

A dedicated login node

A bit more security for the SMS Semi-stateful node provisioning Management of GPU drivers

Filtered result

```
wwsh provision print c1 | grep = | cut -d: -f2-
```

```
MASTER
                     UNDEF
BOOTSTRAP
                   = 6.1.96-1.el9.elrepo.x86 64
                   = rocky9.4
VNFS
VALIDATE
                   = FALSE
FILES
                   = dynamic hosts, group, munge.key, network,
  passwd, shadow
. . .
KARGS
                   = "net.ifnames=0 biosdevname=0 quiet"
BOOTLOCAL
                    FALSE
```

Much more useful.

Making a function for this

We may be typing that command pipeline a lot, so let's make a shell function to cut down on typing:

```
[user1@sms-0 ~]$ function proprint() {
  wwsh provision print $@ | grep = | cut -d: -f2-; }
[user1@sms-0 ~]$ proprint c1
  MASTER = UNDEF
  BOOTSTRAP = 6.1.96-1.el9.elrepo.x86_64
...
```

diff-ing the outputs

We could redirect a proprint c1 and a proprint login to files and diff the resulting files, or we can use the shell's <() operator to treat command output as a file:

```
[user1@sms-0 ~] $ diff -u <(proprint c1) <(proprint login)
[user1@sms-0 ~] $
```

Either of those shows there are zero provisioning differences between a compute node and the login node.

Adding the custom slurm.conf to the login node

Add a file to login's FILES property with:

```
[user1@sms-0 ~]$ sudo wwsh -y provision set login \
  --fileadd=slurm.conf.login
```

(refer to section 3.9.3 of the install guide for previous examples of --fileadd).

Rerun the previous diff command to easily see what's changed:

```
[user1@sms-0 ~] $ diff -u <(proprint c1) <(proprint login)
--- /dev/fd/63 2024-07-06 11:11:07.682959677 -0400
+++ /dev/fd/62 2024-07-06 11:11:07.683959681 -0400
00 - 2.7 + 2.7 00
 BOOTSTRAP
                   = 6.1.96-1.el9.elrepo.x86 64
 VNFS
                   = rocky9.4
 VALTDATE.
                   = FALSE
- FILES
                   = dynamic hosts, group, munge.key, network,
 passwd, shadow
+ FILES
                   = dynamic hosts, group, munge.key, network,
 passwd, shadow, slurm.conf.login
 PRESHELL.
                   = FALSE
 POSTSHELL
                   = FALSE
 POSTNETDOWN
                   = FALSE
```

Ensuring slurmd doesn't run on the login node

To disable the slurmd service on just the login node, we can take advantage of conditions in the systemd service file. Back on the login node as root:

```
[user1@sms-0 ~]$ sudo ssh login
[root@login ~]# systemctl edit slurmd
```

Insert three lines between the lines of ### Anything between here... and
Lines below this comment...:

```
[Unit]
ConditionHost=|c*
ConditionHost=|g*
```

This will only run the service on nodes whose hostnames start with c or g.

Ensuring slurmd doesn't run on the login node

Once that file is saved, try to start the slurmd service with systemctl start slurmd and check its status with systemctl status slurmd:

```
o slurmd.service - Slurm node daemon
...
Condition: start condition failed at Sat 2024-07-06 18:12:17
EDT; 4min 22s ago
...
Jul 06 17:14:16 login systemd[1]: Stopped Slurm node daemon.
Jul 06 18:12:17 login systemd[1]: Slurm node daemon was skipped because of an unmet condition check (ConditionHost=c*).
```

A bit more security for the SMS

(going to talk about fail2ban here, maybe also firewalld)

Semi-stateful node provisioning

(talking about the gparted and filesystem-related pieces here.)

Management of GPU drivers

(installing GPU drivers – mostly rsync'ing a least-common-denominator chroot into a GPU-named chroot, copying the NVIDIA installer into the chroot, mounting /proc and /sys, running the installer, umounting /proc and /sys, and building a second VNFS)

Configuration settings for different node types

(have been leading into this a bit with the wwsh file entries, systemd conditions, etc. But here we can also talk about nodes with two drives instead of one, nodes with and without Infiniband, nodes with different provisioning interfaces, etc.)

Automation for Warewulf3 provisioning

(here we can show some sample Python scripts where we can store node attributes and logic for managing the different VNFSes)

Configuring Slurm policies

Can adapt a lot of Mike's CaRCC Emerging Centers talk from a couple years ago for this. Fair share, hard limits on resource consumption, QOSes for limiting number of GPU jobs or similar.

Sample slide

Left column

This slide has two columns. They don't always have to have columns. It also has a titled block of content in the left column. Make sure you've always got a ::: notes block after the slide content, even if it has no content.

Use # and ## headers in the Markdown file to make level-1 and level-2 headings, ### headers to make slide titles, and #### to make block titles.