

# **Libtetrabz Documentation**

Release 2.0.0

kawamura

# **CONTENTS**

1	Introduction	1
2	Installation 2.1 Important files and directories 2.2 Prerequisite	2 2 2 2 4
3	Linking libtetrabz	5
4	4.6 A part of DFPT calculation	6 7 8 9 10 11 12 13 14
5	Piece of sample code	16
6 7	6.1 Contain libtetrabz in your program 6.2 Build libtetrabz without Autoconf 6.3 MIT License	17 17 17 18
/	Contacts	19
8	8.1 Inverse interpolation	20 20 21
4	Reference	23

#### INTRODUCTION

This document explains a tetrahedron method library libtetrabz. libtetrabz is a library to calculate the total energy, the charge density, partial density of states, response functions, etc. in a solid by using the optimized tetrahedron method [1]. Subroutines in this library receive the orbital (Kohn-Sham) energies as an input and calculate weights  $w_{nn'k}$  for integration such as

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} F(\varepsilon_{nk}, \varepsilon_{n'k+q}) X_{nn'k} = \sum_{nn'} \sum_{k}^{N_k} w_{nn'k} X_{nn'k}$$
(1.1)

libtetrabz supports following Brillouin-zone integrations

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \theta(\varepsilon_{F} - \varepsilon_{nk}) X_{nk}$$
(1.2)

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \delta(\omega - \varepsilon_{nk}) X_{nk}(\omega)$$
(1.3)

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \delta(\varepsilon_{F} - \varepsilon_{nk}) \delta(\varepsilon_{F} - \varepsilon'_{n'k}) X_{nn'k}$$
(1.4)

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \theta(\varepsilon_F - \varepsilon_{nk}) \theta(\varepsilon_{nk} - \varepsilon'_{n'k}) X_{nn'k}$$
(1.5)

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \frac{\theta(\varepsilon_{F} - \varepsilon_{nk})\theta(\varepsilon'_{n'k} - \varepsilon_{F})}{\varepsilon'_{n'k} - \varepsilon_{nk}} X_{nn'k}$$
(1.6)

$$\sum_{\rm red} \int_{\rm BZ} \frac{d^3k}{V_{\rm BZ}} \theta(\varepsilon_{\rm F} - \varepsilon_{nk}) \theta(\varepsilon'_{n'k} - \varepsilon_{\rm F}) \delta(\varepsilon'_{n'k} - \varepsilon_{nk} - \omega) X_{nn'k}(\omega)$$
(1.7)

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \frac{\theta(\varepsilon_{F} - \varepsilon_{nk})\theta(\varepsilon'_{n'k} - \varepsilon_{F})}{\varepsilon'_{n'k} - \varepsilon_{nk} + i\omega} X_{nn'k}(\omega)$$
(1.8)

#### **TWO**

#### INSTALLATION

# 2.1 Important files and directories

doc/

[Directory for manuals]

- doc/index.html : Index page

• src/: Directory for the sources of the library

• example/: Directory for the sample program

• test/: Directory for tests

• configure : Configuration script for the build

## 2.2 Prerequisite

libtetrabz requires the following

- fortran and C compiler
- MPI library (If you use MPI/Hybrid version)

# 2.3 Installation guide

1. Download .tar.gz file from following web page.

http://osdn.jp/projects/libtetrabz/releases/

2. Uncompress .tar.gz file and enter the generated directory.

```
$ tar xzvf xzvf libtetrabz_1.0.1.tar.gz
$ cd libtetrabz
```

3. Configure the build environment.

```
$ ./configure --prefix=install_dir
```

Then, this script checks the compiler and the libraries required for the installation, and creates Makefiles. install\_dir indicates the full path of the directory where the library is installed (you should replace it according to your case). If none is specified, /use/local/ is chosen for storing libraries by make install

(Therefore, if one is not the admin, install\_dir must be specified to the different directory). configure has many options, and they are used according to the environment etc. For more details, please see *Options for configure*.

4. After configure finishes successfully and Makefiles are generated, please type

\$ make

to build libraries. Then please type

\$ make install

to store libraries and the sample program to install\_dir/lib and install\_dir/bin, respectively. Although one can use libraries and the sample program without make install, they are a little different to the installed one.

5. Add the libtetrabz's library directory (install\_dir/lib) to the search path of the dynamically linked program (environment variable LD\_LIBRARY\_PATH).

\$ export LD\_LIBRARY\_PATH=\${LD\_LIBRARY\_PATH}:install\_dir/lib

6. Sample programs using libtetrabz are also compiled in example/.

example/dos.x: Compute DOS of a tight-binding model in the cubic lattice. The source code is dos.f90




Fig. 1: Density of states of the tight-binding model on the cubic lattice calculated by using dos.x. The solid line indicates the result converged about the number of k. " + " and " × " indicate results by using the linear tetrahedron method and the optimized tetrahedron method, respectively with  $8 \times 8 \times 8k$  grid.

example/lindhard.x: Compute the Lindhard function. The source code is lindhard.f90




Fig. 2: (solid line) The analytical result of the Lindhard function. "+" and " $\times$ " indicate results by using the linear tetrahedron method and the optimized tetrahedron method, respectively with  $8\times 8\times 8k$  grid.

# 2.4 Options for configure

configure has many options and environment variables. They can be specified at once. E.g.

```
$ ./configure --prefix=/home/libtetrabz/ --with-mpi=yes FC=mpif90
```

All options and variables have default values. We show a part of them as follows:

---prefix

Default: ---prefix=/usr/local/. Specify the directory where the library etc. are installed.

--with-mpi

Default: --with-mpi=no (without MPI). Whether use MPI (--with-mpi=yes), or not.

--with-openmp

Default: --with-openmp=yes (with OpenMP). Whether use OpenMP or not (--with-openmp=no).

--enable-shared

Default: --enable-shared. Whether generate shared library.

--enable-static

Default: --enable-static. Whether generate static library.

FC, C

Default: The fortran/C compiler chosen automatically from those in the system. When --with-mpi is specified, the corresponding MPI compiler (such as mpif90) is searched. If FC printed the end of the standard-output of configure is not what you want, please set it manually as ./configure FC=gfortran.

--help

Display all options including above, and stop without configuration.

### **THREE**

## LINKING LIBTETRABZ

#### e. g. / For intel fortran

```
$ ifort program.f90 -L install_dir/lib -I install_dir/include -ltetrabz -
fopenmp
$ mpiifort program.f90 -L install_dir/lib -I install_dir/include -ltetrabz -
fopenmp
```

#### e. g. / For intel C

#### **FOUR**

#### **SUBROUTINES**

You can call a subroutine in this library as follows:

```
USE libtetrabz, ONLY : libtetrabz_occ
CALL libtetrabz_occ(ltetra,bvec,nb,nge,eig,ngw,wght)
```

Every subroutine has a name starts from libtetrabz\_.

For the C program, it can be used as follows:

```
#include "libtetrabz.h"
libtetrabz_occ(&ltetra,bvec,&nb,nge,eig,ngw,wght)
```

Variables should be passed as pointers. Arrays should be declared as one dimensional arrays. Also, the communicator argument for the routine should be transformed from the C/C++'s one to the fortran's one as follows.

```
comm_f = MPI_Comm_c2f(comm_c);
```

# 4.1 Total energy, charge density, occupations

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \theta(\varepsilon_{F} - \varepsilon_{nk}) X_{nk}$$
(4.1)

CALL libtetrabz\_occ(ltetra,bvec,nb,nge,eig,ngw,wght,comm)

**Parameters** 

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

Specify the k-grid for input orbital energy.

```
REAL(8), INTENT(IN) :: eig(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ).

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

The integration weights.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.2 Fermi energy and occupations

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \theta(\varepsilon_{F} - \varepsilon_{nk}) X_{nk}$$
(4.2)

CALL libtetrabz\_fermieng(ltetra,bvec,nb,nge,eig,ngw,wght,ef,nelec,comm)

Parameters

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER,INTENT(IN) :: nge(3)
```

```
REAL(8),INTENT(IN) :: eig(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ).

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
REAL(8), INTENT(OUT) :: ef
```

The Fermi energy.

```
REAL(8), INTENT(IN) :: nelec
```

The number of (valence) electrons per spin.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.3 Partial density of states

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \delta(\omega - \varepsilon_{nk}) X_{nk}(\omega)$$
(4.3)

CALL libtetrabz\_dos(ltetra,bvec,nb,nge,eig,ngw,wght,ne,e0,comm)

Parameters

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER,INTENT(IN) :: nge(3)
```

```
REAL(8), INTENT(IN) :: eig(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ).

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(ne,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN) :: ne
```

The number of energy where DOS is calculated.

```
REAL(8), INTENT(IN) :: e0(ne)
```

Energies where DOS is calculated.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.4 Integrated density of states

$$\sum_{n} \int_{BZ} \frac{d^{3}k}{V_{BZ}} \theta(\omega - \varepsilon_{nk}) X_{nk}(\omega)$$
(4.4)

CALL libtetrabz\_intdos(ltetra,bvec,nb,nge,eig,ngw,wght,ne,e0,comm)

Parameters

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

```
REAL(8),INTENT(IN) :: eig(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ).

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(ne,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN) :: ne
```

The number of energy where DOS is calculated.

```
REAL(8), INTENT(IN) :: e0(ne)
```

Energies where DOS is calculated.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

# 4.5 Nesting function and Fr&oumlhlich parameter

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \delta(\varepsilon_{F} - \varepsilon_{nk}) \delta(\varepsilon_{F} - \varepsilon'_{n'k}) X_{nn'k}$$
(4.5)

CALL libtetrabz\_dbldelta(ltetra,bvec,nb,nge,eig1,eig2,ngw,wght,comm)

**Parameters** 

```
INTEGER, INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

```
REAL(8),INTENT(IN) :: eig1(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ). Do the same with eig2.

```
REAL(8),INTENT(IN) :: eig2(nb,nge(1),nge(2),nge(3))
```

Another orbital energy. E.g.  $\varepsilon_{k+q}$  on a shifted grid.

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(nb,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.6 A part of DFPT calculation

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \theta(\varepsilon_F - \varepsilon_{nk}) \theta(\varepsilon_{nk} - \varepsilon'_{n'k}) X_{nn'k}$$
(4.6)

CALL libtetrabz\_dblstep(ltetra,bvec,nb,nge,eig1,eig2,ngw,wght,comm)

Parameters

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

Specify the k-grid for input orbital energy.

```
REAL(8),INTENT(IN) :: eig1(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy ( $\varepsilon_{\rm F}=0$ ). Do the same with eig2.

```
REAL(8),INTENT(IN) :: eig2(nb,nge(1),nge(2),nge(3))
```

Another orbital energy. E.g.  $\varepsilon_{k+q}$  on a shifted grid.

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(nb,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.7 Static polarization function

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \frac{\theta(\varepsilon_{F} - \varepsilon_{nk})\theta(\varepsilon'_{n'k} - \varepsilon_{F})}{\varepsilon'_{n'k} - \varepsilon_{nk}} X_{nn'k}$$
(4.7)

CALL libtetrabz\_polstat(ltetra,bvec,nb,nge,eig1,eig2,ngw,wght,comm)

Parameters

```
INTEGER, INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

Specify the k-grid for input orbital energy.

```
REAL(8), INTENT(IN) :: eig1(nb, nge(1), nge(2), nge(3))
```

The orbital energy measured from the Fermi energy ( $\varepsilon_{\rm F}=0$ ). Do the same with eig2.

```
REAL(8),INTENT(IN) :: eig2(nb,nge(1),nge(2),nge(3))
```

Another orbital energy. E.g.  $\varepsilon_{k+q}$  on a shifted grid.

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
REAL(8), INTENT(OUT) :: wght(nb,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

#### 4.8 Phonon linewidth

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \theta(\varepsilon_{F} - \varepsilon_{nk}) \theta(\varepsilon'_{n'k} - \varepsilon_{F}) \delta(\varepsilon'_{n'k} - \varepsilon_{nk} - \omega) X_{nn'k}(\omega)$$
(4.8)

CALL libtetrabz\_fermigr(ltetra,bvec,nb,nge,eig1,eig2,ngw,wght,ne,e0,comm)

**Parameters** 

```
INTEGER, INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8),INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

Specify the k-grid for input orbital energy.

```
REAL(8),INTENT(IN) :: eig1(nb,nge(1),nge(2),nge(3))
```

The orbital energy measured from the Fermi energy (  $\varepsilon_{\rm F}=0$  ). Do the same with eig2.

```
REAL(8), INTENT(IN) :: eig2(nb,nge(1),nge(2),nge(3))
```

Another orbital energy. E.g.  $\varepsilon_{k+q}$  on a shifted grid.

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

4.8. Phonon linewidth

```
REAL(8), INTENT(OUT) :: wght(ne,nb,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN) :: ne
```

The number of branches of the phonon.

```
REAL(8), INTENT(IN) :: e0(ne)
```

Phonon frequencies.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

## 4.9 Polarization function (complex frequency)

$$\sum_{nn'} \int_{BZ} \frac{d^3k}{V_{BZ}} \frac{\theta(\varepsilon_{F} - \varepsilon_{nk})\theta(\varepsilon'_{n'k} - \varepsilon_{F})}{\varepsilon'_{n'k} - \varepsilon_{nk} + i\omega} X_{nn'k}(\omega)$$
(4.9)

CALL libtetrabz\_polcmplx(ltetra,bvec,nb,nge,eig1,eig2,ngw,wght,ne,e0,comm)

Parameters

```
INTEGER,INTENT(IN) :: ltetra
```

Specify the type of the tetrahedron method.  $1 \cdots$  the linear tetrahedron method.  $2 \cdots$  the optimized tetrahedron method [1].

```
REAL(8), INTENT(IN) :: bvec(3,3)
```

Reciprocal lattice vectors (arbitrary unit). Because they are used to choose the direction of tetrahedra, only their ratio is used.

```
INTEGER, INTENT(IN) :: nb
```

The number of bands.

```
INTEGER, INTENT(IN) :: nge(3)
```

Specify the k-grid for input orbital energy.

```
REAL(8), INTENT(IN) :: eig1(nb, nge(1), nge(2), nge(3))
```

The orbital energy measured from the Fermi energy ( $\varepsilon_{\rm F}=0$ ). Do the same with eig2.

```
REAL(8),INTENT(IN) :: eig2(nb,nge(1),nge(2),nge(3))
```

Another orbital energy. E.g.  $\varepsilon_{k+q}$  on a shifted grid.

```
INTEGER, INTENT(IN) :: ngw(3)
```

Specify the k-grid for output integration weights. You can make  $ngw \neq nge$  (See Appendix).

```
COMPLEX(8), INTENT(OUT) :: wght(ne,nb,nb,ngw(1),ngw(2),ngw(3))
```

The integration weights.

```
INTEGER, INTENT(IN) :: ne
```

The number of imaginary frequencies where polarization functions are calculated.

```
COMPLEX(8), INTENT(IN) :: e0(ne)
```

Complex frequencies where polarization functions are calculated.

```
INTEGER, INTENT(IN), OPTIONAL :: comm
```

Optional argument. Communicators for MPI such as MPI\_COMM\_WORLD. Only for MPI / Hybrid parallelization. For C compiler without MPI, just pass NULL to omit this argment.

#### PIECE OF SAMPLE CODE

This sample shows the calculation of the charge density.

$$\rho(r) = 2\sum_{nk} \theta(\varepsilon_{\rm F} - \varepsilon_{nk})|\varphi_{nk}(r)|^2$$
(5.1)

```
SUBROUTINE calc_rho(nr,nb,ng,nelec,bvec,eig,ef,phi,rho)
 USE libtetrabz, ONLY : libtetrabz_fermieng
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: nr ! number of r
  INTEGER, INTENT(IN) :: nb ! number of bands
  INTEGER, INTENT(IN) :: ng(3)
  ! k-point mesh
  REAL(8),INTENT(IN) :: nelec ! number of electrons per spin
  REAL(8), INTENT(IN) :: bvec(3,3) ! reciplocal lattice vector
  REAL(8),INTENT(IN) :: eig(nb,ng(1),ng(2),ng(3)) ! Kohn-Sham eigenvalues
  REAL(8), INTENT(OUT) :: ef ! Fermi energy
  COMPLEX(8), INTENT(IN) :: phi(nr,nb,ng(1),ng(2),ng(3)) ! Kohn-Sham orbitals
  REAL(8), INTENT(OUT) :: rho(nr) ! Charge density
  INTEGER :: ib, i1, i2, i3, ltetra
  REAL(8) :: wght(nb,ng(1),ng(2),ng(3))
  ltetra = 2
  CALL libtetrabz_fermieng(ltetra,bvec,nb,ng,eig,ng,wght,ef,nelec)
  rho(1:nr) = 0d0
  DO i1 = 1, ng(3)
    DO i2 = 1, ng(2)
       D0 i1 = 1, ng(1)
           DO ib = 1, nb
              rho(1:nr) = rho(1:nr) + 2d0 * wght(ib,i1,i2,i3) &
                    * DBLE(CONJG(phi(1:nr,ib,i1,i2,i3)) * phi(1:nr,ib,i1,i2,i3))
           END DO
        END DO
    END DO
  END DO
END SUBROUTINE calc_rho
```

SIX

#### **RE-DISTRIBUTION OF THIS PROGRAM**

## 6.1 Contain libtetrabz in your program

libtetrabz is distributed with the *MIT License*. To summarize this, you can freely modify, copy and paste libtetrabz to any program such as a private program (in the research group, co-workers, etc.), open-source, free, and commercial software. Also, you can freely choose the license to distribute your program.

#### 6.2 Build libtetrabz without Autoconf

In this package, libtetrabz is built with Autotools (Autoconf, Automake, Libtool). If you do not want to use Autotools for your distributed program with libtetrabz's source, you can use the following simple Makefile (please care about TAB).

```
F90 = gfortran
FFLAGS = -fopenmp -02 -g
OBJS = \setminus
libtetrabz.o \
libtetrabz_dbldelta_mod.o \
libtetrabz_dblstep_mod.o \
libtetrabz_dos_mod.o \
libtetrabz_fermigr_mod.o \
libtetrabz_occ_mod.o \
libtetrabz_polcmplx_mod.o \
libtetrabz_polstat_mod.o \
libtetrabz_common.o \
.SUFFIXES :
.SUFFIXES : .o .F90
libtetrabz.a:$(OBJS)
     ar cr $@ $(OBJS)
.F90.o:
      $(F90) $(FFLAGS) -c $<
clean:
      rm -f *.a *.o *.mod
```

(continues on next page)

(continued from previous page)

```
libtetrabz.o:libtetrabz_fermigr_mod.o
libtetrabz.o:libtetrabz_fermigr_mod.o
libtetrabz.o:libtetrabz_doldelta_mod.o
libtetrabz.o:libtetrabz_dblstep_mod.o
libtetrabz.o:libtetrabz_dos_mod.o
libtetrabz.o:libtetrabz_occ_mod.o
libtetrabz_dbldelta_mod.o:libtetrabz_common.o
libtetrabz_dblstep_mod.o:libtetrabz_common.o
libtetrabz_dos_mod.o:libtetrabz_common.o
libtetrabz_fermigr_mod.o:libtetrabz_common.o
libtetrabz_fermigr_mod.o:libtetrabz_common.o
libtetrabz_polcmplx_mod.o:libtetrabz_common.o
libtetrabz_polcmplx_mod.o:libtetrabz_common.o
```

#### 6.3 MIT License

Copyright (c) 2014 Mitsuaki Kawamura

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## **SEVEN**

## **CONTACTS**

Please post bug reports and questions to the forum

http://sourceforge.jp/projects/fermisurfer/forums/

When you want to join us, please contact me as follows.

The Institute of Solid State Physics

Mitsuaki Kawamura

mkawamura\_\_at\_\_issp.u-tokyo.ac.jp

#### **APPENDIX**

## 8.1 Inverse interpolation

We consider an integration as follows:

$$\langle X \rangle = \sum_{k} X_k w(\varepsilon_k) \tag{8.1}$$

If this integration has conditions that

- $w(\varepsilon_k)$  is sensitive to  $\varepsilon_k$  (e. g. the stepfunction, the delta function, etc.) and requires  $\varepsilon_k$  on a dense k grid, and
- the numerical cost to obtain  $X_k$  is much larger than the cost for  $\varepsilon_k$  (e. g. the polarization function),

it is efficient to interpolate  $X_k$  into a denser k grid and evaluate that integration in a dense k grid. This method is performed as follows:

- 1. Calculate  $\varepsilon_k$  on a dense k grid.
- 2. Calculate  $X_k$  on a coarse k grid and obtain that on a dense k grid by using the linear interpolation, the polynomial interpolation, the spline interpolation, etc.

$$X_k^{\text{dense}} = \sum_{k'}^{\text{coarse}} F_{kk'} X_{k'}^{\text{coarse}}$$
(8.2)

1. Evaluate that integration in the dense k grid.

$$\langle X \rangle = \sum_{k}^{\text{dense}} X_k^{\text{dense}} w_k^{\text{dense}}$$
 (8.3)

The inverse interpolation method (Appendix of [2]) arrows as to obtain the same result to above without interpolating  $X_k$  into a dense k grid. In this method, we map the integration weight on a dense k grid into that on a coarse k grid (inverse interpolation). Therefore, if we require

$$\sum_{k}^{\text{dense}} X_{k}^{\text{dense}} w_{k}^{\text{dense}} = \sum_{k}^{\text{coarse}} X_{k}^{\text{coarse}} w_{k}^{\text{coarse}}$$
(8.4)

we obtain

$$w_k^{\text{coarse}} = \sum_{k}^{\text{dense}} F_{k'k} w_{k'}^{\text{dense}}$$
(8.5)

The numerical procedure for this method is as follows:

- 1. Calculate the integration weight on a dense k grid  $w_k^{\text{dense}}$  from  $\varepsilon_k$  on a dense k grid.
- 2. Obtain the integration weight on a coarse k grid  $w_k^{\text{coarse}}$  by using the inverse interpolation method.

3. Evaluate that integration in a coarse k grid where  $X_k$  was calculated.

All routines in libtetrabz can perform the inverse interpolation method; if we make k grids for the orbital energy (nge) and the integration weight (ngw) different, we obtain  $w_k^{\text{coarse}}$  calculated by using the inverse interpolation method.

## 8.2 Double delta integration

For the integration

$$\sum_{nn'k} \delta(\varepsilon_{\rm F} - \varepsilon_{nk}) \delta(\varepsilon_{\rm F} - \varepsilon'_{n'k}) X_{nn'k}$$
(8.6)

first, we cut out one or two triangles where  $\varepsilon_{nk} = \varepsilon_F$  from a tetrahedron and evaluate  $\varepsilon_{n'k+q}$  at the corners of each triangles as

$$\varepsilon_i^{\prime k+q} = \sum_{j=1}^4 F_{ij}(\varepsilon_1^k, \cdots, \varepsilon_4^k, \varepsilon_F) \epsilon_j^{k+q}. \tag{8.7}$$

Then we calculate  $\delta(\varepsilon_{n'k+q} - \varepsilon F)$  in each triangles and obtain weights of corners. This weights of corners are mapped into those of corners of the original tetrahedron as

$$W_i = \sum_{j=1}^{3} \frac{S}{\nabla_k \varepsilon_k} F_{ji}(\varepsilon_1^k, \dots, \varepsilon_4^k, \varepsilon_F) W_j'.$$
(8.8)

 $F_{ij}$  and  $\frac{S}{\nabla_k \varepsilon_k}$  are calculated as follows  $(a_{ij} \equiv (\varepsilon_i - \varepsilon_j)/(\varepsilon_{\rm F} - \varepsilon_j))$ :




Fig. 1: How to divide a tetrahedron in the case of  $\epsilon_1 \leq \varepsilon_F \leq \varepsilon_2$  (a),  $\varepsilon_2 \leq \varepsilon_F \leq \varepsilon_3$  (b), and  $\varepsilon_3 \leq \varepsilon_F \leq \varepsilon_4$  (c).

• When  $\varepsilon_1 \le \varepsilon_F \le \varepsilon_2 \le \varepsilon_3 \le \varepsilon_4$  [Fig. 1 (a)],

$$F = \begin{pmatrix} a_{12} & a_{21} & 0 & 0 \\ a_{13} & 0 & a_{31} & 0 \\ a_{14} & 0 & 0 & a_{41} \end{pmatrix}, \qquad \frac{S}{\nabla_k \varepsilon_k} = \frac{3a_{21}a_{31}a_{41}}{\varepsilon_F - \varepsilon_1}$$
(8.9)

• When  $\varepsilon_1 \le \varepsilon_2 \le \varepsilon_F \le \varepsilon_3 \le \varepsilon_4$  [Fig. 1 (b)],

$$F = \begin{pmatrix} a_{13} & 0 & a_{31} & 0 \\ a_{14} & 0 & 0 & a_{41} \\ 0 & a_{24} & 0 & a_{42} \end{pmatrix}, \qquad \frac{S}{\nabla_k \varepsilon_k} = \frac{3a_{31}a_{41}a_{24}}{\varepsilon_F - \varepsilon_1}$$
(8.10)

$$F = \begin{pmatrix} a_{13} & 0 & a_{31} & 0 \\ 0 & a_{23} & a_{32} & 0 \\ 0 & a_{24} & 0 & a_{42} \end{pmatrix}, \qquad \frac{S}{\nabla_k \varepsilon_k} = \frac{3a_{23}a_{31}a_{42}}{\varepsilon_F - \varepsilon_1}$$
(8.11)

• When  $\varepsilon_1 \le \varepsilon_2 \le \varepsilon_3 \le \varepsilon_F \le \varepsilon_4$  [Fig. 1 (c)],

$$F = \begin{pmatrix} a_{14} & 0 & 0 & a_{41} \\ a_{13} & a_{24} & 0 & a_{42} \\ a_{12} & 0 & a_{34} & a_{43} \end{pmatrix}, \qquad \frac{S}{\nabla_k \varepsilon_k} = \frac{3a_{14}a_{24}a_{34}}{\varepsilon_1 - \varepsilon_F}$$
(8.12)

Weights on each corners of the triangle are computed as follows [ $(a'_{ij} \equiv (\varepsilon'_i - \varepsilon'_j)/(\varepsilon_{\rm F} - \varepsilon'_j))$ ]:

• When  $\varepsilon_1' \le \varepsilon_F \le \varepsilon_2' \le \varepsilon_3'$  [Fig. 1 (d)],

$$W_1' = L(a_{12}' + a_{13}'), W_2' = La_{21}', W_3' = La_{31}', L \equiv \frac{a_{21}' a_{31}'}{\varepsilon_F - \varepsilon_1'}$$
 (8.13)

• When  $\varepsilon_1' \le \varepsilon_2' \le \varepsilon_F \le \varepsilon_3'$  [Fig. 1 (e)],

$$W_1' = La_{13}', \qquad W_2' = La_{23}', \qquad W_3' = L(a_{31}' + a_{32}'), \qquad L \equiv \frac{a_{13}' a_{23}'}{\varepsilon_3' - \varepsilon_F}$$
 (8.14)

# **NINE**

# **REFERENCE**

- [1] M. Kawamura, Y. Gohda, and S. Tsuneyuki, Phys. Rev. B 89, 094515 (2014).
- [2] M. Kawamura, R. Akashi, and S. Tsuneyuki, Phys. Rev. B 95, 054506 (2017).