

TEAM NETWORKS

Department of Computer Science and Engineering



Transport Layer

Department of Computer Science and Engineering

PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of reliable data transfer




reliable service abstraction



Principles of reliable data transfer






Principles of reliable data transfer



Complexity of reliable data transfer protocol will depend (strongly) on characteristics of unreliable channel (lose, corrupt, reorder data?)




Principles of reliable data transfer




Sender, receiver do *not* know the "state" of each other, e.g., was a message received?

unless communicated via a message



Reliable data transfer: getting started






Reliable data transfer: getting started

We will:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow in both directions!
- use finite state machines (FSM) to specify sender, receiver







rdt1.0: reliable transfer over a reliable channel

PES
UNIVERSITY
CELEBRATING 50 YEARS

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver reads data from underlying channel







rdt2.0: channel with bit errors

PES
UNIVERSITY
CELEBRATING 50 YEARS

- underlying channel may flip bits in packet
 - checksum (e.g., Internet checksum) to detect bit errors
- the question: how to recover from errors?

How do humans recover from "errors" during conversation?

rdt2.0: channel with bit errors

PES
UNIVERSITY
CELEBRATING 50 YEARS


- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors?
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender *retransmits* pkt on receipt of NAK

Automatic Repeat reQuest

stop and wait

sender sends one packet, then waits for receiver response


rdt2.0: FSM Specifications





rdt2.0: FSM Specifications





Note: "state" of receiver (did the receiver get my message correctly?) isn't known to sender unless somehow communicated from receiver to sender


that's why we need a protocol!

stop-and-wait




rdt2.0: operation with no errors





rdt2.0: corrupted packet scenario





rdt2.0 has a fatal flaw!

PES UNIVERSITY CELEBRATING 50 YEARS

what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

handling duplicates:


- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait

sender sends one packet, then waits for receiver response


rdt2.1: sender, handling garbled ACK/NAKs





rdt2.1: receiver, handling garbled ACK/NAKs





extract(rcvpkt,data) deliver data(data)

udt send(sndpkt)

sndpkt = make_pkt(ACK, chksum)

rdt rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make_pkt(NAK, chksum) udt send(sndpkt) rdt rcv(rcvpkt) && not corrupt(rcvpkt) && has seq0(rcvpkt) sndpkt = make pkt(ACK, chksum) udt send(sndpkt)

rdt2.1: discussion

PES UNIVERSITY CELEBRATING 50 YEARS

sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "expected" pkt should have seq # of 0 or 1

receiver:

- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol


PES
UNIVERSITY
CELEBRATING 50 YEARS

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

As we will see, TCP uses this approach to be NAK-free


rdt2.2: sender fragments





rdt2.2: receiver fragments





rdt3.0: channel with errors and loss

New channel assumption: underlying channel can also lose packets (data, ACKs)

 checksum, sequence #s, ACKs, retransmissions will be of help ... but not quite enough

Q: How do *humans* handle lost sender-to-receiver words in conversation?



rdt3.0: channel with errors and loss

PES UNIVERSITY CELEBRATING 50 YEARS


Approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq #s already handles this!
 - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after "reasonable" amount of time




rdt3.0: sender






rdt3.0: sender






rdt3.0 in action








rdt3.0 in action





Performance of rdt3.0 (stop-and-wait)




- *U* _{sender}: *utilization* fraction of time sender busy sending
- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
 - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8$$
= microsecs

rdt3.0: stop-and-wait operation





rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

rdt3.0: pipelined protocol operations

pipelining: sender allows multiple, "in-flight", yet-to-beacknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation




Pipelining: increased utilization





Go-Back-N: Sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
 - k-bit seq # in pkt header



- cumulative ACK: ACK(n): ACKs all packets up to, including seq # n
 - on receiving ACK(n): move window forward to begin at n+1
- timer for oldest in-flight packet
- timeout(n): retransmit packet n and all higher seq # packets in window




Go-Back-N: Receiver



- ACK-only: always send ACK for correctly-received packet so far, with highest in-order seq #
 - may generate duplicate ACKs
 - need only remember rcv base
 - on receipt of out-of-order packet:
 - can discard (don't buffer) or buffer: an implementation decision
 - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:



received and ACKed


Out-of-order: received but not ACKed

Not received

GBN Applet -

https://computerscience.unicam.it/marcantoni/reti/applet/GoBackProtocol/goback.html

Go-Back-N in action





Go-Back-N: example

PES
UNIVERSITY
CELEBRATING 50 YEARS

In GB3, if every 5th packet that is transmitted is lost and if we have to send 10 packets, then how many transmissions are required?

18



PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


Selective Repeat

PES
UNIVERSITY
CELEBRATING 50 YEARS

- receiver *individually* acknowledges all correctly received packets
 - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
 - sender maintains timer for each unACKed pkt
- sender window
 - *N* consecutive seq #s
 - limits seq #s of sent, unACKed packets

Selective Repeat: sender, receiver windows





Selective Repeat Applet -

https://computerscience.unicam.it/marcantoni/reti/applet/ SelectiveRepeatProtocol/selRepProt.html

Selective Repeat: sender, receiver



sender

data from above:

if next available seq # in window, send packet

timeout(*n*):

resend packet n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yet-received packet

packet n in [rcvbase-N,rcvbase-1]


ACK(n)

otherwise:

ignore

Selective Repeat in action





Selective Repeat: example

PES
UNIVERSITY
CELEBRATING 50 YEARS

In GB3, if every 5th packet that is transmitted is lost and if we have to send 10 packets, then how many transmissions are required?

12





Selective repeat: a dilemma!

PES UNIVERSITY CELEBRATING 50 YEARS

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3






Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: what relationship is needed between sequence # size and window size to avoid problem in scenario (b)?





Suggested Readings








PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP: Overview RFCs: 793,1122,1323, 2018, 2581



- one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size


cumulative ACKs

- pipelining:
 - TCP congestion and flow control set window size
- connection-oriented:
 - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver



TCP segment structure





TCP sequence numbers and ACKs

PES UNIVERSITY CELEBRATING 50 YEARS

Sequence numbers:

 byte stream "number" of first byte in segment's data


Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-oforder segments

 <u>A:</u> TCP spec doesn't say, - up to implementor

outgoing segment from sender






outgoing segment from receiver

source port #		dest port#	
sequence number			
acknowledgement number			
	Α		rwnd
checksum		urg pointer	

TCP sequence numbers and ACKs





simple telnet scenario

TCP round trip time, time out

Q: how to set TCP timeout value?

- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss

Q: how to estimate RTT?


- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT



TCP round trip time, time out

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value: $\alpha = 0.125$






TCP round trip time, time out



- timeout interval: EstimatedRTT plus "safety margin"
 - large variation in **EstimatedRTT:** want a larger safety margin



■ **DevRTT**: EWMA of **SampleRTT** deviation from **EstimatedRTT**:

DevRTT =
$$(1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT|$$

(typically, $\beta = 0.25$)

PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP Sender (simplified)



event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unACKed segment
 - expiration interval:TimeOutInterval


event: timeout

- retransmit segment that caused timeout
- restart timer

event: ACK received

- if ACK acknowledges previously unACKed segments
 - update what is known to be ACKed
 - start timer if there are still unACKed segments


TCP Receiver: ACK Generation





TCP: retransmission scenarios






send cumulative ACK for 120

lost ACK scenario

premature timeout

TCP: retransmission scenarios






TCP fast retransmit



TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

 likely that unACKed segment lost, so don't wait for timeout



-

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!

PES UNIVERSITY


Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP flow control

PES
UNIVERSITY
CELEBRATING 50 YEARS

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?




receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers

Network layer delivering IP datagram payload into TCP socket buffers



receiver protocol stack



TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers

applicati process TCP socket receiver **TCP** code code from sender

flow control


receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast





TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow



LastByteRcvd - LastByteRead ≤ RcvBuffer


rwnd = RcvBuffer - [LastByteRcvd - LastByteRead]



TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept



TCP segment format



Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control




TCP connection management



before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server,client

network
```

TCP 3-way handshake



Server state




Closing a TCP connection



- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Closing a TCP connection





Suggested Readings







PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

PES UNIVERSITY CELEBRATING 50 YEARS

Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!

a top-10 problem!



congestion control:

too many senders, sending too fast


flow control: one sender too fast for one receiver

Causes/costs of congestion: scenario 1


PES UNIVERSITY CELEBRATING 50 YEARS

Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate λ_{in} approaches R/2?



maximum per-connection throughput: R/2




large delays as arrival rate λ_{in} approaches capacity

Causes/costs of congestion: scenario 2

PES
UNIVERSITY
CELEBRATING 50 YEARS

- one router, finite buffers
- sender retransmits lost, timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes retransmissions : $\lambda'_{in} >= \lambda_{in}$





Causes/costs of congestion: scenario 2



Idealization: perfect knowledge

sender sends only when router buffers available






Causes/costs of congestion: scenario 2

PES UNIVERSITY

Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost





Causes/costs of congestion: scenario 2



Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost





R/2


 λ_{in}


Causes/costs of congestion: scenario 2



Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered






Causes/costs of congestion: scenario 2



Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered



"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput


Causes/costs of congestion: scenario 3

PES
UNIVERSITY
CELEBRATING 50 YEARS

- four senders
- multi-hop paths
- timeout/retransmit


 \underline{Q} : what happens as λ_{in} and λ_{in} increase?


A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput \rightarrow 0



Causes/costs of congestion: scenario 3








another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


Causes/costs of congestion: insights

- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream









Approaches towards congestion control


PES UNIVERSITY CELEBRATING 50 YEARS

End-end congestion control:

no explicit feedback from network

congestion inferred from observed loss, delay

approach taken by TCP




Approaches towards congestion control

PES UNIVERSITY

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Suggested Readings








PES UNIVERSITY CELEBRATING 50 YEARS

Transport Layer - Roadmap

- 3.4 principles of reliable data transfer
- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP congestion control: details





TCP sending behavior:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate
$$\approx \frac{cwnd}{RTT}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP: Determine sender rate



- Too fast congestion collapse
- Too cautious and too slowly under utilize the bandwidth
- Send at a high rate without congesting the network
- Guiding principles:
 - A lost segment implies congestion, and hence, the TCP sender's rate should be decreased when a segment is lost.
 - An acknowledged segment indicates that the network is delivering the sender's segments to the receiver, and hence, the sender's rate can be increased when an ACK arrives for a previously unacknowledged segment.
 - Bandwidth probing.
- TCP congestion-control algorithm
 - (1) slow start, (2) congestion avoidance, and (3) fast recovery

TCP congestion control: AIMD




approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

<u>Additive Increase</u>

increase sending rate by 1 maximum segment size every RTT until loss detected

<u>M</u>ultiplicative <u>D</u>ecrease

cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

TCP AIMD: more



Multiplicative decrease detail: sending rate is


- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially **cwnd** = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast





TCP: detecting, reacting to loss



- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)

TCP: from slow start to congestion avoidance




Q: when should the exponential increase switch to linear?


A: when cwnd gets to 1/2 of its value before timeout.

Implementation:

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event



Summary: TCP congestion control







THANK YOU

TEAM NETWORKS

Department of Computer Science and Engineering