# MPI: A Message-Passing Interface Standard Version 3.0

 ${\it ticket 0}.$ 

Message Passing Interface Forum

Draft July 4th, 2011

# Contents

	1	MP	Environmental Management	1
		1.1	Implementation Information	1
			1.1.1 Version Inquiries	1
			1.1.2 Environmental Inquiries	2
			Tag Values	3
			Host Rank	3
			IO Rank	3
			Clock Synchronization	4
		1.2	Memory Allocation	5
		1.3	Error Handling	7
			1.3.1 Error Handlers for Communicators	8
			1.3.2 Error Handlers for Windows	10
			1.3.3 Error Handlers for Files	12
			1.3.4 Freeing Errorhandlers and Retrieving Error Strings	13
		1.4	Error Codes and Classes	14
		1.5	Error Classes, Error Codes, and Error Handlers	16
		1.6	Timers and Synchronization	20
		1.7	Startup	21
			1.7.1 Allowing User Functions at Process Termination	26
			1.7.2 Determining Whether MPI Has Finished	27
		1.8	Portable MPI Process Startup	27
	2	Lan	guage Bindings Summary	30
		2.1	Defined Values and Handles	30
			2.1.1 Defined Constants	30
			2.1.2 Types	41
icket0.			2.1.3 Prototype [d]Definitions	42
icket0.			2.1.4 Deprecated [p]Prototype [d]Definitions	45
icket0.			2.1.5 Info Keys	46
			2.1.6 Info Values	46
	В	ibliog	graphy	48
	<b>E</b> :	xamp	eles Index	49
	$\mathbf{M}$	IPI C	Constant and Predefined Handle Index	<b>5</b> 0
	$\mathbf{M}$	IPI D	Declarations Index	56

MPI Callback Function Prototype Index	57
MPI Function Index	<b>58</b>

# List of Figures

# List of Tables

1.1	Error classes (Part 1)																	15
1.2	Error classes (Part 2)																	16

### Chapter 1

# **MPI** Environmental Management

This chapter discusses routines for getting and, where appropriate, setting various parameters that relate to the MPI implementation and the execution environment (such as error handling). The procedures for entering and leaving the MPI execution environment are also described here.

#### 1.1 Implementation Information

#### 1.1.1 Version Inquiries

In order to cope with changes to the MPI Standard, there are both compile-time and runtime ways to determine which version of the standard is in use in the environment one is using.

The "version" will be represented by two separate integers, for the version and subversion: In C and C++,

```
#define MPI_SUBVERSION 2
in Fortran,
    INTEGER MPI_VERSION, MPI_SUBVERSION
    PARAMETER (MPI_VERSION = 2)
```

PARAMETER (MPI\_SUBVERSION = 2)

#define MPI\_VERSION

For runtime determination,

```
MPI_GET_VERSION( version, subversion )

OUT version version number (integer)

OUT subversion subversion number (integer)

int MPI_Get_version(int *version, int *subversion)

MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)

INTEGER VERSION, SUBVERSION, IERROR
```

```
{void MPI::Get_version(int& version, int& subversion)(binding deprecated, see
                               Section ??) }
ticket204. з
                    Valid (MPI_VERSION, MPI_SUBVERSION) pairs in this and previous versions of the MPI
ticket204. 5
               standard are (2,2), (2,1), (2,0), and (1,2).
ticket204.
                        MPI_GET_LIBRARY_VERSION( version, resultlen )
                 OUT
                           version
                                                        version string (string)
          9
                 OUT
         10
                           resultlen
                                                        Length (in printable characters) of the result returned
         11
                                                        in version (integer)
         12
         13
               int MPI_Get_library_version(char *version, int *resultlen)
         14
               MPI_GET_LIBRARY_VERSION(VERSION, RESULTEN, IERROR)
         15
                    CHARACTER*(*) VERSION
         16
                    INTEGER RESULTLEN, IERROR
         17
         18
                   This routine returns a string representing the implementation specific version of the
         19
               MPI library. The version argument is a character string for maximum flexibility.
```

A high quality implementation of MPI should return a Advice to implementors. different string for every change to its source code that could be visible to the user. (End of advice to implementors.)

The argument version must represent storage that is MPI\_MAX\_LIBRARY\_VERSION\_STRING characters long. MPI\_GET\_LIBRARY\_VERSION may write up to this many characters into version.

The number of characters actually written is returned in the output argument, resultlen. In C, a null character is additionally stored at name[resultlen]. The resultlen cannot be larger then MPI\_MAX\_LIBRARY\_VERSION\_STRING - 1. In Fortran, version is padded on the right with blank characters. The resultlen cannot be larger than MPI\_MAX\_LIBRARY\_VERSION\_STRING.

MPI\_GET\_VERSION [is one] and MPI\_GET\_LIBRARY\_VERSION are two of the few functions that can be called before MPI\_INIT and after MPI\_FINALIZE. [Valid ( MPI\_VERSION, MPI\_SUBVERSION) pairs in this and previous versions of the MPI standard are (2,2), (2,1), (2,0), and (1,2).

#### 1.1.2 **Environmental Inquiries**

A set of attributes that describe the execution environment are attached to the communicator MPI\_COMM\_WORLD when MPI is initialized. The value of these attributes can be inquired by using the function MPI\_COMM\_GET\_ATTR described in Chapter ??. It is erroneous to delete these attributes, free their keys, or change their values.

The list of predefined attribute keys include

MPI\_TAG\_UB Upper bound for tag value.

MPI\_HOST Host process rank, if such exists, MPI\_PROC\_NULL, otherwise.

ticket204. 33 ticket204. 34

20 21

22

23

24 25

26

27

28

29

30 31

36 37 38

39

40

41

42

43

44 45

MPI\_IO rank of a node that has regular I/O facilities (possibly myrank). Nodes in the same communicator may return different values for this parameter.

**MPI\_WTIME\_IS\_GLOBAL** Boolean variable that indicates whether clocks are synchronized.

Vendors may add implementation specific parameters (such as node number, real memory size, virtual memory size, etc.)

These predefined attributes do not change value between MPI initialization (MPI\_INIT and MPI completion (MPI\_FINALIZE), and cannot be updated or deleted by users.

Advice to users. Note that in the C binding, the value returned by these attributes is a pointer to an int containing the requested value. (End of advice to users.)

The required parameter values are discussed in more detail below:

#### Tag Values

Tag values range from 0 to the value returned for MPI\_TAG\_UB inclusive. These values are guaranteed to be unchanging during the execution of an MPI program. In addition, the tag upper bound value must be at least 32767. An MPI implementation is free to make the value of MPI\_TAG\_UB larger than this; for example, the value  $2^{30}-1$  is also a legal value for MPI\_TAG\_UB.

The attribute MPI\_TAG\_UB has the same value on all processes of MPI\_COMM\_WORLD.

#### Host Rank

The value returned for MPI\_HOST gets the rank of the HOST process in the group associated with communicator MPI\_COMM\_WORLD, if there is such. MPI\_PROC\_NULL is returned if there is no host. MPI does not specify what it means for a process to be a HOST, nor does it requires that a HOST exists.

The attribute MPI\_HOST has the same value on all processes of MPI\_COMM\_WORLD.

#### IO Rank

The value returned for MPI\_IO is the rank of a processor that can provide language-standard I/O facilities. For Fortran, this means that all of the Fortran I/O operations are supported (e.g., OPEN, REWIND, WRITE). For C and C++, this means that all of the ISO C and C++, I/O operations are supported (e.g., fopen, fprintf, lseek).

If every process can provide language-standard I/O, then the value MPI\_ANY\_SOURCE will be returned. Otherwise, if the calling process can provide language-standard I/O, then its rank will be returned. Otherwise, if some process can provide language-standard I/O then the rank of one such process will be returned. The same value need not be returned by all processes. If no process can provide language-standard I/O, then the value MPI\_PROC\_NULL will be returned.

Advice to users. Note that input is not collective, and this attribute does not indicate which process can or does provide input. (End of advice to users.)

 Clock Synchronization

The value returned for MPI\_WTIME\_IS\_GLOBAL is 1 if clocks at all processes in MPI\_COMM\_WORLD are synchronized, 0 otherwise. A collection of clocks is considered synchronized if explicit effort has been taken to synchronize them. The expectation is that the variation in time, as measured by calls to MPI\_WTIME, will be less then one half the round-trip time for an MPI message of length zero. If time is measured at a process just before a send and at another process just after a matching receive, the second time should be always higher than the first one.

The attribute MPI\_WTIME\_IS\_GLOBAL need not be present when the clocks are not synchronized (however, the attribute key MPI\_WTIME\_IS\_GLOBAL is always valid). This attribute may be associated with communicators other than MPI\_COMM\_WORLD.

The attribute  $MPI\_WTIME\_IS\_GLOBAL$  has the same value on all processes of  $MPI\_COMM\_WORLD$ .

#### MPI\_GET\_PROCESSOR\_NAME( name, resultlen )

INTEGER RESULTLEN, IERROR

```
OUT name A unique specifier for the actual (as opposed to virtual) node.
```

OUT resultlen Length (in printable characters) of the result returned in name

This routine returns the name of the processor on which it was called at the moment of the call. The name is a character string for maximum flexibility. From this value it must be possible to identify a specific piece of hardware; possible values include "processor 9 in rack 4 of mpp.cs.org" and "231" (where 231 is the actual processor number in the running homogeneous system). The argument name must represent storage that is at least MPI\_MAX\_PROCESSOR\_NAME characters long. MPI\_GET\_PROCESSOR\_NAME may write up to this many characters into name.

The number of characters actually written is returned in the output argument, resultlen. In C, a null character is additionally stored at name[resultlen]. The resultlen cannot be larger then MPI\_MAX\_PROCESSOR\_NAME-1. In Fortran, name is padded on the right with blank characters. The resultlen cannot be larger then MPI\_MAX\_PROCESSOR\_NAME.

Rationale. This function allows MPI implementations that do process migration to return the current processor. Note that nothing in MPI requires or defines process migration; this definition of MPI\_GET\_PROCESSOR\_NAME simply allows such an implementation. (End of rationale.)

Advice to users. The user must provide at least MPI\_MAX\_PROCESSOR\_NAME space to write the processor name — processor names can be this long. The user should

examine the output argument, resultlen, to determine the actual length of the name. (End of advice to users.)

The constant MPI\_BSEND\_OVERHEAD provides an upper bound on the fixed overhead per message buffered by a call to MPI\_BSEND (see Section ??).

#### 1.2 Memory Allocation

In some systems, message-passing and remote-memory-access (RMA) operations run faster when accessing specially allocated memory (e.g., memory that is shared by the other processes in the communicating group on an SMP). MPI provides a mechanism for allocating and freeing such special memory. The use of such memory for message-passing or RMA is not mandatory, and this memory can be used without restrictions as any other dynamically allocated memory. However, implementations may restrict the use of the MPI\_WIN\_LOCK and MPI\_WIN\_UNLOCK functions to windows allocated in such memory (see Section ??.)

```
MPI_ALLOC_MEM(size, info, baseptr)
```

```
    IN
    size
    size of memory segment in bytes (non-negative integer)

    IN
    info
    info argument (handle)

    OUT
    baseptr
    pointer to beginning of memory segment allocated
```

```
int MPI_Alloc_mem(MPI_Aint size, MPI_Info info, void *baseptr)
```

```
MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)
INTEGER INFO, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR
```

The info argument can be used to provide directives that control the desired location of the allocated memory. Such a directive does not affect the semantics of the call. Valid info values are implementation-dependent; a null directive value of info = MPI\_INFO\_NULL is always valid.

The function MPI\_ALLOC\_MEM may return an error code of class MPI\_ERR\_NO\_MEM to indicate it failed because memory is exhausted.

```
MPI_FREE_MEM(base)

IN base initial address of memory segment allocated by MPI_ALLOC_MEM (choice)

int MPI_Free_mem(void *base)

MPI_FREE_MEM(BASE, IERROR)

<type> BASE(*)
```

```
INTEGER IERROR
```

void MPI::Free\_mem(void \*base) (binding deprecated, see Section ??) }

The function MPI\_FREE\_MEM may return an error code of class MPI\_ERR\_BASE to indicate an invalid base argument.

Rationale. The C and C++ bindings of MPI\_ALLOC\_MEM and MPI\_FREE\_MEM are similar to the bindings for the malloc and free C library calls: a call to MPI\_Alloc\_mem(..., &base) should be paired with a call to MPI\_Free\_mem(base) (one less level of indirection). Both arguments are declared to be of same type void\* so as to facilitate type casting. The Fortran binding is consistent with the C and C++ bindings: the Fortran MPI\_ALLOC\_MEM call returns in baseptr the (integer valued) address of the allocated memory. The base argument of MPI\_FREE\_MEM is a choice argument, which passes (a reference to) the variable stored at that location. (End of rationale.)

Advice to implementors. If MPI\_ALLOC\_MEM allocates special memory, then a design similar to the design of C malloc and free functions has to be used, in order to find out the size of a memory segment, when the segment is freed. If no special memory is used, MPI\_ALLOC\_MEM simply invokes malloc, and MPI\_FREE\_MEM invokes free.

A call to MPI\_ALLOC\_MEM can be used in shared memory systems to allocate memory in a shared memory segment. (*End of advice to implementors*.)

#### Example 1.1

Example of use of MPI\_ALLOC\_MEM, in Fortran with pointer support. We assume 4-byte REALs, and assume that pointers are address-sized.

```
REAL A

POINTER (P, A(100,100)) ! no memory is allocated

CALL MPI_ALLOC_MEM(4*100*100, MPI_INFO_NULL, P, IERR)

memory is allocated

A(3,5) = 2.71;

CALL MPI_FREE_MEM(A, IERR) ! memory is freed
```

Since standard Fortran does not support (C-like) pointers, this code is not Fortran 77 or Fortran 90 code. Some compilers (in particular, at the time of writing, g77 and Fortran compilers for Intel) do not support this code.

#### **Example 1.2** Same example, in C

```
float (* f)[100][100];
/* no memory is allocated */
MPI_Alloc_mem(sizeof(float)*100*100, MPI_INFO_NULL, &f);
/* memory allocated */
...
(*f)[5][3] = 2.71;
...
MPI_Free_mem(f);
```

#### 1.3 Error Handling

An MPI implementation cannot or may choose not to handle some errors that occur during MPI calls. These can include errors that generate exceptions or traps, such as floating point errors or access violations. The set of errors that are handled by MPI is implementation-dependent. Each such error generates an MPI exception.

The above text takes precedence over any text on error handling within this document. Specifically, text that states that errors will be handled should be read as may be handled.

A user can associate error handlers to three types of objects: communicators, windows, and files. The specified error handling routine will be used for any MPI exception that occurs during a call to MPI for the respective object. MPI calls that are not related to any objects are considered to be attached to the communicator MPI\_COMM\_WORLD. The attachment of error handlers to objects is purely local: different processes may attach different error handlers to corresponding objects.

Several predefined error handlers are available in MPI:

MPI\_ERRORS\_ARE\_FATAL The handler, when called, causes the program to abort on all executing processes. This has the same effect as if MPI\_ABORT was called by the process that invoked the handler.

MPI\_ERRORS\_RETURN The handler has no effect other than returning the error code to the user.

Implementations may provide additional predefined error handlers and programmers can code their own error handlers.

The error handler MPI\_ERRORS\_ARE\_FATAL is associated by default with MPI\_COMM\_WORLD after initialization. Thus, if the user chooses not to control error handling, every error that MPI handles is treated as fatal. Since (almost) all MPI calls return an error code, a user may choose to handle errors in its main code, by testing the return code of MPI calls and executing a suitable recovery code when the call was not successful. In this case, the error handler MPI\_ERRORS\_RETURN will be used. Usually it is more convenient and more efficient not to test for errors after each MPI call, and have such error handled by a non trivial MPI error handler.

After an error is detected, the state of MPI is undefined. That is, using a user-defined error handler, or MPI\_ERRORS\_RETURN, does *not* necessarily allow the user to continue to use MPI after an error is detected. The purpose of these error handlers is to allow a user to issue user-defined error messages and to take actions unrelated to MPI (such as flushing I/O buffers) before a program exits. An MPI implementation is free to allow MPI to continue after an error but is not required to do so.

1

2

6

7

8 9

10

11

12

13

14

15 16

17

18 19

20

25 26 27

29 30 31

32

33

28

34 35 36

37 38 39

40

41

42

43 44

45

46 47

extent, circumscribe the impact of an error, so that normal processing can continue after an error handler was invoked. The implementation documentation will provide information on the possible effect of each class of errors. (End of advice to implementors.)

Advice to implementors. A good quality implementation will, to the greatest possible

An MPI error handler is an opaque object, which is accessed by a handle. MPI calls are provided to create new error handlers, to associate error handlers with objects, and to test which error handler is associated with an object. C and C++ have distinct typedefs for user defined error handling callback functions that accept communicator, file, and window arguments. In Fortran there are three user routines.

An error handler object is created by a call to MPI\_XXX\_CREATE\_ERRHANDLER(function, errhandler), where XXX is, respectively, COMM, WIN, or FILE.

An error handler is attached to a communicator, window, or file by a call to MPI\_XXX\_SET\_ERRHANDLER. The error handler must be either a predefined error handler, or an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER, with matching XXX. The predefined error handlers MPI\_ERRORS\_RETURN and MPI\_ERRORS\_ARE\_FATAL can be attached to communicators, windows, and files. In C++, the predefined error handler MPI::ERRORS\_THROW\_EXCEPTIONS can also be attached to communicators, windows, and files.

The error handler currently associated with a communicator, window, or file can be retrieved by a call to MPI\_XXX\_GET\_ERRHANDLER.

The MPI function MPI\_ERRHANDLER\_FREE can be used to free an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER.

MPI\_{COMM,WIN,FILE}\_GET\_ERRHANDLER behave as if a new error handler object is created. That is, once the error handler is no longer needed, MPI\_ERRHANDLER\_FREE should be called with the error handler returned from MPI\_ERRHANDLER\_GET or MPI\_{COMM,WIN,FILE}\_GET\_ERRHANDLER to mark the error handler for deallocation. This provides behavior similar to that of MPI\_COMM\_GROUP and MPI\_GROUP\_FREE.

High-quality implementation should raise an error when Advice to implementors. an error handler that was created by a call to MPI\_XXX\_CREATE\_ERRHANDLER is attached to an object of the wrong type with a call to MPI\_YYY\_SET\_ERRHANDLER. To do so, it is necessary to maintain, with each error handler, information on the typedef of the associated user function. (End of advice to implementors.)

The syntax for these calls is given below.

#### 1.3.1 Error Handlers for Communicators

```
MPI_COMM_CREATE_ERRHANDLER(function, errhandler)
```

IN function user defined error handling procedure (function) OUT errhandler MPI error handler (handle)

int MPI\_Comm\_create\_errhandler(MPI\_Comm\_errhandler\_function \*function, MPI\_Errhandler \*errhandler)

The first argument is the communicator in use. The second is the error code to be returned by the MPI routine that raised the error. If the routine would have returned MPI\_ERR\_IN\_STATUS, it is the error code returned in the status for the request that caused the error handler to be invoked. The remaining arguments are "stdargs" arguments whose number and meaning is implementation-dependent. An implementation should clearly document these arguments. Addresses are used so that the handler may be written in Fortran. This typedef replaces MPI\_Handler\_function, whose use is deprecated.

```
In Fortran, the user routine should be of the form:
SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE)
INTEGER COMM, ERROR_CODE
```

Rationale. The variable argument list is provided because it provides an ISO-standard hook for providing additional information to the error handler; without this hook, ISO C prohibits additional arguments. (End of rationale.)

Advice to users. A newly created communicator inherits the error handler that is associated with the "parent" communicator. In particular, the user can specify a "global" error handler for all communicators by associating this handler with the communicator MPI\_COMM\_WORLD immediately after initialization. (End of advice to users.)

```
MPI_COMM_SET_ERRHANDLER(comm, errhandler)

INOUT comm communicator (handle)

IN errhandler new error handler for communicator (handle)

int MPI_Comm_set_errhandler(MPI_Comm comm, MPI_Errhandler errhandler)

MPI_COMM_SET_ERRHANDLER(COMM, ERRHANDLER, IERROR)

INTEGER COMM, ERRHANDLER, IERROR
```

```
1
     {void MPI::Comm::Set_errhandler(const MPI::Errhandler& errhandler) (binding
2
                     deprecated, see Section ??) }
3
          Attaches a new error handler to a communicator. The error handler must be either
4
     a predefined error handler, or an error handler created by a call to
5
     MPI_COMM_CREATE_ERRHANDLER. This call is identical to MPI_ERRHANDLER_SET,
6
     whose use is deprecated.
9
     MPI_COMM_GET_ERRHANDLER(comm, errhandler)
10
       IN
                 comm
                                             communicator (handle)
11
       OUT
                 errhandler
                                             error handler currently associated with communicator
12
                                             (handle)
13
14
15
     int MPI_Comm_get_errhandler(MPI_Comm comm, MPI_Errhandler *errhandler)
16
     MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
17
          INTEGER COMM, ERRHANDLER, IERROR
18
19
     {MPI::Errhandler MPI::Comm::Get_errhandler() const(binding deprecated, see
20
                    Section ??) }
21
         Retrieves the error handler currently associated with a communicator. This call is
22
     identical to MPI_ERRHANDLER_GET, whose use is deprecated.
23
         Example: A library function may register at its entry point the current error handler
24
     for a communicator, set its own private error handler for this communicator, and restore
25
     before exiting the previous error handler.
26
27
     1.3.2 Error Handlers for Windows
28
29
30
31
     MPI_WIN_CREATE_ERRHANDLER(function, errhandler)
32
       IN
                 function
                                             user defined error handling procedure (function)
33
       OUT
                 errhandler
                                             MPI error handler (handle)
34
35
36
     int MPI_Win_create_errhandler(MPI_Win_errhandler_function *function,
37
                    MPI_Errhandler *errhandler)
38
     MPI_WIN_CREATE_ERRHANDLER(FUNCTION, ERRHANDLER, IERROR)
39
          EXTERNAL FUNCTION
40
          INTEGER ERRHANDLER, IERROR
41
42
     {static MPI::Errhandler
43
                    MPI::Win::Create_errhandler(MPI::Win::Errhandler_function*
44
                    function) (binding deprecated, see Section ??) }
45
          Creates an error handler that can be attached to a window object. The user routine
46
     should be, in C, a function of type MPI_Win_errhandler_function which is defined as
47
     typedef void MPI_Win_errhandler_function(MPI_Win *, int *, ...);
```

```
The first argument is the window in use, the second is the error code to be returned.
    In Fortran, the user routine should be of the form:
SUBROUTINE WIN_ERRHANDLER_FUNCTION(WIN, ERROR_CODE)
    INTEGER WIN, ERROR_CODE
    In C++, the user routine should be of the form:
{typedef void MPI::Win::Errhandler_function(MPI::Win &, int *, ...);
               (binding deprecated, see Section ??)}
MPI_WIN_SET_ERRHANDLER(win, errhandler)
                                                                                         11
                                                                                         12
  INOUT
           win
                                       window (handle)
                                                                                         13
  IN
           errhandler
                                       new error handler for window (handle)
                                                                                         14
                                                                                         15
int MPI_Win_set_errhandler(MPI_Win win, MPI_Errhandler errhandler)
                                                                                         16
MPI_WIN_SET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
                                                                                         18
    INTEGER WIN, ERRHANDLER, IERROR
                                                                                         19
{void MPI::Win::Set_errhandler(const MPI::Errhandler& errhandler) (binding
                                                                                         20
               deprecated, see Section ??) }
                                                                                         21
                                                                                         22
    Attaches a new error handler to a window. The error handler must be either a pre-
                                                                                         23
defined error handler, or an error handler created by a call to
                                                                                         24
MPI_WIN_CREATE_ERRHANDLER.
                                                                                         25
                                                                                         26
MPI_WIN_GET_ERRHANDLER(win, errhandler)
                                                                                         27
                                                                                         28
  IN
                                       window (handle)
           win
                                                                                         29
  OUT
           errhandler
                                       error handler currently associated with window (han-
                                                                                         30
                                       dle)
int MPI_Win_get_errhandler(MPI_Win win, MPI_Errhandler *errhandler)
                                                                                         33
                                                                                         34
MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
                                                                                         35
    INTEGER WIN, ERRHANDLER, IERROR
                                                                                         36
{MPI::Errhandler MPI::Win::Get_errhandler() const(binding deprecated, see
                                                                                         37
               Section ??) }
                                                                                         38
                                                                                         39
    Retrieves the error handler currently associated with a window.
                                                                                         41
```

```
Error Handlers for Files
1
     1.3.3
2
3
4
     MPI_FILE_CREATE_ERRHANDLER(function, errhandler)
5
       IN
                 function
                                             user defined error handling procedure (function)
6
       OUT
                 errhandler
7
                                             MPI error handler (handle)
9
     int MPI_File_create_errhandler(MPI_File_errhandler_function *function,
10
                    MPI_Errhandler *errhandler)
11
     MPI_FILE_CREATE_ERRHANDLER(FUNCTION, ERRHANDLER, IERROR)
12
          EXTERNAL FUNCTION
13
          INTEGER ERRHANDLER, IERROR
14
15
     {static MPI::Errhandler
16
                    MPI::File::Create_errhandler(MPI::File::Errhandler_function*
17
                    function) (binding deprecated, see Section ??) }
18
          Creates an error handler that can be attached to a file object. The user routine should
19
     be, in C, a function of type MPI_File_errhandler_function, which is defined as
20
     typedef void MPI_File_errhandler_function(MPI_File *, int *, ...);
21
22
          The first argument is the file in use, the second is the error code to be returned.
23
         In Fortran, the user routine should be of the form:
24
     SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
25
          INTEGER FILE, ERROR_CODE
26
         In C++, the user routine should be of the form:
27
     {typedef void MPI::File::Errhandler_function(MPI::File &, int *, ...);
28
                     (binding deprecated, see Section ??)
29
30
31
32
     MPI_FILE_SET_ERRHANDLER(file, errhandler)
33
       INOUT
                 file
                                             file (handle)
34
       IN
                 errhandler
                                             new error handler for file (handle)
35
36
37
     int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)
38
     MPI_FILE_SET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
39
          INTEGER FILE, ERRHANDLER, IERROR
40
41
     {void MPI::File::Set_errhandler(const MPI::Errhandler& errhandler) (binding
                     deprecated, see Section ??) }
42
43
          Attaches a new error handler to a file. The error handler must be either a predefined
44
     error handler, or an error handler created by a call to MPI_FILE_CREATE_ERRHANDLER.
```

```
MPI_FILE_GET_ERRHANDLER(file, errhandler)
                                                                                            2
  IN
            file
                                        file (handle)
  OUT
           errhandler
                                        error handler currently associated with file (handle)
int MPI_File_get_errhandler(MPI_File file, MPI_Errhandler *errhandler)
MPI_FILE_GET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
    INTEGER FILE, ERRHANDLER, IERROR
{MPI::Errhandler MPI::File::Get_errhandler() const(binding deprecated, see
                                                                                            10
                                                                                            11
               Section ??) }
                                                                                            12
    Retrieves the error handler currently associated with a file.
                                                                                            13
                                                                                            14
       Freeing Errorhandlers and Retrieving Error Strings
                                                                                            15
                                                                                            16
MPI_ERRHANDLER_FREE( errhandler )
                                                                                            18
                                                                                            19
  INOUT
            errhandler
                                        MPI error handler (handle)
                                                                                            20
                                                                                            21
int MPI_Errhandler_free(MPI_Errhandler *errhandler)
                                                                                            22
MPI_ERRHANDLER_FREE(ERRHANDLER, IERROR)
                                                                                            23
    INTEGER ERRHANDLER, IERROR
                                                                                            24
                                                                                            25
{void MPI::Errhandler::Free()(binding deprecated, see Section ??)}
                                                                                            26
    Marks the error handler associated with errhandler for deallocation and sets errhandler
                                                                                            27
to MPI_ERRHANDLER_NULL. The error handler will be deallocated after all the objects
                                                                                            28
                                                                                            29
associated with it (communicator, window, or file) have been deallocated.
                                                                                            30
                                                                                            31
MPI_ERROR_STRING( errorcode, string, resultlen )
                                                                                            32
                                                                                            33
  IN
            errorcode
                                        Error code returned by an MPI routine
                                                                                            34
  OUT
           string
                                        Text that corresponds to the errorcode
                                                                                            35
  OUT
            resultlen
                                        Length (in printable characters) of the result returned
                                                                                            36
                                        in string
                                                                                            37
                                                                                            38
int MPI_Error_string(int errorcode, char *string, int *resultlen)
                                                                                            39
MPI_ERROR_STRING(ERRORCODE, STRING, RESULTLEN, IERROR)
                                                                                            41
    INTEGER ERRORCODE, RESULTLEN, IERROR
                                                                                            42
    CHARACTER*(*) STRING
                                                                                            43
{void MPI::Get_error_string(int errorcode, char* name,
                                                                                            44
               int& resultlen) (binding deprecated, see Section ??) }
                                                                                            45
                                                                                            46
    Returns the error string associated with an error code or class. The argument string
                                                                                            47
```

must represent storage that is at least MPI\_MAX\_ERROR\_STRING characters long.

The number of characters actually written is returned in the output argument, resultlen.

Rationale. The form of this function was chosen to make the Fortran and C bindings similar. A version that returns a pointer to a string has two difficulties. First, the return string must be statically allocated and different for each error message (allowing the pointers returned by successive calls to MPI\_ERROR\_STRING to point to the correct message). Second, in Fortran, a function declared as returning CHARACTER\*(\*) can not be referenced in, for example, a PRINT statement. (End of rationale.)

#### 1.4 Error Codes and Classes

The error codes returned by MPI are left entirely to the implementation (with the exception of MPI\_SUCCESS). This is done to allow an implementation to provide as much information as possible in the error code (for use with MPI\_ERROR\_STRING).

To make it possible for an application to interpret an error code, the routine MPI\_ERROR\_CLASS converts any error code into one of a small set of standard error codes, called *error classes*. Valid error classes are shown in Table 1.1 and Table 1.2.

The error classes are a subset of the error codes: an MPI function may return an error class number; and the function MPI\_ERROR\_STRING can be used to compute the error string associated with an error class. An MPI error class is a valid MPI error code. Specifically, the values defined for MPI error classes are valid MPI error codes.

The error codes satisfy,

```
0 = MPI\_SUCCESS < MPI\_ERR\_... < MPI\_ERR\_LASTCODE.
```

Rationale. The difference between MPI\_ERR\_UNKNOWN and MPI\_ERR\_OTHER is that MPI\_ERROR\_STRING can return useful information about MPI\_ERR\_OTHER.

Note that MPI\_SUCCESS = 0 is necessary to be consistent with C practice; the separation of error classes and error codes allows us to define the error classes this way. Having a known LASTCODE is often a nice sanity check as well. (*End of rationale*.)

```
MPI_ERROR_CLASS( errorcode, errorclass )
```

IN errorcode Error code returned by an MPI routine
OUT errorclass Error class associated with errorcode

int MPI\_Error\_class(int errorcode, int \*errorclass)

MPI\_ERROR\_CLASS(ERRORCODE, ERRORCLASS, IERROR)
INTEGER ERRORCODE, ERRORCLASS, IERROR

{int MPI::Get\_error\_class(int errorcode)(binding deprecated, see Section ??)}

The function MPI\_ERROR\_CLASS maps each standard error code (error class) onto itself.

	1
No error	2
	3
	4
9	5
v •	6
0 0	7
	8
	9
_ ,	10
	11
~ ·	12
•	13
	14
	15
9	16
	17
	18
	19
, –	20
	21
	22
	23
· ·	24
	25
_	26
	27
_	28
v =	29
	30
*	31
	32
<u>-</u>	33
	34
<u>-</u>	35
	36
9	37
9	38
	39
	40
	41
	42
_	43
	44
	No error Invalid buffer pointer Invalid count argument Invalid datatype argument Invalid tag argument Invalid tag argument Invalid rank Invalid request (handle) Invalid root Invalid group Invalid operation Invalid dimension argument Invalid argument of some other kind Unknown error Message truncated on receive Known error not in this list Internal MPI (implementation) error Error code is in status Pending request Invalid keyval has been passed MPI_ALLOC_MEM failed because memory is exhausted Invalid base passed to MPI_FREE_MEM Key longer than MPI_MAX_INFO_KEY Value longer than MPI_MAX_INFO_VAL Invalid key passed to MPI_INFO_DELETE Error in spawning processes Invalid port name passed to MPI_COMM_CONNECT Invalid service name passed to MPI_UNPUBLISH_NAME Invalid service name passed to MPI_LOOKUP_NAME Invalid service name passed to MPI_LOOKUP_NAME Invalid sign argument Invalid sign argument Invalid info argument Invalid info argument Invalid locktype argument Invalid assert argument Conflicting accesses to window Wrong synchronization of RMA calls

Table 1.1: Error classes (Part 1)

1	MPI_ERR_FILE	Invalid file handle
2	MPI_ERR_NOT_SAME	Collective argument not identical on all
3		processes, or collective routines called in
4		a different order by different processes
5	MPI_ERR_AMODE	Error related to the amode passed to
6		MPI_FILE_OPEN
7	MPI_ERR_UNSUPPORTED_DATAREP	Unsupported datarep passed to
8		MPI_FILE_SET_VIEW
9	MPI_ERR_UNSUPPORTED_OPERATION	Unsupported operation, such as seeking on
10		a file which supports sequential access only
11	MPI_ERR_NO_SUCH_FILE	File does not exist
12	MPI_ERR_FILE_EXISTS	File exists
13	MPI_ERR_BAD_FILE	Invalid file name (e.g., path name too long)
14	MPI_ERR_ACCESS	Permission denied
15	MPI_ERR_NO_SPACE	Not enough space
16	MPI_ERR_QUOTA	Quota exceeded
17	MPI_ERR_READ_ONLY	Read-only file or file system
18	MPI_ERR_FILE_IN_USE	File operation could not be completed, as
19		the file is currently open by some process
20	MPI_ERR_DUP_DATAREP	Conversion functions could not be regis-
21		tered because a data representation identi-
22		fier that was already defined was passed to
23		MPI_REGISTER_DATAREP
24	MPI_ERR_CONVERSION	An error occurred in a user supplied data
25		conversion function.
26	MPI_ERR_IO	Other I/O error
27	MPI_ERR_LASTCODE	Last error code
28		

Table 1.2: Error classes (Part 2)

#### 1.5 Error Classes, Error Codes, and Error Handlers

Users may want to write a layered library on top of an existing MPI implementation, and this library may have its own set of error codes and classes. An example of such a library is an I/O library based on MPI, see Chapter ?? on page ??. For this purpose, functions are needed to:

- 1. add a new error class to the ones an MPI implementation already knows.
- 2. associate error codes with this error class, so that MPI\_ERROR\_CLASS works.
- 3. associate strings with these error codes, so that MPI\_ERROR\_STRING works.
- 4. invoke the error handler associated with a communicator, window, or object.

Several functions are provided to do this. They are all local. No functions are provided to free error classes or codes: it is not expected that an application will generate them in significant numbers.

```
MPI_ADD_ERROR_CLASS(errorclass)
OUT errorclass value for the new error class (integer)
int MPI_Add_error_class(int *errorclass)
MPI_ADD_ERROR_CLASS(ERRORCLASS, IERROR)
    INTEGER ERRORCLASS, IERROR
{int MPI::Add_error_class() (binding deprecated, see Section ??) }
    Creates a new error class and returns the value for it.
```

Rationale. To avoid conflicts with existing error codes and classes, the value is set by the implementation and not by the user. (End of rationale.)

Advice to implementors. A high-quality implementation will return the value for a new errorclass in the same deterministic way on all processes. (End of advice to implementors.)

Advice to users. Since a call to MPI\_ADD\_ERROR\_CLASS is local, the same errorclass may not be returned on all processes that make this call. Thus, it is not safe to assume that registering a new error on a set of processes at the same time will yield the same errorclass on all of the processes. However, if an implementation returns the new errorclass in a deterministic way, and they are always generated in the same order on the same set of processes (for example, all processes), then the value will be the same. However, even if a deterministic algorithm is used, the value can vary across processes. This can happen, for example, if different but overlapping groups of processes make a series of calls. As a result of these issues, getting the "same" error on multiple processes may not cause the same value of error code to be generated. (End of advice to users.)

The value of MPI\_ERR\_LASTCODE is a constant value and is not affected by new user-defined error codes and classes. Instead, a predefined attribute key MPI\_LASTUSEDCODE is associated with MPI\_COMM\_WORLD. The attribute value corresponding to this key is the current maximum error class including the user-defined ones. This is a local value and may be different on different processes. The value returned by this key is always greater than or equal to MPI\_ERR\_LASTCODE.

Advice to users. The value returned by the key MPI\_LASTUSEDCODE will not change unless the user calls a function to explicitly add an error class/code. In a multi-threaded environment, the user must take extra care in assuming this value has not changed. Note that error codes and error classes are not necessarily dense. A user may not assume that each error class below MPI\_LASTUSEDCODE is valid. (End of advice to users.)

2

3

4 5 6

7

8

9 10

11

12 13

14

15 16

18

19 20 21

22 23

24

25 26

27 28

29

30

31

32

33 34

35

36

37

38

39

41

42

43

44

45 46 47

```
MPI_ADD_ERROR_CODE(errorclass, errorcode)
  IN
           errorclass
                                       error class (integer)
  OUT
           errorcode
                                       new error code to associated with errorclass (integer)
int MPI_Add_error_code(int errorclass, int *errorcode)
MPI_ADD_ERROR_CODE(ERRORCLASS, ERRORCODE, IERROR)
    INTEGER ERRORCLASS, ERRORCODE, IERROR
{int MPI::Add_error_code(int errorclass)(binding deprecated, see Section ??)}
    Creates new error code associated with errorclass and returns its value in errorcode.
     Rationale. To avoid conflicts with existing error codes and classes, the value of the
     new error code is set by the implementation and not by the user. (End of rationale.)
     Advice to implementors.
                               A high-quality implementation will return the value for
     a new errorcode in the same deterministic way on all processes. (End of advice to
     implementors.)
MPI_ADD_ERROR_STRING(errorcode, string)
  IN
           errorcode
                                       error code or class (integer)
  IN
           string
                                       text corresponding to errorcode (string)
int MPI_Add_error_string(int errorcode, char *string)
MPI_ADD_ERROR_STRING(ERRORCODE, STRING, IERROR)
    INTEGER ERRORCODE, IERROR
    CHARACTER*(*) STRING
{void MPI::Add_error_string(int errorcode, const char* string)(binding
               deprecated, see Section ??) }
```

Associates an error string with an error code or class. The string must be no more than MPI\_MAX\_ERROR\_STRING characters long. The length of the string is as defined in the calling language. The length of the string does not include the null terminator in C or C++. Trailing blanks will be stripped in Fortran. Calling MPI\_ADD\_ERROR\_STRING for an errorcode that already has a string will replace the old string with the new string. It is erroneous to call MPI\_ADD\_ERROR\_STRING for an error code or class with a value < MPI\_ERR\_LASTCODE.

If MPI\_ERROR\_STRING is called when no string has been set, it will return a empty string (all spaces in Fortran, "" in C and C++).

Section 1.3 on page 7 describes the methods for creating and associating error handlers with communicators, files, and windows.

```
MPI_COMM_CALL_ERRHANDLER (comm, errorcode)
                                                                                           2
  IN
           comm
                                        communicator with error handler (handle)
  IN
           errorcode
                                        error code (integer)
int MPI_Comm_call_errhandler(MPI_Comm comm, int errorcode)
MPI_COMM_CALL_ERRHANDLER(COMM, ERRORCODE, IERROR)
    INTEGER COMM, ERRORCODE, IERROR
{void MPI::Comm::Call_errhandler(int errorcode) const(binding deprecated, see
               Section ??) }
                                                                                           11
                                                                                           12
    This function invokes the error handler assigned to the communicator with the error
                                                                                           13
code supplied. This function returns MPI_SUCCESS in C and C++ and the same value in
                                                                                           14
IERROR if the error handler was successfully called (assuming the process is not aborted
                                                                                           15
and the error handler returns).
                                                                                           16
                        Users should note that the default error handler is
     Advice to users.
                                                                                           17
     MPI_ERRORS_ARE_FATAL. Thus, calling MPI_COMM_CALL_ERRHANDLER will abort
                                                                                           18
     the comm processes if the default error handler has not been changed for this com-
                                                                                           19
     municator or on the parent before the communicator was created. (End of advice to
                                                                                           20
     users.)
                                                                                           21
                                                                                           22
                                                                                          23
                                                                                           24
MPI_WIN_CALL_ERRHANDLER (win, errorcode)
                                                                                           25
  IN
           win
                                        window with error handler (handle)
                                                                                           26
  IN
           errorcode
                                        error code (integer)
                                                                                           27
                                                                                           28
int MPI_Win_call_errhandler(MPI_Win win, int errorcode)
                                                                                           29
                                                                                           30
MPI_WIN_CALL_ERRHANDLER(WIN, ERRORCODE, IERROR)
                                                                                           31
    INTEGER WIN, ERRORCODE, IERROR
{void MPI::Win::Call_errhandler(int errorcode) const(binding deprecated, see
                                                                                          33
               Section ??) }
                                                                                          34
                                                                                           35
    This function invokes the error handler assigned to the window with the error code
                                                                                          36
supplied. This function returns MPI_SUCCESS in C and C++ and the same value in IERROR
                                                                                          37
if the error handler was successfully called (assuming the process is not aborted and the
                                                                                           38
error handler returns).
                                                                                           39
     Advice to users. As with communicators, the default error handler for windows is
     MPI_ERRORS_ARE_FATAL. (End of advice to users.)
                                                                                           42
                                                                                           43
MPI_FILE_CALL_ERRHANDLER (fh, errorcode)
                                                                                           44
                                                                                           45
  IN
           fh
                                        file with error handler (handle)
                                                                                           46
```

error code (integer)

IN

errorcode

This function invokes the error handler assigned to the file with the error code supplied. This function returns MPI\_SUCCESS in C and C++ and the same value in IERROR if the error handler was successfully called (assuming the process is not aborted and the error handler returns).

Advice to users. Unlike errors on communicators and windows, the default behavior for files is to have MPI\_ERRORS\_RETURN. (End of advice to users.)

Advice to users. Users are warned that handlers should not be called recursively with MPI\_COMM\_CALL\_ERRHANDLER, MPI\_FILE\_CALL\_ERRHANDLER, or MPI\_WIN\_CALL\_ERRHANDLER. Doing this can create a situation where an infinite recursion is created. This can occur if MPI\_COMM\_CALL\_ERRHANDLER, MPI\_FILE\_CALL\_ERRHANDLER, or MPI\_WIN\_CALL\_ERRHANDLER is called inside an error handler.

Error codes and classes are associated with a process. As a result, they may be used in any error handler. Error handlers should be prepared to deal with any error code they are given. Furthermore, it is good practice to only call an error handler with the appropriate error codes. For example, file errors would normally be sent to the file error handler. (*End of advice to users.*)

#### 1.6 Timers and Synchronization

MPI defines a timer. A timer is specified even though it is not "message-passing," because timing parallel programs is important in "performance debugging" and because existing timers (both in POSIX 1003.1-1988 and 1003.4D 14.1 and in Fortran 90) are either inconvenient or do not provide adequate access to high-resolution timers. See also Section ?? on page ??.

```
MPI_WTIME()
double MPI_Wtime(void)
DOUBLE PRECISION MPI_WTIME()
{double MPI::Wtime()(binding deprecated, see Section ??)}
```

MPI\_WTIME returns a floating-point number of seconds, representing elapsed wall-clock time since some time in the past.

The "time in the past" is guaranteed not to change during the life of the process. The user is responsible for converting large numbers of seconds to other units if they are preferred.

1.7. STARTUP 21

This function is portable (it returns seconds, not "ticks"), it allows high-resolution, and carries no unnecessary baggage. One would use it like this:

```
double starttime, endtime;
starttime = MPI_Wtime();
.... stuff to be timed ...
endtime = MPI_Wtime();
printf("That took %f seconds\n",endtime-starttime);
}
```

The times returned are local to the node that called them. There is no requirement that different nodes return "the same time." (But see also the discussion of MPI\_WTIME\_IS\_GLOBAL).

```
MPI_WTICK()
double MPI_Wtick(void)

DOUBLE PRECISION MPI_WTICK()
{double MPI::Wtick() (binding deprecated, see Section ??) }
```

MPI\_WTICK returns the resolution of MPI\_WTIME in seconds. That is, it returns, as a double precision value, the number of seconds between successive clock ticks. For example, if the clock is implemented by the hardware as a counter that is incremented every millisecond, the value returned by MPI\_WTICK should be  $10^{-3}$ .

#### 1.7 Startup

One goal of MPI is to achieve source code portability. By this we mean that a program written using MPI and complying with the relevant language standards is portable as written, and must not require any source code changes when moved from one system to another. This explicitly does not say anything about how an MPI program is started or launched from the command line, nor what the user must do to set up the environment in which an MPI program will run. However, an implementation may require some setup to be performed before other MPI routines may be called. To provide for this, MPI includes an initialization routine MPI\_INIT.

ticket204. <sup>4</sup>

All MPI programs must contain exactly one call to an MPI initialization routine: MPI\_INIT or MPI\_INIT\_THREAD. Subsequent calls to any initialization routines are erroneous. The only MPI functions that may be invoked before the MPI initialization routines are called are MPI\_GET\_VERSION, []MPI\_GET\_LIBRARY\_VERSION, MPI\_INITIALIZED, and MPI\_FINALIZED. The version for ISO C accepts the argc and argv that are provided by the arguments to main or NULL:

```
int main(int argc, char **argv)
{
    MPI_Init(&argc, &argv);

    /* parse arguments */
    /* main program */

    MPI_Finalize();    /* see below */
}
```

The Fortran version takes only IERROR.

Conforming implementations of MPI are required to allow applications to pass NULL for both the argc and argv arguments of main in C and C++. In C++, there is an alternative binding for MPI::Init that does not have these arguments at all.

Rationale. In some applications, libraries may be making the call to MPI\_Init, and may not have access to argc and argv from main. It is anticipated that applications requiring special information about the environment or information supplied by mpiexec can get that information from environment variables. (End of rationale.)

This routine cleans up all MPI state. Each process must call MPI\_FINALIZE before it exits. Unless there has been a call to MPI\_ABORT, each process must ensure that all pending nonblocking communications are (locally) complete before calling MPI\_FINALIZE. Further, at the instant at which the last process calls MPI\_FINALIZE, all pending sends must be matched by a receive, and all pending receives must be matched by a send.

For example, the following program is correct:

1.7. STARTUP 23

Without the matching receive, the program is erroneous:

A successful return from a blocking communication operation or from MPI\_WAIT or MPI\_TEST tells the user that the buffer can be reused and means that the communication is completed by the user, but does not guarantee that the local process has no more work to do. A successful return from MPI\_REQUEST\_FREE with a request handle generated by an MPI\_ISEND nullifies the handle but provides no assurance of operation completion. The MPI\_ISEND is complete only when it is known by some means that a matching receive has completed. MPI\_FINALIZE guarantees that all local actions required by communications the user has completed will, in fact, occur before it returns.

MPI\_FINALIZE guarantees nothing about pending communications that have not been completed (completion is assured only by MPI\_WAIT, MPI\_TEST, or MPI\_REQUEST\_FREE combined with some other verification of completion).

**Example 1.3** This program is correct:

**Example 1.4** This program is erroneous and its behavior is undefined:

If no MPI\_BUFFER\_DETACH occurs between an MPI\_BSEND (or other buffered send) and MPI\_FINALIZE, the MPI\_FINALIZE implicitly supplies the MPI\_BUFFER\_DETACH.

**Example 1.5** This program is correct, and after the MPI\_Finalize, it is as if the buffer had been detached.

rank 1

rank 0

1

```
2
3
4
     buffer = malloc(1000000);
                                       MPI_Recv();
5
     MPI_Buffer_attach();
                                       MPI_Finalize();
6
     MPI_Bsend();
                                        exit();
7
     MPI_Finalize();
8
     free(buffer);
9
     exit();
10
11
     Example 1.6
                     In this example, MPI_lprobe() must return a FALSE flag.
12
     MPI_Test_cancelled() must return a TRUE flag, independent of the relative order of execu-
13
     tion of MPI_Cancel() in process 0 and MPI_Finalize() in process 1.
14
         The MPI_Iprobe() call is there to make sure the implementation knows that the "tag1"
15
     message exists at the destination, without being able to claim that the user knows about
16
17
18
19
     rank 0
                                        rank 1
20
     _____
21
     MPI_Init();
                                        MPI_Init();
22
     MPI_Isend(tag1);
23
     MPI_Barrier();
                                       MPI_Barrier();
24
                                       MPI_Iprobe(tag2);
25
     MPI_Barrier();
                                       MPI_Barrier();
26
                                       MPI_Finalize();
27
                                        exit();
28
     MPI_Cancel();
29
     MPI_Wait();
30
     MPI_Test_cancelled();
31
     MPI_Finalize();
32
     exit();
33
```

Advice to implementors. An implementation may need to delay the return from MPI\_FINALIZE until all potential future message cancellations have been processed. One possible solution is to place a barrier inside MPI\_FINALIZE (End of advice to implementors.)

Once MPI\_FINALIZE returns, no MPI routine (not even MPI\_INIT) may be called, except for MPI\_GET\_VERSION, []MPI\_GET\_LIBRARY\_VERSION, MPI\_INITIALIZED, and MPI\_FINALIZED. Each process must complete any pending communication it initiated before it calls MPI\_FINALIZE. If the call returns, each process may continue local computations, or exit, without participating in further MPI communication with other processes. MPI\_FINALIZE is collective over all connected processes. If no processes were spawned, accepted or connected then this means over MPI\_COMM\_WORLD; otherwise it is collective over the union of all processes that have been and continue to be connected, as explained in Section ?? on page ??.

43

ticket204. 41

34 35

36

37

39

44

45

 $^{46}$ 

47

1.7. STARTUP 25

Advice to implementors. Even though a process has completed all the communication it initiated, such communication may not yet be completed from the viewpoint of the underlying MPI system. E.g., a blocking send may have completed, even though the data is still buffered at the sender. The MPI implementation must ensure that a process has completed any involvement in MPI communication before MPI\_FINALIZE returns. Thus, if a process exits after the call to MPI\_FINALIZE, this will not cause an ongoing communication to fail. (End of advice to implementors.)

Although it is not required that all processes return from MPI\_FINALIZE, it is required that at least process 0 in MPI\_COMM\_WORLD return, so that users can know that the MPI portion of the computation is over. In addition, in a POSIX environment, they may desire to supply an exit code for each process that returns from MPI\_FINALIZE.

**Example 1.7** The following illustrates the use of requiring that at least one process return and that it be known that process 0 is one of the processes that return. One wants code like the following to work no matter how many processes return.

```
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);
    MPI_Finalize();
    if (myrank == 0) {
        resultfile = fopen("outfile","w");
        dump_results(resultfile);
        fclose(resultfile);
    }
    exit(0);
MPI_INITIALIZED( flag )
 OUT
                                     Flag is true if MPI_INIT has been called and false
           flag
                                     otherwise.
int MPI_Initialized(int *flag)
MPI_INITIALIZED(FLAG, IERROR)
    LOGICAL FLAG
    INTEGER IERROR
{bool MPI::Is_initialized()(binding deprecated, see Section ??)}
```

This routine may be used to determine whether MPI\_INIT has been called. MPI\_INITIALIZED returns true if the calling process has called MPI\_INIT. Whether MPI\_FINALIZE has been called does not affect the behavior of MPI\_INITIALIZED. It is one of the few routines that may be called before MPI\_INIT is called.

2

3

4 5

7

8

9

11

12

13

14

15

16

17

18

19

20 21

22

23

24

25 26

27

28

29 30 31

32

33

34 35

36

37

38

39

40

41

42

43

44

45

46

47

48

```
MPI_ABORT( comm, errorcode )
       IN
                comm
                                            communicator of tasks to abort
       IN
                errorcode
                                            error code to return to invoking environment
6
     int MPI_Abort(MPI_Comm comm, int errorcode)
     MPI_ABORT(COMM, ERRORCODE, IERROR)
         INTEGER COMM, ERRORCODE, IERROR
10
     {void MPI::Comm::Abort(int errorcode)(binding deprecated, see Section ??)}
```

This routine makes a "best attempt" to abort all tasks in the group of comm. This function does not require that the invoking environment take any action with the error code. However, a Unix or POSIX environment should handle this as a return errorcode from the main program.

It may not be possible for an MPI implementation to abort only the processes represented by comm if this is a subset of the processes. In this case, the MPI implementation should attempt to abort all the connected processes but should not abort any unconnected processes. If no processes were spawned, accepted or connected then this has the effect of aborting all the processes associated with MPI\_COMM\_WORLD.

Rationale. The communicator argument is provided to allow for future extensions of MPI to environments with, for example, dynamic process management. In particular, it allows but does not require an MPI implementation to abort a subset of MPI\_COMM\_WORLD. (End of rationale.)

Advice to users. Whether the errorcode is returned from the executable or from the MPI process startup mechanism (e.g., mpiexec), is an aspect of quality of the MPI library but not mandatory. (End of advice to users.)

Advice to implementors. Where possible, a high-quality implementation will try to return the errorcode from the MPI process startup mechanism (e.g. mpiexec or singleton init). (End of advice to implementors.)

#### Allowing User Functions at Process Termination

There are times in which it would be convenient to have actions happen when an MPI process finishes. For example, a routine may do initializations that are useful until the MPI job (or that part of the job that being terminated in the case of dynamically created processes) is finished. This can be accomplished in MPI by attaching an attribute to MPI\_COMM\_SELF with a callback function. When MPI\_FINALIZE is called, it will first execute the equivalent of an MPI\_COMM\_FREE on MPI\_COMM\_SELF. This will cause the delete callback function to be executed on all keys associated with MPI\_COMM\_SELF, in the reverse order that they were set on MPI\_COMM\_SELF. If no key has been attached to MPI\_COMM\_SELF, then no callback is invoked. The "freeing" of MPI\_COMM\_SELF occurs before any other parts of MPI are affected. Thus, for example, calling MPI\_FINALIZED will return false in any of these callback functions. Once done with MPI\_COMM\_SELF, the order and rest of the actions taken by MPI\_FINALIZE is not specified.

Advice to implementors. Since attributes can be added from any supported language, the MPI implementation needs to remember the creating language so the correct callback is made. Implementations that use the attribute delete callback on MPI\_COMM\_SELF internally should register their internal callbacks before returning from MPI\_INIT / MPI\_INIT\_THREAD, so that libraries or applications will not have portions of the MPI implementation shut down before the application-level callbacks are made. (End of advice to implementors.)

#### 1.7.2 Determining Whether MPI Has Finished

One of the goals of MPI was to allow for layered libraries. In order for a library to do this cleanly, it needs to know if MPI is active. In MPI the function MPI\_INITIALIZED was provided to tell if MPI had been initialized. The problem arises in knowing if MPI has been finalized. Once MPI has been finalized it is no longer active and cannot be restarted. A library needs to be able to determine this to act accordingly. To achieve this the following function is needed:

```
MPI_FINALIZED(flag)
OUT flag true if MPI was finalized (logical)

int MPI_Finalized(int *flag)

MPI_FINALIZED(FLAG, IERROR)
    LOGICAL FLAG
    INTEGER IERROR

{bool MPI::Is_finalized() (binding deprecated, see Section ??) }

This routine returns true if MPI_FINALIZE has completed. It is legal to call
```

This routine returns true if MPI\_FINALIZE has completed. It is legal to call MPI\_FINALIZED before MPI\_INIT and after MPI\_FINALIZE.

Advice to users. MPI is "active" and it is thus safe to call MPI functions if MPI\_INIT has completed and MPI\_FINALIZE has not completed. If a library has no other way of knowing whether MPI is active or not, then it can use MPI\_INITIALIZED and MPI\_FINALIZED to determine this. For example, MPI is "active" in callback functions that are invoked during MPI\_FINALIZE. (End of advice to users.)

#### 1.8 Portable MPI Process Startup

A number of implementations of MPI provide a startup command for MPI programs that is of the form

```
mpirun <mpirun arguments> <program> <program arguments>
```

Separating the command to start the program from the program itself provides flexibility, particularly for network and heterogeneous implementations. For example, the startup script need not run on one of the machines that will be executing the MPI program itself.

Having a standard startup mechanism also extends the portability of MPI programs one step further, to the command lines and scripts that manage them. For example, a validation

suite script that runs hundreds of programs can be a portable script if it is written using such a standard starup mechanism. In order that the "standard" command not be confused with existing practice, which is not standard and not portable among implementations, instead of mpirun MPI specifies mpiexec.

While a standardized startup mechanism improves the usability of MPI, the range of environments is so diverse (e.g., there may not even be a command line interface) that MPI cannot mandate such a mechanism. Instead, MPI specifies an mpiexec startup command and recommends but does not require it, as advice to implementors. However, if an implementation does provide a command called mpiexec, it must be of the form described below.

It is suggested that

```
mpiexec -n <numprocs>                                                                                                                                                                                                                                                                                                                                                  <p
```

be at least one way to start contains <numprocs> processes. Other arguments to mpiexec may be implementation-dependent.

Advice to implementors. Implementors, if they do provide a special startup command for MPI programs, are advised to give it the following form. The syntax is chosen in order that mpiexec be able to be viewed as a command-line version of MPI\_COMM\_SPAWN (See Section ??).

Analogous to MPI\_COMM\_SPAWN, we have

```
mpiexec -n
               <maxprocs>
       -soft
              <
                        >
                        >
       -host <
       -arch
              <
                        >
       -wdir <
       -path
              <
                        >
       -file
              <
       <command line>
```

for the case where a single command line for the application program and its arguments will suffice. See Section ?? for the meanings of these arguments. For the case corresponding to MPI\_COMM\_SPAWN\_MULTIPLE there are two possible formats:

Form A:

```
mpiexec { <above arguments> } : { ... } : { ... }
```

As with MPI\_COMM\_SPAWN, all the arguments are optional. (Even the -n x argument is optional; the default is implementation dependent. It might be 1, it might be taken from an environment variable, or it might be specified at compile time.) The names and meanings of the arguments are taken from the keys in the info argument to MPI\_COMM\_SPAWN. There may be other, implementation-dependent arguments as well.

12 13

14 15 16

19 20 21

22

23 24

252627

28

29 30

31

34 35

36

37 38

39

42

43

44 45

46 47

Note that Form A, though convenient to type, prevents colons from being program arguments. Therefore an alternate, file-based form is allowed:

Form B:

```
mpiexec -configfile <filename>
```

where the lines of <filename> are of the form separated by the colons in Form A. Lines beginning with '#' are comments, and lines may be continued by terminating the partial line with '\'.

**Example 1.8** Start 16 instances of myprog on the current or default machine:

```
mpiexec -n 16 myprog
```

Example 1.9 Start 10 processes on the machine called ferrari:

```
mpiexec -n 10 -host ferrari myprog
```

**Example 1.10** Start three copies of the same program with different command-line arguments:

```
mpiexec myprog infile1 : myprog infile2 : myprog infile3
```

**Example 1.11** Start the ocean program on five Suns and the atmos program on 10 RS/6000's:

```
mpiexec -n 5 -arch sun ocean : -n 10 -arch rs6000 atmos
```

It is assumed that the implementation in this case has a method for choosing hosts of the appropriate type. Their ranks are in the order specified.

**Example 1.12** Start the ocean program on five Suns and the atmos program on 10 RS/6000's (Form B):

```
mpiexec -configfile myfile
```

where myfile contains

```
-n 5 -arch sun ocean
-n 10 -arch rs6000 atmos
```

(End of advice to implementors.)

### Chapter 2

## Language Bindings Summary

In this section we summarize the specific bindings for C, Fortran, and C++. First we present the constants, type definitions, info values and keys. Then we present the routine prototypes separately for each binding. Listings are alphabetical within chapter.

#### 2.1 Defined Values and Handles

#### 2.1.1 Defined Constants

The C and Fortran name is listed in the left column and the C++ name is listed in the middle or right column. Constants with the type **const** int may also be implemented as literal integer constants substituted by the preprocessor.

#### **Return Codes**

icetain Codes									
C type: const int (or unnamed enum)	C++ type: const int								
Fortran type: INTEGER	(or unnamed enum)								
MPI_SUCCESS	MPI::SUCCESS								
MPI_ERR_BUFFER	MPI::ERR_BUFFER								
MPI_ERR_COUNT	MPI::ERR_COUNT								
MPI_ERR_TYPE	MPI::ERR_TYPE								
MPI_ERR_TAG	MPI::ERR_TAG								
MPI_ERR_COMM	MPI::ERR_COMM								
MPI_ERR_RANK	MPI::ERR_RANK								
MPI_ERR_REQUEST	MPI::ERR_REQUEST								
MPI_ERR_ROOT	MPI::ERR_ROOT								
MPI_ERR_GROUP	MPI::ERR_GROUP								
MPI_ERR_OP	MPI::ERR_OP								
MPI_ERR_TOPOLOGY	MPI::ERR_TOPOLOGY								
MPI_ERR_DIMS	MPI::ERR_DIMS								
MPI_ERR_ARG	MPI::ERR_ARG								
MPI_ERR_UNKNOWN	MPI::ERR_UNKNOWN								
MPI_ERR_TRUNCATE	MPI::ERR_TRUNCATE								
MPI_ERR_OTHER	MPI::ERR_OTHER								
MPI_ERR_INTERN	MPI::ERR_INTERN								
MPI_ERR_PENDING	MPI::ERR_PENDING								

(Continued on next page)

Return Codes (con		s (continued)	1
	MPI_ERR_IN_STATUS	MPI::ERR_IN_STATUS	2
	MPI_ERR_ACCESS	MPI::ERR_ACCESS	3
	MPI_ERR_AMODE	MPI::ERR_AMODE	4
	MPI_ERR_ASSERT	MPI::ERR_ASSERT	5
	MPI_ERR_BAD_FILE	MPI::ERR_BAD_FILE	6
	MPI_ERR_BASE	MPI::ERR_BASE	7
	MPI_ERR_CONVERSION	MPI::ERR_CONVERSION	8
	MPI_ERR_DISP	MPI::ERR_DISP	9
	MPI_ERR_DUP_DATAREP	MPI::ERR_DUP_DATAREP	10
	MPI_ERR_FILE_EXISTS	MPI::ERR_FILE_EXISTS	11
	MPI_ERR_FILE_IN_USE	MPI::ERR_FILE_IN_USE	12
	MPI_ERR_FILE	MPI::ERR_FILE	13
	MPI_ERR_INFO_KEY	MPI::ERR_INFO_VALUE	14
	MPI_ERR_INFO_NOKEY	MPI::ERR_INFO_NOKEY	15
	MPI_ERR_INFO_VALUE	MPI::ERR_INFO_KEY	16
	MPI_ERR_INFO	MPI::ERR_INFO	17
	MPI_ERR_IO	MPI::ERR_IO	18
	MPI_ERR_KEYVAL	MPI::ERR_KEYVAL	19
	MPI_ERR_LOCKTYPE	MPI::ERR_LOCKTYPE	20
	MPI_ERR_NAME	MPI::ERR_NAME	21
	MPI_ERR_NO_MEM	MPI::ERR_NO_MEM	22
	MPI_ERR_NOT_SAME	MPI::ERR_NOT_SAME	23
	MPI_ERR_NO_SPACE	MPI::ERR_NO_SPACE	24
	MPI_ERR_NO_SUCH_FILE	MPI::ERR_NO_SUCH_FILE	25
	MPI_ERR_PORT	MPI::ERR_PORT	26
	MPI_ERR_QUOTA	MPI::ERR_QUOTA	27
	MPI_ERR_READ_ONLY	MPI::ERR_READ_ONLY	28
	MPI_ERR_RMA_CONFLICT	MPI::ERR_RMA_CONFLICT	29
	MPI_ERR_RMA_SYNC	MPI::ERR_RMA_SYNC	30
	MPI_ERR_SERVICE	MPI::ERR_SERVICE	31
	MPI_ERR_SIZE	MPI::ERR_SIZE	32
	MPI_ERR_SPAWN	MPI::ERR_SPAWN	33
	MPI_ERR_UNSUPPORTED_DATAREP	MPI::ERR_UNSUPPORTED_DATAREP	34
	MPI_ERR_UNSUPPORTED_OPERATION	MPI::ERR_UNSUPPORTED_OPERATION	35
	MPI_ERR_WIN	MPI::ERR_WIN	36
	MPI_ERR_LASTCODE	MPI::ERR_LASTCODE	37

### **Buffer Address Constants**

C type: void * const	C++ type:
Fortran type: (predefined memory location)	<pre>void * const</pre>
MPI_BOTTOM	MPI::BOTTOM
MPI_IN_PLACE	MPI::IN_PLACE

1	Assorted Con	nstants
C type: const int (or unnamed enum) C++ type:		C++ type:
3	Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
4	MPI_PROC_NULL	MPI::PROC_NULL
5	MPI_ANY_SOURCE	MPI::ANY_SOURCE
6	MPI_ANY_TAG	MPI::ANY_TAG
7	MPI_UNDEFINED	MPI::UNDEFINED
8	MPI_BSEND_OVERHEAD	MPI::BSEND_OVERHEAD
9	MPI_KEYVAL_INVALID	MPI::KEYVAL_INVALID
10	MPI_LOCK_EXCLUSIVE	MPI::LOCK_EXCLUSIVE
11	MPI_LOCK_SHARED	MPI::LOCK_SHARED
12	MPI_ROOT	MPI::ROOT
13		

## Status size and reserved index values (Fortran only)

Fortran type: INTEGER	
MPI_STATUS_SIZE	Not defined for C++
MPI_SOURCE	Not defined for C++
MPI_TAG	Not defined for C++
MPI_ERROR	Not defined for C++

## Variable Address Size (Fortran only)

Fortran type: INTEGER	
MPI_ADDRESS_KIND	Not defined for C++
MPI_INTEGER_KIND	Not defined for C++
MPI OFFSET KIND	Not defined for C++

#### Error-handling specifiers

C type: MPI_Errhandler	C++ type: MPI::Errhandler	
Fortran type: INTEGER		
MPI_ERRORS_ARE_FATAL	MPI::ERRORS_ARE_FATAL	
MPI_ERRORS_RETURN	MPI::ERRORS_RETURN	
	MPI::ERRORS THROW EXCEPTIONS	

#### Maximum Sizes for Strings

	•
C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_MAX_PROCESSOR_NAME	MPI::MAX_PROCESSOR_NAME
[ticket204.][] MPI_MAX_LIBRARY_VERSION_STRING	
MPI_MAX_ERROR_STRING	MPI::MAX_ERROR_STRING
MPI_MAX_DATAREP_STRING	MPI::MAX_DATAREP_STRING
MPI_MAX_INFO_KEY	MPI::MAX_INFO_KEY
MPI_MAX_INFO_VAL	MPI::MAX_INFO_VAL
MPI_MAX_OBJECT_NAME	MPI::MAX_OBJECT_NAME
MPI_MAX_PORT_NAME	MPI::MAX_PORT_NAME

Named Predefined Datatypes		C/C++ types	1
C type: MPI_Datatype	C++ type: MPI::Datatype		_ 3
Fortran type: INTEGER			4
MPI_CHAR	MPI::CHAR	char	 5
		(treated as printable	6
		character)	7
MPI_SHORT	MPI::SHORT	signed short int	8
MPI_INT	MPI::INT	signed int	9
MPI_LONG	MPI::LONG	signed long	10
MPI_LONG_LONG_INT	MPI::LONG_LONG_INT	signed long long	11
MPI_LONG_LONG	MPI::LONG_LONG	long long (synonym)	12
MPI_SIGNED_CHAR	MPI::SIGNED_CHAR	signed char	13
	_	(treated as integral value)	14
MPI_UNSIGNED_CHAR	MPI::UNSIGNED_CHAR	unsigned char	15
	<del>-</del>	(treated as integral value)	16
MPI_UNSIGNED_SHORT	MPI::UNSIGNED_SHORT	unsigned short	17
MPI_UNSIGNED	MPI::UNSIGNED	unsigned int	18
MPI_UNSIGNED_LONG	MPI::UNSIGNED_LONG	unsigned long	19
MPI_UNSIGNED_LONG_LONG	MPI::UNSIGNED_LONG_LONG	unsigned long long	20
MPI_FLOAT	MPI::FLOAT	float	21
MPI_DOUBLE	MPI::DOUBLE	double	22
MPI_LONG_DOUBLE	MPI::LONG_DOUBLE	long double	23
MPI_WCHAR	MPI::WCHAR	wchar_t	24
		(defined in <stddef.h>)</stddef.h>	25
		(treated as printable	26
		character)	27
MPI_C_BOOL	(use C datatype handle)	_Bool	28
MPI_INT8_T	(use C datatype handle)	int8_t	29
MPI_INT16_T	(use C datatype handle)	int16_t	30
MPI_INT32_T	(use C datatype handle)	int32_t	31
MPI_INT64_T	(use C datatype handle)	int64_t	32
MPI_UINT8_T	(use C datatype handle)	uint8_t	33
MPI_UINT16_T	(use C datatype handle)	uint16_t	34
MPI_UINT32_T	(use C datatype handle)	uint32_t	35
MPI_UINT64_T	(use C datatype handle)	uint64_t	36
MPI_AINT	(use C datatype handle)	MPI_Aint	37
MPI_OFFSET	(use C datatype handle)	MPI_Offset	38
MPI_C_COMPLEX	(use C datatype handle)	float _Complex	39
MPI_C_FLOAT_COMPLEX	(use C datatype handle)	float _Complex	40
MPI_C_DOUBLE_COMPLEX	(use C datatype handle)	double _Complex	41
MPI_C_LONG_DOUBLE_COMPLEX	(use C datatype handle)	long double _Complex	42
MPI_BYTE	MPI::BYTE	(any C/C++ type)	43
MPI_PACKED	MPI::PACKED	(any C/C++ type)	44

(any Fortran type)

2	Named Predefined Datatypes		Fortran types
3	C type: MPI_Datatype	C++ type: MPI::Datatype	
4	Fortran type: INTEGER		
5	MPI_INTEGER	MPI::INTEGER	INTEGER
6	MPI_REAL	MPI::REAL	REAL
7	MPI_DOUBLE_PRECISION	MPI::DOUBLE_PRECISION	DOUBLE PRECISION
8	MPI_COMPLEX	MPI::F_COMPLEX	COMPLEX
9	MPI_LOGICAL	MPI::LOGICAL	LOGICAL
10	MPI_CHARACTER	MPI::CHARACTER	CHARACTER(1)
11	MPI_AINT	(use C datatype handle)	<pre>INTEGER (KIND=MPI_ADDRESS_KIND)</pre>
12	MPI_OFFSET	(use C datatype handle)	<pre>INTEGER (KIND=MPI_OFFSET_KIND)</pre>
13	MPI_BYTE	MPI::BYTE	(any Fortran type)

MPI\_PACKED

C++-Only Named Predefined Datatypes	C++ types	
C++ type: MPI::Datatype		
MPI::BOOL	bool	
MPI::COMPLEX	Complex <float></float>	
MPI::DOUBLE_COMPLEX	Complex <double></double>	
MPI::LONG_DOUBLE_COMPLEX	Complex <long double=""></long>	

MPI::PACKED

Optional datatypes (Fortran)		Fortran types
C type: MPI_Datatype	C++ type: MPI::Datatype	
Fortran type: INTEGER		
MPI_DOUBLE_COMPLEX	MPI::F_DOUBLE_COMPLEX	DOUBLE COMPLEX
MPI_INTEGER1	MPI::INTEGER1	INTEGER*1
MPI_INTEGER2	MPI::INTEGER2	INTEGER*8
MPI_INTEGER4	MPI::INTEGER4	INTEGER*4
MPI_INTEGER8	MPI::INTEGER8	INTEGER*8
MPI_INTEGER16		INTEGER*16
MPI_REAL2	MPI::REAL2	REAL*2
MPI_REAL4	MPI::REAL4	REAL*4
MPI_REAL8	MPI::REAL8	REAL*8
MPI_REAL16		REAL*16
MPI_COMPLEX4		COMPLEX*4
MPI_COMPLEX8		COMPLEX*8
MPI_COMPLEX16		COMPLEX*16
MPI_COMPLEX32		COMPLEX*32

Datatypes for reduction functions (C and C++	
C++ type: MPI::Datatype	
MPI::FLOAT_INT	
MPI::DOUBLE_INT	
MPI::LONG_INT	
MPI::TWOINT	
MPI::SHORT_INT	
MPI::LONG_DOUBLE_INT	

## Datatypes for reduction functions (Fortran)

	,
${ m C}$ type: MPI_Datatype	C++ type: MPI::Datatype
Fortran type: INTEGER	
MPI_2REAL	MPI::TWOREAL
MPI_2DOUBLE_PRECISION	MPI::TWODOUBLE_PRECISION
MPI_2INTEGER	MPI::TWOINTEGER

#### Special datatypes for constructing derived datatypes

C type: MPI_Datatype Fortran type: INTEGER	C++ type: MPI::Datatype
MPI_UB	MPI::UB
MPI_LB	MPI::LB

#### Reserved communicators

C type: MPI_Comm	C++ type: MPI::Intracomm
Fortran type: INTEGER	
MPI_COMM_WORLD	MPI::COMM_WORLD
MPI_COMM_SELF	MPI::COMM_SELF

#### Results of communicator and group comparisons

C type: const int (or unnamed enum)	C++ type: const int
Fortran type: INTEGER	(or unnamed enum)
MPI_IDENT	MPI::IDENT
MPI_CONGRUENT	MPI::CONGRUENT
MPI_SIMILAR	MPI::SIMILAR
MPI_UNEQUAL	MPI::UNEQUAL

#### Environmental inquiry keys

-	
C type: const int (or unnamed enum)	C++ type: const int
Fortran type: INTEGER	(or unnamed enum)
MPI_TAG_UB	MPI::TAG_UB
MPI_IO	MPI::IO
MPI_HOST	MPI::HOST
MPI_WTIME_IS_GLOBAL	MPI::WTIME_IS_GLOBAL

36	CHA	PTER 2. LANGUAGE BINI	
1	Collecti	Collective Operations	
2	C type: MPI_Op	C++ type: const MPI::Op	
3	Fortran type: INTEGER		
4	MPI_MAX	MPI::MAX	
5	MPI_MIN	MPI::MIN	
6	MPI_SUM	MPI::SUM	
7	MPI_PROD	MPI::PROD	
8	MPI_MAXLOC	MPI::MAXLOC	
9	MPI_MINLOC	MPI::MINLOC	
10	MPI_BAND	MPI::BAND	
11	MPI_BOR	MPI::BOR	
12	MPI_BXOR	MPI::BXOR	
13	MPI_LAND	MPI::LAND	
14	MPI_LOR	MPI::LOR	
15	MPI_LXOR	MPI::LXOR	
16	MPI_REPLACE	MPI::REPLACE	
17			
18			
19	Nul	l Handles	
20	C/Fortran name	C++ name	
21	C type / Fortran type	C++ type	
22	MPI_GROUP_NULL	MPI::GROUP_NULL	
23	MPI_Group / INTEGER	const MPI::Group	

1,011 1	idiidios
C/Fortran name	C++ name
C type / Fortran type	C++ type
MPI_GROUP_NULL	MPI::GROUP_NULL
MPI_Group / INTEGER	const MPI::Group
MPI_COMM_NULL	MPI::COMM_NULL
MPI_Comm / INTEGER	$^{1})$
MPI_DATATYPE_NULL	MPI::DATATYPE_NULL
${\tt MPI\_Datatype} \; / \; {\tt INTEGER}$	const MPI::Datatype
MPI_REQUEST_NULL	MPI::REQUEST_NULL
${\tt MPI\_Request / INTEGER}$	const MPI::Request
MPI_OP_NULL	MPI::OP_NULL
MPI_Op / INTEGER	const MPI::Op
MPI_ERRHANDLER_NULL	MPI::ERRHANDLER_NULL
${\tt MPI\_Errhandler} \; / \; {\tt INTEGER}$	const MPI::Errhandler
MPI_FILE_NULL	MPI::FILE_NULL
MPI_File / INTEGER	
MPI_INFO_NULL	MPI::INFO_NULL
<pre>MPI_Info / INTEGER</pre>	const MPI::Info
MPI_WIN_NULL	MPI::WIN_NULL
MPI_Win / INTEGER	
1/0	. 99 . 1'

<sup>1)</sup> C++ type: See Section ?? on page ?? regarding class hierarchy and the specific type of MPI::COMM\_NULL

# Empty group

C type: MPI_Group	C++ type: const MPI::Group
Fortran type: INTEGER	
MPI_GROUP_EMPTY	MPI::GROUP_EMPTY

Topologies	
C type: const int (or unnamed enum)	C++ type: const int
Fortran type: INTEGER	(or unnamed enum)
MPI_GRAPH	MPI::GRAPH
MPI_CART	MPI::CART
MPI_DIST_GRAPH	MPI::DIST_GRAPH

# Predefined functions

C/Fortran name	C++ name
C type / Fortran type	C++ type
MPI_COMM_NULL_COPY_FN	MPI_COMM_NULL_COPY_FN
MPI_Comm_copy_attr_function	same as in $C^{1}$ )
/ COMM_COPY_ATTR_FN	
MPI_COMM_DUP_FN	MPI_COMM_DUP_FN
MPI_Comm_copy_attr_function	same as in $C^{1}$ )
/ COMM_COPY_ATTR_FN	
MPI_COMM_NULL_DELETE_FN	MPI_COMM_NULL_DELETE_FN
MPI_Comm_delete_attr_function	same as in $C^{-1}$ )
/ COMM_DELETE_ATTR_FN	
MPI_WIN_NULL_COPY_FN	MPI_WIN_NULL_COPY_FN
MPI_Win_copy_attr_function	same as in $C^{-1}$ )
/ WIN_COPY_ATTR_FN	
MPI_WIN_DUP_FN	MPI_WIN_DUP_FN
MPI_Win_copy_attr_function	same as in $C^{-1}$ )
/ WIN_COPY_ATTR_FN	1481 W/W 1881 851 555 51
MPI_WIN_NULL_DELETE_FN	MPI_WIN_NULL_DELETE_FN
MPI_Win_delete_attr_function	same as in $C^{-1}$ )
/ WIN_DELETE_ATTR_FN	MADE TYPE MULL GODY EN
MPI_TYPE_NULL_COPY_FN	MPI_TYPE_NULL_COPY_FN
MPI_Type_copy_attr_function	same as in $C^{-1}$ )
/ TYPE_COPY_ATTR_FN	MADL TYPE DUD EN
MPI_TYPE_DUP_FN	MPI_TYPE_DUP_FN
MPI_Type_copy_attr_function	same as in C $^{1}$ )
/ TYPE_COPY_ATTR_FN	MOLTYDE MILL DELETE EN
MPI_TYPE_NULL_DELETE_FN	MPI_TYPE_NULL_DELETE_FN
MPI_Type_delete_attr_function	same as in C $^{1}$ )
/ TYPE_DELETE_ATTR_FN	MDI COMM NIIII CODY EN
-	MPI_COMM_NULL_COPY_FN, in
Section ?? on page ??	

**Unofficial Draft for Comment Only** 

 $^{23}$ 

Deprecated predefined functions	
C/Fortran name	C++ name
C type / Fortran type	C++ type
MPI_NULL_COPY_FN	MPI::NULL_COPY_FN
MPI_Copy_function / COPY_FUNCTION	MPI::Copy_function
MPI_DUP_FN	MPI::DUP_FN
MPI_Copy_function / COPY_FUNCTION	MPI::Copy_function
MPI_NULL_DELETE_FN	MPI::NULL_DELETE_FN
MPI_Delete_function / DELETE_FUNCTION	MPI::Delete_function

 Predefined Attribute Keys

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_APPNUM	MPI::APPNUM
MPI_LASTUSEDCODE	MPI::LASTUSEDCODE
MPI_UNIVERSE_SIZE	MPI::UNIVERSE_SIZE
MPI_WIN_BASE	MPI::WIN_BASE
MPI_WIN_DISP_UNIT	MPI::WIN_DISP_UNIT
MPI_WIN_SIZE	MPI::WIN_SIZE

**Mode Constants** 

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_MODE_APPEND	MPI::MODE_APPEND
MPI_MODE_CREATE	MPI::MODE_CREATE
MPI_MODE_DELETE_ON_CLOSE	MPI::MODE_DELETE_ON_CLOSE
MPI_MODE_EXCL	MPI::MODE_EXCL
MPI_MODE_NOCHECK	MPI::MODE_NOCHECK
MPI_MODE_NOPRECEDE	MPI::MODE_NOPRECEDE
MPI_MODE_NOPUT	MPI::MODE_NOPUT
MPI_MODE_NOSTORE	MPI::MODE_NOSTORE
MPI_MODE_NOSUCCEED	MPI::MODE_NOSUCCEED
MPI_MODE_RDONLY	MPI::MODE_RDONLY
MPI_MODE_RDWR	MPI::MODE_RDWR
MPI_MODE_SEQUENTIAL	MPI::MODE_SEQUENTIAL
MPI_MODE_UNIQUE_OPEN	MPI::MODE_UNIQUE_OPEN
MPI_MODE_WRONLY	MPI::MODE_WRONLY

Datatype	Decoding	Constants
----------	----------	-----------

v 1	<u> </u>
C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_COMBINER_CONTIGUOUS	MPI::COMBINER_CONTIGUOUS
MPI_COMBINER_DARRAY	MPI::COMBINER_DARRAY
MPI_COMBINER_DUP	MPI::COMBINER_DUP
MPI_COMBINER_F90_COMPLEX	MPI::COMBINER_F90_COMPLEX
MPI_COMBINER_F90_INTEGER	MPI::COMBINER_F90_INTEGER
MPI_COMBINER_F90_REAL	MPI::COMBINER_F90_REAL
MPI_COMBINER_HINDEXED_INTEGER	MPI::COMBINER_HINDEXED_INTEGER
MPI_COMBINER_HINDEXED	MPI::COMBINER_HINDEXED
MPI_COMBINER_HVECTOR_INTEGER	MPI::COMBINER_HVECTOR_INTEGER
MPI_COMBINER_HVECTOR	MPI::COMBINER_HVECTOR
MPI_COMBINER_INDEXED_BLOCK	MPI::COMBINER_INDEXED_BLOCK
MPI_COMBINER_INDEXED	MPI::COMBINER_INDEXED
MPI_COMBINER_NAMED	MPI::COMBINER_NAMED
MPI_COMBINER_RESIZED	MPI::COMBINER_RESIZED
MPI_COMBINER_STRUCT_INTEGER	MPI::COMBINER_STRUCT_INTEGER
MPI_COMBINER_STRUCT	MPI::COMBINER_STRUCT
MPI_COMBINER_SUBARRAY	MPI::COMBINER_SUBARRAY
MPI_COMBINER_VECTOR	MPI::COMBINER_VECTOR

#### **Threads Constants**

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_THREAD_FUNNELED	MPI::THREAD_FUNNELED
MPI_THREAD_MULTIPLE	MPI::THREAD_MULTIPLE
MPI_THREAD_SERIALIZED	MPI::THREAD_SERIALIZED
MPI_THREAD_SINGLE	MPI::THREAD_SINGLE

## File Operation Constants, Part 1

C type: const MPI_Offset (or unnamed enum)	C++ type:
Fortran type: INTEGER (KIND=MPI_OFFSET_KIND)	<pre>const MPI::Offset (or unnamed enum)</pre>
MPI_DISPLACEMENT_CURRENT	MPI::DISPLACEMENT_CURRENT

File Operation	Constants,	Part	<b>2</b>
----------------	------------	------	----------

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_DISTRIBUTE_BLOCK	MPI::DISTRIBUTE_BLOCK
MPI_DISTRIBUTE_CYCLIC	MPI::DISTRIBUTE_CYCLIC
MPI_DISTRIBUTE_DFLT_DARG	MPI::DISTRIBUTE_DFLT_DARG
MPI_DISTRIBUTE_NONE	MPI::DISTRIBUTE_NONE
MPI_ORDER_C	MPI::ORDER_C
MPI_ORDER_FORTRAN	MPI::ORDER_FORTRAN
MPI_SEEK_CUR	MPI::SEEK_CUR
MPI_SEEK_END	MPI::SEEK_END
MPI_SEEK_SET	MPI::SEEK_SET

# F90 Datatype Matching Constants

v <b>-</b>	9
C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_TYPECLASS_COMPLEX	MPI::TYPECLASS_COMPLEX
MPI_TYPECLASS_INTEGER	MPI::TYPECLASS_INTEGER
MPI_TYPECLASS_REAL	MPI::TYPECLASS_REAL

#### Constants Specifying Empty or Ignored Input

C/Fortran name	C++ name
C type / Fortran type	C++ type
MPI_ARGVS_NULL	MPI::ARGVS_NULL
char*** / 2-dim. array of CHARACTER*(*)	<pre>const char ***</pre>
MPI_ARGV_NULL	MPI::ARGV_NULL
<pre>char** / array of CHARACTER*(*)</pre>	<pre>const char **</pre>
MPI_ERRCODES_IGNORE	Not defined for C++
int* / INTEGER array	
MPI_STATUSES_IGNORE	Not defined for C++
<pre>MPI_Status* / INTEGER, DIMENSION(MPI_STATUS_SIZE,*)</pre>	
MPI_STATUS_IGNORE	Not defined for C++
<pre>MPI_Status* / INTEGER, DIMENSION(MPI_STATUS_SIZE)</pre>	
MPI_UNWEIGHTED	Not defined for C++

# C Constants Specifying Ignored Input (no C++ or Fortran)

C type: MPI_Fint*	
MPI_F_STATUSES_IGNORE	
MPI_F_STATUS_IGNORE	

#### C and C++ preprocessor Constants and Fortran Parameters

C/C++ type: const int (or unnamed enum)
Fortran type: INTEGER
MPI_SUBVERSION
MPI_VERSION

```
2.1.2 Types
                                                                                                  2
The following are defined C type definitions, included in the file mpi.h.
/* C opaque types */
MPI_Aint
\mathsf{MPI}\mathsf{\_Fint}
MPI_Offset
MPI_Status
/* C handles to assorted structures */
MPI_Comm
                                                                                                  11
MPI_Datatype
                                                                                                  12
                                                                                                  13
MPI_Errhandler
MPI_File
                                                                                                  14
MPI_Group
                                                                                                  15
                                                                                                  16
MPI_Info
MPI_Op
                                                                                                  18
MPI_Request
MPI_Win
                                                                                                  19
                                                                                                 20
// C++ opaque types (all within the MPI namespace)
                                                                                                 21
MPI::Aint
                                                                                                 22
MPI::Offset
                                                                                                 23
MPI::Status
                                                                                                  24
                                                                                                  25
                                                                                                  26
// C++ handles to assorted structures (classes,
// all within the MPI namespace)
                                                                                                 27
MPI::Comm
                                                                                                 28
MPI::Intracomm
                                                                                                 29
                                                                                                  30
MPI::Graphcomm
                                                                                                  31
MPI::Distgraphcomm
MPI::Cartcomm
                                                                                                  33
MPI::Intercomm
                                                                                                 34
MPI::Datatype
MPI::Errhandler
                                                                                                 35
MPI::Exception
                                                                                                 36
MPI::File
                                                                                                 37
MPI::Group
                                                                                                  38
MPI::Info
                                                                                                  39
MPI::Op
                                                                                                  41
MPI::Request
                                                                                                  42
MPI::Prequest
                                                                                                  43
MPI::Grequest
MPI::Win
                                                                                                  44
                                                                                                  45
                                                                                                  46
```

ticket0.

```
1
     2.1.3 Prototype [d] Definitions
2
     The following are defined C typedefs for user-defined functions, also included in the file
3
     mpi.h.
     /* prototypes for user-defined functions */
6
     typedef void MPI_User_function(void *invec, void *inoutvec, int *len,
                    MPI_Datatype *datatype);
9
     typedef int MPI_Comm_copy_attr_function(MPI_Comm oldcomm,
10
                    int comm_keyval, void *extra_state, void *attribute_val_in,
11
                    void *attribute_val_out, int*flag);
12
     typedef int MPI_Comm_delete_attr_function(MPI_Comm comm,
13
                    int comm_keyval, void *attribute_val, void *extra_state);
14
15
     typedef int MPI_Win_copy_attr_function(MPI_Win oldwin, int win_keyval,
16
                    void *extra_state, void *attribute_val_in,
17
                    void *attribute_val_out, int *flag);
18
     typedef int MPI_Win_delete_attr_function(MPI_Win win, int win_keyval,
19
                    void *attribute_val, void *extra_state);
20
21
     typedef int MPI_Type_copy_attr_function(MPI_Datatype oldtype,
22
                    int type_keyval, void *extra_state,
23
                    void *attribute_val_in, void *attribute_val_out, int *flag);
24
     typedef int MPI_Type_delete_attr_function(MPI_Datatype type,
25
                    int type_keyval, void *attribute_val, void *extra_state);
26
27
     typedef void MPI_Comm_errhandler_function(MPI_Comm *, int *, ...);
28
     typedef void MPI_Win_errhandler_function(MPI_Win *, int *, ...);
29
     typedef void MPI_File_errhandler_function(MPI_File *, int *, ...);
30
31
     typedef int MPI_Grequest_query_function(void *extra_state,
32
                  MPI_Status *status);
33
     typedef int MPI_Grequest_free_function(void *extra_state);
34
     typedef int MPI_Grequest_cancel_function(void *extra_state, int complete);
35
36
     typedef int MPI_Datarep_extent_function(MPI_Datatype datatype,
37
                 MPI_Aint *file_extent, void *extra_state);
38
     typedef int MPI_Datarep_conversion_function(void *userbuf,
39
                  MPI_Datatype datatype, int count, void *filebuf,
                 MPI_Offset position, void *extra_state);
41
42
         For Fortran, here are examples of how each of the user-defined subroutines should be
43
     declared.
44
         The user-function argument to MPI_OP_CREATE should be declared like this:
45
^{46}
     SUBROUTINE USER_FUNCTION(INVEC, INOUTVEC, LEN, TYPE)
47
        <type> INVEC(LEN), INOUTVEC(LEN)
        INTEGER LEN, TYPE
```

The copy and delete function arguments to MPI_COMM_CREATE_KEYVAL should be declared like these:
SUBROUTINE COMM_COPY_ATTR_FN(OLDCOMM, COMM_KEYVAL, EXTRA_STATE,
SUBROUTINE COMM_DELETE_ATTR_FN(COMM, COMM_KEYVAL, ATTRIBUTE_VAL,  EXTRA_STATE, IERROR)  INTEGER COMM, COMM_KEYVAL, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
The copy and delete function arguments to $MPI\_WIN\_CREATE\_KEYVAL$ should be declared like these:
SUBROUTINE WIN_COPY_ATTR_FN(OLDWIN, WIN_KEYVAL, EXTRA_STATE,  ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)  INTEGER OLDWIN, WIN_KEYVAL, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,  ATTRIBUTE_VAL_OUT  LOGICAL FLAG
SUBROUTINE WIN_DELETE_ATTR_FN(WIN, WIN_KEYVAL, ATTRIBUTE_VAL,  EXTRA_STATE, IERROR)  INTEGER WIN, WIN_KEYVAL, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
The copy and delete function arguments to MPI_TYPE_CREATE_KEYVAL should be declared like these:
SUBROUTINE TYPE_COPY_ATTR_FN(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE,  ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)  INTEGER OLDTYPE, TYPE_KEYVAL, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE,  ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT  LOGICAL FLAG
SUBROUTINE TYPE_DELETE_ATTR_FN(TYPE, TYPE_KEYVAL, ATTRIBUTE_VAL,  EXTRA_STATE, IERROR)  INTEGER TYPE, TYPE_KEYVAL, IERROR  INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
The handler-function argument to MPI_COMM_CREATE_ERRHANDLER should be declared like this:
SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE) INTEGER COMM, ERROR_CODE

```
1
         The handler-function argument to MPI_WIN_CREATE_ERRHANDLER should be de-
2
     clared like this:
4
     SUBROUTINE WIN_ERRHANDLER_FUNCTION(WIN, ERROR_CODE)
        INTEGER WIN, ERROR_CODE
5
6
         The handler-function argument to MPI_FILE_CREATE_ERRHANDLER should be de-
     clared like this:
9
     SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
10
        INTEGER FILE, ERROR_CODE
11
12
         The query, free, and cancel function arguments to MPI_GREQUEST_START should be
13
     declared like these:
14
15
     SUBROUTINE GREQUEST_QUERY_FUNCTION(EXTRA_STATE, STATUS, IERROR)
16
        INTEGER STATUS(MPI_STATUS_SIZE), IERROR
17
        INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
18
19
     SUBROUTINE GREQUEST_FREE_FUNCTION(EXTRA_STATE, IERROR)
20
        INTEGER IERROR
21
        INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
22
23
     SUBROUTINE GREQUEST_CANCEL_FUNCTION(EXTRA_STATE, COMPLETE, IERROR)
24
        INTEGER IERROR
25
        INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
        LOGICAL COMPLETE
27
28
         The extend and conversion function arguments to MPI_REGISTER_DATAREP should
29
     be declared like these:
30
31
     SUBROUTINE DATAREP_EXTENT_FUNCTION(DATATYPE, EXTENT, EXTRA_STATE, IERROR)
32
         INTEGER DATATYPE, IERROR
33
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT, EXTRA_STATE
34
35
     SUBROUTINE DATAREP_CONVERSION_FUNCTION(USERBUF, DATATYPE, COUNT, FILEBUF,
36
                   POSITION, EXTRA_STATE, IERROR)
37
         <TYPE> USERBUF(*), FILEBUF(*)
38
         INTEGER COUNT, DATATYPE, IERROR
         INTEGER(KIND=MPI_OFFSET_KIND) POSITION
         INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
41
42
         The following are defined C++ typedefs, also included in the file mpi.h.
43
     namespace MPI {
44
45
       typedef void User_function(const void* invec, void *inoutvec,
46
                    int len, const Datatype& datatype);
47
       typedef int Comm::Copy_attr_function(const Comm& oldcomm,
```

}

clared like these:

```
int comm_keyval, void* extra_state, void* attribute_val_in,
              void* attribute_val_out, bool& flag);
 typedef int Comm::Delete_attr_function(Comm& comm, int
              comm_keyval, void* attribute_val, void* extra_state);
 typedef int Win::Copy_attr_function(const Win& oldwin,
              int win_keyval, void* extra_state, void* attribute_val_in,
              void* attribute_val_out, bool& flag);
 typedef int Win::Delete_attr_function(Win& win, int
              win_keyval, void* attribute_val, void* extra_state);
                                                                                   11
 typedef int Datatype::Copy_attr_function(const Datatype& oldtype,
                                                                                   12
                                                                                   13
              int type_keyval, void* extra_state,
                                                                                   14
              const void* attribute_val_in, void* attribute_val_out,
                                                                                   15
              bool& flag);
                                                                                   16
 typedef int Datatype::Delete_attr_function(Datatype& type,
              int type_keyval, void* attribute_val, void* extra_state);
                                                                                   18
                                                                                   19
 typedef void Comm::Errhandler_function(Comm &, int *, ...);
  typedef void Win::Errhandler_function(Win &, int *, ...);
                                                                                   20
                                                                                   21
  typedef void File::Errhandler_function(File &, int *, ...);
                                                                                   22
                                                                                   23
 typedef int Grequest::Query_function(void* extra_state, Status& status);
                                                                                   24
 typedef int Grequest::Free_function(void* extra_state);
 typedef int Grequest::Cancel_function(void* extra_state, bool complete);
                                                                                   26
 typedef void Datarep_extent_function(const Datatype& datatype,
                                                                                   27
                                                                                   28
               Aint& file_extent, void* extra_state);
                                                                                   29
 typedef void Datarep_conversion_function(void* userbuf,
                                                                                   30
               Datatype& datatype, int count, void* filebuf,
                                                                                   31
               Offset position, void* extra_state);
                                                                                   32
                                                                                   ^{34} ticket0.
      Deprecated [p]Prototype [d]Definitions
                                                                                   ^{35} ticket0.
The following are defined C typedefs for deprecated user-defined functions, also included in
the file mpi.h.
                                                                                   37
                                                                                   38
/* prototypes for user-defined functions */
typedef int MPI_Copy_function(MPI_Comm oldcomm, int keyval,
              void *extra_state, void *attribute_val_in,
              void *attribute_val_out, int *flag);
                                                                                   42
typedef int MPI_Delete_function(MPI_Comm comm, int keyval,
                                                                                   43
              void *attribute_val, void *extra_state);
                                                                                   44
typedef void MPI_Handler_function(MPI_Comm *, int *, ...);
                                                                                   45
                                                                                   46
    The following are deprecated Fortran user-defined callback subroutine prototypes. The
                                                                                   47
deprecated copy and delete function arguments to MPI_KEYVAL_CREATE should be de-
```

```
1
     SUBROUTINE COPY_FUNCTION(OLDCOMM, KEYVAL, EXTRA_STATE,
2
                       ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERR)
3
         INTEGER OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
4
                ATTRIBUTE_VAL_OUT, IERR
5
         LOGICAL FLAG
6
     SUBROUTINE DELETE_FUNCTION(COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR)
7
          INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR
8
9
          The deprecated handler-function for error handlers should be declared like this:
10
11
     SUBROUTINE HANDLER_FUNCTION(COMM, ERROR_CODE)
12
         INTEGER COMM, ERROR_CODE
13
14
     2.1.5 Info Keys
15
16
     access_style
17
     appnum
18
     arch
19
     cb_block_size
20
     cb_buffer_size
21
     cb_nodes
22
     chunked_item
23
     chunked_size
^{24}
     chunked
25
     collective_buffering
     file_perm
27
     filename
28
     file
29
     host
30
     io_node_list
31
     ip_address
32
     ip_port
     nb_proc
34
     no_locks
35
     num_io_nodes
36
     path
37
38
     striping_factor
39
     striping_unit
40
     wdir
41
42
43
            Info Values
     2.1.6
44
45
     false
^{46}
     random
47
     read_mostly
      read_once
```

$reverse\_sequential$
sequential
true
write_mostly
write_once

# **Bibliography**

[1] Martin Schulz and Bronis R. de Supinski.  $P^N$ MPI Tools: A Whole Lot Greater Than the Sum of Their Parts. In ACM/IEEE Supercomputing Conference (SC), pages 1–10. ACM, 2007.

# Examples Index

This index lists code examples throughout the text. Some examples are referred to by content; others are listed by the major MPI function that they are demonstrating. MPI functions listed in all capital letter are Fortran examples; MPI functions listed in mixed case are C/C++ examples.

```
MPI_ALLOC_MEM, 6
MPI_Alloc_mem, 6
MPI_Barrier, 23, 24
MPI_Buffer_attach, 23
MPI_Cancel, 24
MPI_Finalize, 23–25
MPI_FREE_MEM, 6
MPI_Iprobe, 24
MPI_Request_free, 23
MPI_Test_cancelled, 24
mpiexec, 29
```

# MPI Constant and Predefined Handle Index

This index lists predefined MPI constants and handles.

10 11

12 13

14

15

16

17

18

19

20

21

22

23

24

26

27

28

30

31

34

35

36

37

39

41

42

43

44

```
MPI::ANY_SOURCE, 32
                                    MPI::COMM_NULL, 36
MPI::ANY_TAG, 32
                                    MPI::COMM_SELF, 35
MPI::APPNUM, 38
                                    MPI::COMM_WORLD, 35
MPI::ARGV_NULL, 40
                                    MPI::COMPLEX, 34
MPI::ARGVS_NULL, 40
                                    MPI::CONGRUENT, 35
                                    MPI::DATATYPE_NULL, 36
MPI::BAND, 36
MPI::BOOL, 34
                                    MPI::DISPLACEMENT_CURRENT, 39
MPI::BOR, 36
                                    MPI::DIST_GRAPH, 37
MPI::BOTTOM, 31
                                    MPI::DISTRIBUTE_BLOCK, 40
                                    MPI::DISTRIBUTE_CYCLIC, 40
MPI::BSEND_OVERHEAD, 32
MPI::BXOR, 36
                                    MPI::DISTRIBUTE_DFLT_DARG, 40
MPI::BYTE, 33, 34
                                    MPI::DISTRIBUTE_NONE, 40
MPI::CART, 37
                                    MPI::DOUBLE, 33
                                    MPI::DOUBLE_COMPLEX, 34
MPI::CHAR, 33
MPI::CHARACTER, 34
                                    MPI::DOUBLE_INT, 35
MPI::COMBINER_CONTIGUOUS, 39
                                    MPI::DOUBLE_PRECISION, 34
MPI::COMBINER_DARRAY, 39
                                    MPI::DUP_FN, 38
MPI::COMBINER_DUP, 39
                                    MPI::ERR_ACCESS, 31
MPI::COMBINER_F90_COMPLEX, 39
                                    MPI::ERR_AMODE, 31
MPI::COMBINER_F90_INTEGER, 39
                                    MPI::ERR_ARG, 30
MPI::COMBINER_F90_REAL, 39
                                    MPI::ERR_ASSERT, 31
MPI::COMBINER_HINDEXED, 39
                                    MPI::ERR_BAD_FILE, 31
MPI::COMBINER_HINDEXED_INTEGER,
                                    MPI::ERR_BASE, 31
                                    MPI::ERR_BUFFER, 30
MPI::COMBINER_HVECTOR, 39
                                    MPI::ERR_COMM, 30
MPI::COMBINER_HVECTOR_INTEGER,
                                    MPI::ERR_CONVERSION, 31
                                    MPI::ERR_COUNT, 30
MPI::COMBINER_INDEXED, 39
                                    MPI::ERR_DIMS, 30
MPI::COMBINER_INDEXED_BLOCK, 39
                                    MPI::ERR_DISP, 31
MPI::COMBINER_NAMED, 39
                                    MPI::ERR_DUP_DATAREP, 31
MPI::COMBINER_RESIZED, 39
                                    MPI::ERR_FILE, 31
MPI::COMBINER_STRUCT, 39
                                    MPI::ERR_FILE_EXISTS, 31
MPI::COMBINER_STRUCT_INTEGER, 39
                                    MPI::ERR_FILE_IN_USE, 31
MPI::COMBINER_SUBARRAY, 39
                                    MPI::ERR_GROUP, 30
MPI::COMBINER_VECTOR, 39
                                    MPI::ERR_IN_STATUS, 31
```

```
MPI::ERR_INFO, 31
                                     MPI::GROUP_EMPTY, 36
MPI::ERR_INFO_KEY, 31
                                     MPI::GROUP_NULL, 36
MPI::ERR_INFO_NOKEY, 31
                                     MPI::HOST, 35
MPI::ERR_INFO_VALUE, 31
                                     MPI::IDENT, 35
MPI::ERR_INTERN, 30
                                     MPI::IN_PLACE, 31
MPI::ERR_IO, 31
                                     MPI::INFO_NULL, 36
MPI::ERR_KEYVAL, 31
                                     MPI::INT, 33
MPI::ERR_LASTCODE, 31
                                     MPI::INTEGER, 34
MPI::ERR_LOCKTYPE, 31
                                     MPI::INTEGER1, 34
MPI::ERR_NAME, 31
                                     MPI::INTEGER2, 34
MPI::ERR_NO_MEM, 31
                                     MPI::INTEGER4, 34
MPI::ERR_NO_SPACE, 31
                                     MPI::INTEGER8, 34
                                                                          12
MPI::ERR_NO_SUCH_FILE, 31
                                     MPI::IO, 35
                                                                          13
MPI::ERR_NOT_SAME, 31
                                     MPI::KEYVAL_INVALID, 32
                                                                          14
                                                                          15
MPI::ERR_OP, 30
                                     MPI::LAND, 36
MPI::ERR_OTHER, 30
                                     MPI::LASTUSEDCODE, 38
MPI::ERR_PENDING, 30
                                     MPI::LB, 35
MPI::ERR_PORT, 31
                                     MPI::LOCK_EXCLUSIVE, 32
MPI::ERR_QUOTA, 31
                                     MPI::LOCK_SHARED, 32
                                                                          19
MPI::ERR_RANK, 30
                                     MPI::LOGICAL, 34
                                                                          20
MPI::ERR_READ_ONLY, 31
                                     MPI::LONG, 33
                                                                          21
MPI::ERR_REQUEST, 30
                                     MPI::LONG_DOUBLE, 33
MPI::ERR_RMA_CONFLICT, 31
                                     MPI::LONG_DOUBLE_COMPLEX, 34
                                                                          24
MPI::ERR_RMA_SYNC, 31
                                     MPI::LONG_DOUBLE_INT, 35
MPI::ERR_ROOT, 30
                                     MPI::LONG_INT, 35
                                                                          26
MPI::ERR_SERVICE, 31
                                     MPI::LONG_LONG, 33
MPI::ERR_SIZE, 31
                                     MPI::LONG_LONG_INT, 33
                                                                          27
MPI::ERR_SPAWN, 31
                                     MPI::LOR, 36
                                                                          28
MPI::ERR_TAG, 30
                                     MPI::LXOR, 36
MPI::ERR_TOPOLOGY, 30
                                     MPI::MAX, 36
MPI::ERR_TRUNCATE, 30
                                     MPI::MAX_DATAREP_STRING, 32
MPI::ERR_TYPE, 30
                                     MPI::MAX_ERROR_STRING, 32
                                                                          33
MPI::ERR_UNKNOWN, 30
                                     MPI::MAX_INFO_KEY, 32
                                                                          34
MPI::ERR_UNSUPPORTED_DATAREP, 31
                                     MPI::MAX_INFO_VAL, 32
MPI::ERR_UNSUPPORTED_OPERATION,
                                     MPI::MAX_OBJECT_NAME, 32
                                                                          35
                                     MPI::MAX_PORT_NAME, 32
      31
                                     MPI::MAX_PROCESSOR_NAME, 32
                                                                          37
MPI::ERR_WIN, 31
MPI::ERRHANDLER_NULL, 36
                                     MPI::MAXLOC, 36
MPI::ERRORS_ARE_FATAL, 32
                                     MPI::MIN, 36
MPI::ERRORS_RETURN, 32
                                     MPI::MINLOC, 36
MPI::ERRORS_THROW_EXCEPTIONS, 8,
                                     MPI::MODE_APPEND, 38
                                                                          42
                                     MPI::MODE_CREATE, 38
      32
MPI::F_COMPLEX, 34
                                     MPI::MODE_DELETE_ON_CLOSE, 38
                                                                          43
                                     MPI::MODE_EXCL, 38
MPI::F_DOUBLE_COMPLEX, 34
                                                                          44
MPI::FILE_NULL, 36
                                     MPI::MODE_NOCHECK, 38
                                                                          45
MPI::FLOAT, 33
                                     MPI::MODE_NOPRECEDE, 38
                                     MPI::MODE_NOPUT, 38
MPI::FLOAT_INT, 35
MPI::GRAPH, 37
                                     MPI::MODE_NOSTORE, 38
```

```
MPI::MODE_NOSUCCEED, 38
                                         MPI::UNSIGNED_LONG, 33
    MPI::MODE_RDONLY, 38
                                         MPI::UNSIGNED_LONG_LONG, 33
3
    MPI::MODE_RDWR, 38
                                         MPI::UNSIGNED_SHORT, 33
4
    MPI::MODE_SEQUENTIAL, 38
                                         MPI::WCHAR, 33
5
    MPI::MODE_UNIQUE_OPEN, 38
                                          MPI::WIN_BASE, 38
6
    MPI::MODE_WRONLY, 38
                                         MPI::WIN_DISP_UNIT, 38
7
    MPI::NULL_COPY_FN, 38
                                          MPI::WIN_NULL, 36
    MPI::NULL_DELETE_FN, 38
                                         MPI::WIN_SIZE, 38
    MPI::OP_NULL, 36
                                         MPI::WTIME_IS_GLOBAL, 35
10
    MPI::ORDER_C, 40
                                         MPI_2DOUBLE_PRECISION, 35
11
    MPI::ORDER_FORTRAN, 40
                                          MPI_2INT, 35
12
    MPI::PACKED, 33, 34
                                          MPI_2INTEGER, 35
13
    MPI::PROC_NULL, 32
                                         MPI_2REAL, 35
14
                                         MPI_ADDRESS_KIND, 32
    MPI::PROD, 36
15
    MPI::REAL, 34
                                         MPI_AINT, 33, 34
    MPI::REAL2, 34
                                         MPI_ANY_SOURCE, 3, 32
17
    MPI::REAL4, 34
                                         MPI_ANY_TAG, 32
18
    MPI::REAL8, 34
                                         MPI_APPNUM, 38
19
    MPI::REPLACE, 36
                                         MPI_ARGV_NULL, 40
20
    MPI::REQUEST_NULL, 36
                                         MPI_ARGVS_NULL, 40
^{21}
    MPI::ROOT, 32
                                         MPI_BAND, 36
^{22}
    MPI::SEEK_CUR, 40
                                         MPI_BOR, 36
    MPI::SEEK_END, 40
                                         MPI_BOTTOM, 31
    MPI::SEEK_SET, 40
                                         MPI_BSEND_OVERHEAD, 5, 32
    MPI::SHORT, 33
                                         MPI_BXOR, 36
26
    MPI::SHORT_INT, 35
                                          MPI_BYTE, 33, 34
^{27}
    MPI::SIGNED_CHAR, 33
                                         MPI_C_BOOL, 33
^{28}
    MPI::SIMILAR, 35
                                         MPI_C_COMPLEX, 33
^{29}
    MPI::SUCCESS, 30
                                         MPI_C_DOUBLE_COMPLEX, 33
30
    MPI::SUM, 36
                                         MPI_C_FLOAT_COMPLEX, 33
    MPI::TAG_UB, 35
                                         MPI_C_LONG_DOUBLE_COMPLEX, 33
    MPI::THREAD_FUNNELED, 39
                                         MPI_CART, 37
33
    MPI::THREAD_MULTIPLE, 39
                                         MPI_CHAR, 33
34
                                         MPI_CHARACTER, 34
    MPI::THREAD_SERIALIZED, 39
35
    MPI::THREAD_SINGLE, 39
                                          MPI_COMBINER_CONTIGUOUS, 39
36
    MPI::TWODOUBLE_PRECISION, 35
                                          MPI_COMBINER_DARRAY, 39
37
    MPI::TWOINT, 35
                                          MPI_COMBINER_DUP, 39
    MPI::TWOINTEGER, 35
                                          MPI_COMBINER_F90_COMPLEX, 39
    MPI::TWOREAL, 35
                                         MPI_COMBINER_F90_INTEGER, 39
40
    MPI::TYPECLASS_COMPLEX, 40
                                          MPI_COMBINER_F90_REAL, 39
41
                                          MPI_COMBINER_HINDEXED, 39
    MPI::TYPECLASS_INTEGER, 40
42
    MPI::TYPECLASS_REAL, 40
                                          MPI_COMBINER_HINDEXED_INTEGER,
43
    MPI::UB, 35
44
    MPI::UNDEFINED, 32
                                          MPI_COMBINER_HVECTOR, 39
    MPI::UNEQUAL, 35
                                          MPI_COMBINER_HVECTOR_INTEGER,
    MPI::UNIVERSE_SIZE, 38
47
                                          MPI_COMBINER_INDEXED, 39
    MPI::UNSIGNED, 33
    MPI::UNSIGNED_CHAR, 33
                                         MPI_COMBINER_INDEXED_BLOCK, 39
```

```
MPI_COMBINER_NAMED, 39
                                     MPI_ERR_INFO_NOKEY, 15, 31
MPI_COMBINER_RESIZED, 39
                                     MPI_ERR_INFO_VALUE, 15, 31
MPI_COMBINER_STRUCT, 39
                                     MPI_ERR_INTERN, 15, 30
MPI_COMBINER_STRUCT_INTEGER, 39
                                     MPI_ERR_IO, 16, 31
MPI_COMBINER_SUBARRAY, 39
                                     MPI_ERR_KEYVAL, 15, 31
MPI_COMBINER_VECTOR, 39
                                     MPI_ERR_LASTCODE, 14, 16-18, 31
MPI_COMM_NULL, 36
                                     MPI_ERR_LOCKTYPE, 15, 31
MPI_COMM_SELF, 26, 27, 35
                                     MPI_ERR_NAME, 15, 31
MPI_COMM_WORLD, 2-4, 7, 9, 17, 24-
                                     MPI_ERR_NO_MEM, 5, 15, 31
      26, 28, 35
                                     MPI_ERR_NO_SPACE, 16, 31
MPI_COMPLEX, 34
                                     MPI_ERR_NO_SUCH_FILE, 16, 31
MPI_COMPLEX16, 34
                                     MPI_ERR_NOT_SAME, 16, 31
                                                                          12
MPI_COMPLEX32, 34
                                     MPI_ERR_OP, 15, 30
                                                                          13
                                                                          14
MPI_COMPLEX4, 34
                                     MPI_ERR_OTHER, 14, 15, 30
                                                                          15
MPI_COMPLEX8, 34
                                     MPI_ERR_PENDING, 15, 30
                                                                          16
MPI_CONGRUENT, 35
                                     MPI_ERR_PORT, 15, 31
                                                                          17
MPI_DATATYPE_NULL, 36
                                     MPI_ERR_QUOTA, 16, 31
                                                                          18
MPI_DISPLACEMENT_CURRENT, 39
                                     MPI_ERR_RANK, 15, 30
MPI_DIST_GRAPH, 37
                                     MPI_ERR_READ_ONLY, 16, 31
                                                                          19
MPI_DISTRIBUTE_BLOCK, 40
                                                                          20
                                     MPI_ERR_REQUEST, 15, 30
MPI_DISTRIBUTE_CYCLIC, 40
                                     MPI_ERR_RMA_CONFLICT, 15, 31
                                                                          21
MPI_DISTRIBUTE_DFLT_DARG, 40
                                     MPI_ERR_RMA_SYNC, 15, 31
MPI_DISTRIBUTE_NONE, 40
                                     MPI_ERR_ROOT, 15, 30
MPI_DOUBLE, 33
                                     MPI_ERR_SERVICE, 15, 31
MPI_DOUBLE_COMPLEX, 34
                                     MPI_ERR_SIZE, 15, 31
                                                                          26
MPI_DOUBLE_INT, 35
                                     MPI_ERR_SPAWN, 15, 31
MPI_DOUBLE_PRECISION, 34
                                     MPI_ERR_TAG, 15, 30
                                                                          27
MPI_DUP_FN, 38
                                     MPI_ERR_TOPOLOGY, 15, 30
                                                                          28
MPI_ERR_ACCESS, 16, 31
                                     MPI_ERR_TRUNCATE, 15, 30
MPI_ERR_AMODE, 16, 31
                                     MPI_ERR_TYPE, 15, 30
MPI_ERR_ARG, 15, 30
                                     MPI_ERR_UNKNOWN, 14, 15, 30
MPI_ERR_ASSERT, 15, 31
                                     MPI_ERR_UNSUPPORTED_DATAREP, 16,
MPI_ERR_BAD_FILE, 16, 31
                                           31
MPI_ERR_BASE, 6, 15, 31
                                     MPI_ERR_UNSUPPORTED_OPERATION,
MPI_ERR_BUFFER, 15, 30
                                           16, 31
MPI_ERR_COMM, 15, 30
                                     MPI_ERR_WIN, 15, 31
MPI_ERR_CONVERSION, 16, 31
                                                                          37
                                     MPI_ERRCODES_IGNORE, 40
MPI_ERR_COUNT, 15, 30
                                     MPI_ERRHANDLER_NULL, 13, 36
MPI_ERR_DIMS, 15, 30
                                     MPI_ERROR, 32
MPI_ERR_DISP, 15, 31
                                     MPI_ERROR_STRING, 14
                                     MPI_ERRORS_ARE_FATAL, 7, 8, 19, 32
MPI_ERR_DUP_DATAREP, 16, 31
                                                                          42
MPI_ERR_FILE, 16, 31
                                     MPI_ERRORS_RETURN, 7, 8, 20, 32
MPI_ERR_FILE_EXISTS, 16, 31
                                     MPI_F_STATUS_IGNORE, 40
                                                                          43
MPI_ERR_FILE_IN_USE, 16, 31
                                     MPI_F_STATUSES_IGNORE, 40
                                                                          44
MPI_ERR_GROUP, 15, 30
                                     MPI_FILE_NULL, 36
                                                                          45
MPI_ERR_IN_STATUS, 9, 15, 31
                                     MPI_FLOAT, 33
MPI_ERR_INFO, 15, 31
                                     MPI_FLOAT_INT, 35
MPI_ERR_INFO_KEY, 15, 31
                                     MPI_GRAPH, 37
```

```
MPI_GROUP_EMPTY, 36
                                          MPI_MODE_CREATE, 38
    MPI_GROUP_NULL, 36
                                          MPI_MODE_DELETE_ON_CLOSE, 38
3
    MPI_HOST, 2, 3, 35
                                          MPI_MODE_EXCL, 38
4
    MPI_IDENT, 35
                                          MPI_MODE_NOCHECK, 38
5
    MPI_IN_PLACE, 31
                                          MPI_MODE_NOPRECEDE, 38
6
    MPI_INFO_NULL, 36
                                          MPI_MODE_NOPUT, 38
7
                                          MPI_MODE_NOSTORE, 38
    MPI_INT, 33
    MPI_INT16_T, 33
                                          MPI_MODE_NOSUCCEED, 38
    MPI_INT32_T, 33
                                          MPI_MODE_RDONLY, 38
10
    MPI_INT64_T, 33
                                          MPI_MODE_RDWR, 38
11
    MPI_INT8_T, 33
                                          MPI_MODE_SEQUENTIAL, 38
12
    MPI_INTEGER, 34
                                          MPI_MODE_UNIQUE_OPEN, 38
13
    MPI_INTEGER1, 34
                                          MPI_MODE_WRONLY, 38
14
                                          MPI_NULL_COPY_FN, 38
    MPI_INTEGER16, 34
15
    MPI_INTEGER2, 34
                                          MPI_NULL_DELETE_FN, 38
    MPI_INTEGER4, 34
                                          MPI_OFFSET, 33, 34
17
    MPI_INTEGER8, 34
                                          MPI_OFFSET_KIND, 32
18
    MPI_INTEGER_KIND, 32
                                          MPI_OP_NULL, 36
19
    MPI_IO, 3, 35
                                          MPI_ORDER_C, 40
                                          MPI_ORDER_FORTRAN, 40
20
    MPI_KEYVAL_INVALID, 32
^{21}
    MPI_LAND, 36
                                          MPI_PACKED, 33, 34
^{22}
    MPI_LASTUSEDCODE, 17, 38
                                          MPI_PROC_NULL, 2, 3, 32
^{23}
    MPI_LB, 35
                                          MPI_PROD, 36
^{24}
    MPI_LOCK_EXCLUSIVE, 32
                                          MPI_REAL, 34
    MPI_LOCK_SHARED, 32
                                          MPI_REAL16, 34
26
    MPI_LOGICAL, 34
                                          MPI_REAL2, 34
^{27}
    MPI_LONG, 33
                                          MPI_REAL4, 34
^{28}
    MPI_LONG_DOUBLE, 33
                                          MPI_REAL8, 34
^{29}
    MPI_LONG_DOUBLE_INT, 35
                                          MPI_REPLACE, 36
30
    MPI_LONG_INT, 35
                                          MPI_REQUEST_NULL, 36
31
    MPI_LONG_LONG, 33
                                          MPI_ROOT, 32
    MPI_LONG_LONG_INT, 33
                                          MPI_SEEK_CUR, 40
33
    MPI_LOR, 36
                                          MPI_SEEK_END, 40
34
    MPI_LXOR, 36
                                          MPI_SEEK_SET, 40
35
    MPI_MAX, 36
                                          MPI_SHORT, 33
36
    MPI_MAX_DATAREP_STRING, 32
                                          MPI_SHORT_INT, 35
37
    MPI_MAX_ERROR_STRING, 13, 18, 32
                                          MPI_SIGNED_CHAR, 33
38
    MPI_MAX_INFO_KEY, 15, 32
                                          MPI_SIMILAR, 35
    MPI_MAX_INFO_VAL, 15, 32
                                          MPI_SOURCE, 32
40
    MPI_MAX_LIBRARY_VERSION_STRING,
                                          MPI_STATUS_IGNORE, 40
41
                                          MPI_STATUS_SIZE, 32
42
    MPI_MAX_OBJECT_NAME, 32
                                          MPI_STATUSES_IGNORE, 40
43
    MPI_MAX_PORT_NAME, 32
                                          MPI_SUBVERSION, 2, 40
44
    MPI_MAX_PROCESSOR_NAME, 4, 32
                                          MPI_SUCCESS, 14, 15, 19, 20, 30
45
    MPI_MAXLOC, 36
                                          MPI_SUM, 36
    MPI_MIN, 36
                                          MPI_TAG, 32
47
                                          MPI_TAG_UB, 2, 3, 35
    MPI_MINLOC, 36
    MPI_MODE_APPEND, 38
                                          MPI_THREAD_FUNNELED, 39
```

MPI_THREAD_MULTIPLE, 39
MPI_THREAD_SERIALIZED, 39
MPI_THREAD_SINGLE, 39
MPI_TYPECLASS_COMPLEX, 40
MPI_TYPECLASS_INTEGER, 40
MPI_TYPECLASS_REAL, 40
MPI_UB, 35
MPI_UINT16_T, 33
MPI_UINT32_T, 33
$MPI\_UINT64\_T, 33$
MPI_UINT8_T, 33
MPI_UNDEFINED, 32
MPI_UNEQUAL, 35
MPI_UNIVERSE_SIZE, 38
MPI_UNSIGNED, 33
MPI_UNSIGNED_CHAR, 33
MPI_UNSIGNED_LONG, 33
MPI_UNSIGNED_LONG_LONG, 33
MPI_UNSIGNED_SHORT, 33
MPI_UNWEIGHTED, 40
MPI_VERSION, 2, 40
MPI_WCHAR, 33
MPI_WIN_BASE, 38
MPI_WIN_DISP_UNIT, 38
MPI_WIN_NULL, 36
MPI_WIN_SIZE, 38
MPI_WTIME_IS_GLOBAL, 3, 4, 21, 35

# **MPI Declarations Index**

This index refers to declarations needed in C/C++, such as address kind integers, handles, etc. The underlined page numbers is the "main" reference (sometimes there are more than one when key concepts are discussed in multiple areas).

```
13
      MPI::Aint, 41
14
      MPI::Cartcomm, 41
15
      MPI::Comm, 41
16
      MPI::Datatype, 41
17
      MPI::Distgraphcomm, 41
18
      MPI::Errhandler, 8, 9–13, 41
19
      MPI::Exception, 41
20
      MPI::File, 12, 13, 19, 41
21
      MPI::Graphcomm, 41
^{22}
      MPI::Grequest, 41
23
      MPI::Group, 41
^{24}
      MPI::Info, 5, 41
25
      MPI::Intercomm, 41
26
      MPI::Intracomm, 41
27
      MPI::Offset, 41
28
      MPI::Op, 41
^{29}
      MPI::Prequest, 41
30
      MPI::Request, 41
31
      MPI::Status, 41
32
      MPI::Win, 10, 11, 19, 41
33
      MPI_Aint, 41
34
      MPI_Comm, 35, 36, 41
35
      MPI_Datatype, 33–36, 41
36
      MPI_Errhandler, 8, 9–13, 32, 36, 41
37
      MPI_File, 12, 13, 19, 36, 41
38
      MPI_Fint, 40, 41
39
      MPI_Group, 36, 41
40
      MPI_Info, 5, 36, 41
41
      MPI_Offset, 41
42
      MPI_Op, 36, 41
43
      MPI_Request, 36, 41
44
      MPI_Status, 40, 41
45
      MPI_Win, 10, 11, 19, 36, 41
^{46}
```

1 2 3

10

11

12

# MPI Callback Function Prototype Index

This index lists the C typedef names for callback routines, such as those used with attribute caching or user-defined reduction operations. C++ names for these typedefs and Fortran example prototypes are given near the text of the C name.

```
MPI_Comm_copy_attr_function, 37, 42
MPI_Comm_delete_attr_function, 37, 42
MPI_Comm_errhandler_function, 9, 42
MPI_Copy_function, 38, 45
MPI_Datarep_conversion_function, 42
MPI_Datarep_extent_function, 42
MPI_Delete_function, 38, 45
MPI_File_errhandler_function, 12, 42
MPI_Grequest_cancel_function, 42
MPI_Grequest_free_function, 42
MPI_Grequest_query_function, 42
MPI_Handler_function, 45
MPI_Type_copy_attr_function, 37, 42
MPI_Type_delete_attr_function, 37, 42
MPI_User_function, 42
MPI_Win_copy_attr_function, 37, 42
MPI_Win_delete_attr_function, 37, 42
MPI_Win_errhandler_function, 10, 42
```

12

13

14 15

16

18

19

20

21

22

23

26

27

28

29

30

# MPI Function Index

2

6 7 8

10 11

12

13

14

15

16

17

18

19

20

21

 $^{22}$ 

 $^{23}$ 

 $^{24}$ 

26

 $^{27}$ 

28

 $^{29}$ 

30

31

33

34

35

36

37

38

40

41

42

43

44

45

47

The underlined page numbers refer to the function definitions.

```
MPI_ABORT, 7, 22, 26
                                    MPI_FINALIZED, 22, 24, 26, 27, 27
MPI_ADD_ERROR_CLASS, 17, 17
                                    MPI\_FREE\_MEM, 5, 6, 15
MPI_ADD_ERROR_CODE, 18
                                    MPI\_GET\_LIBRARY\_VERSION, 2, 2, 22,
MPI_ADD_ERROR_STRING, 18, 18
                                          24
MPI_ALLOC_MEM, 5, 5, 6, 15
                                    MPI_GET_PROCESSOR_NAME, 4, 4
MPI_BSEND, 5, 23
                                    MPI_GET_VERSION, <u>1</u>, 2, 22, 24
MPI_BUFFER_DETACH, 23
                                    MPI_GREQUEST_START, 44
MPI_COMM_CALL_ERRHANDLER, 19,
                                    MPI_GROUP_FREE, 8
                                    MPI_INFO_DELETE, 15
      20
                                    MPI_INIT, 2, 3, 21, 21, 22, 24, 25, 27
MPI_COMM_CONNECT, 15
                                    MPI_INIT_THREAD, 22, 27
MPI_COMM_CREATE_ERRHANDLER, 8,
                                    MPI_INITIALIZED, 22, 24, 25, 25, 27
      8, 10, 43
MPI_COMM_CREATE_KEYVAL, 43
                                    MPI_ISEND, 23
MPI_COMM_DUP_FN, 37
                                    MPI_KEYVAL_CREATE, 45
MPI_COMM_FREE, 26
                                    MPI_LOOKUP_NAME, 15
MPI_COMM_GET_ATTR, 2
                                    MPI_OP_CREATE, 42
MPI_COMM_GET_ERRHANDLER, 8, 10
                                    MPI_REGISTER_DATAREP, 16, 44
                                    MPI_REQUEST_FREE, 23
MPI_COMM_GROUP, 8
MPI_COMM_NULL_COPY_FN, 37
                                    MPI_TEST, 23
MPI_COMM_NULL_DELETE_FN, 37
                                    MPI_TYPE_CREATE_KEYVAL, 43
MPI_COMM_SET_ERRHANDLER, 8, 9
                                    MPI_TYPE_DUP_FN, 37
MPI_COMM_SPAWN, 28
                                    MPI_TYPE_NULL_COPY_FN, 37
MPI_COMM_SPAWN_MULTIPLE, 28
                                    MPI_TYPE_NULL_DELETE_FN, 37
MPI_ERRHANDLER_CREATE, 9
                                    MPI_UNPUBLISH_NAME, 15
MPI_ERRHANDLER_FREE, 8, 13
                                    MPI_WAIT, 23
MPI_ERRHANDLER_GET, 8, 10
                                    MPI_WIN_CALL_ERRHANDLER, 19, 20
MPI_ERRHANDLER_SET, 10
                                    MPI_WIN_CREATE_ERRHANDLER, 8, 10,
MPI_ERROR_CLASS, 14, 14, 16
                                          11, 44
MPI_ERROR_STRING, <u>13</u>, 14, 16, 18
                                    MPI_WIN_CREATE_KEYVAL, 43
MPI_FILE_CALL_ERRHANDLER, 19, 20
                                    MPI_WIN_DUP_FN, 37
MPI_FILE_CREATE_ERRHANDLER, 8, 12,
                                    MPI_WIN_GET_ERRHANDLER, 8, 11
      12, 44
                                    MPI_WIN_LOCK, 5
MPI_FILE_GET_ERRHANDLER, 8, 13
                                    MPI_WIN_NULL_COPY_FN, 37
MPI_FILE_OPEN, 16
                                    MPI_WIN_NULL_DELETE_FN, 37
MPI_FILE_SET_ERRHANDLER, 8, 12
                                    MPI_WIN_SET_ERRHANDLER, 8, 11
MPI_FILE_SET_VIEW, 16
                                    MPI_WIN_UNLOCK, 5
MPI_FINALIZE, 2, 3, 22, <u>22</u>, 23–27
                                    MPI_WTICK, 21, 21
```

MPI Function Index 59

MPI\_WTIME, 4, 20,  $\underline{20}$ , 21 mpiexec, 22, 26, 28,  $\underline{28}$  mpirun, 27, 28