MPI: A Message-Passing Interface Standard Version 3.0

(Draft, with MPI 3 Nonblocking Collectives

and new Fortran 2008 Interface)

Unofficial, for comment only

Message Passing Interface Forum

March 26, 2011

ticket 0.

 $ticket 229\hbox{-}A.$

ticket0. ¹

3 4 6

This document describes the Message-Passing Interface (MPI) standard, version [2.2]3.0. The MPI standard includes point-to-point message-passing, collective communications, group and communicator concepts, process topologies, environmental management, process creation and management, one-sided communications, extended collective operations, external interfaces, I/O, some miscellaneous topics, and a profiling interface. Language bindings for C, C++ and Fortran are defined.

ticket0.

9

10

11

12

13

14

17

18

Technically, this version of the standard is based on "MPI: A Message-Passing Interface Standard, version 2.1, June 23, 2008. The MPI Forum added seven new routines and a number of enhancements and clarifications to the standard.

Historically, the evolution of the standards is from MPI-1.0 (June 1994) to MPI-1.1 (June 12, 1995) to MPI-1.2 (July 18, 1997), with several clarifications and additions and published as part of the MPI-2 document, to MPI-2.0 (July 18, 1997), with new functionality, to MPI-1.3 (May 30, 2008), combining for historical reasons the documents 1.1 and 1.2 and some errata documents to one combined document, and to MPI-2.1 (June 23, 2008), combining the previous documents. [This version, MPI-2.2, is based on MPI-2.1 and provides additional clarifications and errata corrections as well as a few enhancements. Version MPI-2.2 (September 2009) added additional clarifications and seven new routines. This version, MPI-3.0, is an extension of MPI-2.2.

ticket0. 15 16

> 19 20

> > 22 23

> > > 24

21

25 26 27

28 29 30

36 37 38

35

41 42

43

46 47

48

39

44 ticket0. 45

©1993, 1994, 1995, 1996, 1997, 2008, 2009, 2010 University of Tennessee, Knoxville, Tennessee. Permission to copy without fee all or part of this material is granted, provided the University of Tennessee copyright notice and the title of this document appear, and notice is given that copying is by permission of the University of Tennessee.

			Problems Due to Strong Typing	544	
			Problems Due to Data Copying and Sequence Association	545	
			Special Constants	548	
			Fortran[90]Derived Types	548	ticket 237-I.
			A Problem with Register Optimization and Temporary Memory Mod-		ticket238-J.
			ifications	549	
		16.2.3		557	ticket230-B.
		16.2.4	[Extended]Fortran Support Through the mpi Module	558	ticket230-B.
			The mpi Module	558	ticket230-B.
			No Type Mismatch Problems for Subroutines with Choice Arguments		ticket 230-B.
		16.2.5	Fortran Support Through the mpi_f08 Module	560	ticket230-B.
			Additional Support for Fortran Register-Memory-Synchronization .	562	tichet200 B.
			Additional Support for Fortran Numeric Intrinsic Types	563	
		10.2.1	Parameterized Datatypes with Specified Precision and Exponent Range		
			Support for Size-specific MPI Datatypes	567	
			Communication With Size-specific Types	570	
	16.9	Langu	age Interoperability	570	
	10.5	_			
			Introduction	571	
			Assumptions	572	
			Initialization	572	
			Transfer of Handles	573	
			Status	576	
		16.3.6	MPI Opaque Objects	578	
			Datatypes	578	
			Callback Functions	580	
			Error Handlers	580	
			Reduce Operations	580	
			Addresses	580	
			Attributes	581	
		16.3.8	Extra State	585	
			Constants	585	
		16.3.10	OInterlanguage Communication	586	
	Towns on D's Paris Course				
A			Bindings Summary	589	
	A.1		d Values and Handles	589	
		A.1.1	Defined Constants	589	
		A.1.2	Types	601	
		A.1.3	Prototype [d] Definitions	602	ticket0.
		A.1.4	Deprecated [p]Prototype [d]Definitions	606	ticket0.
		A.1.5	Info Keys	606	ticket0.
		A.1.6	Info Values	607	
	A.2	C Bine	0	608	
		A.2.1	Point-to-Point Communication C Bindings	608	
		A.2.2	Datatypes C Bindings	609	
		A.2.3	Collective Communication C Bindings	611	
		A.2.4	Groups, Contexts, Communicators, and Caching C Bindings	614	
		A.2.5	Process Topologies C Bindings	616	
		A.2.6	MPI Environmental Management C Bindings	617	

Chapter 1

Introduction to MPI

1.1 Overview and Goals

MPI (Message-Passing Interface) is a message-passing library interface specification. All parts of this definition are significant. MPI addresses primarily the message-passing parallel programming model, in which data is moved from the address space of one process to that of another process through cooperative operations on each process. [(]Extensions to the "classical" message-passing model are provided in collective operations, remote-memory access operations, dynamic process creation, and parallel I/O.[)] MPI is a specification, not an implementation; there are multiple implementations of MPI. This specification is for a library interface; MPI is not a language, and all MPI operations are expressed as functions, subroutines, or methods, according to the appropriate language bindings, which for C, C++, [Fortran-77, and Fortran-95]and Fortran, are part of the MPI standard. The standard has been defined through an open process by a community of parallel computing vendors, computer scientists, and application developers. The next few sections provide an overview of the history of MPI's development.

The main advantages of establishing a message-passing standard are portability and ease of use. In a distributed memory communication environment in which the higher level routines and/or abstractions are built upon lower level message-passing routines the benefits of standardization are particularly apparent. Furthermore, the definition of a message-passing standard, such as that proposed here, provides vendors with a clearly defined base set of routines that they can implement efficiently, or in some cases [provide hardware support for for which they can provide hardware support, thereby enhancing scalability.

The goal of the Message-Passing Interface simply stated is to develop a widely used standard for writing message-passing programs. As such the interface should establish a practical, portable, efficient, and flexible standard for message passing.

A complete list of goals follows.

- Design an application programming interface (not necessarily for compilers or a system implementation library).
- Allow efficient communication: Avoid memory-to-memory copying, allow overlap of computation and communication, and offload to communication co-processor, where available.
- Allow for implementations that can be used in a heterogeneous environment.

ticket0.

11 12 13

15 16

17

24

27

28

29

31

36

37

38

39

42

43

45

46 47

ticket0.

 $^{\circ}$ ticket 230-B.

ticket0.

ticket230-B. ¹

6

4

5

9 10

11 12

> 13 14 15

16

20

17 18 19

26

27

36

37

38

39

40 41

42

43

44 45 46

47 48 • Allow convenient C, C++, [Fortran-77, and Fortran-95] and Fortran bindings for the interface.

- Assume a reliable communication interface: the user need not cope with communication failures. Such failures are dealt with by the underlying communication subsystem.
- Define an interface that can be implemented on many vendor's platforms, with no significant changes in the underlying communication and system software.
- Semantics of the interface should be language independent.
- The interface should be designed to allow for thread safety.

Background of MPI-1.0 1.2

MPI sought to make use of the most attractive features of a number of existing messagepassing systems, rather than selecting one of them and adopting it as the standard. Thus, MPI was strongly influenced by work at the IBM T. J. Watson Research Center [1, 2], Intel's NX/2 [44], Express [12], nCUBE's Vertex [40], p4 [7, 8], and PARMACS [5, 9]. Other important contributions have come from Zipcode [47, 48], Chimp [16, 17], PVM [4, 14], Chameleon [25], and PICL [24].

The MPI standardization effort involved about 60 people from 40 organizations mainly from the United States and Europe. Most of the major vendors of concurrent computers were involved in MPI, along with researchers from universities, government laboratories, and industry. The standardization process began with the Workshop on Standards for Message-Passing in a Distributed Memory Environment, sponsored by the Center for Research on Parallel Computing, held April 29-30, 1992, in Williamsburg, Virginia [55]. At this workshop the basic features essential to a standard message-passing interface were discussed, and a working group established to continue the standardization process.

A preliminary draft proposal, known as MPI1, was put forward by Dongarra, Hempel, Hey, and Walker in November 1992, and a revised version was completed in February 1993 [15]. MPI1 embodied the main features that were identified at the Williamsburg workshop as being necessary in a message passing standard. Since MPI1 was primarily intended to promote discussion and "get the ball rolling," it focused mainly on point-to-point communications. MPI1 brought to the forefront a number of important standardization issues, but did not include any collective communication routines and was not thread-safe.

In November 1992, a meeting of the MPI working group was held in Minneapolis, at which it was decided to place the standardization process on a more formal footing, and to generally adopt the procedures and organization of the High Performance Fortran Forum. Subcommittees were formed for the major component areas of the standard, and an email discussion service established for each. In addition, the goal of producing a draft MPI standard by the Fall of 1993 was set. To achieve this goal the MPI working group met every 6 weeks for two days throughout the first 9 months of 1993, and presented the draft MPI standard at the Supercomputing 93 conference in November 1993. These meetings and the email discussion together constituted the MPI Forum, membership of which has been open to all members of the high performance computing community.

ticket0. 9

ticket0.

ticket0. 33

ticket230-B.

ticket232-D.

ticket 233-E.

 MPI-2.0 was released, and a second ballot was voted on May 22, 2002. Both votes were done electronically. Both ballots were combined into one document: "Errata for MPI-2", May 15, 2002. This errata process was then interrupted, but the Forum and its e-mail reflectors kept working on new requests for clarification.

Restarting regular work of the MPI Forum was initiated in three meetings, at EuroPVM/MPI'06 in Bonn, at EuroPVM/MPI'07 in Paris, and at SC'07 in Reno. In December 2007, a steering committee started the organization of new MPI Forum meetings at regular 8-weeks intervals. At the January 14-16, 2008 meeting in Chicago, the MPI Forum decided to combine the existing and future MPI documents to one [single] document for each version of the MPI standard. For technical and historical reasons, this series was started with MPI-1.3. Additional Ballots 3 and 4 solved old questions from the errata list started in 1995 up to new questions from the last years. After all documents (MPI-1.1, MPI-2, Errata for MPI-1.1 (Oct. 12, 1998), and MPI-2.1 Ballots 1-4) were combined into one draft document, for each chapter, a chapter author and review team were defined. They cleaned up the document to achieve a consistent MPI-2.1 document. The final MPI-2.1 standard document was finished in June 2008, and finally released with a second vote in September 2008 in the meeting at Dublin, just before EuroPVM/MPI'08. The major work of the current MPI Forum is the preparation of MPI-3.

1.5 Background of MPI-2.2

MPI-2.2 is a minor update to the MPI-2.1 standard. This version addresses additional errors and ambiguities that were not corrected in the MPI-2.1 standard as well as a small number of extensions to MPI-2.1 that met the following criteria:

- Any correct MPI-2.1 program is a correct MPI-2.2 program.
- Any extension must have significant benefit for users.
- Any extension must not require significant implementation effort. To that end, all such changes are accompanied by an open source implementation.

The discussions of MPI-2.2 proceeded concurrently with the MPI-3 discussions; in some cases, extensions were proposed for MPI-2.2 but were later moved to MPI-3.

1.6 Background of MPI-3.0

MPI-3.0 is a major update to the MPI standard. Areas of particular interest are the extension of collective operations to include nonblocking and sparse-group routines and more flexible and powerful one-sided operations. This *draft* contains the MPI Forum's current draft of nonblocking collective routines.

A new Fortran mpi_f08 module is introduced to provide extended compile-time argument checking and buffer handling in nonblocking routines. The existing mpi module provides compile-time argument checking on the basis of existing MPI-2.2 routine definitions. The use of mpif.h is strongly discouraged.

7

9

10

11

1

2

12 13 14

17 18 19

20

21

15

16

22 23 24

25

26

27 28 29

30

31

32

33

34 35 36

37

38

39

40

41 42

43 44

47

48

ticket244-P. 45

MPI_CLASS_ACTION. For C and Fortran we use the C++ terminology to define the Class. In C++, the routine is a method on Class and is named MPI::Class::Action_subset. If the routine is associated with a certain class, but does not make sense as an object method, it is a static member function of the class.

- 2. If the routine is not associated with a class, the name should be of the form MPI_Action_subset in C and MPI_ACTION_SUBSET in Fortran, and in C++ should be scoped in the MPI namespace, MPI::Action_subset.
- 3. The names of certain actions have been standardized. In particular, Create creates a new object, **Get** retrieves information about an object, **Set** sets this information, **Delete** deletes information, **Is** asks whether or not an object has a certain property.

C and Fortran names for some MPI functions (that were defined during the MPI-1 process) violate these rules in several cases. The most common exceptions are the omission of the Class name from the routine and the omission of the Action where one can be inferred.

MPI identifiers are limited to 30 characters (31 with the profiling interface). This is done to avoid exceeding the limit on some compilation systems.

2.3 Procedure Specification

MPI procedures are specified using a language-independent notation. The arguments of procedure calls are marked as IN, OUT or INOUT. The meanings of these are:

- IN: the call may use the input value but does not update the argument,
- OUT: the call may update the argument but does not use its input value,
- INOUT: the call may both use and update the argument.

There is one special case — if an argument is a handle to an opaque object (these terms are defined in Section 2.5.1), and the object is updated by the procedure call, then the argument is marked INOUT or OUT. It is marked this way even though the handle itself is not modified — we use the INOUT or OUT attribute to denote that what the handle references is updated. Thus, in C++, IN arguments are usually either references or pointers to const objects.

Rationale. The definition of MPI tries to avoid, to the largest possible extent, the use of INOUT arguments, because such use is error-prone, especially for scalar arguments. (End of rationale.)

MPI's use of IN, OUT and INOUT is intended to indicate to the user how an argument is to be used, but does not provide a rigorous classification that can be translated directly into all language bindings (e.g., INTENT in Fortran 90 bindings or const in C bindings). For instance, the "constant" MPI_BOTTOM can usually be passed to OUT buffer arguments. Similarly, MPI_STATUS_IGNORE can be passed as the OUT status argument (with the mpi module or mpif.h).

A common occurrence for MPI functions is an argument that is used as IN by some processes and OUT by other processes. Such an argument is, syntactically, an INOUT argument

and is marked as such, although, semantically, it is not used in one call both for input and for output on a single process.

Another frequent situation arises when an argument value is needed only by a subset of the processes. When an argument is not significant at a process then an arbitrary value can be passed as an argument.

Unless specified otherwise, an argument of type OUT or type INOUT cannot be aliased with any other argument passed to an MPI procedure. An example of argument aliasing in C appears below. If we define a C procedure like this,

```
void copyIntBuffer( int *pin, int *pout, int len )
{   int i;
   for (i=0; i<len; ++i) *pout++ = *pin++;
}</pre>
```

then a call to it in the following code fragment has aliased arguments.

```
int a[10];
copyIntBuffer( a, a+3, 7);
```

Although the C language allows this, such usage of MPI procedures is forbidden unless otherwise specified. Note that Fortran prohibits aliasing of arguments.

All MPI functions are first specified in the language-independent notation. Immediately below this, [the ISO C version of the function is shown followed by a version of the same function in Fortran and then the C++ binding.]language dependent bindings follow:

- The ISO C version of the function.
- The Fortran version of the same function used with USE mpi or INCLUDE 'mpif.h'
- The Fortran version used with USE mpi_f08.
- The C++ binding (which is deprecated).

Fortran in this document refers to Fortran 90 and higher; see Section 2.6.

2.4 Semantic Terms

When discussing MPI procedures the following semantic terms are used.

nonblocking A procedure is nonblocking if the procedure may return before the operation completes, and before the user is allowed to reuse resources (such as buffers) specified in the call. A nonblocking request is **started** by the call that initiates it, e.g., MPI_ISEND. The word complete is used with respect to operations, requests, and communications. An **operation completes** when the user is allowed to reuse resources, and any output buffers have been updated; i.e. a call to MPI_TEST will return flag = true. A **request is completed** by a call to wait, which returns, or a test or get status call which returns flag = true. This completing call has two effects: the status is extracted from the request; in the case of test and wait, if the request was nonpersistent, it is **freed**, and becomes **inactive** if it was persistent. A **communication completes** when all participating operations complete.

 $_{22}$ ticket230-B.

³¹ ticket230-B.

- **blocking** A procedure is blocking if return from the procedure indicates the user is allowed to reuse resources specified in the call.
- **local** A procedure is local if completion of the procedure depends only on the local executing process.
- **non-local** A procedure is non-local if completion of the operation may require the execution of some MPI procedure on another process. Such an operation may require communication occurring with another user process.
- **collective** A procedure is collective if all processes in a process group need to invoke the procedure. A collective call may or may not be synchronizing. Collective calls over the same communicator must be executed in the same order by all members of the process group.
- predefined A predefined datatype is a datatype with a predefined (constant) name (such as MPI_INT, MPI_FLOAT_INT, or MPI_UB) or a datatype constructed with MPI_TYPE_CREATE_F90_INTEGER, MPI_TYPE_CREATE_F90_REAL, or MPI_TYPE_CREATE_F90_COMPLEX. The former are named whereas the latter are unnamed.
- **derived** A derived datatype is any datatype that is not predefined.
- portable A datatype is portable, if it is a predefined datatype, or it is derived from a portable datatype using only the type constructors MPI_TYPE_CONTIGUOUS, MPI_TYPE_VECTOR, MPI_TYPE_INDEXED, MPI_TYPE_CREATE_INDEXED_BLOCK, MPI_TYPE_CREATE_SUBARRAY, MPI_TYPE_DUP, and MPI_TYPE_CREATE_DARRAY. Such a datatype is portable because all displacements in the datatype are in terms of extents of one predefined datatype. Therefore, if such a datatype fits a data layout in one memory, it will fit the corresponding data layout in another memory, if the same declarations were used, even if the two systems have different architectures. On the other hand, if a datatype was constructed using MPI_TYPE_CREATE_HINDEXED, MPI_TYPE_CREATE_HVECTOR or MPI_TYPE_CREATE_STRUCT, then the datatype contains explicit byte displacements (e.g., providing padding to meet alignment restrictions). These displacements are unlikely to be chosen correctly if they fit data layout on one memory, but are used for data layouts on another process, running on a processor with a different architecture.
- **equivalent** Two datatypes are equivalent if they appear to have been created with the same sequence of calls (and arguments) and thus have the same typemap. Two equivalent datatypes do not necessarily have the same cached attributes or the same names.

2.5 Data Types

2.5.1 Opaque Objects

MPI manages **system memory** that is used for buffering messages and for storing internal representations of various MPI objects such as groups, communicators, datatypes, etc. This memory is not directly accessible to the user, and objects stored there are **opaque**: their

2.5. DATA TYPES 13

size and shape is not visible to the user. Opaque objects are accessed via **handles**, which exist in user space. MPI procedures that operate on opaque objects are passed handle arguments to access these objects. In addition to their use by MPI calls for object access, handles can participate in assignments and comparisons.

In Fortran with USE mpi or INCLUDE 'mpif.h', all handles have type INTEGER. In Fortran with USE mpi_f08, and in C and C++, a different handle type is defined for each category of objects. With Fortran USE mpi_f08, the handles are defined as Fortran sequenced derived types that consist of only one element INTEGER:: MPI_VAL. The internal handle value is identical to the Fortran INTEGER value used in the mpi module and in mpif.h. The names are identical to the names in C, except that they are not case sensitive. For example:

```
TYPE MPI_Comm

SEQUENCE

INTEGER :: MPI_VAL

END TYPE MPI_Comm
```

In addition, handles themselves are distinct objects in C++. The C and C++ types must support the use of the assignment and equality operators.

Advice to implementors. In Fortran, the handle can be an index into a table of opaque objects in a system table; in C it can be such an index or a pointer to the object. C++ handles can simply "wrap up" a table index or pointer. (End of advice to implementors.)

Rationale. Due to the sequence attribute in the definition of handles in the mpi_f08 module, the new Fortran handles are associated with one numerical storage unit, i.e., they have the same C binding as the INTEGER handles of the mpi module. Due to the equivalence of the integer values, applications can easily convert MPI handles between all three supported Fortran methods. For example, an integer communicator handle COMM can be converted directly into an exactly equivalent mpi_f08 communicator handle named comm_f08 by comm_f08%MPI_VAL=COMM, and vice versa. (End of rationale.)

Opaque objects are allocated and deallocated by calls that are specific to each object type. These are listed in the sections where the objects are described. The calls accept a handle argument of matching type. In an allocate call this is an OUT argument that returns a valid reference to the object. In a call to deallocate this is an INOUT argument which returns with an "invalid handle" value. MPI provides an "invalid handle" constant for each object type. Comparisons to this constant are used to test for validity of the handle.

A call to a deallocate routine invalidates the handle and marks the object for deal-location. The object is not accessible to the user after the call. However, MPI need not deallocate the object immediately. Any operation pending (at the time of the deallocate) that involves this object will complete normally; the object will be deallocated afterwards.

An opaque object and its handle are significant only at the process where the object was created and cannot be transferred to another process.

MPI provides certain predefined opaque objects and predefined, static handles to these objects. The user must not free such objects. In C++, this is enforced by declaring the handles to these predefined objects to be static const.

ticket231-C.
 ticket231-C.
 ticket231-C.

24 ticket231-C

Rationale. This design hides the internal representation used for MPI data structures, thus allowing similar calls in C, C++, and Fortran. It also avoids conflicts with the typing rules in these languages, and easily allows future extensions of functionality. The mechanism for opaque objects used here loosely follows the POSIX Fortran binding standard.

The explicit separation of handles in user space and objects in system space allows space-reclaiming and deallocation calls to be made at appropriate points in the user program. If the opaque objects were in user space, one would have to be very careful not to go out of scope before any pending operation requiring that object completed. The specified design allows an object to be marked for deallocation, the user program can then go out of scope, and the object itself still persists until any pending operations are complete.

The requirement that handles support assignment/comparison is made since such operations are common. This restricts the domain of possible implementations. The alternative would have been to allow handles to have been an arbitrary, opaque type. This would force the introduction of routines to do assignment and comparison, adding complexity, and was therefore ruled out. (*End of rationale*.)

Advice to users. A user may accidently create a dangling reference by assigning to a handle the value of another handle, and then deallocating the object associated with these handles. Conversely, if a handle variable is deallocated before the associated object is freed, then the object becomes inaccessible (this may occur, for example, if the handle is a local variable within a subroutine, and the subroutine is exited before the associated object is deallocated). It is the user's responsibility to avoid adding or deleting references to opaque objects, except as a result of MPI calls that allocate or deallocate such objects. (End of advice to users.)

Advice to implementors. The intended semantics of opaque objects is that opaque objects are separate from one another; each call to allocate such an object copies all the information required for the object. Implementations may avoid excessive copying by substituting referencing for copying. For example, a derived datatype may contain references to its components, rather then copies of its components; a call to MPI_COMM_GROUP may return a reference to the group associated with the communicator, rather than a copy of this group. In such cases, the implementation must maintain reference counts, and allocate and deallocate objects in such a way that the visible effect is as if the objects were copied. (End of advice to implementors.)

2.5.2 Array Arguments

An MPI call may need an argument that is an array of opaque objects, or an array of handles. The array-of-handles is a regular array with entries that are handles to objects of the same type in consecutive locations in the array. Whenever such an array is used, an additional len argument is required to indicate the number of valid entries (unless this number can be derived otherwise). The valid entries are at the beginning of the array; len indicates how many of them there are, and need not be the size of the entire array. The same approach is followed for other array arguments. In some cases NULL handles are considered valid entries. When a NULL argument is desired for an array of statuses, one uses MPI_STATUSES_IGNORE. With the mpi_f08 module, optional arguments through function overloading are used instead of

ticket244-P. ⁴⁷

2.5. DATA TYPES 15

MPI_STATUS_IGNORE, MPI_STATUSES_IGNORE, MPI_ERRCODES_IGNORE, and MPI_UNWEIGHTED. The constants MPI_ARGV_NULL and MPI_ARGVS_NULL are not substituted by function overloading.

2.5.3 State

MPI procedures use at various places arguments with *state* types. The values of such a data type are all identified by names, and no operation is defined on them. For example, the MPI_TYPE_CREATE_SUBARRAY routine has a state argument order with values MPI_ORDER_C and MPI_ORDER_FORTRAN.

2.5.4 Named Constants

MPI procedures sometimes assign a special meaning to a special value of a basic type argument; e.g., tag is an integer-valued argument of point-to-point communication operations, with a special wild-card value, MPI_ANY_TAG. Such arguments will have a range of regular values, which is a proper subrange of the range of values of the corresponding basic type; special values (such as MPI_ANY_TAG) will be outside the regular range. The range of regular values, such as tag, can be queried using environmental inquiry functions (Chapter 7 of the MPI-1 document). The range of other values, such as source, depends on values given by other MPI routines (in the case of source it is the communicator size).

MPI also provides predefined named constant handles, such as MPI_COMM_WORLD.

All named constants, with the exceptions noted below for Fortran, can be used in initialization expressions or assignments, but not necessarily in array declarations or as labels in C/C++ switch or Fortran select/case statements. This implies named constants to be link-time but not necessarily compile-time constants. The named constants listed below are required to be compile-time constants in both C/C++ and Fortran. These constants do not change values during execution. Opaque objects accessed by constant handles are defined and do not change value between MPI initialization (MPI_INIT) and MPI completion (MPI_FINALIZE). The handles themselves are constants and can be also used in initialization expressions or assignments.

The constants that are required to be compile-time constants (and can thus be used for array length declarations and labels in C/C++ switch and Fortran case/select statements) are:

```
MPI_MAX_PROCESSOR_NAME
MPI_MAX_ERROR_STRING
MPI_MAX_DATAREP_STRING
MPI_MAX_INFO_KEY
MPI_MAX_INFO_VAL
MPI_MAX_OBJECT_NAME
MPI_MAX_PORT_NAME
MPI_STATUS_SIZE (Fortran only)
MPI_ADDRESS_KIND (Fortran only)
MPI_INTEGER_KIND (Fortran only)
MPI_OFFSET_KIND (Fortran only)
and their C++ counterparts where appropriate.
```

The constants that cannot be used in initialization expressions or assignments in Fortran are:

MPI_BOTTOM
MPI_STATUS_IGNORE
MPI_STATUSES_IGNORE
MPI_ERRCODES_IGNORE
MPI_IN_PLACE
MPI_ARGV_NULL
MPI_ARGVS_NULL
MPI_UNWEIGHTED

Advice to implementors. In Fortran the implementation of these special constants may require the use of language constructs that are outside the Fortran standard. Using special values for the constants (e.g., by defining them through PARAMETER statements) is not possible because an implementation cannot distinguish these values from legal data. Typically, these constants are implemented as predefined static variables (e.g., a variable in an MPI-declared COMMON block), relying on the fact that the target compiler passes data by address. Inside the subroutine, this address can be extracted by some mechanism outside the Fortran standard (e.g., by Fortran extensions or by implementing the function in C). (End of advice to implementors.)

2.5.5 Choice

MPI functions sometimes use arguments with a *choice* (or union) data type. Distinct calls to the same routine may pass by reference actual arguments of different types. The mechanism for providing such arguments will differ from language to language. For Fortran with the include file mpif.h or the mpi module, the document uses <type> to represent a choice variable; with the Fortran mpi_f08 module, such arguments are declared with the Fortran 2008 syntax TYPE(*), DIMENSION(..); for C and C++, we use void *.

Advice to implementors. The implementor can freely choose how to implement choice arguments in the mpi module, e.g., with a non-standard compiler-dependent method that has the quality of the call mechanism in the implicit Fortran interfaces, or with the method defined for the mpi_f08 module. (End of advice to implementors.)

2.5.6 Addresses

Some MPI procedures use *address* arguments that represent an absolute address in the calling program. The datatype of such an argument is MPI_Aint in C, MPI::Aint in C++ and INTEGER (KIND=MPI_ADDRESS_KIND) in Fortran. These types must have the same width and encode address values in the same manner such that address values in one language may be passed directly to another language without conversion. There is the MPI constant MPI_BOTTOM to indicate the start of the address range.

2.5.7 File Offsets

For I/O there is a need to give the size, displacement, and offset into a file. These quantities can easily be larger than 32 bits which can be the default size of a Fortran integer. To overcome this, these quantities are declared to be INTEGER (KIND=MPI_OFFSET_KIND) in Fortran. In C one uses MPI_Offset whereas in C++ one uses MPI::Offset. These types

ticket234-F. $_{24}$

ticket234-F. $_{26}$ ticket234-F. $_{27}$

must have the same width and encode address values in the same manner such that offset values in one language may be passed directly to another language without conversion.

2.6 Language Binding

This section defines the rules for MPI language binding in general and for Fortran, ISO C, and C++, in particular. (Note that ANSI C has been replaced by ISO C.) The C++ language bindings have been deprecated. Defined here are various object representations, as well as the naming conventions used for expressing this standard. The actual calling sequences are defined elsewhere.

MPI bindings are for Fortran 90 or later, though they [are]were originally designed to be usable in Fortran 77 environments. With the mpi_f08 module, the two Fortran 2008 features assumed type and assumed rank are also required, see Section 2.5.5 on page 16.

Since the word PARAMETER is a keyword in the Fortran language, we use the word "argument" to denote the arguments to a subroutine. These are normally referred to as parameters in C and C++, however, we expect that C and C++ programmers will understand the word "argument" (which has no specific meaning in C/C++), thus allowing us to avoid unnecessary confusion for Fortran programmers.

Since Fortran is case insensitive, linkers may use either lower case or upper case when resolving Fortran names. Users of case sensitive languages should avoid the "mpi_" and "pmpi_" prefixes.

2.6.1 Deprecated Names and Functions

A number of chapters refer to deprecated or replaced MPI-1 constructs. These are constructs that continue to be part of the MPI standard, as documented in Chapter 15, but that users are recommended not to continue using, since better solutions were provided with MPI-2. For example, the Fortran binding for MPI-1 functions that have address arguments uses INTEGER. This is not consistent with the C binding, and causes problems on machines with 32 bit INTEGERs and 64 bit addresses. In MPI-2, these functions were given new names with new bindings for the address arguments. The use of the old functions is deprecated. For consistency, here and in a few other cases, new C functions are also provided, even though the new functions are equivalent to the old functions. The old names are deprecated. Another example is provided by the MPI-1 predefined datatypes MPI_UB and MPI_LB. They are deprecated, since their use is awkward and error-prone. The MPI-2 function MPI_TYPE_CREATE_RESIZED provides a more convenient mechanism to achieve the same

Table 2.1 shows a list of all of the deprecated constructs. Note that the constants MPI_LB and MPI_UB are replaced by the function MPI_TYPE_CREATE_RESIZED; this is because their principal use was as input datatypes to MPI_TYPE_STRUCT to create resized datatypes. Also note that some C typedefs and Fortran subroutine names are included in this list; they are the types of callback functions.

2.6.2 Fortran Binding Issues

effect.

Originally, MPI-1.1 provided bindings for Fortran 77. These bindings are retained, but they are now interpreted in the context of the Fortran 90 standard. MPI can still be used with

ticket234-F. ticket234-F. ticket234-F.

1	Deprecated	MPI-2 Replacement
2	MPI_ADDRESS	MPI_GET_ADDRESS
3	MPI_TYPE_HINDEXED	MPI_TYPE_CREATE_HINDEXED
4	MPI_TYPE_HVECTOR	MPI_TYPE_CREATE_HVECTOR
5	MPI_TYPE_STRUCT	MPI_TYPE_CREATE_STRUCT
6	MPI_TYPE_EXTENT	MPI_TYPE_GET_EXTENT
7	MPI_TYPE_UB	MPI_TYPE_GET_EXTENT
8	MPI_TYPE_LB	MPI_TYPE_GET_EXTENT
9	MPI_LB	MPI_TYPE_CREATE_RESIZED
10	MPI_UB	MPI_TYPE_CREATE_RESIZED
11	MPI_ERRHANDLER_CREATE	MPI_COMM_CREATE_ERRHANDLER
12	MPI_ERRHANDLER_GET	MPI_COMM_GET_ERRHANDLER
13	MPI_ERRHANDLER_SET	MPI_COMM_SET_ERRHANDLER
14	MPI _ $Handler$ _ $function$	MPI_Comm_errhandler_function
15	MPI_KEYVAL_CREATE	MPI_COMM_CREATE_KEYVAL
16	MPI_KEYVAL_FREE	MPI_COMM_FREE_KEYVAL
17	MPI_DUP_FN	MPI_COMM_DUP_FN
18	MPI_NULL_COPY_FN	MPI_COMM_NULL_COPY_FN
19	MPI_NULL_DELETE_FN	MPI_COMM_NULL_DELETE_FN
20	MPI_Copy_function	MPI_Comm_copy_attr_function
21	COPY_FUNCTION	COMM_COPY_ATTR_[ticket250-V.][FN]FUNCTION
22	MPI_Delete_function	MPI_Comm_delete_attr_function
23	DELETE_FUNCTION	COMM_DELETE_ATTR_[ticket250-V.][FN]FUNCTION
24	MPI_ATTR_DELETE	MPI_COMM_DELETE_ATTR
25	MPI_ATTR_GET	MPI_COMM_GET_ATTR
26	MPI_ATTR_PUT	MPI_COMM_SET_ATTR
27		

Table 2.1: Deprecated constructs

29 30 31

34

35

36

42

43

44

47

most Fortran 77 compilers, as noted below. When the term Fortran is used it means Fortran 90 or later; it means Fortran 2008 and later if the mpi_f08 module is used.

All MPI names have an MPI_ prefix, and all characters are capitals. Programs must not declare variables, parameters, or functions with names beginning with the prefix MPI_. To avoid conflicting with the profiling interface, programs should also avoid functions with the prefix PMPI_. This is mandated to avoid possible name collisions.

All MPI Fortran subroutines have a return code in the last argument. With USE mpi_f08, this last argument is declared as OPTIONAL, except for user-defined callback functions (e.g., COMM_COPY_ATTR_FUNCTION) and their predefined callbacks (e.g., MPI_NULL_COPY_FN). A few MPI operations which are functions do not have the return code argument. The return code value for successful completion is MPI_SUCCESS. Other

error codes are implementation dependent; see the error codes in Chapter 8 and Annex A. Constants representing the maximum length of a string are one smaller in Fortran than in C and C++ as discussed in Section 16.3.9.

Handles are represented in Fortran as INTEGERS, or with the mpi_f08 module as a derived type, see Section 2.5.1 on page 12. Binary-valued variables are of type LOGICAL.

Array arguments are indexed from one.

ticket234-F. $^{32}_{33}$

ticket 239-K. $^{37}_{38}$ ticket 250-V. 39

ticket239-K. 40

ticket231-C. 45

¹ ticket230-B.

² ticket230-B.

³ ticket230-B.

The MPI Fortran binding [is]s are inconsistent with the Fortran [90] standard in several respects. These inconsistencies, such as register optimization problems, have implications for user codes that are discussed in detail in Section 16.2.2. [They are also inconsistent with Fortran 77.]

2.6.3 C Binding Issues

We use the ISO C declaration format. All MPI names have an MPI_ prefix, defined constants are in all capital letters, and defined types and functions have one capital letter after the prefix. Programs must not declare variables or functions with names beginning with the prefix MPI_. To support the profiling interface, programs should not declare functions with names beginning with the prefix PMPI_.

The definition of named constants, function prototypes, and type definitions must be supplied in an include file mpi.h.

Almost all C functions return an error code. The successful return code will be MPI_SUCCESS, but failure return codes are implementation dependent.

Type declarations are provided for handles to each category of opaque objects.

Array arguments are indexed from zero.

Logical flags are integers with value 0 meaning "false" and a non-zero value meaning "true."

Choice arguments are pointers of type void *.

Address arguments are of MPI defined type MPI_Aint. File displacements are of type MPI_Offset. MPI_Aint is defined to be an integer of the size needed to hold any valid address on the target architecture. MPI_Offset is defined to be an integer of the size needed to hold any valid file size on the target architecture.

2.6.4 C++ Binding Issues

The C++ language bindings have been deprecated. There are places in the standard that give rules for C and not for C++. In these cases, the C rule should be applied to the C++ case, as appropriate. In particular, the values of constants given in the text are the ones for C and Fortran. A cross index of these with the C++ names is given in Annex A.

We use the ISO C++ declaration format. All MPI names are declared within the scope of a namespace called MPI and therefore are referenced with an MPI:: prefix. Defined constants are in all capital letters, and class names, defined types, and functions have only their first letter capitalized. Programs must not declare variables or functions in the MPI namespace. This is mandated to avoid possible name collisions.

The definition of named constants, function prototypes, and type definitions must be supplied in an include file mpi.h.

Advice to implementors. The file mpi.h may contain both the C and C++ definitions. Usually one can simply use the defined value (generally __cplusplus, but not required) to see if one is using C++ to protect the C++ definitions. It is possible that a C compiler will require that the source protected this way be legal C code. In this case, all the C++ definitions can be placed in a different include file and the "#include" directive can be used to include the necessary C++ definitions in the mpi.h file. (End of advice to implementors.)

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17 18

19 20

21

22 23 operation to select a particular message. The last three parameters of the send operation, along with the rank of the sender, specify the envelope for the message sent. Process one (myrank = 1) receives this message with the receive operation MPI_RECV. The message to be received is selected according to the value of its envelope, and the message data is stored into the receive buffer. In the example above, the receive buffer consists of the storage containing the string message in the memory of process one. The first three parameters of the receive operation specify the location, size and type of the receive buffer. The next three parameters are used for selecting the incoming message. The last parameter is used to return information on the message just received.

The next sections describe the blocking send and receive operations. We discuss send, receive, blocking communication semantics, type matching requirements, type conversion in heterogeneous environments, and more general communication modes. Nonblocking communication is addressed next, followed by channel-like constructs and send-receive operations, Nonblocking communication is addressed next, followed by channel-like constructs and send-receive operations, ending with a description of the "dummy" process, MPI_PROC_NULL.

3.2 Blocking Send and Receive Operations

3.2.1 Blocking Send

The syntax of the blocking send operation is given below.

```
24
                 MPI_SEND(buf, count, datatype, dest, tag, comm)
            25
            26
                   IN
                             buf
                                                          initial address of send buffer (choice)
            27
                   IN
                                                          number of elements in send buffer (non-negative inte-
                             count
            28
                                                          ger)
            29
                   IN
                             datatype
                                                          datatype of each send buffer element (handle)
            30
            31
                   IN
                             dest
                                                          rank of destination (integer)
            32
                   IN
                             tag
                                                          message tag (integer)
            33
                   IN
                             comm
                                                          communicator (handle)
            34
            35
                 int MPI_Send(void* buf, int count, MPI_Datatype datatype, int dest,
            36
                                 int tag, MPI_Comm comm)
            37
            38
                 MPI_SEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
            39
                      <type> BUF(*)
                      INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
ticket-248T. <sup>41</sup>
                 MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
                      TYPE(*), DIMENSION(..) :: buf
            43
                      INTEGER, INTENT(IN) :: count, dest, tag
            44
                      TYPE(MPI_Datatype), INTENT(IN) :: datatype
            45
                      TYPE(MPI_Comm), INTENT(IN) :: comm
            46
                      INTEGER, OPTIONAL, INTENT(OUT) ::
            47
```

A predefined communicator MPI_COMM_WORLD is provided by MPI. It allows communication with all processes that are accessible after MPI initialization and processes are identified by their rank in the group of MPI_COMM_WORLD.

3 4 5

6

9 10

11

12

1

2

Advice to users. Users that are comfortable with the notion of a flat name space for processes, and a single communication context, as offered by most existing communication libraries, need only use the predefined variable MPI_COMM_WORLD as the comm argument. This will allow communication with all the processes available at initialization time.

Users may define new communicators, as explained in Chapter 6. Communicators provide an important encapsulation mechanism for libraries and modules. They allow modules to have their own disjoint communication universe and their own process numbering scheme. (*End of advice to users.*)

13 14 15

16

17

18

Advice to implementors. The message envelope would normally be encoded by a fixed-length message header. However, the actual encoding is implementation dependent. Some of the information (e.g., source or destination) may be implicit, and need not be explicitly carried by messages. Also, processes may be identified by relative ranks, or absolute ids, etc. (End of advice to implementors.)

19 20 21

22

23

26

27 28

29 30

31

32 33

34

35

36 37

38 39

40

41

42

43

46

47

3.2.4 Blocking Receive

The syntax of the blocking receive operation is given below.

24 25

```
MPI_RECV (buf, count, datatype, source, tag, comm, status)
```

```
OUT
           buf
                                       initial address of receive buffer (choice)
 IN
                                        number of elements in receive buffer (non-negative in-
           count
 IN
                                        datatype of each receive buffer element (handle)
           datatype
 IN
                                       rank of source or MPI_ANY_SOURCE (integer)
           source
  IN
                                       message tag or MPI_ANY_TAG (integer)
           tag
  IN
           comm
                                       communicator (handle)
 OUT
           status
                                       status object (Status)
int MPI_Recv(void* buf, int count, MPI_Datatype datatype, int source,
               int tag, MPI_Comm comm, MPI_Status *status)
MPI_RECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS, IERROR)
    <type> BUF(*)
    INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE),
    IERROR
```

ticket-248T. ⁴⁴

```
MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, source, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

The blocking semantics of this call are described in Section 3.4.

The receive buffer consists of the storage containing count consecutive elements of the type specified by datatype, starting at address buf. The length of the received message must be less than or equal to the length of the receive buffer. An overflow error occurs if all incoming data does not fit, without truncation, into the receive buffer.

If a message that is shorter than the receive buffer arrives, then only those locations corresponding to the (shorter) message are modified.

Advice to users. The MPI_PROBE function described in Section 3.8 can be used to receive messages of unknown length. (End of advice to users.)

Advice to implementors. Even though no specific behavior is mandated by MPI for erroneous programs, the recommended handling of overflow situations is to return in status information about the source and tag of the incoming message. The receive operation will return an error code. A quality implementation will also ensure that no memory that is outside the receive buffer will ever be overwritten.

In the case of a message shorter than the receive buffer, MPI is quite strict in that it allows no modification of the other locations. A more lenient statement would allow for some optimizations but this is not allowed. The implementation must be ready to end a copy into the receiver memory exactly at the end of the receive buffer, even if it is an odd address. (*End of advice to implementors*.)

The selection of a message by a receive operation is governed by the value of the message envelope. A message can be received by a receive operation if its envelope matches the source, tag and comm values specified by the receive operation. The receiver may specify a wildcard MPI_ANY_SOURCE value for source, and/or a wildcard MPI_ANY_TAG value for tag, indicating that any source and/or tag are acceptable. It cannot specify a wildcard value for comm. Thus, a message can be received by a receive operation only if it is addressed to the receiving process, has a matching communicator, has matching source unless source=MPI_ANY_SOURCE in the pattern, and has a matching tag unless tag=MPI_ANY_TAG in the pattern.

The message tag is specified by the tag argument of the receive operation. The argument source, if different from MPI_ANY_SOURCE, is specified as a rank within the process group associated with that same communicator (remote process group, for intercommunicators). Thus, the range of valid values for the source argument is $\{0,...,n-1\}\cup\{MPI_ANY_SOURCE\}$, where n is the number of processes in this group.

Note the asymmetry between send and receive operations: A receive operation may accept messages from an arbitrary sender, on the other hand, a send operation must specify

a unique receiver. This matches a "push" communication mechanism, where data transfer is effected by the sender (rather than a "pull" mechanism, where data transfer is effected by the receiver).

Source = destination is allowed, that is, a process can send a message to itself. (However, it is unsafe to do so with the blocking send and receive operations described above, since this may lead to deadlock. See Section 3.5.)

Advice to implementors. Message context and other communicator information can be implemented as an additional tag field. It differs from the regular message tag in that wild card matching is not allowed on this field, and that value setting for this field is controlled by communicator manipulation functions. (End of advice to implementors.)

3.2.5 Return Status

The source or tag of a received message may not be known if wildcard values were used in the receive operation. Also, if multiple requests are completed by a single MPI function (see Section 3.7.5), a distinct error code may need to be returned for each request. The information is returned by the status argument of MPI_RECV. The type of status is MPI-defined. Status variables need to be explicitly allocated by the user, that is, they are not system objects.

In C, status is a structure that contains three fields named MPI_SOURCE, MPI_TAG, and MPI_ERROR; the structure may contain additional fields. Thus, status.MPI_SOURCE, status.MPI_TAG and status.MPI_ERROR contain the source, tag, and error code, respectively, of the received message.

In Fortran with USE mpi or INCLUDE 'mpif.h', status is an array of INTEGERs of size MPI_STATUS_SIZE. The constants MPI_SOURCE, MPI_TAG and MPI_ERROR are the indices of the entries that store the source, tag and error fields. Thus, status(MPI_SOURCE), status(MPI_TAG) and status(MPI_ERROR) contain, respectively, the source, tag and error code of the received message.

With Fortran USE mpi_f08, status is defined as the Fortran derived type TYPE(MPI_Status), which contains three fields named MPI_SOURCE, MPI_TAG, and MPI_ERROR; the derived type may contain additional fields. Thus, status%MPI_SOURCE, status%MPI_TAG and status%MPI_ERROR contain the source, tag, and error code, respectively, of the received message. Additionally, within the mpi and the mpi_f08 module, both, the constants MPI_STATUS_SIZE, MPI_SOURCE, MPI_TAG, MPI_ERROR, and the TYPE(MPI_Status) is defined to allow with both modules the conversion between both status declarations.

Rationale. It is allowed to have the same name (e.g., MPI_SOURCE) defined as a constant (e.g., Fortran parameter) and as a field of a derived type. (End of rationale.)

Advice to implementors. The Fortran TYPE(MPI_Status) may be defined as a sequence derived type to achieve the same data layout as in C. (End of advice to implementors.)

In C++, the status object is handled through the following methods:
{int MPI::Status::Get_source() const(binding deprecated, see Section 15.2) }

ticket243-O. $_{26}$

ticket 243-O. $_{30}$

12 13

14

15

16

17

18 19

20

21

22 23

2425

26

27

28 29 30

31

32

35

36

37

38

41 42

43

44

45

46 47 ticket-248T

```
{void MPI::Status::Set_source(int source) (binding deprecated, see Section 15.2) }
{int MPI::Status::Get_tag() const(binding deprecated, see Section 15.2) }
{void MPI::Status::Set_tag(int tag) (binding deprecated, see Section 15.2) }
{int MPI::Status::Get_error() const(binding deprecated, see Section 15.2) }
{void MPI::Status::Set_error(int error) (binding deprecated, see Section 15.2) }
```

In general, message-passing calls do not modify the value of the error code field of status variables. This field may be updated only by the functions in Section 3.7.5 which return multiple statuses. The field is updated if and only if such function returns with an error code of MPI_ERR_IN_STATUS.

Rationale. The error field in status is not needed for calls that return only one status, such as MPI_WAIT, since that would only duplicate the information returned by the function itself. The current design avoids the additional overhead of setting it, in such cases. The field is needed for calls that return multiple statuses, since each request may have had a different failure. (End of rationale.)

The status argument also returns information on the length of the message received. However, this information is not directly available as a field of the status variable and a call to MPI_GET_COUNT is required to "decode" this information.

```
MPI_GET_COUNT(status, datatype, count)
```

```
IN
          status
                                     return status of receive operation (Status)
 IN
          datatype
                                     datatype of each receive buffer entry (handle)
 OUT
          count
                                     number of received entries (integer)
int MPI_Get_count(MPI_Status *status, MPI_Datatype datatype, int *count)
MPI_GET_COUNT(STATUS, DATATYPE, COUNT, IERROR)
    INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR
MPI_Get_count(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{int MPI::Status::Get_count(const MPI::Datatype& datatype) const(binding
              deprecated, see Section 15.2) }
```

Returns the number of entries received. (Again, we count *entries*, each of type *datatype*, not *bytes*.) The datatype argument should match the argument provided by the receive call that set the status variable. (We shall later see, in Section 4.1.11, that MPI_GET_COUNT may return, in certain situations, the value MPI_UNDEFINED.)

Rationale. Some message-passing libraries use INOUT count, tag and source arguments, thus using them both to specify the selection criteria for incoming

ticket244-P.

messages and return the actual envelope values of the received message. The use of a separate status argument prevents errors that are often attached with INOUT argument (e.g., using the MPI_ANY_TAG constant as the tag in a receive). Some libraries use calls that refer implicitly to the "last message received." This is not thread safe.

The datatype argument is passed to MPI_GET_COUNT so as to improve performance. A message might be received without counting the number of elements it contains, and the count value is often not needed. Also, this allows the same function to be used after a call to MPI_PROBE or MPI_IPROBE. With a status from MPI_PROBE or MPI_IPROBE, the same datatypes are allowed as in a call to MPI_RECV to receive this message. (*End of rationale*.)

The value returned as the count argument of MPI_GET_COUNT for a datatype of length zero where zero bytes have been transferred is zero. If the number of bytes transferred is greater than zero, MPI_UNDEFINED is returned.

Rationale. Zero-length datatypes may be created in a number of cases. An important case is MPI_TYPE_CREATE_DARRAY, where the definition of the particular darray results in an empty block on some MPI process. Programs written in an SPMD style will not check for this special case and may want to use MPI_GET_COUNT to check the status. (End of rationale.)

Advice to users. The buffer size required for the receive can be affected by data conversions and by the stride of the receive datatype. In most cases, the safest approach is to use the same datatype with MPI_GET_COUNT and the receive. (End of advice to users.)

All send and receive operations use the buf, count, datatype, source, dest, tag, comm and status arguments in the same way as the blocking MPI_SEND and MPI_RECV operations described in this section.

3.2.6 Passing MPI_STATUS_IGNORE for Status

Every call to MPI_RECV includes a status argument, wherein the system can return details about the message received. There are also a number of other MPI calls where status is returned. An object of type MPI_STATUS is not an MPI opaque object; its structure is declared in mpi.h and mpif.h, and it exists in the user's program. In many cases, application programs are constructed so that it is unnecessary for them to examine the status fields. In these cases, it is a waste for the user to allocate a status object, and it is particularly wasteful for the MPI implementation to fill in fields in this object.

To cope with this problem, there are two predefined constants, MPI_STATUS_IGNORE and MPI_STATUSES_IGNORE with the C language bindings and the Fortran bindings through the mpi module and the mpif.h include file, which when passed to a receive, wait, or test function, inform the implementation that the status fields are not to be filled in. Note that MPI_STATUS_IGNORE is not a special type of MPI_STATUS object; rather, it is a special value for the argument. In C one would expect it to be NULL, not the address of a special MPI_STATUS.

MPI_STATUS_IGNORE, and the array version MPI_STATUSES_IGNORE, can be used everywhere a status argument is passed to a receive, wait, or test function. MPI_STATUS_IGNORE

 17 ticket 244-P.

²¹ ticket244-P.

²² ticket244-P.²³ ticket244-P.

24 ticket244-P.

₂₅ ticket244-P.

cannot be used when status is an IN argument. Note that in Fortran MPI_STATUS_IGNORE and MPI_STATUSES_IGNORE are objects like MPI_BOTTOM (not usable for initialization or assignment). See Section 2.5.4.

In general, this optimization can apply to all functions for which status or an array of statuses is an OUT argument. Note that this converts status into an INOUT argument. The functions that can be passed MPI_STATUS_IGNORE are all the various forms of MPI_RECV, MPI_TEST, and MPI_WAIT, as well as MPI_REQUEST_GET_STATUS. When an array is passed, as in the MPI_{TEST|WAIT}{ALL|SOME} functions, a separate constant, MPI_STATUSES_IGNORE, is passed for the array argument. It is possible for an MPI function to return MPI_ERR_IN_STATUS even when MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE has been passed to that function.

MPI_STATUS_IGNORE and MPI_STATUSES_IGNORE are not required to have the same values in C and Fortran.

It is not allowed to have some of the statuses in an array of statuses for $MPI_{TEST|WAIT}_{ALL|SOME}$ functions set to MPI_{STATUS_IGNORE} ; one either specifies ignoring all of the statuses in such a call with $MPI_{STATUSES_IGNORE}$, or *none* of them by passing normal statuses in all positions in the array of statuses.

[There are no C++ bindings for MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE.] With the Fortran bindings through the mpi_f08 module and the C++ bindings, MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE does not exist. To allow an OUT or INOUT TYPE(MPI_Status) or MPI::Status argument to be ignored, all MPI mpi_f08 or C++ bindings that have OUT or INOUT TYPE(MPI_Status) or MPI::Status parameters are overloaded with a second version that omits the OUT or INOUT TYPE(MPI_Status) or MPI::Status parameter.

Example 3.1 The mpi_f08 bindings for MPI_PROBE are:

```
SUBROUTINE MPI_Probe(source, tag, comm, status, ierror)
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Status), INTENT(OUT) :: status
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    END SUBROUTINE

SUBROUTINE MPI_Probe(source, tag, comm, ierror)
    INTEGER, INTENT(IN) :: source, tag
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
    END SUBROUTINE
```

Example 3.2 The C++ bindings for MPI_PROBE are:

```
void MPI::Comm::Probe(int source, int tag, MPI::Status& status) const
void MPI::Comm::Probe(int source, int tag) const
```

3.3 Data Type Matching and Data Conversion

3.3.1 Type Matching Rules

One can think of message transfer as consisting of the following three phases.

Unofficial Draft for Comment Only

ticket-248T.

Start a nonblocking receive.

These calls allocate a communication request object and associate it with the request handle (the argument request). The request can be used later to query the status of the communication or wait for its completion.

A nonblocking send call indicates that the system may start copying data out of the send buffer. The sender should not modify any part of the send buffer after a nonblocking send operation is called, until the send completes.

A nonblocking receive call indicates that the system may start writing data into the receive buffer. The receiver should not access any part of the receive buffer after a nonblocking receive operation is called, until the receive completes.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in subsections "Problems Due to Data Copying and Sequence Association," and "A Problem with Register Optimization and Temporary Memory Modifications" in Section 16.2.2 on pages 545 and 549. (End of advice to users.)

3.7.3 Communication Completion

The functions MPI_WAIT and MPI_TEST are used to complete a nonblocking communication. The completion of a send operation indicates that the sender is now free to update the locations in the send buffer (the send operation itself leaves the content of the send buffer unchanged). It does not indicate that the message has been received, rather, it may have been buffered by the communication subsystem. However, if a synchronous mode send was used, the completion of the send operation indicates that a matching receive was initiated, and that the message will eventually be received by this matching receive.

The completion of a receive operation indicates that the receive buffer contains the received message, the receiver is now free to access it, and that the status object is set. It does not indicate that the matching send operation has completed (but indicates, of course, that the send was initiated).

We shall use the following terminology: A **null** handle is a handle with value MPI_REQUEST_NULL. A persistent request and the handle to it are **inactive** if the request is not associated with any ongoing communication (see Section 3.9). A handle is **active** if it is neither null nor inactive. An **empty** status is a status which is set to return tag

 $\int_{0}^{\infty} \text{ticket } 238\text{-J.}$

3

4

5

6

9

10

11

12

13

14

15

44

45 46

47

3.9 Persistent Communication Requests

Often a communication with the same argument list is repeatedly executed within the inner loop of a parallel computation. In such a situation, it may be possible to optimize the communication by binding the list of communication arguments to a persistent communication request once and, then, repeatedly using the request to initiate and complete messages. The persistent request thus created can be thought of as a communication port or a "half-channel." It does not provide the full functionality of a conventional channel, since there is no binding of the send port to the receive port. This construct allows reduction of the overhead for communication between the process and communication controller, but not of the overhead for communication between one communication controller and another. It is not necessary that messages sent with a persistent request be received by a receive operation using a persistent request, or vice versa.

A persistent communication request is created using one of the five following calls. These calls involve no communication.

```
16
```

```
17
                 MPI_SEND_INIT(buf, count, datatype, dest, tag, comm, request)
           18
                   IN
                            buf
                                                        initial address of send buffer (choice)
           19
           20
                   IN
                            count
                                                        number of elements sent (non-negative integer)
           21
                                                        type of each element (handle)
                   IN
                            datatype
           22
                            dest
                   IN
                                                        rank of destination (integer)
           23
           24
                   IN
                                                        message tag (integer)
                            tag
                   IN
                                                        communicator (handle)
                            comm
           26
                   OUT
                                                        communication request (handle)
                            request
           27
           28
           29
                 int MPI_Send_init(void* buf, int count, MPI_Datatype datatype, int dest,
           30
                                int tag, MPI_Comm comm, MPI_Request *request)
           31
                 MPI_SEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
           32
                     <type> BUF(*)
ticket
250-V. _{34}
                     INTEGER [REQUEST, ] COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
ticket-248T. _{35}
                 MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
           36
                     TYPE(*), DIMENSION(..) :: buf
           37
                     INTEGER, INTENT(IN) :: count, dest, tag
           38
                     TYPE(MPI_Datatype), INTENT(IN) :: datatype
           39
                     TYPE(MPI_Comm), INTENT(IN) :: comm
                     TYPE(MPI_Request), INTENT(OUT) :: request
           41
                     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           42
                 {MPI::Prequest MPI::Comm::Send_init(const void* buf, int count, const
           43
                                MPI::Datatype& datatype, int dest, int tag) const(binding
```

Creates a persistent communication request for a standard mode send operation, and binds to it all the arguments of a send operation.

deprecated, see Section 15.2) }

```
MPI_BSEND_INIT(buf, count, datatype, dest, tag, comm, request)
                                                                                          2
  IN
           buf
                                       initial address of send buffer (choice)
  IN
           count
                                       number of elements sent (non-negative integer)
  IN
           datatype
                                       type of each element (handle)
           dest
                                       rank of destination (integer)
  IN
  IN
                                       message tag (integer)
           tag
                                       communicator (handle)
  IN
           comm
  OUT
                                       communication request (handle)
           request
                                                                                          12
int MPI_Bsend_init(void* buf, int count, MPI_Datatype datatype, int dest,
                                                                                          13
               int tag, MPI_Comm comm, MPI_Request *request)
                                                                                          14
                                                                                          15
MPI_BSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
                                                                                          16
    <type> BUF(*)
                                                                                          ^{17} ticket 250-V.
    INTEGER [REQUEST, ] COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
                                                                                          ^{18} ticket-248T.
MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                          19
    TYPE(*), DIMENSION(..)
                               :: buf
                                                                                          20
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                          21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                          22
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                          23
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                          24
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                          26
{MPI::Prequest MPI::Comm::Bsend_init(const void* buf, int count, const
                                                                                          27
               MPI::Datatype& datatype, int dest, int tag) const/binding
                                                                                          28
               deprecated, see Section 15.2) }
                                                                                          29
    Creates a persistent communication request for a buffered mode send.
                                                                                          30
                                                                                          31
MPI_SSEND_INIT(buf, count, datatype, dest, tag, comm, request)
                                                                                          33
  IN
           buf
                                       initial address of send buffer (choice)
                                                                                          34
                                                                                          35
  IN
           count
                                       number of elements sent (non-negative integer)
                                                                                          36
  IN
           datatype
                                       type of each element (handle)
                                                                                          37
  IN
           dest
                                       rank of destination (integer)
                                                                                          38
                                                                                          39
  IN
           tag
                                       message tag (integer)
  IN
                                       communicator (handle)
           comm
  OUT
                                       communication request (handle)
           request
                                                                                          42
                                                                                          43
int MPI_Ssend_init(void* buf, int count, MPI_Datatype datatype, int dest,
                                                                                          44
               int tag, MPI_Comm comm, MPI_Request *request)
                                                                                          45
                                                                                          46
MPI_SSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
    <type> BUF(*)
```

where * indicates zero or more repetitions. If the same communication object is used in several concurrent threads, it is the user's responsibility to coordinate calls so that the correct sequence is obeyed.

A send operation initiated with MPI_START can be matched with any receive operation and, likewise, a receive operation initiated with MPI_START can receive messages generated by any send operation.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in subsections "Problems Due to Data Copying and Sequence Association," and "A Problem with Register Optimization and Temporary Memory Modifications" in Section 16.2.2 on pages 545 and 549. (End of advice to users.)

3.10 Send-Receive

The **send-receive** operations combine in one call the sending of a message to one destination and the receiving of another message, from another process. The two (source and destination) are possibly the same. A send-receive operation is very useful for executing a shift operation across a chain of processes. If blocking sends and receives are used for such a shift, then one needs to order the sends and receives correctly (for example, even processes send, then receive, odd processes receive first, then send) so as to prevent cyclic dependencies that may lead to deadlock. When a send-receive operation is used, the communication subsystem takes care of these issues. The send-receive operation can be used in conjunction with the functions described in Chapter 7 in order to perform shifts on various logical topologies. Also, a send-receive operation is useful for implementing remote procedure calls.

A message sent by a send-receive operation can be received by a regular receive operation or probed by a probe operation; a send-receive operation can receive a message sent by a regular send operation.

¹¹ ticket238-J.

6 7

9

10

11

12

14 15

16 17 18

19

20 21

22 23

24

25

28

29

30

31

35

36

37 38

39

42

43

44

45

46

47

ticket-248T.

13 ticket238-J.

Advice to users. C users may be tempted to avoid the usage of MPI_GET_ADDRESS and rely on the availability of the address operator &. Note, however, that & cast-expression is a pointer, not an address. ISO C does not require that the value of a pointer (or the pointer cast to int) be the absolute address of the object pointed at — although this is commonly the case. Furthermore, referencing may not have a unique definition on machines with a segmented address space. The use of MPI_GET_ADDRESS to "reference" C variables guarantees portability to such machines as well. (End of advice to users.)

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in subsections "Problems Due to Data Copying and Sequence Association," and "A Problem with Register Optimization and Temporary Memory Modifications" in Section 16.2.2 on pages 545 and 549. (End of advice to users.)

The following auxiliary function provides useful information on derived datatypes.

```
MPI_TYPE_SIZE(datatype, size)
 IN
          datatype
                                     datatype (handle)
 OUT
          size
                                     datatype size (integer)
int MPI_Type_size(MPI_Datatype datatype, int *size)
MPI_TYPE_SIZE(DATATYPE, SIZE, IERROR)
    INTEGER DATATYPE, SIZE, IERROR
MPI_Type_size(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) ::
                                         datatype
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{int MPI::Datatype::Get_size() const(binding deprecated, see Section 15.2) }
```

MPI_TYPE_SIZE returns the total size, in bytes, of the entries in the type signature associated with datatype; i.e., the total size of the data in a message that would be created with this datatype. Entries that occur multiple times in the datatype are counted with their multiplicity.

4.1.6 Lower-Bound and Upper-Bound Markers

It is often convenient to define explicitly the lower bound and upper bound of a type map, and override the definition given on page 106. This allows one to define a datatype that has "holes" at its beginning or its end, or a datatype with entries that extend above the upper bound or below the lower bound. Examples of such usage are provided in Section 4.1.14. Also, the user may want to overide the alignment rules that are used to compute upper bounds and extents. E.g., a C compiler may allow the user to overide default alignment rules for some of the structures within a program. The user has to specify explicitly the bounds of the datatypes that match these structures.

4.1.10 Duplicating a Datatype

ticket 252-W.

ticket 252-W.

```
MPI_TYPE_DUP(oldtype, newtype)

IN type datatype (handle)

OUT newtype copy of oldtype (handle)

int MPI_Type_dup(MPI_Datatype oldtype, MPI_Datatype *newtype)

MPI_TYPE_DUP(OLDTYPE, NEWTYPE, IERROR)
    INTEGER OLDTYPE, NEWTYPE, IERROR

MPI_Type_dup(oldtype, newtype, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

{MPI::Datatype MPI::Datatype::Dup() const(binding deprecated, see Section 15.2)}

MPI_TYPE_DIP_is a type constructor which duplicates the existing
```

MPI_TYPE_DUP is a type constructor which duplicates the existing type with associated key values. For each key value, the respective copy callback function determines the attribute value associated with this key in the new communicator; one particular action that a copy callback may take is to delete the attribute from the new datatype. Returns in newtype a new datatype with exactly the same properties as oldtype and any copied cached information, see Section 6.7.4 on page 275. The new datatype has identical upper bound and lower bound and yields the same net result when fully decoded with the functions in Section 4.1.13. The newtype has the same committed state as the old oldtype.

4.1.11 Use of General Datatypes in Communication

Handles to derived datatypes can be passed to a communication call wherever a datatype argument is required. A call of the form MPI_SEND(buf, count, datatype, ...), where count > 1, is interpreted as if the call was passed a new datatype which is the concatenation of count copies of datatype. Thus, MPI_SEND(buf, count, datatype, dest, tag, comm) is equivalent to,

```
MPI_TYPE_CONTIGUOUS(count, datatype, newtype)
MPI_TYPE_COMMIT(newtype)
MPI_SEND(buf, 1, newtype, dest, tag, comm).
```

Similar statements apply to all other communication functions that have a **count** and **datatype** argument.

Suppose that a send operation MPI_SEND(buf, count, datatype, dest, tag, comm) is executed, where datatype has type map,

```
\{(type_0, disp_0), ..., (type_{n-1}, disp_{n-1})\},\
```

and extent extent. (Empty entries of "pseudo-type" MPI_UB and MPI_LB are not listed in the type map, but they affect the value of extent.) The send operation sends $n \cdot \text{count}$

11 ticket252-W.
12 ticket252-W.
13 ticket-248T.

14

15

16

18 19

20

21

22

28 29

30

31

33

34

35 36

37

38

39

41

42

43

44

45 46

47

ticket252-W.

 $_{24}^{23}$ ticket 252-W.

ticket252-W.

10

13 14

15

16

19

23

25

26

27

28

29

31

35

36

37

38

43

44

45 46

47

ticket252-W

 $_{18}$ ticket252-W.

 20 ticket252-W.

 21 ticket252-W.

24 ticket-248T.

ticket252-W.

41 ticket252-W.

Rationale. The definition of MPI_MINLOC and MPI_MAXLOC given here has the advantage that it does not require any special-case handling of these two operations: they are handled like any other reduce operation. A programmer can provide his or her own definition of MPI_MAXLOC and MPI_MINLOC, if so desired. The disadvantage is that values and indices have to be first interleaved, and that indices and values have to be coerced to the same type, in Fortran. (End of rationale.)

5.9.5 User-Defined Reduction Operations

```
MPI_OP_CREATE([function]user_fn, commute, op)
           [ticket252-W.][function]user_fn user defined function (function)
 IN
 IN
           commute
                                     true if commutative; false otherwise.
 OUT
                                     operation (handle)
          op
int MPI_Op_create(MPI_User_function* [function]user_fn, int commute,
              MPI_Op* op)
MPI_OP_CREATE( [FUNCTION] USER_FN, COMMUTE, OP, IERROR)
    EXTERNAL [FUNCTION] USER_FN
    LOGICAL COMMUTE
    INTEGER OP, IERROR
MPI_Op_create(user_fn, commute, op, ierror)
    EXTERNAL :: user_fn
    LOGICAL, INTENT(IN) ::
                              commute
    TYPE(MPI_Op), INTENT(OUT) :: op
    INTEGER, OPTIONAL, INTENT(OUT) ::
{void MPI::Op::Init(MPI::User_function* [function]user_fn,
              bool commute) (binding deprecated, see Section 15.2) }
```

MPI_OP_CREATE binds a user-defined reduction operation to an op handle that can subsequently be used in MPI_REDUCE, MPI_ALLREDUCE, MPI_REDUCE_SCATTER, MPI_SCAN, and MPI_EXSCAN. The user-defined operation is assumed to be associative. If commute = true, then the operation should be both commutative and associative. If commute = false, then the order of operands is fixed and is defined to be in ascending, process rank order, beginning with process zero. The order of evaluation can be changed, talking advantage of the associativity of the operation. If commute = true then the order of evaluation can be changed, taking advantage of commutativity and associativity.

The argument [function]user_fn is the user-defined function, which must have the following four arguments: invec, inoutvec, len and datatype.

```
The ISO C prototype for the function is the following.

typedef void MPI_User_function(void* invec, void* inoutvec, int* len,

MPI_Datatype* datatype);
```

The Fortran declaration of the user-defined function appears below. SUBROUTINE USER_FUNCTION(INVEC, INOUTVEC, LEN, TYPE)

```
<type> INVEC(LEN), INOUTVEC(LEN)
   INTEGER LEN, TYPE

The C++ declaration of the user-defined function appears below.
{typedef void MPI::User_function(const void* invec, void* inoutvec, int len, const Datatype& datatype); (binding deprecated, see
```

Section 15.2)}

The datatype argument is a handle to the data type that was passed into the call to MPI_REDUCE. The user reduce function should be written such that the following holds: Let u[0], ..., u[len-1] be the len elements in the communication buffer described by the arguments invec, len and datatype when the function is invoked; let v[0], ..., v[len-1] be len elements in the communication buffer described by the arguments inoutvec, len and datatype when the function is invoked; let w[0], ..., w[len-1] be len elements in the communication buffer described by the arguments inoutvec, len and datatype when the function returns; then w[i] = u[i] ov[i], for i=0, ..., len-1, where o is the reduce operation that the function computes.

Informally, we can think of invec and inoutvec as arrays of len elements that $[function]user_fn$ is combining. The result of the reduction over-writes values in inoutvec, hence the name. Each invocation of the function results in the pointwise evaluation of the reduce operator on len elements: i.e., the function returns in inoutvec[i] the value invec[i] \circ inoutvec[i], for $i=0,\ldots,count-1$, where \circ is the combining operation computed by the function.

Rationale. The len argument allows MPI_REDUCE to avoid calling the function for each element in the input buffer. Rather, the system can choose to apply the function to chunks of input. In C, it is passed in as a reference for reasons of compatibility with Fortran.

By internally comparing the value of the datatype argument to known, global handles, it is possible to overload the use of a single user-defined function for several, different data types. (*End of rationale*.)

General datatypes may be passed to the user function. However, use of datatypes that are not contiguous is likely to lead to inefficiencies.

No MPI communication function may be called inside the user function. MPI_ABORT may be called inside the function in case of an error.

Advice to users. Suppose one defines a library of user-defined reduce functions that are overloaded: the datatype argument is used to select the right execution path at each invocation, according to the types of the operands. The user-defined reduce function cannot "decode" the datatype argument that it is passed, and cannot identify, by itself, the correspondence between the datatype handles and the datatype they represent. This correspondence was established when the datatypes were created. Before the library is used, a library initialization preamble must be executed. This preamble code will define the datatypes that are used by the library, and store handles to these datatypes in global, static variables that are shared by the user code and the library code.

The Fortran version of MPI_REDUCE will invoke a user-defined reduce function using the Fortran calling conventions and will pass a Fortran-type datatype argument; the

ticket 252-W. 18

43

46

47

45 ticket-248T.

```
MPI_REDUCE_LOCAL( inbuf, inoutbuf, count, datatype, op)
                                                                                          2
 IN
           inbuf
                                       input buffer (choice)
 INOUT
           inoutbuf
                                       combined input and output buffer (choice)
 IN
           count
                                       number of elements in inbuf and inoutbuf buffers (non-
                                       negative integer)
 IN
           datatype
                                       data type of elements of inbuf and inoutbuf buffers
                                       (handle)
 IN
                                       operation (handle)
           op
                                                                                          10
                                                                                          11
int MPI_Reduce_local(void* inbuf, void* inoutbuf, int count,
                                                                                          12
               MPI_Datatype datatype, MPI_Op op)
                                                                                          13
MPI_REDUCE_LOCAL(INBUF, INOUTBUF, COUNT, DATATYPE, OP, IERROR)
                                                                                            ticket250-V.
    <type> INBUF(*), INOUTBUF(*)
                                                                                          16
    INTEGER COUNT, DATATYPE, OP, IERROR
                                                                                          ^{17} ticket-248T.
MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
    TYPE(*), DIMENSION(..) :: inbuf, inoutbuf
                                                                                          19
    INTEGER, INTENT(IN) :: count
                                                                                          20
    TYPE(MPI_Datatype), INTENT(IN) ::
                                                                                          21
                                            datatype
    TYPE(MPI_Op), INTENT(IN) :: op
                                                                                          22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                          23
{void MPI::Op::Reduce_local(const void* inbuf, void* inoutbuf, int count,
               const MPI::Datatype& datatype) const(binding deprecated, see
                                                                                          26
               Section 15.2) }
                                                                                          27
    The function applies the operation given by op element-wise to the elements of inbuf
                                                                                          28
                                                                                          29
and inoutbuf with the result stored element-wise in inoutbuf, as explained for user-defined
                                                                                          30
operations in Section 5.9.5. Both inbuf and inoutbuf (input as well as result) have the
                                                                                          31
same number of elements given by count and the same datatype given by datatype. The
MPI_IN_PLACE option is not allowed.
                                                                                          33
    Reduction operations can be queried for their commutativity.
                                                                                          34
                                                                                          35
MPI_OP_COMMUTATIVE( op, commute)
                                                                                          36
                                                                                          37
 IN
                                       operation (handle)
           op
  OUT
                                       true if op is commutative, false otherwise (logical)
           commute
int MPI_Op_commutative(MPI_Op op, int *commute)
```

```
Unofficial Draft for Comment Only
```

MPI_OP_COMMUTATIVE(OP, COMMUTE, IERROR)

MPI_Op_commutative(op, commute, ierror)

LOGICAL, INTENT(OUT) :: commute

TYPE(MPI_Op), INTENT(IN) ::

LOGICAL COMMUTE
INTEGER OP, IERROR

13 14

15

16

21

22

23

26

27

28

31

33

34

35

36

37

38

42

43

 17 ticket 250-V.

20 ticket-248T.

ticket250-V

no pending communication on peer_comm that could interfere with this communication.

Advice to users. We recommend using a dedicated peer communicator, such as a duplicate of MPI_COMM_WORLD, to avoid trouble with peer communicators. (End of advice to users.)

```
MPI_INTERCOMM_MERGE(intercomm, high, newintracomm)
```

```
    IN
    intercomm
    Inter-Communicator (handle)

    IN
    high
    (logical)

    OUT
    newintracomm
    new intra-communicator (handle)
```

```
MPI_INTERCOMM_MERGE(INTERCOMM, HIGH, NEWINTRACOMM, IERROR)
INTEGER NEWINTERCOMM, INTRACOMM, IERROR
LOGICAL HIGH
```

```
MPI_Intercomm_merge(intercomm, high, newintracomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: intercomm
    LOGICAL, INTENT(IN) :: high
    TYPE(MPI_Comm), INTENT(OUT) :: newintracomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
{MPI::Intracomm MPI::Intercomm::Merge(bool high) const(binding deprecated, see Section 15.2)}
```

This function creates an intra-communicator from the union of the two groups that are associated with intercomm. All processes should provide the same high value within each of the two groups. If processes in one group provided the value high = false and processes in the other group provided the value high = true then the union orders the "low" group before the "high" group. If all processes provided the same high argument then the order of the union is arbitrary. This call is blocking and collective within the union of the two groups.

The error handler on the new intercommunicator in each process is inherited from the communicator that contributes the local group. Note that this can result in different processes in the same communicator having different error handlers.

Advice to implementors. The implementation of MPI_INTERCOMM_MERGE, MPI_COMM_FREE and MPI_COMM_DUP are similar to the implementation of MPI_INTERCOMM_CREATE, except that contexts private to the input inter-communicator are used for communication between group leaders rather than contexts inside a bridge communicator. (End of advice to implementors.)

ticket-248T. $^{45}_{47}$

- obtain a key value (used to identify an attribute); the user specifies "callback" functions by which MPI informs the application when the communicator is destroyed or copied.
- store and retrieve the value of an attribute;

Advice to implementors. Caching and callback functions are only called synchronously, in response to explicit application requests. This avoid problems that result from repeated crossings between user and system space. (This synchronous calling rule is a general property of MPI.)

The choice of key values is under control of MPI. This allows MPI to optimize its implementation of attribute sets. It also avoids conflict between independent modules caching information on the same communicators.

A much smaller interface, consisting of just a callback facility, would allow the entire caching facility to be implemented by portable code. However, with the minimal callback interface, some form of table searching is implied by the need to handle arbitrary communicators. In contrast, the more complete interface defined here permits rapid access to attributes through the use of pointers in communicators (to find the attribute table) and cleverly chosen key values (to retrieve individual attributes). In light of the efficiency "hit" inherent in the minimal interface, the more complete interface defined here is seen to be superior. (*End of advice to implementors*.)

MPI provides the following services related to caching. They are all process local.

6.7.2 Communicators

Functions for caching on communicators are:

```
MPI_COMM_CREATE_KEYVAL(comm_copy_attr_fn, comm_delete_attr_fn, comm_keyval, extra_state)
```

```
IN comm_copy_attr_fn copy callback function for comm_keyval (function)

IN comm_delete_attr_fn delete callback function for comm_keyval (function)

OUT comm_keyval key value for future access (integer)

IN extra_state extra state for callback functions
```

```
MPI_COMM_CREATE_KEYVAL(COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN, COMM_KEYVAL,
EXTRA_STATE, IERROR)
```

```
EXTERNAL COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN
INTEGER COMM_KEYVAL, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
```

6.7. CACHING 267

```
EXTERNAL :: comm_copy_attr_fn, comm_delete_attr_fn
    INTEGER, INTENT(OUT) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{static int MPI::Comm::Create_keyval(MPI::Comm::Copy_attr_function*
              comm_copy_attr_fn,
              MPI::Comm::Delete_attr_function* comm_delete_attr_fn,
              void* extra_state) (binding deprecated, see Section 15.2) }
    Generates a new attribute key. Keys are locally unique in a process, and opaque to
                                                                                      11
user, though they are explicitly stored in integers. Once allocated, the key value can be
used to associate attributes and access them on any locally defined communicator.
                                                                                      12
                                                                                      13
    This function replaces MPI_KEYVAL_CREATE, whose use is deprecated. The C binding
                                                                                      14
is identical. The Fortran binding differs in that extra_state is an address-sized integer.
                                                                                      15
Also, the copy and delete callback functions have Fortran bindings that are consistent with
                                                                                      16
address-sized attributes.
    The C callback functions are:
                                                                                      18
typedef int MPI_Comm_copy_attr_function(MPI_Comm oldcomm, int comm_keyval,
                                                                                      19
              void *extra_state, void *attribute_val_in,
                                                                                      20
              void *attribute_val_out, int *flag);
                                                                                      21
    and
                                                                                      22
typedef int MPI_Comm_delete_attr_function(MPI_Comm comm, int comm_keyval,
                                                                                      23
              void *attribute_val, void *extra_state);
                                                                                      24
which are the same as the MPI-1.1 calls but with a new name. The old names are deprecated.
    The Fortran callback functions are:
                                                                                      ^{27} ticket 250-V.
SUBROUTINE COMM_COPY_ATTR_[FN] FUNCTION(OLDCOMM, COMM_KEYVAL, EXTRA_STATE,
              ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
                                                                                      29
    INTEGER OLDCOMM, COMM_KEYVAL, IERROR
                                                                                      30
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                      31
        ATTRIBUTE_VAL_OUT
    LOGICAL FLAG
    and
                                                                                      35 ticket250-V.
SUBROUTINE COMM_DELETE_ATTR_[FN] FUNCTION (COMM, COMM_KEYVAL, ATTRIBUTE_VAL,
              EXTRA_STATE, IERROR)
                                                                                      36
    INTEGER COMM, COMM_KEYVAL, IERROR
                                                                                      37
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
    The C++ callbacks are:
{typedef int MPI::Comm::Copy_attr_function(const MPI::Comm& oldcomm,
                                                                                      41
              int comm_keyval, void* extra_state, void* attribute_val_in,
                                                                                      42
              void* attribute_val_out, bool& flag); (binding deprecated, see
                                                                                      43
              Section 15.2)
                                                                                      44
                                                                                      45
{typedef int MPI::Comm::Delete_attr_function(MPI::Comm& comm,
                                                                                      46
              int comm_keyval, void* attribute_val, void* extra_state);
```

(binding deprecated, see Section 15.2)}

The comm_copy_attr_fn function is invoked when a communicator is duplicated by

MPI_COMM_DUP. comm_copy_attr_fn should be of type MPI_Comm_copy_attr_function. The copy callback function is invoked for each key value in oldcomm in arbitrary order. Each call to the copy callback is made with a key value and its corresponding attribute. If it returns flag = 0, then the attribute is deleted in the duplicated communicator. Otherwise (flag = 1), the new attribute value is set to the value returned in attribute_val_out. The function returns MPI_SUCCESS on success and an error code on failure (in which case MPI_COMM_DUP will fail).

The argument comm_copy_attr_fn may be specified as MPI_COMM_NULL_COPY_FN or MPI_COMM_DUP_FN from either C, C++, or Fortran. MPI_COMM_NULL_COPY_FN is a function that does nothing other than returning flag = 0 and MPI_SUCCESS. MPI_COMM_DUP_FN is a simple-minded copy function that sets flag = 1, returns the value of attribute_val_in in attribute_val_out, and returns MPI_SUCCESS. These replace the MPI-1 predefined callbacks MPI_NULL_COPY_FN and MPI_DUP_FN, whose use is deprecated.

 Advice to users. Even though both formal arguments attribute_val_in and attribute_val_out are of type void *, their usage differs. The C copy function is passed by MPI in attribute_val_in the value of the attribute, and in attribute_val_out the address of the attribute, so as to allow the function to return the (new) attribute value. The use of type void * for both is to avoid messy type casts.

 A valid copy function is one that completely duplicates the information by making a full duplicate copy of the data structures implied by an attribute; another might just make another reference to that data structure, while using a reference-count mechanism. Other types of attributes might not copy at all (they might be specific to oldcomm only). (End of advice to users.)

Advice to implementors. A C interface should be assumed for copy and delete functions associated with key values created in C; a Fortran calling interface should be assumed for key values created in Fortran. (End of advice to implementors.)

Analogous to comm_copy_attr_fn is a callback deletion function, defined as follows. The comm_delete_attr_fn function is invoked when a communicator is deleted by MPI_COMM_FREE or when a call is made explicitly to MPI_COMM_DELETE_ATTR. comm_delete_attr_fn should be of type MPI_Comm_delete_attr_function.

This function is called by MPI_COMM_FREE, MPI_COMM_DELETE_ATTR, and MPI_COMM_SET_ATTR to do whatever is needed to remove an attribute. The function returns MPI_SUCCESS on success and an error code on failure (in which case MPI_COMM_FREE will fail).

The argument comm_delete_attr_fn may be specified as MPI_COMM_NULL_DELETE_FN from either C, C++, or Fortran. MPI_COMM_NULL_DELETE_FN is a function that does nothing, other than returning MPI_SUCCESS. MPI_COMM_NULL_DELETE_FN replaces MPI_NULL_DELETE_FN, whose use is deprecated.

If an attribute copy function or attribute delete function returns other than MPI_SUCCESS, then the call that caused it to be invoked (for example, MPI_COMM_FREE), is erroneous.

The special key value MPI_KEYVAL_INVALID is never returned by MPI_KEYVAL_CREATE. Therefore, it can be used for static initialization of key values.

 6.7. CACHING 269

Advice to implementors. To be able to use the predefined C functions MPI_COMM_NULL_COPY_FN or MPI_COMM_DUP_FN as comm_copy_attr_fn argument and/or MPI_COMM_NULL_DELETE_FN as the comm_delete_attr_fn argument in a call to the C++ routine MPI::Comm::Create_keyval, this routine may be overloaded with 3 additional routines that accept the C functions as the first, the second, or both input arguments (instead of an argument that matches the C++ prototype). (End of advice to implementors.)

 24 ticket-248T.

Advice to users. If a user wants to write a "wrapper" routine that internally calls MPI::Comm::Create_keyval and comm_copy_attr_fn and/or comm_delete_attr_fn are arguments of this wrapper routine, and if this wrapper routine should be callable with both user-defined C++ copy and delete functions and with the predefined C functions, then the same overloading as described above in the advice to implementors may be necessary. (End of advice to users.)

```
MPI_COMM_FREE_KEYVAL(comm_keyval)
INOUT comm_keyval key value (integer)

int MPI_Comm_free_keyval(int *comm_keyval)

MPI_COMM_FREE_KEYVAL(COMM_KEYVAL, IERROR)
    INTEGER COMM_KEYVAL, IERROR

MPI_Comm_free_keyval(comm_keyval, ierror)
    INTEGER, INTENT(INOUT) :: comm_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

{static void MPI::Comm::Free_keyval(int& comm_keyval) (binding deprecated, see Section 15.2) }
```

Frees an extant attribute key. This function sets the value of keyval to MPI_KEYVAL_INVALID. Note that it is not erroneous to free an attribute key that is in use, because the actual free does not transpire until after all references (in other communicators on the process) to the key have been freed. These references need to be explictly freed by the program, either via calls to MPI_COMM_DELETE_ATTR that free one attribute instance, or by calls to MPI_COMM_FREE that free all attribute instances associated with the freed communicator.

This call is identical to the MPI-1 call MPI_KEYVAL_FREE but is needed to match the new communicator-specific creation function. The use of MPI_KEYVAL_FREE is deprecated.

MPI_COMM_SET_ATTR(comm, comm_keyval, attribute_val)

INOUT	comm	communicator from which attribute will be attached (handle)
IN	comm_keyval	key value (integer)
IN	attribute_val	attribute value

```
1
                6.7.3 Windows
           2
                The new functions for caching on windows are:
           3
           4
           5
                MPI_WIN_CREATE_KEYVAL(win_copy_attr_fn, win_delete_attr_fn, win_keyval, extra_state)
           6
           7
                  IN
                           win_copy_attr_fn
                                                       copy callback function for win_keyval (function)
           8
                  IN
                           win_delete_attr_fn
                                                       delete callback function for win_keyval (function)
           9
           10
                  OUT
                           win_keyval
                                                       key value for future access (integer)
           11
                  IN
                            extra_state
                                                       extra state for callback functions
           12
           13
                int MPI_Win_create_keyval(MPI_Win_copy_attr_function *win_copy_attr_fn,
           14
                               MPI_Win_delete_attr_function *win_delete_attr_fn,
           15
                               int *win_keyval, void *extra_state)
           16
           17
                MPI_WIN_CREATE_KEYVAL(WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN, WIN_KEYVAL,
           18
                               EXTRA_STATE, IERROR)
           19
                     EXTERNAL WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN
           20
                     INTEGER WIN_KEYVAL, IERROR
           21
                     INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
ticket-248T. 22
                MPI_Win_create_keyval(win_copy_attr_fn, win_delete_attr_fn, win_keyval,
           23
                               extra_state, ierror)
           24
                     EXTERNAL :: win_copy_attr_fn, win_delete_attr_fn
           25
           26
                     INTEGER, INTENT(OUT) :: win_keyval
                     INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
           27
                     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           28
           29
                {static int MPI::Win::Create_keyval(MPI::Win::Copy_attr_function*
           30
                               win_copy_attr_fn,
           31
                               MPI::Win::Delete_attr_function* win_delete_attr_fn,
           32
                               void* extra_state) (binding deprecated, see Section 15.2) }
           33
           34
                     The argument win_copy_attr_fn may be specified as MPI_WIN_NULL_COPY_FN or
                MPI_WIN_DUP_FN from either C, C++, or Fortran. MPI_WIN_NULL_COPY_FN is a
           35
                function that does nothing other than returning flag = 0 and MPI_SUCCESS.
           36
                MPI_WIN_DUP_FN is a simple-minded copy function that sets flag = 1, returns the value
           37
                of attribute_val_in in attribute_val_out, and returns MPI_SUCCESS.
           38
                     The argument win_delete_attr_fn may be specified as MPI_WIN_NULL_DELETE_FN
           39
                from either C, C++, or Fortran. MPI_WIN_NULL_DELETE_FN is a function that does
           40
                nothing, other than returning MPI_SUCCESS.
           41
           42
                     The C callback functions are:
                typedef int MPI_Win_copy_attr_function(MPI_Win oldwin, int win_keyval,
           43
                               void *extra_state, void *attribute_val_in,
           44
                               void *attribute_val_out, int *flag);
           45
           46
                     and
           47
```

6.7. CACHING 273

```
typedef int MPI_Win_delete_attr_function(MPI_Win win, int win_keyval,
              void *attribute_val, void *extra_state);
    The Fortran callback functions are:
                                                                                        ticket250-V.
SUBROUTINE WIN_COPY_ATTR_[FN] FUNCTION(OLDWIN, WIN_KEYVAL, EXTRA_STATE,
              ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
    INTEGER OLDWIN, WIN_KEYVAL, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
        ATTRIBUTE_VAL_OUT
    LOGICAL FLAG
                                                                                      10
    and
SUBROUTINE WIN_DELETE_ATTR_[FN] FUNCTION(WIN, WIN_KEYVAL, ATTRIBUTE_VAL,
                                                                                      <sup>12</sup> ticket250-V.
                                                                                      13
              EXTRA_STATE, IERROR)
                                                                                      14
    INTEGER WIN, WIN_KEYVAL, IERROR
                                                                                      15
    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
                                                                                      16
    The C++ callbacks are:
{typedef int MPI::Win::Copy_attr_function(const MPI::Win& oldwin,
              int win_keyval, void* extra_state, void* attribute_val_in,
                                                                                      19
              void* attribute_val_out, bool& flag); (binding deprecated, see
                                                                                      20
              Section 15.2)
                                                                                      21
                                                                                      22
    and
                                                                                      23
{typedef int MPI::Win::Delete_attr_function(MPI::Win& win, int win_keyval,
                                                                                      24
              void* attribute_val, void* extra_state); (binding deprecated, see
              Section 15.2)
                                                                                      26
    If an attribute copy function or attribute delete function returns other than
                                                                                      27
MPI_SUCCESS, then the call that caused it to be invoked (for example, MPI_WIN_FREE), is
                                                                                      28
erroneous.
                                                                                      29
                                                                                      30
                                                                                      31
MPI_WIN_FREE_KEYVAL(win_keyval)
  INOUT
           win_keyval
                                      key value (integer)
                                                                                      34
int MPI_Win_free_keyval(int *win_keyval)
                                                                                      35
                                                                                      36
MPI_WIN_FREE_KEYVAL(WIN_KEYVAL, IERROR)
                                                                                      37
    INTEGER WIN_KEYVAL, IERROR
                                                                                      ^{38} ticket-248T.
                                                                                      39
MPI_Win_free_keyval(win_keyval, ierror)
    INTEGER, INTENT(INOUT) :: win_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      42
{static void MPI::Win::Free_keyval(int& win_keyval)(binding deprecated, see
                                                                                      43
              Section 15.2) }
                                                                                      44
```

6.7. CACHING 275

```
MPI_WIN_DELETE_ATTR(win, win_keyval)
  INOUT
                                      window from which the attribute is deleted (handle)
           win
  IN
           win_keyval
                                      key value (integer)
int MPI_Win_delete_attr(MPI_Win win, int win_keyval)
MPI_WIN_DELETE_ATTR(WIN, WIN_KEYVAL, IERROR)
    INTEGER WIN, WIN_KEYVAL, IERROR
                                                                                         ticket-248T.
MPI_Win_delete_attr(win, win_keyval, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                       11
    INTEGER, INTENT(IN) :: win_keyval
                                                                                       12
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       13
                                                                                       14
{void MPI::Win::Delete_attr(int win_keyval)(binding deprecated, see Section 15.2)
                                                                                       15
               }
                                                                                       16
                                                                                       18
6.7.4
      Datatypes
                                                                                       19
The new functions for caching on datatypes are:
                                                                                       20
                                                                                       21
MPI_TYPE_CREATE_KEYVAL(type_copy_attr_fn, type_delete_attr_fn, type_keyval, extra_state)
  IN
           type_copy_attr_fn
                                      copy callback function for type_keyval (function)
                                                                                       26
  IN
           type_delete_attr_fn
                                      delete callback function for type_keyval (function)
                                                                                       27
  OUT
           type_keyval
                                      key value for future access (integer)
                                                                                       28
  IN
           extra_state
                                      extra state for callback functions
                                                                                       29
                                                                                       30
int MPI_Type_create_keyval(MPI_Type_copy_attr_function *type_copy_attr_fn,
              MPI_Type_delete_attr_function *type_delete_attr_fn,
                                                                                       33
              int *type_keyval, void *extra_state)
                                                                                       34
MPI_TYPE_CREATE_KEYVAL(TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN, TYPE_KEYVAL,
                                                                                       35
              EXTRA_STATE, IERROR)
                                                                                       36
    EXTERNAL TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN
                                                                                       37
    INTEGER TYPE_KEYVAL, IERROR
                                                                                       38
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                       ^{39} ticket-248T.
MPI_Type_create_keyval(type_copy_attr_fn, type_delete_attr_fn, type_keyval,
              extra_state, ierror)
                                                                                       42
    EXTERNAL :: type_copy_attr_fn, type_delete_attr_fn
    INTEGER, INTENT(OUT) :: type_keyval
                                                                                       43
                                                                                       44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       45
{static int MPI::Datatype::Create_keyval(MPI::Datatype::Copy_attr_function*
                                                                                       47
              type_copy_attr_fn, MPI::Datatype::Delete_attr_function*
```

```
ticket 252-W.^{-1}
                MPI_TYPE_GET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
ticket252-W. <sup>2</sup>
                     INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                     INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
                     LOGICAL FLAG
ticket-248T.
                 MPI_Type_get_attr(datatype, type_keyval, attribute_val, flag, ierror)
                     TYPE(MPI_Datatype), INTENT(IN) :: datatype
            7
                     INTEGER, INTENT(IN) :: type_keyval
                     INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
            9
                     LOGICAL, INTENT(OUT) :: flag
           10
                     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           11
           12
                 {bool MPI::Datatype::Get_attr(int type_keyval, void* attribute_val)
           13
                               const(binding deprecated, see Section 15.2) }
           14
           15
ticket 252-W.
                 MPI_TYPE_DELETE_ATTR(datatype, type_keyval)
                            [ticket252-W.]datatype
                  INOUT
                                                       datatype from which the attribute is deleted (handle)
           19
                  IN
                            type_keyval
                                                       key value (integer)
           20
ticket 252-W.
                 int MPI_Type_delete_attr(MPI_Datatype datatype, int type_keyval)
                MPI_TYPE_DELETE_ATTR(DATATYPE, TYPE_KEYVAL, IERROR)
{
m ticket 252	ext{-}W.} 23
ticket252	ext{-W}. 24
                     INTEGER DATATYPE, TYPE_KEYVAL, IERROR
ticket-248T. 25
                 MPI_Type_delete_attr(datatype, type_keyval, ierror)
           26
                     TYPE(MPI_Datatype), INTENT(IN) :: datatype
           27
                     INTEGER, INTENT(IN) :: type_keyval
           28
                     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           29
                 {void MPI::Datatype::Delete_attr(int type_keyval)(binding deprecated, see
           30
                               Section 15.2) }
           31
           32
           33
                       Error Class for Invalid Keyval
           34
           35
                 Key values for attributes are system-allocated, by MPI_{TYPE,COMM,WIN}_CREATE_KEYVAL.
           36
                 Only such values can be passed to the functions that use key values as input arguments.
           37
                 In order to signal that an erroneous key value has been passed to one of these functions,
                 there is a new MPI error class: MPI_ERR_KEYVAL. It can be returned by
           38
           39
                 MPI_ATTR_PUT, MPI_ATTR_GET, MPI_ATTR_DELETE, MPI_KEYVAL_FREE,
           40
                 MPI_{TYPE,COMM,WIN}_DELETE_ATTR, MPI_{TYPE,COMM,WIN}_SET_ATTR,
           41
                 MPI_{TYPE,COMM,WIN}_GET_ATTR, MPI_{TYPE,COMM,WIN}_FREE_KEYVAL,
           42
                 MPI_COMM_DUP, MPI_COMM_DISCONNECT, and MPI_COMM_FREE. The last three are
                 included because keyval is an argument to the copy and delete functions for attributes.
           43
           44
           45
                 6.7.6 Attributes Example
           46
                      Advice to users.
                                         This example shows how to write a collective communication
           47
                      operation that uses caching to be more efficient after the first call. The coding style
```

10

12 13

14 15

16

17

18

19

20

21

22

23

24

25 26

27 28

30

42

43 44

45

46 47

²⁹ ticket252-W.

35 ticket252-W.

ticket252-W

ticket252-W.

 39 ticket-248T.

reasons:

- It is not, in general, possible to store a string as an attribute from Fortran.
- It is not easy to set up the delete function for a string attribute unless it is known to have been allocated from the heap.
- To make the attribute key useful additional code to call strdup is necessary. If this is not standardized then users have to write it. This is extra unneeded work which we can easily eliminate.
- The Fortran binding is not trivial to write (it will depend on details of the Fortran compilation system), and will not be portable. Therefore it should be in the library rather than in user code.

```
(End of rationale.)
```

Advice to users. The above definition means that it is safe simply to print the string returned by MPI_COMM_GET_NAME, as it is always a valid string even if there was no name.

Note that associating a name with a communicator has no effect on the semantics of an MPI program, and will (necessarily) increase the store requirement of the program, since the names must be saved. Therefore there is no requirement that users use these functions to associate names with communicators. However debugging and profiling MPI applications may be made easier if names are associated with communicators, since the debugger or profiler should then be able to present information in a less cryptic manner. (*End of advice to users*.)

The following functions are used for setting and getting names of datatypes.

```
MPI_TYPE_SET_NAME (datatype, type_name)
           [ticket252-W.]datatype
 INOUT
                                     datatype whose identifier is to be set (handle)
 IN
           type_name
                                     the character string which is remembered as the name
                                     (string)
int MPI_Type_set_name(MPI_Datatype datatype, char *type_name)
MPI_TYPE_SET_NAME(DATATYPE, TYPE_NAME, IERROR)
    INTEGER DATATYPE, IERROR
    CHARACTER*(*) TYPE_NAME
MPI_Type_set_name(datatype, type_name, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    CHARACTER(LEN=*), INTENT(IN) :: type_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{void MPI::Datatype::Set_name(const char* type_name)(binding deprecated, see
              Section 15.2) }
```

ticket252-W.

```
284
```

```
MPI_TYPE_GET_NAME (datatype, type_name, resultlen)
            2
                   IN
                             [ticket252-W.]datatype
                                                        datatype whose name is to be returned (handle)
            3
                   OUT
                             type_name
                                                        the name previously stored on the datatype, or a empty
                                                        string if no such name exists (string)
                   OUT
                             resultlen
                                                        length of returned name (integer)
ticket 252-W.
                 int MPI_Type_get_name(MPI_Datatype datatype, char *type_name, int
                                *resultlen)
ticket252-W. 11
                 MPI_TYPE_GET_NAME(DATATYPE, TYPE_NAME, RESULTLEN, IERROR)
ticket 252	ext{-W}. 12
                      INTEGER DATATYPE, RESULTLEN, IERROR
                     CHARACTER*(*) TYPE_NAME
ticket-248T.
                 MPI_Type_get_name(datatype, type_name, resultlen, ierror)
            15
                     TYPE(MPI_Datatype), INTENT(IN) :: datatype
            16
                     CHARACTER(LEN=*), INTENT(OUT) :: type_name
            17
                     INTEGER, INTENT(OUT) :: resultlen
            18
                     INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            19
                 {void MPI::Datatype::Get_name(char* type_name, int& resultlen) const(binding
            20
                                deprecated, see Section 15.2) }
           21
            22
                     Named predefined datatypes have the default names of the datatype name. For exam-
           23
                 ple, MPI_WCHAR has the default name of MPI_WCHAR.
            24
                     The following functions are used for setting and getting names of windows.
            25
            26
            27
                 MPI_WIN_SET_NAME (win, win_name)
            28
                   INOUT
                            win
                                                        window whose identifier is to be set (handle)
            29
                   IN
                            win_name
                                                        the character string which is remembered as the name
            30
                                                        (string)
            31
            32
           33
                 int MPI_Win_set_name(MPI_Win win, char *win_name)
            34
                 MPI_WIN_SET_NAME(WIN, WIN_NAME, IERROR)
            35
                      INTEGER WIN, IERROR
            36
                     CHARACTER*(*) WIN_NAME
ticket-248T. ^{37}
                 MPI_Win_set_name(win, win_name, ierror)
                     TYPE(MPI_Win), INTENT(IN) :: win
            40
                     CHARACTER(LEN=*), INTENT(IN) :: win_name
            41
                      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            42
                 {void MPI::Win::Set_name(const char* win_name)(binding deprecated, see
            43
                                Section 15.2) }
            44
            45
```

Chapter 8

MPI Environmental Management

This chapter discusses routines for getting and, where appropriate, setting various parameters that relate to the MPI implementation and the execution environment (such as error handling). The procedures for entering and leaving the MPI execution environment are also described here.

8.1 Implementation Information

8.1.1 Version Inquiries

#define MPI_VERSION

In order to cope with changes to the MPI Standard, there are both compile-time and runtime ways to determine which version of the standard is in use in the environment one is using.

The "version" will be represented by two separate integers, for the version and subversion: In C and C++,

```
#define MPI_SUBVERSION 2
in Fortran,
    INTEGER [ticket240-L.]:: MPI_VERSION, MPI_SUBVERSION
    PARAMETER (MPI_VERSION
    PARAMETER (MPI_SUBVERSION = 2)
For runtime determination,
MPI_GET_VERSION( version, subversion )
 OUT
          version
                                     version number (integer)
 OUT
          subversion
                                     subversion number (integer)
int MPI_Get_version(int *version, int *subversion)
MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)
    INTEGER VERSION, SUBVERSION, IERROR
MPI_Get_version(version, subversion, ierror)
```

12 13 14

15

17

18 19

20 21

22

23

24

26

27 28

29

30 31

34

35 36

37

42 43

```
{void MPI::Get_processor_name(char* name, int& resultlen)(binding deprecated, see Section 15.2)}
```

This routine returns the name of the processor on which it was called at the moment of the call. The name is a character string for maximum flexibility. From this value it must be possible to identify a specific piece of hardware; possible values include "processor 9 in rack 4 of mpp.cs.org" and "231" (where 231 is the actual processor number in the running homogeneous system). The argument name must represent storage that is at least MPI_MAX_PROCESSOR_NAME characters long. MPI_GET_PROCESSOR_NAME may write up to this many characters into name.

The number of characters actually written is returned in the output argument, resultlen. In C, a null character is additionally stored at name[resultlen]. The resultlen cannot be larger then MPI_MAX_PROCESSOR_NAME-1. In Fortran, name is padded on the right with blank characters. The resultlen cannot be larger then MPI_MAX_PROCESSOR_NAME.

Rationale. This function allows MPI implementations that do process migration to return the current processor. Note that nothing in MPI requires or defines process migration; this definition of MPI_GET_PROCESSOR_NAME simply allows such an implementation. (End of rationale.)

Advice to users. The user must provide at least MPI_MAX_PROCESSOR_NAME space to write the processor name — processor names can be this long. The user should examine the output argument, resultlen, to determine the actual length of the name. (End of advice to users.)

The constant MPI_BSEND_OVERHEAD provides an upper bound on the fixed overhead per message buffered by a call to MPI_BSEND (see Section 3.6.1).

8.2 Memory Allocation

In some systems, message-passing and remote-memory-access (RMA) operations run faster when accessing specially allocated memory (e.g., memory that is shared by the other processes in the communicating group on an SMP). MPI provides a mechanism for allocating and freeing such special memory. The use of such memory for message-passing or RMA is not mandatory, and this memory can be used without restrictions as any other dynamically allocated memory. However, implementations may restrict the use of the MPI_WIN_LOCK and MPI_WIN_UNLOCK functions to windows allocated in such memory (see Section 11.4.3.)

```
MPI_ALLOC_MEM(size, info, baseptr)
```

```
IN size size of memory segment in bytes (non-negative integer)

IN info info argument (handle)

OUT baseptr pointer to beginning of memory segment allocated
```

int MPI_Alloc_mem(MPI_Aint size, MPI_Info info, void *baseptr)

MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)

ticket-248T.

²⁹ ticket-248T.

```
INTEGER INFO, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR

MPI_Alloc_mem(size, info, baseptr, ierror)
    USE, INTRINSIC :: ISO_C_BINDING
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

{void* MPI::Alloc_mem(MPI::Aint size, const MPI::Info& info)(binding deprecated, see Section 15.2)}
```

The info argument can be used to provide directives that control the desired location of the allocated memory. Such a directive does not affect the semantics of the call. Valid info values are implementation-dependent; a null directive value of info = MPI_INFO_NULL is always valid.

The function MPI_ALLOC_MEM may return an error code of class MPI_ERR_NO_MEM to indicate it failed because memory is exhausted.

The function MPI_FREE_MEM may return an error code of class MPI_ERR_BASE to indicate an invalid base argument.

Rationale. The C and C++ bindings of MPI_ALLOC_MEM and MPI_FREE_MEM are similar to the bindings for the malloc and free C library calls: a call to MPI_Alloc_mem(..., &base) should be paired with a call to MPI_Free_mem(base) (one less level of indirection). Both arguments are declared to be of same type void* so as to facilitate type casting. The Fortran binding is consistent with the C and C++ bindings: the Fortran MPI_ALLOC_MEM call returns in baseptr the (integer valued) address of the allocated memory. The base argument of MPI_FREE_MEM is a choice argument, which passes (a reference to) the variable stored at that location. (End of rationale.)

Advice to implementors. If MPI_ALLOC_MEM allocates special memory, then a design similar to the design of C malloc and free functions has to be used, in order to find out the size of a memory segment, when the segment is freed. If no special memory is used, MPI_ALLOC_MEM simply invokes malloc, and MPI_FREE_MEM invokes free.

A call to MPI_ALLOC_MEM can be used in shared memory systems to allocate memory in a shared memory segment. (End of advice to implementors.)

Example 8.1

Example of use of MPI_ALLOC_MEM, in Fortran with pointer support. We assume 4-byte REALs, and assume that pointers are address-sized.

```
REAL A
14
     POINTER (P, A(100,100))
                                  ! no memory is allocated
15
     CALL MPI_ALLOC_MEM(4*100*100, MPI_INFO_NULL, P, IERR)
16
     ! memory is allocated
17
     . . .
18
     A(3,5) = 2.71;
19
     . . .
20
     CALL MPI_FREE_MEM(A, IERR) ! memory is freed
21
```

Since standard Fortran does not support (C-like) pointers, this code is not Fortran 77 or Fortran 90 code. Some compilers (in particular, at the time of writing, g77 and Fortran compilers for Intel) do not support this code.

```
Example 8.2 Same example, in C
```

```
float (* f)[100][100];
/* no memory is allocated */
MPI_Alloc_mem(sizeof(float)*100*100, MPI_INFO_NULL, &f);
/* memory allocated */
(*f)[5][3] = 2.71;

MPI_Free_mem(f);
```

8.3 Error Handling

An MPI implementation cannot or may choose not to handle some errors that occur during MPI calls. These can include errors that generate exceptions or traps, such as floating point errors or access violations. The set of errors that are handled by MPI is implementation-dependent. Each such error generates an MPI exception.

The above text takes precedence over any text on error handling within this document. Specifically, text that states that errors *will* be handled should be read as *may* be handled.

A user can associate error handlers to three types of objects: communicators, windows, and files. The specified error handling routine will be used for any MPI exception that occurs during a call to MPI for the respective object. MPI calls that are not related to any objects are considered to be attached to the communicator MPI_COMM_WORLD. The attachment

2

3

4

5

6

7

8 9

10

11

12

13 14

15 16

17 18

26

33

34

35

36

37

38

39

41

42

43

44

45

46

47

48

ticket 252-W. ²⁷

ticket252-W. $_{29}$

ticket252-W. $_{31}$

ticket-248T.

ticket252-W. $_{40}$

The MPI function MPI_ERRHANDLER_FREE can be used to free an error handler that was created by a call to MPI_XXX_CREATE_ERRHANDLER.

MPI_{COMM,WIN,FILE}_GET_ERRHANDLER behave as if a new error handler object

is created. That is, once the error handler is no longer needed, MPI_ERRHANDLER_FREE should be called with the error handler returned from MPI_ERRHANDLER_GET or MPI_{COMM,WIN,FILE}_GET_ERRHANDLER to mark the error handler for deallocation.

This provides behavior similar to that of MPI_COMM_GROUP and MPI_GROUP_FREE.

Advice to implementors. High-quality implementation should raise an error when an error handler that was created by a call to MPI_XXX_CREATE_ERRHANDLER is attached to an object of the wrong type with a call to MPI_YYY_SET_ERRHANDLER. To do so, it is necessary to maintain, with each error handler, information on the typedef of the associated user function. (End of advice to implementors.)

The syntax for these calls is given below.

8.3.1 Error Handlers for Communicators

INTEGER ERRHANDLER, IERROR

```
ticket252-W. 20 MPI_COMM_CREATE_ERRHANDLER([function]comm_errhandler_fn, errhandler)

IN [ticket252-W.][function]comm_errhandler_fn user defined error handling procedure (function)

24 OUT errhandler MPI error handler (handle)
```

int MPI_Comm_create_errhandler(MPI_Comm_errhandler_function

```
*[function]comm_errhandler_fn, MPI_Errhandler *errhandler)
MPI_COMM_CREATE_ERRHANDLER([FUNCTION]COMM_ERRHANDLER_FN, ERRHANDLER,
```

```
IERROR)

EXTERNAL [FUNCTION] COMM_ERRHANDLER_FN
```

```
MPI_Comm_create_errhandler(comm_errhandler_fn, errhandler, ierror)
    EXTERNAL :: comm_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{
static MPI::Errhandler
```

```
[function] comm_errhandler_fn) (binding deprecated, see Section 15.2) }
Creates an error handler that can be attached to communicators. This function is
```

MPI::Comm::Create_errhandler(MPI::Comm::Errhandler_function*

identical to MPI_ERRHANDLER_CREATE, whose use is deprecated.

The user routine should be, in C, a function of type MPI_Comm_errhandler_function, which is defined as

```
typedef void MPI_Comm_errhandler_function(MPI_Comm *, int *, ...);
```

The first argument is the communicator in use. The second is the error code to be returned by the MPI routine that raised the error. If the routine would have returned

Unofficial Draft for Comment Only

MPI_ERR_IN_STATUS, it is the error code returned in the status for the request that caused the error handler to be invoked. The remaining arguments are "stdargs" arguments whose number and meaning is implementation-dependent. An implementation should clearly document these arguments. Addresses are used so that the handler may be written in Fortran. This typedef replaces MPI_Handler_function, whose use is deprecated.

```
In Fortran, the user routine should be of the form:
SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE)
INTEGER COMM, ERROR_CODE
In C++, the user routine should be of the form:
```

Rationale. The variable argument list is provided because it provides an ISO-standard hook for providing additional information to the error handler; without this hook, ISO C prohibits additional arguments. (*End of rationale*.)

Advice to users. A newly created communicator inherits the error handler that is associated with the "parent" communicator. In particular, the user can specify a "global" error handler for all communicators by associating this handler with the communicator MPI_COMM_WORLD immediately after initialization. (End of advice to users.)

```
MPI_COMM_SET_ERRHANDLER(comm, errhandler)
```

```
INOUT comm communicator (handle)

IN errhandler new error handler for communicator (handle)

int MPI_Comm_set_errhandler(MPI_Comm comm, MPI_Errhandler errhandler)

MPI_COMM_SET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
    INTEGER COMM, ERRHANDLER, IERROR

MPI_Comm_set_errhandler(comm, errhandler, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

{void MPI::Comm::Set_errhandler(const MPI::Errhandler& errhandler) (binding deprecated, see Section 15.2) }
```

Attaches a new error handler to a communicator. The error handler must be either a predefined error handler, or an error handler created by a call to MPI_COMM_CREATE_ERRHANDLER. This call is identical to MPI_ERRHANDLER_SET, whose use is deprecated.

 $_{34}$ ticket-248T.

```
MPI_COMM_GET_ERRHANDLER(comm, errhandler)
            2
                   IN
                             comm
                                                         communicator (handle)
            3
                   OUT
                             errhandler
                                                         error handler currently associated with communicator
                                                         (handle)
            6
                 int MPI_Comm_get_errhandler(MPI_Comm comm, MPI_Errhandler *errhandler)
            7
                 MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR)
                      INTEGER COMM, ERRHANDLER, IERROR
ticket-248
T. ^{\scriptscriptstyle 10}
            11
                 MPI_Comm_get_errhandler(comm, errhandler, ierror)
            12
                      TYPE(MPI_Comm), INTENT(IN) :: comm
                      TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
            13
            14
                      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            15
                 {MPI::Errhandler MPI::Comm::Get_errhandler() const(binding deprecated, see
            16
                                 Section 15.2) }
            17
            18
                      Retrieves the error handler currently associated with a communicator. This call is
            19
                 identical to MPI_ERRHANDLER_GET, whose use is deprecated.
            20
                      Example: A library function may register at its entry point the current error handler
           21
                 for a communicator, set its own private error handler for this communicator, and restore
            22
                 before exiting the previous error handler.
            23
            24
                 8.3.2 Error Handlers for Windows
{
m ticket 252-W} .
                 MPI_WIN_CREATE_ERRHANDLER([function]win_errhandler_fn, errhandler)
                   IN
                             [ticket252-W.][function]win_errhandler_fn user defined error handling procedure (func-
            29
                                                         tion)
            30
            31
                   OUT
                             errhandler
                                                         MPI error handler (handle)
                 int MPI_Win_create_errhandler(MPI_Win_errhandler_function
ticket 252-W.
                                *[function]win_errhandler_fn, MPI_Errhandler *errhandler)
ticket252-W. 36
                 MPI_WIN_CREATE_ERRHANDLER([FUNCTION]WIN_ERRHANDLER_FN, ERRHANDLER, IERROR)
ticket252-W. 37
                      EXTERNAL [FUNCTION] WIN_ERRHANDLER_FN
                      INTEGER ERRHANDLER, IERROR
ticket-248T. _{39}^{\circ\circ}
                 MPI_Win_create_errhandler(win_errhandler_fn, errhandler, ierror)
                      EXTERNAL :: win_errhandler_fn
            41
                      TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
            42
                      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            43
                 {static MPI::Errhandler
            44
                                MPI::Win::Create_errhandler(MPI::Win::Errhandler_function*
            45
ticket 252	ext{-W}. 46
                                 [function]win_errhandler_fn) (binding deprecated, see Section 15.2) }
```

```
Creates an error handler that can be attached to a window object. The user routine
should be, in C, a function of type MPI_Win_errhandler_function which is defined as
typedef void MPI_Win_errhandler_function(MPI_Win *, int *, ...);
    The first argument is the window in use, the second is the error code to be returned.
    In Fortran, the user routine should be of the form:
SUBROUTINE WIN_ERRHANDLER_FUNCTION(WIN, ERROR_CODE)
    INTEGER WIN, ERROR_CODE
    In C++, the user routine should be of the form:
{typedef void MPI::Win::Errhandler_function(MPI::Win &, int *, ...);
               (binding deprecated, see Section 15.2)
                                                                                       12
                                                                                       13
                                                                                       14
MPI_WIN_SET_ERRHANDLER(win, errhandler)
                                                                                       15
  INOUT
                                      window (handle)
           win
                                                                                       16
  IN
           errhandler
                                      new error handler for window (handle)
                                                                                       18
                                                                                       19
int MPI_Win_set_errhandler(MPI_Win win, MPI_Errhandler errhandler)
                                                                                       20
MPI_WIN_SET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
                                                                                       21
    INTEGER WIN, ERRHANDLER, IERROR
                                                                                         ticket-248T
MPI_Win_set_errhandler(win, errhandler, ierror)
                                                                                       24
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
                                                                                       26
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                       27
{void MPI::Win::Set_errhandler(const MPI::Errhandler& errhandler) (binding
                                                                                       28
               deprecated, see Section 15.2) }
                                                                                       29
                                                                                       30
    Attaches a new error handler to a window. The error handler must be either a pre-
                                                                                       31
defined error handler, or an error handler created by a call to
MPI_WIN_CREATE_ERRHANDLER.
                                                                                       33
                                                                                       34
MPI_WIN_GET_ERRHANDLER(win, errhandler)
                                                                                       35
                                                                                       36
  IN
           win
                                      window (handle)
                                                                                       37
  OUT
           errhandler
                                      error handler currently associated with window (han-
                                      dle)
int MPI_Win_get_errhandler(MPI_Win win, MPI_Errhandler *errhandler)
                                                                                       41
                                                                                       42
MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
                                                                                       43
    INTEGER WIN, ERRHANDLER, IERROR
                                                                                       44 ticket-248T.
MPI_Win_get_errhandler(win, errhandler, ierror)
                                                                                       46
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
1
                 {MPI::Errhandler MPI::Win::Get_errhandler() const(binding deprecated, see
            2
                                Section 15.2) }
                     Retrieves the error handler currently associated with a window.
                        Error Handlers for Files
                 8.3.3
            6
ticket252-W. 9
                 MPI_FILE_CREATE_ERRHANDLER([function]file_errhandler_fn, errhandler)
                             [ticket252-W.][function]file_errhandler_fn user defined error handling procedure (func-
                   IN
            11
                                                         tion)
            12
                   OUT
                             errhandler
                                                         MPI error handler (handle)
            13
            14
                 int MPI_File_create_errhandler(MPI_File_errhandler_function
            15
ticket252-W. 16
                                *[function]file_errhandler_fn, MPI_Errhandler *errhandler)
ticket252-W.
                 MPI_FILE_CREATE_ERRHANDLER([FUNCTION]FILE_ERRHANDLER_FN, ERRHANDLER,
                                IERROR)
ticket 252-W.
                      EXTERNAL [FUNCTION] FILE_ERRHANDLER_FN
                      INTEGER ERRHANDLER, IERROR
ticket-248T. 21
                 MPI_File_create_errhandler(file_errhandler_fn, errhandler, ierror)
                      EXTERNAL :: file_errhandler_fn
            23
                      TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
            24
                      INTEGER, OPTIONAL, INTENT(OUT) :: ierror
            26
                 {static MPI::Errhandler
            27
                                MPI::File::Create_errhandler(MPI::File::Errhandler_function*
ticket252-W.
                                 [function]file_errhandler_fn) (binding deprecated, see Section 15.2) }
                      Creates an error handler that can be attached to a file object. The user routine should
            30
                 be, in C, a function of type MPI_File_errhandler_function, which is defined as
            31
                 typedef void MPI_File_errhandler_function(MPI_File *, int *, ...);
            32
            33
                     The first argument is the file in use, the second is the error code to be returned.
            34
                     In Fortran, the user routine should be of the form:
           35
                 SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
            36
                      INTEGER FILE, ERROR_CODE
           37
            38
                     In C++, the user routine should be of the form:
                 {typedef void MPI::File::Errhandler_function(MPI::File &, int *, ...);
            39
                                 (binding deprecated, see Section 15.2)
            41
            42
            43
                 MPI_FILE_SET_ERRHANDLER(file, errhandler)
            44
                   INOUT
            45
                   IN
                             errhandler
                                                         new error handler for file (handle)
            46
            47
            48
                 int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)
```

Chapter 9

The Info Object

Many of the routines in MPI take an argument info. info is an opaque object with a handle of type MPI_Info in C and Fortran with the mpi_f08 module, MPI::Info in C++, and INTEGER in Fortran with the mpi module or the include file mpif.h. It stores an unordered set of (key,value) pairs (both key and value are strings). A key can have only one value. MPI reserves several keys and requires that if an implementation uses a reserved key, it must provide the specified functionality. An implementation is not required to support these keys and may support any others not reserved by MPI.

An implementation must support info objects as caches for arbitrary (key, value) pairs, regardless of whether it recognizes the key. Each function that takes hints in the form of an MPI_Info must be prepared to ignore any key it does not recognize. This description of info objects does not attempt to define how a particular function should react if it recognizes a key but not the associated value. MPI_INFO_GET_NKEYS, MPI_INFO_GET_NTHKEY, MPI_INFO_GET_VALUELEN, and MPI_INFO_GET must retain all (key,value) pairs so that layered functionality can also use the Info object.

Keys have an implementation-defined maximum length of MPI_MAX_INFO_KEY, which is at least 32 and at most 255. Values have an implementation-defined maximum length of MPI_MAX_INFO_VAL. In Fortran, leading and trailing spaces are stripped from both. Returned values will never be larger than these maximum lengths. Both key and value are case sensitive.

Rationale. Keys have a maximum length because the set of known keys will always be finite and known to the implementation and because there is no reason for keys to be complex. The small maximum size allows applications to declare keys of size MPI_MAX_INFO_KEY. The limitation on value sizes is so that an implementation is not forced to deal with arbitrarily long strings. (End of rationale.)

Advice to users. MPI_MAX_INFO_VAL might be very large, so it might not be wise to declare a string of that size. (End of advice to users.)

When it is an argument to a nonblocking routine, info is parsed before that routine returns, so that it may be modified or freed immediately after return.

When the descriptions refer to a key or value as being a boolean, an integer, or a list, they mean the string representation of these types. An implementation may define its own rules for how info value strings are converted to other types, but to ensure portability, every implementation must support the following representations. Legal values for a boolean must

¹⁵ ticket231-C. ¹⁶ ticket231-C.

ticket-248T.

11

12 13

14

15

16

18

19

20

21

22

23

24

26

27

28

35

36

37

42

43

44

45

46

47 48

```
int MPI_Comm_spawn(char *command, char *argv[], int maxprocs, MPI_Info
             info, int root, MPI_Comm comm, MPI_Comm *intercomm,
             int array_of_errcodes[])
MPI_COMM_SPAWN(COMMAND, ARGV, MAXPROCS, INFO, ROOT, COMM, INTERCOMM,
             ARRAY_OF_ERRCODES, IERROR)
    CHARACTER*(*) COMMAND, ARGV(*)
    INTEGER INFO, MAXPROCS, ROOT, COMM, INTERCOMM, ARRAY_OF_ERRCODES(*),
    IERROR
MPI_Comm_spawn(command, argv, maxprocs, info, root, comm, intercomm,
             array_of_errcodes, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: command, argv(*)
    INTEGER, INTENT(IN) :: maxprocs, root
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER, INTENT(OUT) :: array_of_errcodes(*) ! optional by
    overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
{MPI::Intercomm MPI::Intracomm::Spawn(const char* command,
             const char* argv[], int maxprocs, const MPI::Info& info,
             int root, int array_of_errcodes[]) const(binding deprecated, see
             Section 15.2) }
{MPI::Intercomm MPI::Intracomm::Spawn(const char* command,
             const char* argv[], int maxprocs, const MPI::Info& info,
             int root) const(binding deprecated, see Section 15.2) }
```

MPI_COMM_SPAWN tries to start maxprocs identical copies of the MPI program specified by command, establishing communication with them and returning an intercommunicator. The spawned processes are referred to as children. The children have their own MPI_COMM_WORLD, which is separate from that of the parents. MPI_COMM_SPAWN is collective over comm, and also may not return until MPI_INIT has been called in the children. Similarly, MPI_INIT in the children may not return until all parents have called MPI_COMM_SPAWN. In this sense, MPI_COMM_SPAWN in the parents and MPI_INIT in the children form a collective operation over the union of parent and child processes. The intercommunicator returned by MPI_COMM_SPAWN contains the parent processes in the local group and the child processes in the remote group. The ordering of processes in the local and remote groups is the same as the ordering of the group of the comm in the parents and of MPI_COMM_WORLD of the children, respectively. This intercommunicator can be obtained in the children through the function MPI_COMM_GET_PARENT.

Advice to users. An implementation may automatically establish communication before MPI_INIT is called by the children. Thus, completion of MPI_COMM_SPAWN in the parent does not necessarily mean that MPI_INIT has been called in the children (although the returned intercommunicator can be used immediately). (End of advice to users.)

8

12

13

14

15

16

17

18

19

20

21

22

23

24

25 26

27

28

29 30

31

32

33

34

35

36

37

47

48

1

2

3

9 ticket231-C.

ticket 231-C. 10

The info argument The info argument to all of the routines in this chapter is an opaque handle of type MPI_Info in C and Fortran with the mpi_f08 module, MPI::Info in C++ and INTEGER in Fortran with the mpi module or the include file mpif.h. It is a container for a number of user-specified (key,value) pairs. key and value are strings (null-terminated char* in C, character*(*) in Fortran). Routines to create and manipulate the info argument are described in Section 9 on page 349.

spawning. (End of advice to users.)

Advice to users. By default, requests are hard and MPI errors are fatal. This means

that by default there will be a fatal error if MPI cannot spawn all the requested

processes. If you want the behavior "spawn as many processes as possible, up to N," you should do a soft spawn, where the set of allowed values $\{m_i\}$ is $\{0...N\}$. However,

this is not completely portable, as implementations are not required to support soft

For the SPAWN calls, info provides additional (and possibly implementation-dependent) instructions to MPI and the runtime system on how to start processes. An application may pass MPI_INFO_NULL in C or Fortran. Portable programs not requiring detailed control over process locations should use MPI_INFO_NULL.

MPI does not specify the content of the info argument, except to reserve a number of special key values (see Section 10.3.4 on page 366). The info argument is quite flexible and could even be used, for example, to specify the executable and its command-line arguments. In this case the command argument to MPI_COMM_SPAWN could be empty. The ability to do this follows from the fact that MPI does not specify how an executable is found, and the info argument can tell the runtime system where to "find" the executable "" (empty string). Of course a program that does this will not be portable across MPI implementations.

The root argument All arguments before the root argument are examined only on the process whose rank in comm is equal to root. The value of these arguments on other processes is ignored.

The array_of_errcodes argument The array_of_errcodes is an array of length maxprocs in which MPI reports the status of each process that MPI was requested to start. If all maxprocs processes were spawned, array_of_errcodes is filled in with the value MPI_SUCCESS. If only m $(0 \le m \le \text{maxprocs})$ processes are spawned, m of the entries will contain MPI_SUCCESS and the rest will contain an implementation-specific error code indicating the reason MPI could not start the process. MPI does not specify which entries correspond to failed processes. An implementation may, for instance, fill in error codes in one-to-one correspondence with a detailed specification in the info argument. These error codes all belong to the error class MPI_ERR_SPAWN if there was no error in the argument list. In C or in the Fortran mpi module or mpif.h include file, an application may pass MPI_ERRCODES_IGNORE if it is not interested in the error codes. In the Fortran mpi_f08 module or in C++ this constant does not exist, and the array_of_errcodes argument may be omitted from the argument list.

ticket244-P. ticket244-P. ticket244-P. 41

ticket244-P. 43

ticket244-P. 44 ticket244-P. 45

MPI_ERRCODES_IGNORE[in Fortran] is a special type of constant, like MPI_BOTTOM. See the discussion in Section 2.5.4 on page 15. In the Fortran mpi_f08 module, the optional argument has to be implemented through function overloading. See the discussion in Section 2.5.2 on page 14. (End of advice to implementors.)

Advice to implementors. In the Fortran mpi module or mpif.h include file,

MPI standard, process 0 must return from the complete call after a bounded delay, even if process 1 does not reach any MPI call in this period of time. According to another interpretation, the complete call may block until process 1 reaches the wait call, or reaches another MPI call. The qualitative behavior is the same, under both interpretations, unless a process is caught in an infinite compute loop, in which case the difference may not matter. However, the quantitative expectations are different. Different MPI implementations reflect these different interpretations. While this ambiguity is unfortunate, it does not seem to affect many real codes. The MPI forum decided not to decide which interpretation of the standard is the correct one, since the issue is very contentious, and a decision would have much impact on implementors but less impact on users. (End of rationale.)

11.7.3 Registers and Compiler Optimizations

Advice to users. All the material in this section is an advice to users. (End of advice to users.)

A coherence problem exists between variables kept in registers and the memory value of these variables. An RMA call may access a variable in memory (or cache), while the up-to-date value of this variable is in register. A get will not return the latest variable value, and a put may be overwritten when the register is stored back in memory.

The problem is illustrated by the following code:

Source of Process 1	Source of Process 2	Executed in Process 2
bbbb = 777	buff = 999	reg_A:=999
call MPI_WIN_FENCE	call MPI_WIN_FENCE	
call MPI_PUT(bbbb		stop appl.thread
into buff of process 2)		buff:=777 in PUT handler
		continue appl.thread
call MPI_WIN_FENCE	call MPI_WIN_FENCE	
	ccc = buff	ccc:=reg_A

In this example, variable buff is allocated in the register reg_A and therefore ccc will have the old value of buff and not the new value 777.

This problem, which also afflicts in some cases send/receive communication, is discussed more at length in Section 16.2.2.

MPI implementations will avoid this problem for standard conforming C programs. Many Fortran compilers will avoid this problem, without disabling compiler optimizations. However, in order to avoid register coherence problems in a completely portable manner, users should restrict their use of RMA windows to variables stored in in modules or COMMON blocks, or to variables that were declared VOLATILE [(while VOLATILE is not a standard Fortran declaration, it is supported by many Fortran compilers).](but this attribute may inhibit optimization of any code containing the RMA window). [Details]Further details and [an] additional solutions are discussed in Section 16.2.2, "A Problem with Register Optimization and Temporary Memory Modifications," on page 549. See also, "Problems Due to Data Copying and Sequence Association," on page 545, for additional Fortran problems.

ticket238-J. ticket238-J.

 $_{^{43}}$ ticket238-J. ticket238-J. ticket238-J. ticket238-J.

428 1 For a regular request, the operation associated with the request is performed by the 2 MPI implementation, and the operation completes without intervention by the application. 3 For a generalized request, the operation associated with the request is performed by the 4 application; therefore, the application must notify MPI when the operation completes. This 5 is done by making a call to MPI_GREQUEST_COMPLETE. MPI maintains the "completion" 6 status of generalized requests. Any other request state has to be maintained by the user. 7 A new generalized request is started with 8 9 MPI_GREQUEST_START(query_fn, free_fn, cancel_fn, extra_state, request) 10 11 IN query_fn callback function invoked when request status is queried 12 (function) 13 IN free_fn callback function invoked when request is freed (func-14 tion) 15 IN cancel_fn callback function invoked when request is cancelled 16 (function) 17 18 IN extra state extra_state 19 OUT request generalized request (handle) 20 21 int MPI_Grequest_start(MPI_Grequest_query_function *query_fn, 22

```
MPI_Grequest_free_function *free_fn,
MPI_Grequest_cancel_function *cancel_fn, void *extra_state,
MPI_Request *request)
```

```
MPI_GREQUEST_START(QUERY_FN, FREE_FN, CANCEL_FN, EXTRA_STATE, REQUEST,
             IERROR)
```

INTEGER REQUEST, IERROR

EXTERNAL QUERY_FN, FREE_FN, CANCEL_FN

INTEGER, OPTIONAL, INTENT(OUT) ::

INTEGER (KIND=MPI_ADDRESS_KIND) EXTRA_STATE

```
MPI_Grequest_start(query_fn, free_fn, cancel_fn, extra_state, request,
             ierror)
   EXTERNAL ::
                query_fn, free_fn, cancel_fn
   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
   TYPE(MPI_Request), INTENT(OUT) :: request
```

{static MPI::Grequest

23

24

25 26

27

28

29

32

33

34

35

36

37 38

39

41

42

43 44

45

46

47

ticket-248T. $_{31}$

```
MPI::Grequest::Start(const MPI::Grequest::Query_function*
query_fn, const MPI::Grequest::Free_function* free_fn,
const MPI::Grequest::Cancel_function* cancel_fn,
void *extra_state) (binding deprecated, see Section 15.2) }
```

ierror

Note that a generalized request belongs, in C++, to the class Advice to users. MPI::Grequest, which is a derived class of MPI::Request. It is of the same type as regular requests, in C and Fortran. (End of advice to users.)

The call starts a generalized request and returns a handle to it in request.

Unofficial Draft for Comment Only

```
The syntax and meaning of the callback functions are listed below. All callback func-
tions are passed the extra_state argument that was associated with the request by the
starting call MPI_GREQUEST_START[. This can]; extra_state can be used to maintain
                                                                                           <sup>3</sup> ticket0.
user-defined state for the request.
    In C, the query function is
typedef int MPI_Grequest_query_function(void *extra_state,
               MPI_Status *status);
in Fortran
SUBROUTINE GREQUEST_QUERY_FUNCTION(EXTRA_STATE, STATUS, IERROR)
                                                                                           11
    INTEGER STATUS (MPI_STATUS_SIZE), IERROR
                                                                                           12
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                           13
and in C++
                                                                                           14
                                                                                           15
{typedef int MPI::Grequest::Query_function(void* extra_state,
                                                                                           16
               MPI::Status& status); (binding deprecated, see Section 15.2)}
                                                                                           ^{17} ticket0.
    [query_fn] The query_fn function computes the status that should be returned for the
generalized request. The status also includes information about successful/unsuccessful
                                                                                           19
cancellation of the request (result to be returned by MPI_TEST_CANCELLED).
                                                                                           20 ticket0.
    [query_fn]The query_fn callback is invoked by the MPI_{WAIT|TEST}{ANY|SOME|ALL}
                                                                                           21
call that completed the generalized request associated with this callback. The callback
                                                                                           22
function is also invoked by calls to MPI_REQUEST_GET_STATUS, if the request is com-
plete when the call occurs. In both cases, the callback is passed a reference to the cor-
                                                                                           24
responding status variable passed by the user to the MPI call; the status set by the call-
back function is returned by the MPI call. If the user provided MPI_STATUS_IGNORE or
MPI_STATUSES_IGNORE to the MPI function that causes query_fn to be called or has omit-
                                                                                           <sup>27</sup> ticket 244-P.
ted the status argument (with the mpi_f08 Fortran module or C++), then MPI will pass a
                                                                                           28
valid status object to query_fn, and this status will be ignored upon return of the callback
                                                                                           29
function. Note that query_fn is invoked only after MPI_GREQUEST_COMPLETE is called
on the request; it may be invoked several times for the same generalized request, e.g., if
the user calls MPI_REQUEST_GET_STATUS several times for this request. Note also that
a call to MPI_{WAIT|TEST}{SOME|ALL} may cause multiple invocations of query_fn call-
                                                                                           33
back functions, one for each generalized request that is completed by the MPI call. The
                                                                                           34
order of these invocations is not specified by MPI.
                                                                                           35
    In C, the free function is
                                                                                           36
                                                                                           37
typedef int MPI_Grequest_free_function(void *extra_state);
                                                                                           38
and in Fortran
                                                                                           39
SUBROUTINE GREQUEST_FREE_FUNCTION(EXTRA_STATE, IERROR)
                                                                                           41
    INTEGER IERROR
                                                                                           42
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                           43
and in C++
                                                                                           44
                                                                                           45
{typedef int MPI::Grequest::Free_function(void* extra_state); (binding
               deprecated, see Section 15.2)
                                                                                           <sup>47</sup> ticket0.
```

ticket0. 41

ticket0. 43

[free_fn]The free_fn function is invoked to clean up user-allocated resources when the generalized request is freed.

ticket0.

[free_fn]The free_fn callback is invoked by the MPI_{WAIT|TEST}_{ANY|SOME|ALL} call that completed the generalized request associated with this callback. free_fn is invoked after the call to query_fn for the same request. However, if the MPI call completed multiple generalized requests, the order in which free_fn callback functions are invoked is not specified by MPI.

[free_fn]The free_fn callback is also invoked for generalized requests that are freed by a call to MPI_REQUEST_FREE (no call to WAIT_{WAIT|TEST}_{ANY|SOME|ALL}) will occur for such a request). In this case, the callback function will be called either in the MPI call MPI_REQUEST_FREE(request), or in the MPI call MPI_GREQUEST_COMPLETE(request), whichever happens last, i.e., in this case the actual freeing code is executed as soon as both calls MPI_REQUEST_FREE and MPI_GREQUEST_COMPLETE have occurred. The request is not deallocated until after free_fn completes. Note that free_fn will be invoked only once per request by a correct program.

Advice to users. Calling MPI_REQUEST_FREE(request) will cause the request handle to be set to MPI_REQUEST_NULL. This handle to the generalized request is no longer valid. However, user copies of this handle are valid until after free_fn completes since MPI does not deallocate the object until then. Since free_fn is not called until after MPI_GREQUEST_COMPLETE, the user copy of the handle can be used to make this call. Users should note that MPI will deallocate the object after free_fn executes. At this point, user copies of the request handle no longer point to a valid request. MPI will not set user copies to MPI_REQUEST_NULL in this case, so it is up to the user to avoid accessing this stale handle. This is a special case [where]in which MPI defers deallocating the object until a later time that is known by the user. (End of advice to users.)

```
In C, the cancel function is
typedef int MPI_Grequest_cancel_function(void *extra_state, int complete);
in Fortran
SUBROUTINE GREQUEST_CANCEL_FUNCTION(EXTRA_STATE, COMPLETE, IERROR)
    INTEGER IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
    LOGICAL COMPLETE
and in C++
{typedef int MPI::Grequest::Cancel_function(void* extra_state, bool complete); (binding deprecated, see Section 15.2)}
```

[cancel_fn] The cancel_fn function is invoked to start the cancelation of a generalized request. It is called by MPI_CANCEL(request). MPI passes [to the callback function complete=true] complete=true to the callback function if MPI_GREQUEST_COMPLETE was already called on the request, and complete=false otherwise.

All callback functions return an error code. The code is passed back and dealt with as appropriate for the error code by the MPI function that invoked the callback function. For example, if error codes are returned then the error code returned by the callback function

will be returned by the MPI function that invoked the callback function. In the case of an MPI_{WAIT|TEST}{ANY} call that invokes both query_fn and free_fn, the MPI call will return the error code returned by the last callback, namely free_fn. If one or more of the requests in a call to MPI_{WAIT|TEST}{SOME|ALL} failed, then the MPI call will return MPI_ERR_IN_STATUS. In such a case, if the MPI call was passed an array of statuses, then MPI will return in each of the statuses that correspond to a completed generalized request the error code returned by the corresponding invocation of its free_fn callback function. However, if the MPI function was passed MPI_STATUSES_IGNORE or the status argument was omitted, then the individual error codes returned by each callback functions will be lost.

Advice to users. query_fn must **not** set the error field of status since query_fn may be called by MPI_WAIT or MPI_TEST, in which case the error field of status should not change. The MPI library knows the "context" in which query_fn is invoked and can decide correctly when to put in the error field of status the returned error code. (End of advice to users.)

```
MPI_GREQUEST_COMPLETE(request)
INOUT request generalized request (handle)

int MPI_Grequest_complete(MPI_Request request)

MPI_GREQUEST_COMPLETE(REQUEST, IERROR)
    INTEGER REQUEST, IERROR

MPI_Grequest_complete(request, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror

{void MPI::Grequest::Complete() (binding deprecated, see Section 15.2) }
```

The call informs MPI that the operations represented by the generalized request request are complete (see definitions in Section 2.4). A call to MPI_WAIT(request, status) will return and a call to MPI_TEST(request, flag, status) will return flag=true only after a call to MPI_GREQUEST_COMPLETE has declared that these operations are complete.

MPI imposes no restrictions on the code executed by the callback functions. However, new nonblocking operations should be defined so that the general semantic rules about MPI calls such as MPI_TEST, MPI_REQUEST_FREE, or MPI_CANCEL still hold. For example, all these calls are supposed to be local and nonblocking. Therefore, the callback functions query_fn, free_fn, or cancel_fn should invoke blocking MPI communication calls only if the context is such that these calls are guaranteed to return in finite time. Once MPI_CANCEL is invoked, the cancelled operation should complete in finite time, irrespective of the state of other processes (the operation has acquired "local" semantics). It should either succeed, or fail without side-effects. The user should guarantee these same properties for newly defined operations.

Advice to implementors. A call to MPI_GREQUEST_COMPLETE may unblock a blocked user process/thread. The MPI library should ensure that the blocked user computation will resume. (*End of advice to implementors.*)

ticket244-P.

ticket-248T.

13.4. DATA ACCESS 461

It is erroneous to access the local buffer of a nonblocking data access operation, or to use that buffer as the source or target of other communications, between the initiation and completion of the operation.

The split collective routines support a restricted form of "nonblocking" operations for collective data access (see Section 13.4.5, page 480).

Coordination

Every noncollective data access routine MPI_FILE_XXX has a collective counterpart. For most routines, this counterpart is MPI_FILE_XXX_ALL or a pair of MPI_FILE_XXX_BEGIN and MPI_FILE_XXX_END. The counterparts to the MPI_FILE_XXX_SHARED routines are MPI_FILE_XXX_ORDERED.

The completion of a noncollective call only depends on the activity of the calling process. However, the completion of a collective call (which must be called by all members of the process group) may depend on the activity of the other processes participating in the collective call. See Section 13.6.4, page 502, for rules on semantics of collective calls.

Collective operations may perform much better than their noncollective counterparts, as global data accesses have significant potential for automatic optimization.

Data Access Conventions

Data is moved between files and processes by calling read and write routines. Read routines move data from a file into memory. Write routines move data from memory into a file. The file is designated by a file handle, fh. The location of the file data is specified by an offset into the current view. The data in memory is specified by a triple: buf, count, and datatype. Upon completion, the amount of data accessed by the calling process is returned in a status.

An offset designates the starting position in the file for an access. The offset is always in etype units relative to the current view. Explicit offset routines pass offset as an argument (negative values are erroneous). The file pointer routines use implicit offsets maintained by MPI.

A data access routine attempts to transfer (read or write) count data items of type datatype between the user's buffer buf and the file. The datatype passed to the routine must be a committed datatype. The layout of data in memory corresponding to buf, count, datatype is interpreted the same way as in MPI communication functions; see Section 3.2.2 on page 29 and Section 4.1.11 on page 111. The data is accessed from those parts of the file specified by the current view (Section 13.3, page 456). The type signature of datatype must match the type signature of some number of contiguous copies of the etype of the current view. As in a receive, it is erroneous to specify a datatype for reading that contains overlapping regions (areas of memory which would be stored into more than once).

The nonblocking data access routines indicate that MPI can start a data access and associate a request handle, request, with the I/O operation. Nonblocking operations are completed via MPI_TEST, MPI_WAIT, or any of their variants.

Data access operations, when completed, return the amount of data accessed in status.

Advice to users. To prevent problems with the argument copying and register optimization done by Fortran compilers, please note the hints in subsections "Problems Due to Data Copying and Sequence Association," and "A Problem with Register Optimization and Temporary Memory Modifications" in Section 16.2.2, pages 545 and 549. (End of advice to users.)

 47 ticket238-J.

ticket-248T. 38

ticket244-P. ⁶ ticket244-P. ⁸

For blocking routines, status is returned directly. For nonblocking routines and split collective routines, status is returned when the operation is completed. The number of datatype entries and predefined elements accessed by the calling process can be extracted from status by using MPI_GET_COUNT and MPI_GET_ELEMENTS, respectively. The interpretation of the MPI_ERROR field is the same as for other operations — normally undefined, but meaningful if an MPI routine returns MPI_ERR_IN_STATUS. The user can pass (in C and with the Fortran mpi module or mpif.h include file) MPI_STATUS_IGNORE in the status argument if the return value of this argument is not needed. [In]With the Fortran mpi_f08 module or in C++, the status argument is optional. The status can be passed to MPI_TEST_CANCELLED to determine if the operation was cancelled. All other fields of status are undefined.

When reading, a program can detect the end of file by noting that the amount of data read is less than the amount requested. Writing past the end of file increases the file size. The amount of data accessed will be the amount requested, unless an error is raised (or a read reaches the end of file).

13.4.2 Data Access with Explicit Offsets

If MPI_MODE_SEQUENTIAL mode was specified when the file was opened, it is erroneous to call the routines in this section.

```
MPI_FILE_READ_AT(fh, offset, buf, count, datatype, status)

IN fh file handle (handle)
```

```
IN offset file offset (integer)

OUT buf initial address of buffer (choice)

IN count number of elements in buffer (integer)

IN datatype datatype of each buffer element (handle)
```

OUT status object (Status)

```
MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

13.4. DATA ACCESS 481

 On any MPI process, each file handle may have at most one active split collective operation at any time.

- Begin calls are collective over the group of processes that participated in the collective open and follow the ordering rules for collective calls.
- End calls are collective over the group of processes that participated in the collective open and follow the ordering rules for collective calls. Each end call matches the preceding begin call for the same collective operation. When an "end" call is made, exactly one unmatched "begin" call for the same operation must precede it.
- An implementation is free to implement any split collective data access routine using
 the corresponding blocking collective routine when either the begin call (e.g.,
 MPI_FILE_READ_ALL_BEGIN) or the end call (e.g., MPI_FILE_READ_ALL_END) is
 issued. The begin and end calls are provided to allow the user and MPI implementation
 to optimize the collective operation.
- Split collective operations do not match the corresponding regular collective operation. For example, in a single collective read operation, an MPI_FILE_READ_ALL on one process does not match an MPI_FILE_READ_ALL_BEGIN/MPI_FILE_READ_ALL_END pair on another process.
- Split collective routines must specify a buffer in both the begin and end routines. By specifying the buffer that receives data in the end routine, we can avoid many (though not all) of the problems described in "A Problem with Register Optimization and Temporary Memory Modifications," Section 16.2.2, page 549.
- No collective I/O operations are permitted on a file handle concurrently with a split collective access on that file handle (i.e., between the begin and end of the access). That is

```
MPI_File_read_all_begin(fh, ...);
...
MPI_File_read_all(fh, ...);
...
MPI_File_read_all_end(fh, ...);
```

is erroneous.

• In a multithreaded implementation, any split collective begin and end operation called by a process must be called from the same thread. This restriction is made to simplify the implementation in the multithreaded case. (Note that we have already disallowed having two threads begin a split collective operation on the same file handle since only one split collective operation can be active on a file handle at any time.)

The arguments for these routines have the same meaning as for the equivalent collective versions (e.g., the argument definitions for MPI_FILE_READ_ALL_BEGIN and MPI_FILE_READ_ALL_END are equivalent to the arguments for MPI_FILE_READ_ALL). The begin routine (e.g., MPI_FILE_READ_ALL_BEGIN) begins a split collective operation that, when completed with the matching end routine (i.e., MPI_FILE_READ_ALL_END)

 † ticket 238-J.

35

36

37

38

39

40

ticket-248T. ⁴²

Advice to implementors. When converting a larger size integer to a smaller size integer, only the less significant bytes are moved. Care must be taken to preserve the sign bit value. This allows no conversion errors if the data range is within the range of the smaller size integer. (End of advice to implementors.)

Table 13.2 specifies the sizes of predefined datatypes in "external32" format.

13.5.3 User-Defined Data Representations

There are two situations that cannot be handled by the required representations:

- 1. a user wants to write a file in a representation unknown to the implementation, and
- 2. a user wants to read a file written in a representation unknown to the implementation.

User-defined data representations allow the user to insert a third party converter into the I/O stream to do the data representation conversion.

```
\label{eq:mpi_read_conversion_fn} \begin{aligned} & \mathsf{MPI\_REGISTER\_DATAREP}(\mathsf{datarep},\ \mathsf{read\_conversion\_fn},\ \mathsf{write\_conversion\_fn},\ \mathsf{dtype\_file\_extent\_fn},\ \mathsf{extra\_state}) \end{aligned}
```

```
IN
           datarep
                                            data representation identifier (string)
           read_conversion_fn
IN
                                           function invoked to convert from file representation to
                                            native representation (function)
IN
           write_conversion_fn
                                            function invoked to convert from native representation
                                           to file representation (function)
IN
           dtype_file_extent_fn
                                           function invoked to get the extent of a datatype as
                                           represented in the file (function)
IN
                                            extra state
           extra_state
```

```
int MPI_Register_datarep(char *datarep,
```

```
MPI_Datarep_conversion_function *read_conversion_fn,
MPI_Datarep_conversion_function *write_conversion_fn,
MPI_Datarep_extent_function *dtype_file_extent_fn,
void *extra_state)
```

MPI_REGISTER_DATAREP(DATAREP, READ_CONVERSION_FN, WRITE_CONVERSION_FN, DTYPE_FILE_EXTENT_FN, EXTRA_STATE, IERROR)

CHARACTER*(*) DATAREP

EXTERNAL READ_CONVERSION_FN, WRITE_CONVERSION_FN, DTYPE_FILE_EXTENT_FN INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE INTEGER IERROR

```
MPI_Register_datarep(datarep, read_conversion_fn, write_conversion_fn,

dtype_file_extent_fn, extra_state, ierror)

CHARACTER(LEN=*), INTENT(IN) :: datarep

EXTERNAL :: read_conversion_fn, write_conversion_fn,

dtype_file_extent_fn

INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
```

The call associates read_conversion_fn, write_conversion_fn, and dtype_file_extent_fn with the data representation identifier datarep. datarep can then be used as an argument to MPI_FILE_SET_VIEW, causing subsequent data access operations to call the conversion functions to convert all data items accessed between file data representation and native representation. MPI_REGISTER_DATAREP is a local operation and only registers the data representation for the calling MPI process. If datarep is already defined, an error in the error class MPI_ERR_DUP_DATAREP is raised using the default file error handler (see Section 13.7, page 508). The length of a data representation string is limited to the value of MPI_MAX_DATAREP_STRING must have a value of at least 64. No routines are provided to delete data representations and free the associated resources; it is not expected that an application will generate them in significant numbers.

Extent Callback

```
SUBROUTINE DATAREP_EXTENT_FUNCTION(DATATYPE, EXTENT, EXTRA_STATE, IERROR)
INTEGER DATATYPE, IERROR
INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT, EXTRA_STATE
```

```
{typedef void MPI::Datarep_extent_function(const MPI::Datatype& datatype, MPI::Aint& file_extent, void* extra_state); (binding deprecated, see Section 15.2)}
```

The function dtype_file_extent_fn must return, in file_extent, the number of bytes required to store datatype in the file representation. The function is passed, in extra_state, the argument that was passed to the MPI_REGISTER_DATAREP call. MPI will only call this routine with predefined datatypes employed by the user.

Datarep Conversion Functions

```
SUBROUTINE DATAREP_CONVERSION_FUNCTION(USERBUF, DATATYPE, COUNT, FILEBUF, POSITION, EXTRA_STATE, IERROR)
```

```
<TYPE> USERBUF(*), FILEBUF(*)
INTEGER COUNT, DATATYPE, IERROR
INTEGER(KIND=MPI_OFFSET_KIND) POSITION
INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
```

The function read_conversion_fn must convert from file data representation to native representation. Before calling this routine, MPI allocates and fills filebuf with count contiguous data items. The type of each data item matches the corresponding entry for the predefined datatype in the type signature of datatype. The function is passed, in extra_state, the argument that was passed to the MPI_REGISTER_DATAREP call. The function must copy all count data items from filebuf to userbuf in the distribution described by datatype, converting each data item from file representation to native representation. datatype will be equivalent to the datatype that the user passed to the read function. If the size of datatype is less than the size of the count data items, the conversion function must treat datatype as being contiguously tiled over the userbuf. The conversion function must begin storing converted data at the location in userbuf specified by position into the (tiled) datatype.

Advice to users. Although the conversion functions have similarities to MPI_PACK and MPI_UNPACK, one should note the differences in the use of the arguments count and position. In the conversion functions, count is a count of data items (i.e., count of typemap entries of datatype), and position is an index into this typemap. In MPI_PACK, incount refers to the number of whole datatypes, and position is a number of bytes. (End of advice to users.)

Advice to implementors. A converted read operation could be implemented as follows:

- 1. Get file extent of all data items
- 2. Allocate a filebuf large enough to hold all count data items
- 3. Read data from file into filebuf
- 4. Call read_conversion_fn to convert data and place it into userbuf
- 5. Deallocate filebuf

(End of advice to implementors.)

If MPI cannot allocate a buffer large enough to hold all the data to be converted from a read operation, it may call the conversion function repeatedly using the same datatype and userbuf, and reading successive chunks of data to be converted in filebuf. For the first call (and in the case when all the data to be converted fits into filebuf), MPI will call the function with position set to zero. Data converted during this call will be stored in the userbuf according to the first count data items in datatype. Then in subsequent calls to the conversion function, MPI will increment the value in position by the count of items converted in the previous call, and the userbuf pointer will be unchanged.

Rationale. Passing the conversion function a position and one datatype for the transfer allows the conversion function to decode the datatype only once and cache an internal representation of it on the datatype. Then on subsequent calls, the conversion function can use the position to quickly find its place in the datatype and continue storing converted data where it left off at the end of the previous call. (End of rationale.)

13.6.7 MPI_Offset Type

MPI_Offset is an integer type of size sufficient to represent the size (in bytes) of the largest file supported by MPI. Displacements and offsets are always specified as values of type MPI_Offset.

In Fortran, the corresponding integer is an integer [of kind] with kind parameter MPI_OFFSET_KIND, [defined in mpif.h and the mpi module] which is defined in the mpi_f08 module, the mpi module and the mpif.h include file.

In Fortran 77 environments that do not support KIND parameters, MPI_Offset arguments should be declared as an INTEGER of suitable size. The language interoperability implications for MPI_Offset are similar to those for addresses (see Section 16.3, page 571).

13.6.8 Logical vs. Physical File Layout

MPI specifies how the data should be laid out in a virtual file structure (the view), not how that file structure is to be stored on one or more disks. Specification of the physical file structure was avoided because it is expected that the mapping of files to disks will be system specific, and any specific control over file layout would therefore restrict program portability. However, there are still cases where some information may be necessary to optimize file layout. This information can be provided as *hints* specified via *info* when a file is created (see Section 13.2.8, page 453).

13.6.9 File Size

The size of a file may be increased by writing to the file after the current end of file. The size may also be changed by calling MPI *size changing* routines, such as MPI_FILE_SET_SIZE. A call to a size changing routine does not necessarily change the file size. For example, calling MPI_FILE_PREALLOCATE with a size less than the current size does not change the size.

Consider a set of bytes that has been written to a file since the most recent call to a size changing routine, or since MPI_FILE_OPEN if no such routine has been called. Let the high byte be the byte in that set with the largest displacement. The file size is the larger of

- One plus the displacement of the high byte.
- The size immediately after the size changing routine, or MPI_FILE_OPEN, returned.

When applying consistency semantics, calls to MPI_FILE_SET_SIZE and MPI_FILE_PREALLOCATE are considered writes to the file (which conflict with operations that access bytes at displacements between the old and new file sizes), and MPI_FILE_GET_SIZE is considered a read of the file (which overlaps with all accesses to the file).

Advice to users. Any sequence of operations containing the collective routines MPI_FILE_SET_SIZE and MPI_FILE_PREALLOCATE is a write sequence. As such, sequential consistency in nonatomic mode is not guaranteed unless the conditions in Section 13.6.1, page 498, are satisfied. (End of advice to users.)

File pointer update semantics (i.e., file pointers are updated by the amount accessed) are only guaranteed if file size changes are sequentially consistent.

ticket230-B.

```
1
     MPI_TYPE_UB( datatype, displacement)
2
       IN
                 datatype
                                             datatype (handle)
3
       OUT
                 displacement
                                             displacement of upper bound from origin, in bytes (in-
4
                                             teger)
5
6
7
     int MPI_Type_ub(MPI_Datatype datatype, MPI_Aint* displacement)
8
     MPI_TYPE_UB( DATATYPE, DISPLACEMENT, IERROR)
9
          INTEGER DATATYPE, DISPLACEMENT, IERROR
10
11
         The following function is deprecated and is superseded by
     MPI_COMM_CREATE_KEYVAL in MPI-2.0. The language independent definition of the
12
13
     deprecated function is the same as that of the new function, except for the function name
14
     and a different behavior in the C/Fortran language interoperability, see Section 16.3.7 on
15
     page 581. The language bindings are modified.
16
17
     MPI_KEYVAL_CREATE(copy_fn, delete_fn, keyval, extra_state)
18
19
       IN
                 copy_fn
                                             Copy callback function for keyval
20
       IN
                 delete_fn
                                             Delete callback function for keyval
21
                 keyval
       OUT
                                             key value for future access (integer)
22
23
       IN
                                             Extra state for callback functions
                 extra_state
24
25
     int MPI_Keyval_create(MPI_Copy_function *copy_fn, MPI_Delete_function
26
                    *delete_fn, int *keyval, void* extra_state)
27
     MPI_KEYVAL_CREATE(COPY_FN, DELETE_FN, KEYVAL, EXTRA_STATE, IERROR)
28
          EXTERNAL COPY_FN, DELETE_FN
29
          INTEGER KEYVAL, EXTRA_STATE, IERROR
30
31
         The copy fn function is invoked when a communicator is duplicated by
32
     MPI_COMM_DUP. copy_fn should be of type MPI_Copy_function, which is defined as follows:
33
34
     typedef int MPI_Copy_function(MPI_Comm oldcomm, int keyval,
35
                                       void *extra_state, void *attribute_val_in,
36
37
                                       void *attribute_val_out, int *flag)
38
          A Fortran declaration for such a function is as follows:
39
     SUBROUTINE COPY_FUNCTION(OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
40
                    ATTRIBUTE_VAL_OUT, FLAG, IERR)
41
          INTEGER OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
42
          ATTRIBUTE_VAL_OUT, IERR
43
          LOGICAL FLAG
44
45
          copy_fn may be specified as MPI_NULL_COPY_FN or MPI_DUP_FN from either C or
46
     FORTRAN; MPI_NULL_COPY_FN is a function that does nothing other than returning
47
     flag = 0 and MPI_SUCCESS. MPI_DUP_FN is a simple-minded copy function that sets flag =
```

1, returns the value of attribute_val_in in attribute_val_out, and returns MPI_SUCCESS. Note that MPI_NULL_COPY_FN and MPI_DUP_FN are also deprecated.

Analogous to copy_fn is a callback deletion function, defined as follows. The delete_fn function is invoked when a communicator is deleted by MPI_COMM_FREE or when a call is made explicitly to MPI_ATTR_DELETE. delete_fn should be of type MPI_Delete_function, which is defined as follows:

```
typedef int MPI_Delete_function(MPI_Comm comm, int keyval,
void *attribute_val, void *extra_state);
```

A Fortran declaration for such a function is as follows:

SUBROUTINE DELETE_FUNCTION(COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR)
INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERR

delete_fn may be specified as MPI_NULL_DELETE_FN from either C or FORTRAN; MPI_NULL_DELETE_FN is a function that does nothing, other than returning MPI_SUCCESS. Note that MPI_NULL_DELETE_FN is also deprecated.

The following function is deprecated and is superseded by MPI_COMM_FREE_KEYVAL in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

```
MPI_KEYVAL_FREE(keyval)
```

INOUT keyval Frees the integer key value (integer)

int MPI_Keyval_free(int *keyval)

MPI_KEYVAL_FREE(KEYVAL, IERROR)
INTEGER KEYVAL, IERROR

The following function is deprecated and is superseded by MPI_COMM_SET_ATTR in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

MPI_ATTR_PUT(comm, keyval, attribute_val)

INOUT	comm	communicator to which attribute will be attached (handle) $% \left(\frac{1}{2}\right) =\frac{1}{2}\left(\frac{1}{2}\right) \left(\frac{1}{2}\right) $
IN	keyval	key value, as returned by MPI_KEYVAL_CREATE (integer)
IN	attribute_val	attribute value

int MPI_Attr_put(MPI_Comm comm, int keyval, void* attribute_val)

MPI_ATTR_PUT(COMM, KEYVAL, ATTRIBUTE_VAL, IERROR)
INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, IERROR

The following function is deprecated and is superseded by MPI_COMM_GET_ATTR in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

ticket 252-W.

48

which is defined as:

```
1
                  MPI_ATTR_GET(comm, keyval, attribute_val, flag)
            2
                    IN
                                                            communicator to which attribute is attached (handle)
                              comm
             3
                    IN
                              keyval
                                                           key value (integer)
             4
            5
                    OUT
                              attribute_val
                                                           attribute value, unless flag = false
             6
                    OUT
                              flag
                                                            true if an attribute value was extracted; false if no
                                                            attribute is associated with the key
            9
                  int MPI_Attr_get(MPI_Comm comm, int keyval, void *attribute_val, int *flag)
            10
            11
                  MPI_ATTR_GET(COMM, KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
            12
                       INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, IERROR
            13
                       LOGICAL FLAG
            14
                       The following function is deprecated and is superseded by MPI_COMM_DELETE_ATTR
            15
                  in MPI-2.0. The language independent definition of the deprecated function is the same as
            16
                  of the new function, except of the function name. The language bindings are modified.
            17
            18
            19
                  MPI_ATTR_DELETE(comm, keyval)
            20
                    INOUT
                              comm
                                                           communicator to which attribute is attached (handle)
            21
            22
                    IN
                              keyval
                                                           The key value of the deleted attribute (integer)
            23
            24
                  int MPI_Attr_delete(MPI_Comm comm, int keyval)
            25
                  MPI_ATTR_DELETE(COMM, KEYVAL, IERROR)
            26
                       INTEGER COMM, KEYVAL, IERROR
            27
            28
                       The following function is deprecated and is superseded by
            29
                  MPI_COMM_CREATE_ERRHANDLER in MPI-2.0. The language independent definition
            30
                  of the deprecated function is the same as of the new function, except of the function name.
            31
                  The language bindings are modified.
            32
ticket 252	ext{-W}. <sup>34</sup>
                  MPI_ERRHANDLER_CREATE( [function]handler_fn, errhandler )
            35
                    IN
                              [ticket252-W.][function]handler_fn user defined error handling procedure
            36
                    OUT
                              errhandler
                                                            MPI error handler (handle)
            37
{
m ticket 252	ext{-}W.} з9
                  int MPI_Errhandler_create(MPI_Handler_function *[function]handler_fn,
                                  MPI_Errhandler *errhandler)
                  MPI_ERRHANDLER_CREATE([FUNCTION] HANDLER_FN, ERRHANDLER, IERROR)
ticket252	ext{-W}. _{_{43}}
                       EXTERNAL [FUNCTION] HANDLER_FN
                       INTEGER ERRHANDLER, IERROR
            44
ticket 252-W. 45
                       Register the user routine [function]handler_fn for use as an MPI exception handler.
                  Returns in errhandler a handle to the registered exception handler.
            47
                       In the C language, the user routine should be a C function of type MPI_Handler_function,
```

```
typedef void (MPI_Handler_function)(MPI_Comm *, int *, ...);
```

The first argument is the communicator in use, the second is the error code to be returned.

In the Fortran language, the user routine should be of the form:

```
SUBROUTINE HANDLER_FUNCTION(COMM, ERROR_CODE)
INTEGER COMM, ERROR_CODE
```

The following function is deprecated and is superseded by MPI_COMM_SET_ERRHANDLER in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

MPI_ERRHANDLER_SET(comm, errhandler)

```
INOUT comm communicator to set the error handler for (handle)

IN errhandler new MPI error handler for communicator (handle)
```

int MPI_Errhandler_set(MPI_Comm comm, MPI_Errhandler errhandler)

```
MPI_ERRHANDLER_SET(COMM, ERRHANDLER, IERROR)
INTEGER COMM, ERRHANDLER, IERROR
```

Associates the new error handler errorhandler with communicator comm at the calling process. Note that an error handler is always associated with the communicator.

The following function is deprecated and is superseded by MPI_COMM_GET_ERRHANDLER in MPI-2.0. The language independent definition of the deprecated function is the same as of the new function, except of the function name. The language bindings are modified.

MPI_ERRHANDLER_GET(comm, errhandler)

```
OUT comm communicator to get the error handler from (handle)

MPI error handler currently associated with communicator (handle)
```

```
int MPI_Errhandler_get(MPI_Comm comm, MPI_Errhandler *errhandler)
```

```
MPI_ERRHANDLER_GET(COMM, ERRHANDLER, IERROR)
INTEGER COMM, ERRHANDLER, IERROR
```

Returns in errhandler (a handle to) the error handler that is currently associated with communicator comm.

15.2 Deprecated since MPI-2.2

The entire set of C++ language bindings have been deprecated.

```
1
                2
                5
                 6
                 9
                10
                11
                12
                13
                14
                15
ticket230-B.
ticket230-B. 18
                19
                20
      ticket0. 21
ticket230-B. <sup>23</sup>
                26
ticket230-B. _{28}
ticket230-B. _{29}
ticket
230-B. ^{30}
ticket230-B. ^{31}
ticket
233-E. ^{34}
ticket
230-B. ^{35}
ticket230-B. 36
ticket230-B. 38
ticket230-B. 39
                41
ticket230-B. 43
ticket230-B. 44
ticket230-B. ^{46}
```

ticket230-B. 47

ticket230-B. 48

ticket230-B.

```
Example 16.10 mpi_profile.cc, to be compiled into libpmpi.a.
int MPI::Comm::Get_size() const
{
    // Do profiling stuff
    int ret = pmpi_comm.Get_size();
    // More profiling stuff
    return ret;
}
(End of advice to implementors.)
```

16.2 Fortran Support

16.2.1 Overview

The Fortran [MPI-2]MPI language bindings have been designed to be compatible with the Fortran 90 standard (and later). [These bindings are in most cases compatible with Fortran 77, implicit-style interfaces.]

Rationale. Fortran 90 contains numerous features designed to make it a more "modern" language than Fortran 77. It seems natural that [MPI]MPI should be able to take advantage of these new features with a set of bindings tailored to Fortran 90. [MPI does not (yet) use many of these features because of a number of technical difficulties.]In Fortran 2008, the only new language features used, are of assumed type and assumed rank. They were defined to allow the definition of choice arguments as part of the Fortran language. (End of rationale.)

MPI defines [two levels]three methods of Fortran support[, described in Sections 16.2.3 and 16.2.4. In the rest of this section, "Fortran" and "Fortran 90" shall refer to "Fortran 90" and its successors, unless qualified.]:

- 1. [Basic Fortran Support]INCULDE 'mpif.h' [An implementation with this level of Fortran support provides the original Fortran bindings specified in MPI-1, with small additional requirements specified]This method is described in Section 16.2.3. The use of the include file mpif.h is strongly discouraged since MPI-3.0.
- 2. [Extended Fortran Support] USE mpi [An implementation with this level of Fortran support provides Basic Fortran Support plus additional features that specifically support Fortran 90, as] This method is described in Section 16.2.4 and requires compile-time argument checking.
- 3. **USE mpi_f08** This method is described in Section 16.2.5 and requires compile-time argument checking that includes also unique handle types.

A compliant [MPI-2]MPI-3 implementation providing a Fortran interface must provide [Extended Fortran Support unless the target compiler does not support modules or KIND-parameterized types] all three Fortran support methods.

Application[s] subroutines and functions may use either [the mpi]one of the modules or the mpif.h include file. An implementation may require use of the module to prevent type mismatch errors[(see below)].

ticket230-B. ticket230-B.

Advice to users. It is recommended to use [the mpi]one of the MPI modules even if it is not necessary to use it to avoid type mismatch errors on a particular system. Using a module provides several potential advantages over using an include file. (End of advice to users.)

[It] In a single application, it must be possible to link together routines some of which USE mpi and others of which USE mpi_f08 or INCLUDE mpif.h.

The INTEGER compile-time constant MPI_SUBARRAYS is MPI_SUBARRAYS_SUPPORTED if all choice arguments are defined in explicit interfaces with standardized assumed type and assumed rank, otherwise it equals MPI_SUBARRAYS_UNSUPPORTED. This constant exists with each Fortran support method, but not in the C/C++ header files. The value may be different for each Fortran support method.

Section 16.2.2 gives an overview on known problems when using Fortran together with MPI. Section 16.2.6 and Section 16.2.7 describe additional functionality that is part of the Fortran support. funcMPI_F_SYNC_REG is needed for one of the methods to prevent register optimization problems. A[new] set of functions[to] provides additional support for Fortran intrinsic numeric types, including parameterized types. The functions are: MPI_SIZEOF, MPI_TYPE_MATCH_SIZE, MPI_TYPE_CREATE_F90_INTEGER, MPI_TYPE_CREATE_F90_REAL and MPI_TYPE_CREATE_F90_COMPLEX. Parameterized types are Fortran intrinsic types which are specified using KIND type parameters. [These routines are described in detail in Section 16.2.7.]

16.2.2 Problems With Fortran Bindings for MPI

This section discusses a number of problems that may arise when using MPI in a Fortran program. It is intended as advice to users, and clarifies how MPI interacts with Fortran. It does not add to the standard, but is intended to clarify the standard.

As noted in the original MPI specification, the interface violates the Fortran standard in several ways. While these cause few problems for Fortran 77 programs, they become more significant for Fortran 90 programs, so that users must exercise care when using new Fortran 90 features. The violations were originally adopted and have been retained because they are important for the usability of MPI. The rest of this section describes the potential problems in detail. [It supersedes and replaces the discussion of Fortran bindings in the original MPI specification (for Fortran 90, not Fortran 77).]

The following MPI features are inconsistent with Fortran 90.

- 1. An MPI subroutine with a choice argument may be called with different argument types. Using the mpi_f08 module, this problem is resolved.
- 2. An MPI subroutine with an assumed-size dummy argument may be passed an actual scalar argument.
- 3. Many MPI routines assume that actual arguments are passed by address and that arguments are not copied on entrance to or exit from the subroutine.
- 4. An MPI implementation may read or modify user data (e.g., communication buffers used by nonblocking communications) concurrently with a user program that is executing outside of MPI calls.
- 5. Several named "constants," such as MPI_BOTTOM, MPI_IN_PLACE, MPI_STATUS_IGNORE, MPI_STATUSES_IGNORE, MPI_ERRCODES_IGNORE,

ticket230-B

ticket230-B. ticket234-F.

ticket230-B.

ticket238-J. ticket230-B. ticket238-J. ticket230-B. ticket230-B. ticket230-B. ticket230-B. ticket230-B.

²⁰ ticket230-B.

21

23 24

26

27

28

29

30

31

34

35

38

39

40

42 43

44

45

46 47 ticket235-G.

₃₇ ticket235-G.

ticket235-G

ticket235-G. ticket235-G. ticket235-G.

 45 ticket235-G. 46 ticket235-G. 47

MPI_UNWEIGHTED, MPI_ARGV_NULL, and MPI_ARGVS_NULL are not ordinary Fortran constants and require a special implementation. See Section 2.5.4 on page 15 for more information.

6. The memory allocation routine MPI_ALLOC_MEM can't be usefully used in Fortran without a language extension that allows the allocated memory to be associated with a Fortran variable.

Additionally, MPI is inconsistent with Fortran 77 in a number of ways, as noted below.

- MPI identifiers exceed 6 characters.
- MPI identifiers may contain underscores after the first character.
- MPI requires an include file, mpif.h. On systems that do not support include files, the implementation should specify the values of named constants.
- Many routines in MPI have KIND-parameterized integers (e.g., MPI_ADDRESS_KIND and MPI_OFFSET_KIND) that hold address information. On systems that do not support Fortran 90-style parameterized types, INTEGER*8 or INTEGER should be used instead.

MPI-1 contained several routines that take address-sized information as input or return address-sized information as output. In C such arguments were of type MPI_Aint and in Fortran of type INTEGER. On machines where integers are smaller than addresses, these routines can lose information. In MPI-2 the use of these functions has been deprecated and they have been replaced by routines taking INTEGER arguments of KIND=MPI_ADDRESS_KIND. A number of new MPI-2 functions also take INTEGER arguments of non-default KIND. See Section 2.6 on page 17 and Section 4.1.1 on page 87 for more information.

Problems Due to Strong Typing

All MPI functions with choice arguments associate actual arguments of different Fortran datatypes with the same dummy argument. This is not allowed by Fortran 77, and in Fortran 90 is technically only allowed if the function is overloaded with a different function for each type. In C, the use of void* formal arguments avoids these problems. Similar to C, with Fortran 2008 and later together with the mpi_f08 module, the problem is avoided by declaring choice arguments with TYPE(*), DIMENSION(..), i.e., as assumed type and assumed rank dummy arguments.

[The] Using INCLUDE mpif.h, the following code fragment [is]might technically [illegal] be invalid and may generate a compile-time error.

```
integer i(5)
real x(5)
...
call mpi_send(x, 5, MPI_REAL, ...)
call mpi_send(i, 5, MPI_INTEGER, ...)
```

In practice, it is rare for compilers to do more than issue a warning[, though there is concern that Fortran 90 compilers are more likely to return errors]. Using the mpi_f08 or mpi module, the problem is usually resolved through the standardized assume-type and

assume-rank declarations of the dummy arguments, or with non-standard Fortran options preventing type checking for choice arguments.

It is also technically [illegal]invalid in Fortran to pass a scalar actual argument to an array dummy argument. Thus, when using the mpi_f08 or mpi module, the following code fragment[may generate] usually generates an error since the[buf argument] dims and periods arguments to [MPI_SEND is declared as an assumed-size array <type>buf(*)]MPI_CART_CREATE are declared as assumed size arrays INTEGER, DIMS(*) and LOGICAL, PERIODS(*).

```
[integer a
call mpi_send(a, 1, MPI_INTEGER, ...)

USE mpi_f08
INTEGER size
CALL MPI_Cart_create( comm_old,1,size,.TRUE.,.TRUE.,comm_cart,ierror )
```

Using INCLUDE 'mpif.h', compiler warnings are not expected except if this include file also uses Fortran explicit interfaces.

Advice to users. In the event that you run into one of the problems related to type checking, you may be able to work around it by using a compiler flag, by compiling separately, or by using an MPI implementation with Extended Fortran Support as described in Section 16.2.4. An alternative that will usually work with variables local to a routine but not with arguments to a function or subroutine is to use the EQUIVALENCE statement to create another variable with a type accepted by the compiler. (End of advice to users.)

Problems Due to Data Copying and Sequence Association

• If MPI_SUBARRAYS equals MPI_SUBARRAYS_SUPPORTED:

Choice buffer arguments are declared as TYPE(*), DIMENSION(..). For example, considering the following code fragment:

```
REAL s(100), r(100)

CALL MPI_Isend(s(1:100:5), 3, MPI_REAL, ..., rq, ierror)

CALL MPI_Wait(rq, status, ierror)

CALL MPI_Irecv(r(1:100:5), 3, MPI_REAL, ..., rq, ierror)

CALL MPI_Wait(rq, status, ierror)
```

In this case, the individual elements s(1), s(6), s(11), etc. are sent between the start of MPI_ISEND and the end of MPI_WAIT even though the compiled code may not copy s(1:100:5) to a contiguous temporary scratch buffer. Instead, the compiled code may pass a descriptor to MPI_ISEND that allows MPI to operate directly on s(1), s(6), s(11), ..., s(96).

All nonblocking MPI communication functions behave as if the user-specified elements of choice buffers are copied to a contiguous scratch buffer in the MPI runtime environment. All datatype descriptions (in the example above, "3, MPI_REAL") read and

ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.
 ticket235-G.

19

20

21

22

23

24

25262728

33 34

35

36

37

38

39

42

43

44

45 46

47

³ ticket235-G.

⁴ ticket235-G.

ticket236-H.

store data from and to this virtual contiguous scratch buffer. Displacements in MPI derived datatypes are relative to the beginning of this virtual contiguous scratch buffer. Upon completion of a nonblocking receive operation (e.g., when MPI_WAIT on a corresponding MPI_Request returns), it is as if the received data has been copied from the virtual contiguous scratch buffer back to the non-contiguous application buffer. In the example above, r(1), r(6), and r(11) will be filled with the received data when MPI_WAIT returns.

Advice to implementors. The Fortran descriptor for TYPE(*), DIMENSION(..) arguments contains enough information that the MPI library can make a real contiguous copy of non-contiguous user buffers. Efficient implementations may avoid such additional memory-to-memory data copying. (End of advice to implementors.)

Rationale. If MPI_SUBARRAYS equals MPI_SUBARRAYS_SUPPORTED, non-contiguous buffers are handled inside of the MPI library instead of by the compiled user code. Therefore the scope of scratch buffers can be from the beginning of a nonblocking operation until the completion of the operation although beginning and completion are implemented in different routines. If MPI_SUBARRAYS equals MPI_SUBARRAYS_UNSUPPORTED, such scratch buffers can be organized only by the compiler for the duration of the nonblocking call, which is too short for implementing the whole MPI operation. (End of rationale.)

• If MPI_SUBARRAYS equals MPI_SUBARRAYS_UNSUPPORTED:

Implicit in MPI is the idea of a contiguous chunk of memory accessible through a linear address space. MPI copies data to and from this memory. An MPI program specifies the location of data by providing memory addresses and offsets. In the C language, sequence association rules plus pointers provide all the necessary low-level structure.

In Fortran 90, user data is not necessarily stored contiguously. For example, the array section A(1:N:2) involves only the elements of A with indices 1, 3, 5, The same is true for a pointer array whose target is such a section. Most compilers ensure that an array that is a dummy argument is held in contiguous memory if it is declared with an explicit shape (e.g., B(N)) or is of assumed size (e.g., B(*)). If necessary, they do this by making a copy of the array into contiguous memory. Both Fortran 77 and Fortran 90 are carefully worded to allow such copying to occur, but few Fortran 77 compilers do it.¹

Because MPI dummy buffer arguments are assumed-size arrays, this leads to a serious problem for a nonblocking call: the compiler copies the temporary array back on return but MPI continues to copy data to the memory that held it. For example, consider the following code fragment:

```
real a(100) call MPI_IRECV(a(1:100:2), MPI_REAL, 50, ...)
```

¹Technically, the Fortran standards are worded to allow non-contiguous storage of any array data.

Since the first dummy argument to MPI_IRECV is an assumed-size array (<type>buf(*)), the array section a(1:100:2) is copied to a temporary before being passed to MPI_IRECV, so that it is contiguous in memory. MPI_IRECV returns immediately, and data is copied from the temporary back into the array a. Sometime later, MPI may write to the address of the deallocated temporary. Copying is also a problem for MPI_ISEND since the temporary array may be deallocated before the data has all been sent from it.

Most Fortran 90 compilers do not make a copy if the actual argument is the whole of an explicit-shape or assumed-size array or is a 'simple' section such as A(1:N) of such an array. (We define 'simple' more fully in the next paragraph.) Also, many compilers treat allocatable arrays the same as they treat explicit-shape arrays in this regard (though we know of one that does not). However, the same is not true for assumed-shape and pointer arrays; since they may be discontiguous, copying is often done. It is this copying that causes problems for MPI as described in the previous paragraph.

Our formal definition of a 'simple' array section is

```
name ( [:,]... [<subscript>]:[<subscript>] [,<subscript>]... )
```

That is, there are zero or more dimensions that are selected in full, then one dimension selected without a stride, then zero or more dimensions that are selected with a simple subscript. Examples are

```
A(1:N), A(:,N), A(:,1:N,1), A(1:6,N), A(:,:,1:N)
```

Because of Fortran's column-major ordering, where the first index varies fastest, a simple section of a contiguous array will also be contiguous.²

The same problem can occur with a scalar argument. Some compilers, even for Fortran 77, make a copy of some scalar dummy arguments within a called procedure. That this can cause a problem is illustrated by the example

```
call user1(a,rq)
call MPI_WAIT(rq,status,ierr)
write (*,*) a
subroutine user1(buf,request)
call MPI_IRECV(buf,...,request,...)
end
```

If a is copied, MPI_IRECV will alter the copy when it completes the communication and will not alter a itself.

Note that copying will almost certainly occur for an argument that is a non-trivial expression (one with at least one operator or function call), a section that does not

²To keep the definition of 'simple' simple, we have chosen to require all but one of the section subscripts to be without bounds. A colon without bounds makes it obvious both to the compiler and to the reader that the whole of the dimension is selected. It would have been possible to allow cases where the whole dimension is selected with one or two bounds, but this means for the reader that the array declaration or most recent allocation has to be consulted and for the compiler that a run-time check may be required.

1

9 10 12

14 15

16 17

18

19

20

21

22

23

24

25

26

27

30

31

32

33

41

42

43

45 46

47

6

ticket236-H. 13

ticket242-N.

ticket237-I. ticket237-I. 36

ticket237-I. 37 ticket237-I. 38 ticket237-I. 39

ticket237-I. 44

select a contiguous part of its parent (e.g., A(1:n:2)), a pointer whose target is such a section, or an assumed-shape array that is (directly or indirectly) associated with such a section.

If there is a compiler option that inhibits copying of arguments, in either the calling or called procedure, this should be employed.

If a compiler makes copies in the calling procedure of arguments that are explicit-shape or assumed-size arrays, simple array sections of such arrays, or scalars, and if there is no compiler option to inhibit this, then the compiler cannot be used for applications that use MPI_GET_ADDRESS, or any nonblocking MPI routine. If a compiler copies scalar arguments in the called procedure and there is no compiler option to inhibit this, then this compiler cannot be used for applications that use memory references across subroutine calls as in the example above.

Special Constants

MPI requires a number of special "constants" that cannot be implemented as normal Fortran constants, e.g., MPI_BOTTOM. The complete list can be found in Section 2.5.4 on page 15. In C, these are implemented as constant pointers, usually as NULL and are used where the function prototype calls for a pointer to a variable, not the variable itself.

In Fortran the implementation of these special constants may require the use of language constructs that are outside the Fortran standard. Using special values for the constants (e.g., by defining them through parameter statements) is not possible because an implementation cannot distinguish these values from legal data. Typically these constants are implemented as predefined static variables (e.g., a variable in an MPI-declared COMMON block), relying on the fact that the target compiler passes data by address. Inside the subroutine, this address can be extracted by some mechanism outside the Fortran standard (e.g., by Fortran extensions or by implementing the function in C). With USE mpi_f08, the attributes INTENT(IN), INTENT(OUT), and INTENT(INOUT) are used in the Fortran interface. In most cases INTENT(IN) is used if the C interface uses call-by-value. For all buffer arguments and for OUT dummy arguments that allow one of these special constants as input, an INTENT(...) is not specified.

Fortran 90 Derived Types

MPI does not explicitly support passing Fortran 90 derived types to choice dummy arguments, but does not support Fortran non-sequence derived types. [Indeed, for MPI implementations that provide explicit interfaces through the mpi module a compiler will reject derived type actual arguments at compile time. Even when no explicit interfaces are given, users should be aware that Fortran 90 provides no guarantee of sequence association for derived types or arrays of derived types. For instance, an array of a derived type consisting of two elements may be implemented as an array of the first elements followed by an array of the second. Use of the SEQUENCE attribute may help here, somewhat.

The following code fragment shows one possible way to send a sequence derived type in Fortran. The example assumes that all data is passed by address.

```
type mytype
   [ticket237-I.] SEQUENCE
```

 $_{45}$ ticket238-J.

46

47

```
integer i
                                                                                         2
       real x
       double precision d
    end type mytype
    type(mytype) foo
    integer blocklen(3), type(3)
    integer(MPI_ADDRESS_KIND) disp(3), base
    call MPI_GET_ADDRESS(foo%i, disp(1), ierr)
                                                                                         11
    call MPI_GET_ADDRESS(foo%x, disp(2), ierr)
    call MPI_GET_ADDRESS(foo%d, disp(3), ierr)
                                                                                         12
                                                                                         13
                                                                                         14
    base = disp(1)
                                                                                         15
    disp(1) = disp(1) - base
                                                                                         16
    disp(2) = disp(2) - base
    disp(3) = disp(3) - base
                                                                                         18
                                                                                         19
    blocklen(1) = 1
                                                                                        20
    blocklen(2) = 1
                                                                                        21
    blocklen(3) = 1
                                                                                        22
                                                                                        23
    type(1) = MPI_INTEGER
                                                                                         24
    type(2) = MPI_REAL
    type(3) = MPI_DOUBLE_PRECISION
                                                                                         26
    call MPI_TYPE_CREATE_STRUCT(3, blocklen, disp, type, newtype, ierr)
                                                                                        27
    call MPI_TYPE_COMMIT(newtype, ierr)
                                                                                        28
                                                                                        29
[ticket237-I.][! unpleasant to send foo%i instead of foo, but it works for scalar]
[ticket237-I.][! entities of type mytype]
    call MPI_SEND(foo%i, 1, newtype, ...)
                                                                                        32
                                                                                        33
                                                                                        ^{35} ticket 238-J.
A Problem with Register Optimization and Temporary Memory Modifications
                                                                                        36
MPI provides operations that may be hidden from the user code and run concurrently with
                                                                                        37
it, accessing the same memory as user code. Examples include the data transfer for an
MPI_IRECV. The optimizer of a compiler will assume that it can recognize periods when a
copy of a variable can be kept in a register without reloading from or storing to memory.
                                                                                         40
When the user code is working with a register copy of some variable while the hidden
operation reads or writes the memory copy, problems occur. This section discusses register
                                                                                         _{43} ticket238-J.
optimization pitfalls and problems with temporary memory modifications. These problems
                                                                                        _{44} ticket238-J.
are independent of the Fortran support method, i.e., they occur with the mpi_f08 module,
```

This section shows four problematic usage areas (the abbrevations in parentheses are used in the table below):

• Usage of nonblocking routines (Nonbl.).

the mpi module, and the mif.h include file.

ticket238-J. 44

• Usage of one-sided routines (1-sided).

- Usage of MPI parallel file I/O split collective operations (Split).
- Use of MPI_BOTTOM together with absolute displacements in MPI datatypes, or relative displacements between to variables in such datatypes (Bottom).

The compiler is allowed to cause two optimization problems

- Register optimization problems and code movements (Regis.).
- Temporary memory modifications (Memory).

The optimization problems can occur not in all usage areas:

	Nonbl.	1-sided	Split	Bottom
Register	occurs	occurs	-not-	occurs
Memory	occurs	occurs	occurs	-not-

The application writer has several methods to circumvent parts of these problems with special declarations for the used send and receive buffers:

- Usage of the Fortran ASYNCHRONOUS attribute.
- Usage of the Fortran TARGET attribute.
- Usage of the helper routine MPI_F_SYNC_REG or a user-written dummy routine DD(buf).
- Declaring the buffer as Fortran module data or within a Fortran common block.
- Usage of the Fortran VOLATILE attribute.

Each of these methods may solve only a subset of the problems, may have more or less performance drawbacks, and may be usable not in each application context. The following table shows the usability of each method:

	Nonbl.	Nonbl.	1-sided	1-sided	Split	Bottom	overhead
	Regis.	Memory	Regis.	Memory	Memo.	Regis.	may be
Examples	16.11,	16.13	Section			16.14,	
	16.12		11.7.3			16.15	
ASYNCHRONOUS	solved	solved	may be	may be	solved	may be	medium
TARGET	solved	NOT s.	solved	NOT s.	NOT s.	solved	low-med
MPI_F_SYNC_REG	solved	NOT s.	solved	NOT s.	NOT s.	solved	low
Module Data	solved	NOT s.	solved	NOT s.	NOT s.	solved	low-med
VOLATILE	solved	solved	solved	solved	solved	solved	high

The next paragraphs describe the problems in detail.

4

6

9

11

12

13

14

15

16

17

18

19

20

23

2425

26

27

28

29

30

31

32

35

36

37

38

39

40

44

45

46

47

Example 16.11 Fortran 90 register optimization – extreme.

```
Source
                           compiled as
                                                       or compiled as
[ticket238-J.]REAL :: buf, b1
                                          REAL :: buf, b1
                                                                      REAL :: buf, b1
call MPI_IRECV(buf,..req)
                           call MPI_IRECV(buf,..req)
                                                       call MPI_IRECV(buf,..req)
                           register = buf
                                                       b1 = buf
call MPI_WAIT(req,..)
                           call MPI_WAIT(req,..)
                                                       call MPI_WAIT(req,..)
b1 = buf
                           b1 := register
```

When a variable is local to a Fortran subroutine (i.e., not in a module or COMMON block), the compiler will assume that it cannot be modified by a called subroutine unless it is an actual argument of the call. In the most common linkage convention, the subroutine is expected to save and restore certain registers. Thus, the optimizer will assume that a register which held a valid copy of such a variable before the call will still hold a valid copy on return.

Example 16.11 shows extreme, but allowed, possibilities.

MPI_WAIT on a concurrent thread modifies buf between the invocation of MPI_IRECV and the finish of MPI_WAIT. But the compiler cannot see any possibility that buf can be changed after MPI_IRECV has returned, and may schedule the load of buf earlier than typed in the source. It has no reason to avoid using a register to hold buf across the call to MPI_WAIT. It also may reorder the instructions as in the case on the right.

Example 16.12 Similar example with MPI_ISEND

```
Source
                           compiled as
                                                        or compiled as
REAL :: buf, copy
                            REAL :: buf, copy
                                                        REAL :: buf, copy
buf = val
                            buf = val
                                                        buf = val
                            call MPI_ISEND(buf,..req)
call MPI_ISEND(buf,..req)
                                                        addr = &buf
copy = buf
                            copy=buf
                                                        copy = val
                            buf = val_overwrite
                                                        buf = val_overwrite
call MPI_WAIT(req,..)
                            call MPI_WAIT(req,..)
                                                        send(*addr)
buf = val_overwrite
```

Due to allowed code movement, the content of buf may be already overwritten when sending of the content of buf is executed. The code movement is permitted, because the compiler cannot detect a possible access to buf in MPI_WAIT (or in a second thread between the start of MPI_ISEND and the end of MPI_WAIT).

Note, that code movement can also be executed across subroutine boundaries when subroutines or functions are inlined.

This register optimization / code movement problem does not occur with MPI parallel file I/O split collective operations, because in the ..._BEGIN and ..._END calls, the same buffer has to be provided as actual argument.

Nonblocking operations and temporary memory modifications. The compiler is allowed to modify temporarily data in the memory. Normally, this problem may occur only if overlapping communication and computation. Example 16.13 shows a possibility.

In the substitution of Example 16.13, buf_1dim(10000) is the 1-dimensional equivalence

²² ticket238-J.

 $_{42}$ ticket238-J.

```
Example 16.13 Overlapping Communication and Computation
```

```
USE mpi_f08
REAL :: buf(100,100)
CALL MPI_Irecv(buf(1,1:100),...req,...)
DO j=1,100
    DO i=2,100
    buf(i,j)=....
END DO
END DO
CALL MPI_Wait(req,...)
```

The compiler may substitute the nested loops through loop fusion by

```
EQUIVALENCE (buf(1,1), buf_1dim(1))
D0 h=1,100
  tmp(h)=buf(1,h)
END D0
D0 j=1,10000
  buf_1dim(h)=...
END D0
D0 h=1,100
  buf(1,h)=tmp(h)
END D0
```

of buf(100,100). The nonblocking receive may receive the data in the boundary buf(1,1:100) while the fused loop is using temporarily this part of the buffer. When the tmp data is written back to buf, the old data is restored and the received data is lost.

Note, that this problem occurs also

- with one-sided communication with the local buffer at the origin process between an RMA call and the ensuing synchronization call
- and with the window buffer at the target process between two ensuing synchronization calls,
- and also with MPI parallel file I/O split collective operations with the local buffer between the ..._BEGIN and ..._END call.

This type of compiler optimization can be prevented when buf is declared with the Fortran attribute ASYNCHRONOUS:

```
REAL, ASYNCHRONOUS :: buf(100,100)
```

One-sided communication. An example with instruction reordering due to register optimization can be found in Section 11.7.3 on page 425.

ticket238-J. 44

ticket238-J. $_{47}$

4

5 6

7

9 10 11

12

13 14

15

16

18

19

20

21

22

23

2425

29

30 31

33

34

35

36

37

38 39

41

42

43 44

45 46

47

ticket238-J.

One-sided communication. Normally users are not afflicted with this. But the user should pay attention to this section if in his/her program a buffer argument to an MPI_SEND, MPI_RECV etc., uses a name which hides the actual variables involved. MPI_BOTTOM with an MPI_Datatype containing absolute addresses is one example. Creating a datatype which uses one variable as an anchor and brings along others by using MPI_GET_ADDRESS to determine their offsets from the anchor is another. The anchor variable would be the only one mentioned in the call. Also attention must be paid if MPI operations are used that run in parallel with the user's application.

Example 16.14 shows what Fortran compilers are allowed to do.

Example 16.14 Fortran 90 register optimization.

```
This source ...
                                          can be compiled as:
call MPI_GET_ADDRESS(buf,bufaddr,
                                          call MPI_GET_ADDRESS(buf,...)
               ierror)
call MPI_TYPE_CREATE_STRUCT(1,1,
                                          call MPI_TYPE_CREATE_STRUCT(...)
               bufaddr,
               MPI_REAL, type, ierror)
call MPI_TYPE_COMMIT(type,ierror)
                                          call MPI_TYPE_COMMIT(...)
val_old = buf
                                          register = buf
                                          val_old = register
call MPI_RECV(MPI_BOTTOM,1,type,...)
                                          call MPI_RECV(MPI_BOTTOM,...)
val_new = buf
                                          val_new = register
```

The compiler does not invalidate the register because it cannot see that MPI_RECV changes the value of buf. The access of buf is hidden by the use of MPI_GET_ADDRESS and MPI_BOTTOM.

Example 16.15 Similar example with MPI_SEND

```
This source ...

! buf contains val_old

! buf contains val_old

! dead code:

! buf=val_new is removed

call MPI_SEND(MPI_BOTTOM,1,type,...)

! with buf as a displacement in type

buf = val_overwrite

can be compiled as:

! buf contains val_old

! dead code:

! buf=val_new is removed

call MPI_SEND(...)

! i.e. val_old is sent

buf = val_overwrite
```

Several successive assignments to the same variable can be combined in this way, but only the last assignment is executed. Successive means that no interfering read access to this variable is in between. The compiler cannot detect that the call to MPI_SEND statement is interfering, because the read access to buf is hidden by the usage of MPI_BOTTOM.

Solutions. The following paragraphs show in detail how these problems can be solved in portabel way. Several solutions are presented, because all of these solutions have different implication on the performance. Only one solution (with VOLATILE) solves all problems, but it may have the most negative impact on the performance.

5 6 7

8

9

10 11

1

2

3

12 13 14

15

21 22 23

24

25

26

20

27 28 29

30 31 32

33

34

35 36 37

38

39

40

41 42

Fortran ASYNCHRONOUS attribute. Declaring a buffer with the Fortran ASYNCHRONOUS attribute in a scoping unit (or BLOCK) tells the compiler that any statement of the scoping unit may be executed while the buffer is affected by a pending asynchronous input/output operation. Each library call (e.g., to an MPI routine) within the scoping unit may contain a Fortran asynchronous I/O statement, e.g., the Fortran WAIT statement.

• In the case of nonblocking MPI communication, the send and receive buffers should be declared with the Fortran ASYNCHRONOUS attribute within each scoping unit (or BLOCK) where the buffers are declared and statements are executed between the start (e.g., MPI_IRECV) and completion (e.g., MPI_WAIT) of the nonblocking communication. Declaring REAL, ASYNCHRONOUS: buf in Examples 16.11 and 16.12, and REAL, ASYNCHRONOUS: buf(100,100) in Examples 16.13 solves the register optimization and temporary memory modification problem.

Rationale. A combination of a nonblocking MPI communication call with a buffer in the argument list together with a subsequent call to MPI_WAIT or MPI_TEST is similar to the combination a of Fortran asynchronous read or write together with the matching Fortran wait statement. To prevent incorrect register optimizations or code movement, the Fortran standard requires in the case of Fortran IO, that the ASYNCHRONOUS attribute is defined for the buffer. The ASYNCHONOUS attribute also works with the asynchronous MPI routines because the compiler must expect that inside of the MPI routines such Fortran asynchronous read, write, or wait routines may be called. (End of rationale.)

• In the Examples 16.14 and 16.15 and also in the example in Section 11.7.3 on page 425, the ASYNCHRONOUS attribute may also help but the help is not guaranteed because there is not an IO counterpart to the MPI usage.

In case of using MPI_BOTTOM or one-sided synchronizations (e.g., MPI_WIN_FENCE), the buffer is not specified, i.e., those calls can include only a Fortran WAIT statement (or another routine that finishes an asynchronous IO). Additionally, with Fortran asynchronous IO, it is a clear and forbidden racecondition when storing new data into the buffer while an asynchronous IO is active. Exactly this storing of data into the buffer is done in Example 16.14 when there would have been an initialization buf=val_init prior to the call to MPI_RECV, or in Example 16.15, the statement buf=val_new. (End of rationale.)

Fortran TARGET attribute. Declaring a buffer with the Fortran TARGET attribute in a scoping unit (or BLOCK) tells the compiler that any statement of the scoping unit may be executed while some pointer to the buffer exist. Calling a library routine (e.g., an MPI routine) may imply that such a pointer is used to modify the buffer.

• The TARGET attribute solves problems of instruction reordering, code movement, and register optimization related to nonblocking and one-sided communication, or related to the usage of MPI_BOTTOM and derived datatype handles. Declaring REAL, TARGET :: buf solves the register optimization problem in Examples 16.11, 16.12, 16.14, and 16.15

⁵ ticket238-J.

6 ticket238-J.

¹² ticket238-J.

¹³ ticket238-J. ¹⁴ ticket238-J.

• Unfortunately, the TARGET attribute has **not** any impact on problems caused by asynchronous accesses between the start and end of a nonblocking or one-sided communication, i.e., problems through temporary memory modifications are not solved. Example 16.13 can **not** be solved with the TARGET attribute.

[(Example 16.11 and its following paragraph were moved to an earlier position)]
[To prevent instruction reordering or the allocation of a buffer in a register there are two possibilities in portable Fortran code:]

The compiler may be prevented from moving a reference to a buffer across a call to an MPI subroutine by surrounding the call by calls to an external subroutine with the buffer as an actual argument. The MPI library provides MPI_F_SYNC_REG for this purpose, see Section 16.2.6 on page 562.

U

• Examples 16.11 and 16.12 can be solved by calling MPI_F_SYNC_REG(buf) once directly after MPI_WAIT.

```
First example Second example

call MPI_IRECV(buf,..req) buf = val

call MPI_ISEND(buf,..req)

copy = buf

call MPI_WAIT(req,..) call MPI_WAIT(req,..)

call MPI_F_SYNC_REG(buf)

b1 = buf buf second example

buf = val

call MPI_ISEND(buf,..req)

call MPI_ISEND(buf,..req)

buf = val

call MPI_WAIT(req,..)

call MPI_F_SYNC_REG(buf)

buf = val_overwrite
```

The call MPI_F_SYNC_REG(buf) prevents moving the last line before the MPI_WAIT call. Further calls to MPI_F_SYNC_REG(buf) are not needed, because it is still correct if the additional read access copy=buf is moved behind MPI_WAIT and before buf=val_overwrite.

• Examples 16.14 and 16.15 can be solved with two additional call MPI_F_SYNC_REG(buf), 32 one directly before MPI_RECV/MPI_SEND, and one directly after this communication operation. 34

```
First example Second example
call MPI_F_SYNC_REG(buf) call MPI_F_SYNC_REG(buf)
call MPI_RECV(MPI_BOTTOM,...) call MPI_SEND(MPI_BOTTOM,...)
call MPI_F_SYNC_REG(buf) call MPI_F_SYNC_REG(buf)
```

The first call to MPI_F_SYNC_REG(buf) is needed to finish all load and store references to buf prior to MPI_RECV/MPI_SEND, and the second call is needed to assure that the subsequent access to buf are not moved before MPI_RECV/SEND.

• In the example in Section 16.2.6 on page 562, two asynchronous accesses must be protected: In Process 1, the access to bbbb must be protected similar to Example 16.11, i.e., a call to MPI_F_SYNC_REG(bbbb) is needed after the second MPI_WIN_FENCE to guarantee that further accesses to bbbb are not moved ahead of the call to

ticket238-J. ⁴⁷

ticket238-J. 48

MPI_WIN_FENCE. In Process 2, both calls to MPI_WIN_FENCE together act as a communication call with MPI_BOTTOM as the buffer, i.e., before the first fence and after the second fence, a call to MPI_F_SYNC_REG(buff) is needed to guarantee that accesses to buff are not moved after or ahead of the calls to MPI_WIN_FENCE. Using MPI_GET instead of MPI_PUT, the same calls to MPI_F_SYNC_REG are necessary.

```
Source of Process 1

bbbb = 777

buff = 999

call MPI_F_SYNC_REG(buff)

call MPI_PUT(bbbb

into buff of process 2)

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_WIN_FENCE

call MPI_F_SYNC_REG(bbbb)

call MPI_F_SYNC_REG(buff)

ccc = buff
```

• The temporary memory modification problem, i.e., Example 16.13, can **not** be solved with this method.

A user defined DD instead of MPI_F_SYNC_REG. Instead of MPI_F_SYNC_REG, one can use also a user defined external subroutine, which is separately compiled: [with the separately compiled]

```
subroutine DD(buf)
  integer buf
end
```

Note that if the intent is declared in the external subroutine, it must be OUT or INOUT. The subroutine itself may have an empty body, but the compiler does not know this and has to assume that the buffer may be altered. For example, the above call of MPI_RECV might be replaced by

```
call DD(buf)
call MPI_RECV(MPI_BOTTOM,...)
call DD(buf)
```

[(assuming that buf has type INTEGER). The compiler may be similarly prevented from moving a reference to a variable across a call to an MPI subroutine.

In the case of a nonblocking call, as in the above call of MPI_WAIT, no reference to the buffer is permitted until it has been verified that the transfer has been completed. Therefore, in this case, the extra call ahead of the MPI call is not necessary, i.e., the call of MPI_WAIT in the example might be replaced by

```
/tt call MPI_WAIT(req,..) call DD(buf) ]
```

An alternative is to put the buffer or variable into a module or a common block and access it through a USE or COMMON statement in each scope where it is referenced, defined or appears as an actual argument in a call to an MPI routine. The compiler will then have to assume that the MPI procedure (MPI_RECV in the above example) may alter the buffer or variable, provided that the compiler cannot analyze that the MPI procedure does not reference the module or common block.

- This method solves problems of instruction reordering, code movement, and register optimization related to nonblocking and one-sided communication, or related to the usage of MPI_BOTTOM and derived datatype handles.
- Unfortunately, this method has **not** any impact on problems caused by asynchronous accesses between the start and end of a nonblocking or one-sided communication, i.e., problems through temporary memory modifications are not solved.

П

The VOLATILE attribute[, available in later versions of Fortran], gives the buffer or variable the properties needed, but it may inhibit optimization of any code containing the buffer or variable.

In C, subroutines which modify variables that are not in the argument list will not cause register optimization problems. This is because taking pointers to storage objects by using the & operator and later referencing the objects by way of the pointer is an integral part of the language. A C compiler understands the implications, so that the problem should not occur, in general. However, some compilers do offer optional aggressive optimization levels which may not be safe.

[]

16.2.3 [Basic]Fortran Support Through the mpif.h Include File

The use of the mpif.h include file is strongly discouraged.

Because Fortran 90 is (for all practical purposes) a superset of Fortran 77, Fortran 90 (and future) programs can use the original Fortran interface. The Fortran bindings are compatible with Fortran 77 implicit-style interfaces in most cases. [The following additional requirements are added:] The include file mpif.h must:

- 1. Implementations are required to provide the file mpif.h, as described in the original MPI-1 specification.
- 2. mpif.h must be valid and equivalent for both fixed- and free- source form.

- Define all named MPI constants.
- Declare MPI functions that return a value.

Unofficial Draft for Comment Only

⁶ ticket238-J.

4

11

12

16 17

20

21

22

23

24

27 28 29

ticket238-J.
 ticket238-J.

¹⁸ ticket238-J.

 26 ticket238-J.

³² ticket230-B. ³² ticket230-B. ³³ ticket233-E.

35 ticket230-B. 36 ticket230-B.

зт ticket230-В.

38 39

40

42

43 44 45

46 47

2

4 5

6 7

9

10

11

12

13

14

15

16 17

24

25

26

27

28

29

30 31

32

33 34 35

36 37 38

43

44 45

ticket230-B. 19 ticket230-B. 20

ticket230-B. 21

ticket230-B. 22 ticket230-B. 39 ticket230-B. ticket231-C. 48

- Define all handles as INTEGER. This is reflected in the first of the two Fortran interfaces in each MPI function definition.
- Be valid and equivalent for both fixed- and free- source form.

For each MPI routine, an implementation can choose to use an implicit or explicit interface.

Advice to implementors. To make mpif.h compatible with both fixed- and free-source forms, to allow automatic inclusion by preprocessors, and to allow extended fixed-form line length, it is recommended that requirement two be met by constructing mpif.h without any continuation lines. This should be possible because mpif.h contains only declarations, and because common block declarations can be split among several lines. To support Fortran 77 as well as Fortran 90, it may be necessary to eliminate all comments from mpif.h. (End of advice to implementors.)

16.2.4 [Extended]Fortran Support Through the mpi Module

Implementations with Extended Fortran support must provide:

- 1. An mpi module [
- 2. (List item was moved to another location, and modified) A new set of functions to provide additional support for Fortran intrinsic numeric types, including parameterized types: MPI_SIZEOF, MPI_TYPE_MATCH_SIZE, MPI_TYPE_CREATE_F90_INTEGER, MPI_TYPE_CREATE_F90_REAL and MPI_TYPE_CREATE_F90_COMPLEX. Parameterized types are Fortran intrinsic types which are specified using KIND type parameters. These routines are described in detail in Section 16.2.7.

Additionally, high-quality implementations should provide a mechanism to prevent fatal type mismatch errors for MPI routines with choice arguments.

```
The mpi Module
```

An MPI implementation must provide a module named mpi that can be used in a Fortran [90] program. This module must:

- Define all named MPI constants
- Declare MPI functions that return a value.
- Provide explicit interfaces for all MPI routines, i.e., this module guarantees compiletime argument checking, and allows positional and keyword-based argument lists.
- Define all handles as INTEGER. This is reflected in the first of the two Fortran interfaces in each MPI function definition.

Unofficial Draft for Comment Only

ticket243-O. ticket231-C. • Define also all the named handle types and MPI_Status that are used in the mpi_f08 module. They are needed only when the application needs to convert and old-style INTEGER handle into a new-style handle with a named type.

An MPI implementation may provide other features in the mpi module [other features] that enhance the usability of MPI while maintaining adherence to the standard. For example, it may[:]provide INTENT information in these interface blocks.

- Provide interfaces for all or for a subset of MPI routines.
- Provide INTENT information in these interface blocks.

Advice to implementors. The appropriate INTENT may be different from what is given in the MPI generic interface. Implementations must choose INTENT so that the function adheres to the MPI standard. (End of advice to implementors.)

Rationale. The intent given by the MPI generic interface is not precisely defined and does not in all cases correspond to the correct Fortran INTENT. For instance, receiving into a buffer specified by a datatype with absolute addresses may require associating MPI_BOTTOM with a dummy OUT argument. Moreover, "constants" such as MPI_BOTTOM and MPI_STATUS_IGNORE are not constants as defined by Fortran, but "special addresses" used in a nonstandard way. Finally, the MPI-1 generic intent is changed in several places by MPI-2. For instance, MPI_IN_PLACE changes the sense of an OUT argument to be INOUT. (End of rationale.)

[(Paragraph was moved to another location, and modified) Applications may use either the mpi module or the mpif.h include file. An implementation may require use of the module to prevent type mismatch errors (see below).

Advice to users. It is recommended to use the mpi module even if it is not necessary to use it to avoid type mismatch errors on a particular system. Using a module provides several potential advantages over using an include file. (End of advice to users.)

It must be possible to link together routines some of which $\tt USE\ mpi$ and others of which $\tt INCLUDE\ mpif.h.$]

No Type Mismatch Problems for Subroutines with Choice Arguments

A high-quality MPI implementation should provide a mechanism to ensure that MPI choice arguments do not cause fatal compile-time or run-time errors due to type mismatch. An MPI implementation may require applications to use the mpi module, or require that it be compiled with a particular compiler flag, in order to avoid type mismatch problems.

ticket230-B.
 ticket230-B.
 ticket230-B.
 ticket230-B.

ticket230-B.

₃₇ ticket232-D.

2

3

5 6

ticket232-D.

15 16 17

18

19

20

21

23 24

34

35

37

38

41

42

43 44

45

46

47

14

10

11

12 13

ticket234-F.

ticket 230-B. 25 ticket 230-B. 26

ticket247-S. 28 $ticket 241-M._{29}$ ticket 230-B. $_{30}$ ticket 230-B. $_{\scriptscriptstyle 31}$

33

ticket 231-C. $_{36}$

ticket234-F.

In the case where the compiler does not generate errors, Advice to implementors. nothing needs to be done to the existing interface. In the case where the compiler may generate errors, a set of overloaded functions may be used. See the paper of M. Hennecke [26]. Even if the compiler does not generate errors, explicit interfaces for all routines would be useful for detecting errors in the argument list. Also, explicit interfaces which give INTENT information can reduce the amount of copying for BUF(*) arguments. (End of advice to implementors.)

Advice to implementors. In the mpi module with some compilers, a choice argument can be implemented with the following explicit interface:

```
!DEC$ ATTRIBUTES NO_ARG_CHECK :: BUF
!$PRAGMA IGNORE_TKR BUF
REAL, DIMENSION(*) :: BUF
```

In this case, the compile-time constant MPI_SUBARRAYS equals MPI_SUBARRAYS_UNSUPPORTED. It is explicitly allowed that the choice arguments are implemented in the same way as with the mpi_f08 module. In the case where the compiler does not provide such functionality, a set of overloaded functions may be used. See the paper of M. Hennecke [26]. (End of advice to implementors.)

Fortran Support Through the mpi_f08 Module 16.2.5

An MPI implementation must provide a module named mpi_f08 that can be used in a Fortran program. With this module, new Fortran definitions are added for each MPI routine, except for routines that are deprecated. This module must:

- Define all named MPI constants.
- Declare MPI functions that return a value.
- Provide explicit interfaces for all MPI routines, i.e., this module guarantees compiletime argument checking.
- Define all handles with uniquely named handle types (instead of INTEGER handles in the mpi module). This is reflected in the second of the two Fortran interfaces in each MPI function definition.
- Set the INTEGER compile-time constant MPI_SUBARRAYS to MPI_SUBARRAYS_SUPPORTED and declare choice buffers with the Fortran 2008 feature assumed-type and assumed-rank TYPE(*), DIMENSION(..) if the underlying Fortran compiler supports it. With this, non-contiguous sub-arrays are valid also in nonblocking routines.
- Set the MPI_SUBARRAYS compile-time constant to MPI_SUBARRAYS_UNSUPPORTED and declare choice buffers with a compiler-dependent mechanism that overrides type

checking if the underlying Fortran compiler does not support the Fortran 2008 assumedtype and assumed-rank notation. In this case, the use of non-contiguous sub-arrays in nonblocking calls may be restricted as with the mpi module.

ticket234-F.

Advice to implementors. In this case, the choice argument may be implemented with an explicit interface with compiler directives, for example:

!DEC\$ ATTRIBUTES NO_ARG_CHECK :: BUF !\$PRAGMA IGNORE_TKR BUF REAL, DIMENSION(*) :: BUF

(End of advice to implementors.)

- Declare each argument with an INTENT=IN, OUT, or INOUT as appropriate.
- Declare all status and array_of_statuses output arguments as optional through function overloading, instead of using MPI_STATUS_IGNORE.
- Declare all array_of_errcodes output arguments as optional through function overloading, instead of using MPI_ERRCODES_IGNORE.
- Declare all ierror output arguments as OPTIONAL, except for user-defined callback functions (e.g., ftypeCOMM_COPY_ATTR_FUNCTION) and their predefined callbacks (e.g., MPI_NULL_COPY_FN).

Rationale. For user-defined callback functions (e.g., COMM_COPY_ATTR_FUNCTION) and their predefined callbacks (e.g., MPI_NULL_COPY_FN), the ierror argument is not optional, i.e., these user-defined functions need not to check whether the MPI library calls these routines with or without an actual ierror output argument. (End of rationale.)

The MPI Fortran bindings in the mpi_f08 module are designed based on the Fortran 2008 standard [34] together with the Technical Report (TR) on Further Interoperability with C [35] of the ISO/IEC JTC1/SC22/WG5 (Fortran) working group.

Rationale. The TR on further interoperability with C was defined by WG5 to support the MPI-3.0 standardization. "It is the intention of ISO/IEC JTC1/SC22/WG5 that the semantics and syntax specified by this technical report be included in the next revision of the Fortran International Standard without change unless experience in the implementation and use of this feature identifies errors that need to be corrected, or changes are needed to achieve proper integration, in which case every reasonable effort will be made to minimize the impact of such changes on existing implementations." ³

This TR contains language features that are needed for the MPI bindings in the mpi_f08 module: assumed type and assumed rank. Here, it is important that any

 14 ticket 242-N.

11 12

13

17

27 28

29 30

31

32

35

36 37 38

41

42

43

44

45

46

47

16 ticket244-P.

ticket244-P.

²¹ ticket239-K.

24 ticket250-V.
 25 ticket239-K.
 26 ticket239-K.

зз ticket230-В.

 $^{^{3}[35]}$ page iv, sentence 7.

 possible actual argument can be used for such dummy arguments, e.g., scalars, arrays, assumed-shape arrays, assumed-size arrays, allocatable arrays, and with any element type, e.g., REAL, REAL*4, CHARACTER*5, CHARACTERR*(*), derived types.

Furthermore, the implementors of the MPI Fortran bindings can freely choose whether all bindings are defined as BIND(C). This is important to implement the Fortran mpi_f08 interface with only **one** set of **portable** wrapper routines written in C. For this implementation goal, the following additional features are used: BIND(C) together with OPTIONAL, and with standard Fortran types like INTEGER and CHARACTER (i.e., not only with INTEGER(C_INT)).

The MPI Forum wants to acknoledge this important effort by the Fortran WG5 committee. (*End of rationale.*)

ticket238-J.

16.2.6 Additional Support for Fortran Register-Memory-Synchronization

As described in Section 16.2.2 on page 549, a dummy call is needed to tell the compiler that registers are to be flushed for a given buffer. It is a generic Fortran routine and has only a Fortran binding.

This routine has no operation associated with. It must be compiled in the MPI library in the way that a Fortran compiler cannot detect in the module that the routine has an empty body. It is used only to tell the compiler that a cached register value of a variable or buffer should be flushed, i.e., stored back to the memory (when necessary) or invalidated.

Rationale. This function is not available in other languages because it would not be useful. This routine has not an ierror return argument because there isn't any operation that can detect an error. (End of rationale.)

Advice to implementors. It is recommended to bind this routine to a C routine to minimize the risk that the fortran compiler can learn that this routine is empty, i.e., that the compiler can learn that a call to this routine can be removed as part of the automated optimization. (End of advice to implementors.)

ticket-248T. ²⁷

ticket252-W.

```
MPI_TYPE_MATCH_SIZE(typeclass, size, datatype)
                                                                                          <sup>1</sup> ticket252-W.
 IN
           typeclass
                                       generic type specifier (integer)
 IN
           size
                                       size, in bytes, of representation (integer)
           [ticket252-W.]datatype
 OUT
                                       datatype with correct type, size (handle)
int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *datatype)
MPI_TYPE_MATCH_SIZE(TYPECLASS, SIZE, DATATYPE, IERROR)
                                                                                          9 ticket252-W.
    INTEGER TYPECLASS, SIZE, DATATYPE, IERROR
                                                                                          10 ticket252-W.
                                                                                          11 ticket-248T.
MPI_Type_match_size(typeclass, size, datatype, ierror)
    INTEGER, INTENT(IN) :: typeclass, size
                                                                                          13
    TYPE(MPI_Datatype), INTENT(OUT) :: datatype
                                                                                          14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                          15
{static MPI::Datatype MPI::Datatype::Match_size(int typeclass,
                                                                                          16
               int size) (binding deprecated, see Section 15.2) }
                                                                                          18
    typeclass is one of MPI_TYPECLASS_REAL, MPI_TYPECLASS_INTEGER and
                                                                                          19
MPI_TYPECLASS_COMPLEX, corresponding to the desired typeclass. The function returns
                                                                                          20
an MPI datatype matching a local variable of type (typeclass, size).
                                                                                          21
    This function returns a reference (handle) to one of the predefined named datatypes, not
                                                                                          22
a duplicate. This type cannot be freed. MPI_TYPE_MATCH_SIZE can be used to obtain a
                                                                                          23
size-specific type that matches a Fortran numeric intrinsic type by first calling MPI_SIZEOF
                                                                                          24
in order to compute the variable size, and then calling MPI_TYPE_MATCH_SIZE to find a
suitable datatype. In C and C++, one can use the C function sizeof(), instead of
                                                                                          26
MPI_SIZEOF. In addition, for variables of default kind the variable's size can be computed
                                                                                          27
by a call to MPI_TYPE_GET_EXTENT, if the typeclass is known. It is erroneous to specify
                                                                                          28
a size not supported by the compiler.
                                                                                          29
                                                                                          30
     Rationale. This is a convenience function. Without it, it can be tedious to find the
                                                                                          31
     correct named type. See note to implementors below. (End of rationale.)
                                                                                          33
                                                                                          34
     Advice to implementors. This function could be implemented as a series of tests.
                                                                                          35
                                                                                          36
     int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *rtype)
                                                                                          37
                                                                                          38
       switch(typeclass) {
            case MPI_TYPECLASS_REAL: switch(size) {
              case 4: *rtype = MPI_REAL4; return MPI_SUCCESS;
                                                                                          41
              case 8: *rtype = MPI_REAL8; return MPI_SUCCESS;
                                                                                          42
              default: error(...);
                                                                                          43
                                                                                          44
            case MPI_TYPECLASS_INTEGER: switch(size) {
               case 4: *rtype = MPI_INTEGER4; return MPI_SUCCESS;
                                                                                          45
                                                                                          46
               case 8: *rtype = MPI_INTEGER8; return MPI_SUCCESS;
                                                                                          47
               default: error(...);
```

... etc. ...

 ticket 231-C.

Advice to implementors. Implementations may selectively link language specific MPI libraries only to codes that need them, so as not to increase the size of binaries for codes that use only one language. The MPI initialization code need perform initialization for a language only if that language library is loaded. (End of advice to implementors.)

16.3.4 Transfer of Handles

Handles are passed between Fortran and C or C++ by using an explicit C wrapper to convert Fortran handles to C handles. There is no direct access to C or C++ handles in Fortran. Handles are passed between C and C++ using overloaded C++ operators called from C++ code. There is no direct access to C++ objects from C.

The type definition MPI_Fint is provided in C/C++ for an integer of the size that matches a Fortran INTEGER; usually, MPI_Fint will be equivalent to int. With the Fortran mpi module or the mpif.h include file, a Fortran handle is a Fortran INTEGER value that can be used in the following conversion functions. With the Fortran mpi_f08 module, a Fortran handle is a derived type that contains the Fortran INTEGER field MPI_VAL, which contains the INTEGER value that can be used in the following conversion functions.

The following functions are provided in C to convert from a Fortran communicator handle (which is an integer) to a C communicator handle, and vice versa. See also Section 2.6.5 on page 22.

```
MPI_Comm MPI_Comm_f2c(MPI_Fint comm)
```

If comm is a valid Fortran handle to a communicator, then MPI_Comm_f2c returns a valid C handle to that same communicator; if comm = MPI_COMM_NULL (Fortran value), then MPI_Comm_f2c returns a null C handle; if comm is an invalid Fortran handle, then MPI_Comm_f2c returns an invalid C handle.

```
MPI_Fint MPI_Comm_c2f(MPI_Comm comm)
```

The function MPI_Comm_c2f translates a C communicator handle into a Fortran handle to the same communicator; it maps a null handle into a null handle and an invalid handle into an invalid handle.

Similar functions are provided for the other types of opaque objects.

```
MPI_Datatype MPI_Type_f2c(MPI_Fint datatype)
MPI_Fint MPI_Type_c2f(MPI_Datatype datatype)
MPI_Group MPI_Group_f2c(MPI_Fint group)
MPI_Fint MPI_Group_c2f(MPI_Group group)
MPI_Request MPI_Request_f2c(MPI_Fint request)
MPI_Fint MPI_Request_c2f(MPI_Request request)
MPI_File MPI_File_f2c(MPI_Fint file)
MPI_Fint MPI_File_c2f(MPI_File file)
MPI_Win MPI_Win_f2c(MPI_Fint win)
```

```
1
     // C function prototype
2
     extern "C" {
3
        void c_lib_call(MPI_Comm c_comm);
4
     }
5
6
     void cpp_function()
7
8
        // Create a C++ communicator, and initialize it with a dup of
9
             MPI::COMM_WORLD
10
        MPI::Intracomm cpp_comm(MPI::COMM_WORLD.Dup());
11
        c_lib_call(cpp_comm);
     }
12
13
```

Rationale. Providing conversion from C to C++ via constructors and from C++ to C via casting allows the compiler to make automatic conversions. Calling C from C++ becomes trivial, as does the provision of a C or Fortran interface to a C++ library. (End of rationale.)

Advice to users. Note that the casting and promotion operators return new handles by value. Using these new handles as INOUT parameters will affect the internal MPI object, but will not affect the original handle from which it was cast. (End of advice to users.)

It is important to note that all C++ objects with corresponding C handles can be used interchangeably by an application. For example, an application can cache an attribute on MPI_COMM_WORLD and later retrieve it from MPI::COMM_WORLD.

16.3.5 Status

The following two procedures are provided in C to convert from a Fortran (with the mpi module or mpif.h) status (which is an array of integers) to a C status (which is a structure), and vice versa. The conversion occurs on all the information in status, including that which is hidden. That is, no status information is lost in the conversion.

```
int MPI_Status_f2c(MPI_Fint *f_status, MPI_Status *c_status)
```

If f_status is a valid Fortran status, but not the Fortran value of MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE, then MPI_Status_f2c returns in c_status a valid C status with the same content. If f_status is the Fortran value of MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE, or if f_status is not a valid Fortran status, then the call is erroneous.

The C status has the same source, tag and error code values as the Fortran status, and returns the same answers when queried for count, elements, and cancellation. The conversion function may be called with a Fortran status argument that has an undefined error field, in which case the value of the error field in the C status argument is undefined.

Two global variables of type MPI_Fint*, MPI_F_STATUS_IGNORE and MPI_F_STATUSES_IGNORE are declared in mpi.h. They can be used to test, in C, whether f_status is the Fortran value of MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE, respectively. These are global variables, not C constant expressions and cannot be used in places where C requires constant expressions. Their value is defined only between the calls to MPI_INIT and MPI_FINALIZE and should not be changed by user code.

ticket243-O. 29

tively
when

```
To do the conversion in the other direction, we have the following: int MPI_Status_c2f(MPI_Status *c_status, MPI_Fint *f_status)
```

This call converts a C status into a Fortran status, and has a behavior similar to MPI_Status_f2c. That is, the value of c_status must not be either MPI_STATUS_IGNORE or MPI_STATUSES_IGNORE.

Advice to users. There is not a separate conversion function for arrays of statuses, since one can simply loop through the array, converting each status. (End of advice to users.)

Rationale. The handling of MPI_STATUS_IGNORE is required in order to layer libraries with only a C wrapper: if the Fortran call has passed MPI_STATUS_IGNORE, then the C wrapper must handle this correctly. Note that this constant need not have the same value in Fortran and C. If MPI_Status_f2c were to handle MPI_STATUS_IGNORE, then the type of its result would have to be MPI_Status**, which was considered an inferior solution. (End of rationale.)

Using the mpi_f08 Fortran module, a status is declared as TYPE(MPI_Status). The C datatype MPI_F_status can be used to hand over a Fortran TYPE(MPI_Status) argument into a C routine.

```
int MPI_Status_f082c(MPI_F_status *f08_status, MPI_Status *c_status)
    This C routine converts a Fortran mpi_f08 f08_status into a C c_status.
int MPI_Status_c2f08(MPI_Status *c_status, MPI_F_status *f08_status)
```

This C routine converts a C c_status into a Fortran mpi_f08 f08_status. Conversion between the two Fortran versions of a status can be done with:

INTEGER, OPTIONAL :: ierror

This routine converts a Fortran mpi module status into a Fortran mpi_f08 f08_status.

ticket243-O.

40 ticket-248T.

```
1
                MPI_STATUS_F082F(f08_status, f_status)
           2
                  IN
                           f08_status
                                                      status object declared as named type
           3
                  OUT
                           f_status
                                                      status object declared as array
           4
           5
           6
                int MPI_Status_f082f(MPI_F_status *f08_status, MPI_Fint *f_status)
           7
                MPI_STATUS_F082F(F08_STATUS, F_STATUS, IERROR)
           8
                     TYPE(MPI_Status) :: F08_STATUS
           9
                     INTEGER F_STATUS(MPI_STATUS_SIZE)
           10
                     INTEGER IERROR
ticket-248T. 11
           12
                MPI_Status_f082f(f08_status, f_status, ierror)
                     TYPE(MPI_Status) :: f08_status
           13
           14
                     INTEGER :: f_status(MPI_STATUS_SIZE)
           15
                     INTEGER, OPTIONAL :: ierror
```

This routine converts a Fortran mpi_f08 module f08_status into a Fortran mpi status.

16.3.6 MPI Opaque Objects

Unless said otherwise, opaque objects are "the same" in all languages: they carry the same information, and have the same meaning in both languages. The mechanism described in the previous section can be used to pass references to MPI objects from language to language. An object created in one language can be accessed, modified or freed in another language.

We examine below in more detail, issues that arise for each type of MPI object.

Datatypes

 $\frac{45}{46}$

Datatypes encode the same information in all languages. E.g., a datatype accessor like MPI_TYPE_GET_EXTENT will return the same information in all languages. If a datatype defined in one language is used for a communication call in another language, then the message sent will be identical to the message that would be sent from the first language: the same communication buffer is accessed, and the same representation conversion is performed, if needed. All predefined datatypes can be used in datatype constructors in any language. If a datatype is committed, it can be used for communication in any language.

The function MPI_GET_ADDRESS returns the same value in all languages. Note that we do not require that the constant MPI_BOTTOM have the same value in all languages (see 16.3.9, page 585).

Example 16.19

```
! FORTRAN CODE
REAL R(5)
INTEGER TYPE, IERR, AOBLEN(1), AOTYPE(1)
INTEGER (KIND=MPI_ADDRESS_KIND) AODISP(1)
! create an absolute datatype for array R
AOBLEN(1) = 5
```

Assorted	Constants
----------	-----------

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_PROC_NULL	MPI::PROC_NULL
MPI_ANY_SOURCE	MPI::ANY_SOURCE
MPI_ANY_TAG	MPI::ANY_TAG
MPI_UNDEFINED	MPI::UNDEFINED
MPI_BSEND_OVERHEAD	MPI::BSEND_OVERHEAD
MPI_KEYVAL_INVALID	MPI::KEYVAL_INVALID
MPI_LOCK_EXCLUSIVE	MPI::LOCK_EXCLUSIVE
MPI_LOCK_SHARED	MPI::LOCK_SHARED
MPI_ROOT	MPI::ROOT

Status size and reserved index values (Fortran only)

Fortran type: INTEGER	
MPI_STATUS_SIZE	Not defined for C++
MPI_SOURCE	Not defined for C++
MPI_TAG	Not defined for C++
MPI_ERROR	Not defined for C++

Variable Address Size (Fortran only)

	- ,
Fortran type: INTEGER	
MPI_ADDRESS_KIND	Not defined for C++
MPI_INTEGER_KIND	Not defined for C++
MPI_OFFSET_KIND	Not defined for C++

Error-handling specifiers

C type: MPI_Errhandler	$\mathrm{C}++ \mathrm{\ type}$: MPI::Errhandler
Fortran type: INTEGER	
[ticket231-C.]or TYPE(MPI_Errhandler)	
MPI_ERRORS_ARE_FATAL	MPI::ERRORS_ARE_FATAL
MPI_ERRORS_RETURN	MPI::ERRORS_RETURN
	MPI::ERRORS_THROW_EXCEPTIONS

Maximum Sizes for Strings

With Sizes for Strings				
C type: const int (or unnamed enum)	C++ type:			
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>			
MPI_MAX_PROCESSOR_NAME	MPI::MAX_PROCESSOR_NAME			
MPI_MAX_ERROR_STRING	MPI::MAX_ERROR_STRING			
MPI_MAX_DATAREP_STRING	MPI::MAX_DATAREP_STRING			
MPI_MAX_INFO_KEY	MPI::MAX_INFO_KEY			
MPI_MAX_INFO_VAL	MPI::MAX_INFO_VAL			
MPI_MAX_OBJECT_NAME	MPI::MAX_OBJECT_NAME			
MPI_MAX_PORT_NAME	MPI::MAX_PORT_NAME			

Named Predefine	ed Datatypes	C/C++ types
C type: MPI_Datatype	C++ type: MPI::Datatype	
Fortran type: INTEGER		
[ticket231-C.]or TYPE(MPI_Datatype)		
MPI_CHAR	MPI::CHAR	char
		(treated as printable
		character)
MPI_SHORT	MPI::SHORT	signed short int
MPI_INT	MPI::INT	signed int
MPI_LONG	MPI::LONG	signed long
MPI_LONG_LONG_INT	MPI::LONG_LONG_INT	signed long long
MPI_LONG_LONG	MPI::LONG_LONG	long long (synonym)
MPI_SIGNED_CHAR	MPI::SIGNED_CHAR	signed char
	-	(treated as integral value
MPI_UNSIGNED_CHAR	MPI::UNSIGNED_CHAR	unsigned char
_ ,		(treated as integral value
MPI_UNSIGNED_SHORT	MPI::UNSIGNED_SHORT	unsigned short
MPI_UNSIGNED	MPI::UNSIGNED	unsigned int
MPI_UNSIGNED_LONG	MPI::UNSIGNED_LONG	unsigned long
MPI_UNSIGNED_LONG_LONG	MPI::UNSIGNED_LONG_LONG	unsigned long long
MPI_FLOAT	MPI::FLOAT	float
MPI_DOUBLE	MPI::DOUBLE	double
MPI_LONG_DOUBLE	MPI::LONG_DOUBLE	long double
MPI_WCHAR	MPI::WCHAR	wchar_t
		(defined in <stddef.h>)</stddef.h>
		(treated as printable
		character)
MPI_C_BOOL	(use C datatype handle)	_Bool
MPI_INT8_T	(use C datatype handle)	int8_t
MPI_INT16_T	(use C datatype handle)	int16_t
MPI_INT32_T	(use C datatype handle)	int32_t
MPI_INT64_T	(use C datatype handle)	int64_t
MPI_UINT8_T	(use C datatype handle)	uint8_t
MPI_UINT16_T	(use C datatype handle)	uint16_t
MPI_UINT32_T	(use C datatype handle)	uint32_t
MPI_UINT64_T	(use C datatype handle)	uint64_t
MPI_AINT	(use C datatype handle)	MPI_Aint
MPI_OFFSET	(use C datatype handle)	MPI_Offset
MPI_C_COMPLEX	(use C datatype handle)	
MPI_C_COMPLEX MPI_C_FLOAT_COMPLEX	(use C datatype handle)	float _Complex float _Complex
MPI_C_FLOAT_COMPLEX MPI_C_DOUBLE_COMPLEX	(use C datatype handle)	_
	,	double _Complex
MPI_C_LONG_DOUBLE_COMPLEX	(use C datatype handle) MPI::BYTE	long double _Complex
MPI_BYTE		(any C/C + type)
MPI_PACKED	MPI::PACKED	(any C/C++ type $)$

			1
Named Predefined	Fortran types	2	
C type: MPI_Datatype	C++ type: MPI::Datatype		3
Fortran type: INTEGER			4
[ticket231-C.]or TYPE(MPI_Datatype)			5
MPI_INTEGER	MPI::INTEGER	INTEGER	6
MPI_REAL	MPI::REAL	REAL	7
MPI_DOUBLE_PRECISION	MPI::DOUBLE_PRECISION	DOUBLE PRECISION	8
MPI_COMPLEX	MPI::F_COMPLEX	COMPLEX	9
MPI_LOGICAL	MPI::LOGICAL	LOGICAL	10
MPI_CHARACTER	MPI::CHARACTER	CHARACTER(1)	11
MPI_AINT	(use C datatype handle)	INTEGER (KIND=MPI_A	DDRESS_KIND)
MPI_OFFSET	(use C datatype handle)	INTEGER (KIND=MPI_O	FFSET3_KIND)
MPI_BYTE	MPI::BYTE	(any Fortran type)	14
MPI_PACKED	MPI::PACKED	(any Fortran type)	15
			16
			17

C++-Only Named Predefined Datatypes	C++ types
C++ type: MPI::Datatype	
MPI::BOOL	bool
MPI::COMPLEX	Complex <float></float>
MPI::DOUBLE_COMPLEX	Complex <double></double>
MPI::LONG_DOUBLE_COMPLEX	Complex <long double=""></long>

26 Optional datatypes (Fortran) Fortran types C type: MPI_Datatype C++ type: MPI::Datatype 27 Fortran type: INTEGER 28 [ticket231-C.]or TYPE(MPI_Datatype) 29 30 MPI_DOUBLE_COMPLEX MPI::F_DOUBLE_COMPLEX DOUBLE COMPLEX MPI_INTEGER1 MPI::INTEGER1 INTEGER*1 MPI_INTEGER2 MPI::INTEGER2 INTEGER*8 33 MPI_INTEGER4 MPI::INTEGER4 INTEGER*4 34 MPI::INTEGER8 INTEGER*8 MPI_INTEGER8 35 MPI_INTEGER16 INTEGER*16 36 MPI_REAL2 MPI::REAL2 REAL*2 37 MPI::REAL4 REAL*4 MPI_REAL4 MPI_REAL8 MPI::REAL8 REAL*8 MPI_REAL16 REAL*16 MPI_COMPLEX4 COMPLEX*4 MPI_COMPLEX8 COMPLEX*8 42 MPI_COMPLEX16 COMPLEX*16 MPI_COMPLEX32 COMPLEX*32 43 44

 $\frac{45}{46}$

1	Datatypes for reductio	n functions (C and C++)
2	C type: MPI_Datatype	C++ type: MPI::Datatype
3	Fortran type: INTEGER	
4	[ticket231-C.]or TYPE(MPI_Data	type)
5	MPI_FLOAT_INT	MPI::FLOAT_INT
6	MPI_DOUBLE_INT	MPI::DOUBLE_INT
7	MPI_LONG_INT	MPI::LONG_INT
8	MPI_2INT	MPI::TWOINT
9	MPI_SHORT_INT	MPI::SHORT_INT
10	MPI_LONG_DOUBLE_INT	MPI::LONG_DOUBLE_INT
11		
12		
13	Datatypes for reduct	tion functions (Fortran)
14	C type: MPI_Datatype	C++ type: MPI::Datatype
15	Fortran type: INTEGER	
16	$[{ m ticket}231 ext{-C.}]{ m or}$	pe)
17	MPI_2REAL	MPI::TWOREAL
18	MPI_2DOUBLE_PRECISION	MPI::TWODOUBLE_PRECISION
19	MPI_2INTEGER	MPI::TWOINTEGER
20		
21		
22	Special datatypes for con	structing derived datatypes
23	C type: MPI_Datatype	C++ type: MPI::Datatype
24	Fortran type: INTEGER	31
25	[ticket231-C.]or TYPE(MPI_Data	type)
26	MPI_UB	MPI::UB
27	MPI_LB	MPI::LB
28		
29		
30	Reserved c	ommunicators
31	C type: MPI_Comm	C++ type: MPI::Intracomm
32	Fortran type: INTEGER	O + + type. In 11.11101 docum
33	[ticket231-C.]or TYPE(MPI_Cor	nm)
34	MPI_COMM_WORLD	MPI::COMM_WORLD
35	MPI_COMM_SELF	MPI::COMM_SELF
36	- WI 1_COMM_SEE	WI ICOMM_SEE
37		
38	Posults of communicat	or and group comparisons
39		
40	C type: const int (or unnam	, , , ,
41	Fortran type: INTEGER	(or unnamed enum)
42	MPI_IDENT	MPI::IDENT
43	MPI_CONGRUENT	MPI::CONGRUENT
44	MPI_SIMILAR	MPI::SIMILAR
45	MPI_UNEQUAL	MPI::UNEQUAL

Environmental inquiry keys

C type: const int (or unnamed enum)	C++ type: const int
Fortran type: INTEGER	(or unnamed enum)
MPI_TAG_UB	MPI::TAG_UB
MPI_IO	MPI::IO
MPI_HOST	MPI::HOST
MPI_WTIME_IS_GLOBAL	MPI::WTIME_IS_GLOBAL

Collective Operations

	_
C type: MPI_Op	C++ type: const MPI::Op
Fortran type: INTEGER	
[ticket231-C.]or TYPE(MPI_Op)	
MPI_MAX	MPI::MAX
MPI_MIN	MPI::MIN
MPI_SUM	MPI::SUM
MPI_PROD	MPI::PROD
MPI_MAXLOC	MPI::MAXLOC
MPI_MINLOC	MPI::MINLOC
MPI_BAND	MPI::BAND
MPI_BOR	MPI::BOR
MPI_BXOR	MPI::BXOR
MPI_LAND	MPI::LAND
MPI_LOR	MPI::LOR
MPI_LXOR	MPI::LXOR
MPI_REPLACE	MPI::REPLACE

1	Null Handles	
2	C/Fortran name	C++ name
3	C type / Fortran type	C++ type
4	MPI_GROUP_NULL	MPI::GROUP_NULL
5	MPI_Group / INTEGER	const MPI::Group
6	[ticket231-C.] or TYPE(MPI_Group)	
7	MPI_COMM_NULL	MPI::COMM_NULL
8	MPI_Comm / INTEGER	1)
9	[ticket231-C.] or TYPE(MPI_Comm)	
10	MPI_DATATYPE_NULL	MPI::DATATYPE_NULL
11	${\tt MPI_Datatype / INTEGER}$	const MPI::Datatype
12	[ticket231-C.] or TYPE(MPI_Datatype)	
13	MPI_REQUEST_NULL	MPI::REQUEST_NULL
14	<pre>MPI_Request / INTEGER</pre>	const MPI::Request
15	[ticket231-C.] or TYPE(MPI_Request)	
16	MPI_OP_NULL	MPI::OP_NULL
17	MPI_Op / INTEGER	const MPI::Op
18	[ticket231-C.] or TYPE(MPI_Op)	
19	MPI_ERRHANDLER_NULL	MPI::ERRHANDLER_NULL
20	MPI_Errhandler / INTEGER	const MPI::Errhandler
21	[ticket231-C.] or TYPE(MPI_Errhandler)	
22	MPI_FILE_NULL	MPI::FILE_NULL
23	MPI_File / INTEGER	
24	[ticket231-C.] or TYPE(MPI_File)	
25	MPI_INFO_NULL	MPI::INFO_NULL
26	<pre>MPI_Info / INTEGER</pre>	const MPI::Info
27	[ticket231-C.] or TYPE(MPI_Info)	
28	MPI_WIN_NULL	MPI::WIN_NULL
29	MPI_Win / INTEGER	
30	[ticket231-C.] or TYPE(MPI_Win)	
31	1) C++ type: See Section 16.1.7 on page	e 536 regarding
32	class hierarchy and the specific type of	of MPI::COMM_NULL
33		
34		
35	Empty group	
36	C type: MPI_Group C-	++ type: const MPI::Group
37	Fortran type: INTEGER	
38	[ticket231-C.]or TYPE(MPI_Group)	
39	MPI_GROUP_EMPTY M	PI::GROUP_EMPTY
40		
41		
42	Topologie	\mathbf{s}
43	C type: const int (or unnamed enum	n) C++ type: const int
44	Fortran type: INTEGER	(or unnamed enum)
45	MPI_GRAPH	MPI::GRAPH
46	MPI_CART	MPI::CART
47	MPI_DIST_GRAPH	MPI::DIST_GRAPH
48	-	

Section 6.7.2 on page 266

Predefined functions		
C/Fortran name	C++ name	
C type / Fortran type	C++ type	
MPI_COMM_NULL_COPY_FN	MPI_COMM_NULL_COPY_FN	
MPI_Comm_copy_attr_function	same as in C^{-1})	
/ COMM_COPY_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_COMM_DUP_FN	MPI_COMM_DUP_FN	
MPI_Comm_copy_attr_function	same as in C^{-1})	
/ COMM_COPY_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_COMM_NULL_DELETE_FN	MPI_COMM_NULL_DELETE_FN	
MPI_Comm_delete_attr_function	same as in C^{-1})	
/ COMM_DELETE_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_WIN_NULL_COPY_FN	MPI_WIN_NULL_COPY_FN	
MPI_Win_copy_attr_function	same as in C^{-1})	
/ WIN_COPY_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_WIN_DUP_FN	MPI_WIN_DUP_FN	
MPI_Win_copy_attr_function	same as in C^{-1})	
/ WIN_COPY_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_WIN_NULL_DELETE_FN	MPI_WIN_NULL_DELETE_FN	
MPI_Win_delete_attr_function	same as in C^{-1})	
/ WIN_DELETE_ATTR_[ticket250-V.][FN]FUNCTION		
MPI_TYPE_NULL_COPY_FN	MPI_TYPE_NULL_COPY_FN	
MPI_Type_copy_attr_function	same as in C^{-1})	
/ TYPE_COPY_ATTR_[ticket250-V.] [FN] FUNCTION		
MPI_TYPE_DUP_FN	MPI_TYPE_DUP_FN	
MPI_Type_copy_attr_function	same as in C^{1})	
/ TYPE_COPY_ATTR_[ticket250-V.] [FN] FUNCTION	,	
MPI_TYPE_NULL_DELETE_FN	MPI_TYPE_NULL_DELETE_FN	
MPI_Type_delete_attr_function	same as in C^{-1})	
/ TYPE_DELETE_ATTR_[ticket250-V.] [FN] FUNCTION		
¹ See the advice to implementors on MPI_COMM_NULL_COPY_FN, in		

Deprecated predefined functions

<u>-</u>	
C/Fortran name	C++ name
C type / Fortran type	C++ type
MPI_NULL_COPY_FN	MPI::NULL_COPY_FN
MPI_Copy_function / COPY_FUNCTION	MPI::Copy_function
MPI_DUP_FN	MPI::DUP_FN
MPI_Copy_function / COPY_FUNCTION	MPI::Copy_function
MPI_NULL_DELETE_FN	MPI::NULL_DELETE_FN
${\tt MPI_Delete_function} \; / \; {\tt DELETE_FUNCTION}$	MPI::Delete_function

Unofficial Draft for Comment Only

File Operation Constants, Part 2	
C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_DISTRIBUTE_BLOCK	MPI::DISTRIBUTE_BLOCK
MPI_DISTRIBUTE_CYCLIC	MPI::DISTRIBUTE_CYCLIC
MPI_DISTRIBUTE_DFLT_DARG	MPI::DISTRIBUTE_DFLT_DARG
MPI_DISTRIBUTE_NONE	MPI::DISTRIBUTE_NONE
MPI_ORDER_C	MPI::ORDER_C
MPI_ORDER_FORTRAN	MPI::ORDER_FORTRAN
MPI_SEEK_CUR	MPI::SEEK_CUR
MPI_SEEK_END	MPI::SEEK_END
MPI_SEEK_SET	MPI::SEEK_SET

F90 Datatype Matching Constants

C type: const int (or unnamed enum)	C++ type:
Fortran type: INTEGER	<pre>const int (or unnamed enum)</pre>
MPI_TYPECLASS_COMPLEX	MPI::TYPECLASS_COMPLEX
MPI_TYPECLASS_INTEGER	MPI::TYPECLASS_INTEGER
MPI_TYPECLASS_REAL	MPI::TYPECLASS_REAL

Constants Specifying Empty or Ignored Input

constants specifying Limpty of Ignored input		
C/Fortran name	C++ name	
C type / Fortran type [ticket244-P.]with mpi module	C++ type	
[ticket244-P.]/ Fortran type with mpi_f08 module		
MPI_ARGVS_NULL	MPI::ARGVS_NULL	
char*** / 2-dim. array of CHARACTER*(*)	<pre>const char ***</pre>	
[ticket244-P.]/ 2-dim. array of CHARACTER*(*)		
MPI_ARGV_NULL	MPI::ARGV_NULL	
<pre>char** / array of CHARACTER*(*)</pre>	const char **	
[ticket244-P.]/ array of CHARACTER*(*)		
MPI_ERRCODES_IGNORE	Not defined for C++	
int* / INTEGER array		
[ticket244-P.]/ not defined		
MPI_STATUSES_IGNORE	Not defined for C++	
<pre>MPI_Status* / INTEGER, DIMENSION(MPI_STATUS_SIZE,*)</pre>		
[ticket244-P.]/ not defined		
MPI_STATUS_IGNORE	Not defined for C++	
<pre>MPI_Status* / INTEGER, DIMENSION(MPI_STATUS_SIZE)</pre>		
[ticket244-P.]/ not defined		
MPI_UNWEIGHTED	Not defined for C++	
int* / INTEGER array		
[ticket244-P.]/ not defined		

```
1
                MPI::File
           2
                MPI::Group
           3
                MPI::Info
           4
                MPI::Op
           5
                MPI::Request
           6
                MPI::Prequest
           7
                MPI::Grequest
                MPI::Win
ticket243-O. 9
                    The following are defined Fortran type definitions, included in the mpi_f08 and mpi
           11
                module.
           12
                ! Fortran opaque types in the mpi_f08 and mpi module
           13
                TYPE(MPI_Status)
           14
           15
                ! Fortran handles in the mpi_f08 and mpi module
           16
                TYPE(MPI_Comm)
           17
                TYPE(MPI_Datatype)
                TYPE(MPI_Errhandler)
                TYPE(MPI_File)
           20
                TYPE(MPI_Group)
           21
                TYPE(MPI_Info)
           22
                TYPE(MPI_Op)
           23
                TYPE(MPI_Request)
           24
                TYPE(MPI_Win)
           25
    ticket0._{27}
                A.1.3 Prototype [d] Definitions
           28
                The following are defined C typedefs for user-defined functions, also included in the file
           29
                mpi.h.
           30
           31
                /* prototypes for user-defined functions */
           32
                typedef void MPI_User_function(void *invec, void *inoutvec, int *len,
           33
                               MPI_Datatype *datatype);
           34
           35
                typedef int MPI_Comm_copy_attr_function(MPI_Comm oldcomm,
           36
                                int comm_keyval, void *extra_state, void *attribute_val_in,
           37
                                void *attribute_val_out, int*flag);
           38
                typedef int MPI_Comm_delete_attr_function(MPI_Comm comm,
           39
                                int comm_keyval, void *attribute_val, void *extra_state);
           40
           41
                typedef int MPI_Win_copy_attr_function(MPI_Win oldwin, int win_keyval,
           42
                                void *extra_state, void *attribute_val_in,
           43
                                void *attribute_val_out, int *flag);
           44
                typedef int MPI_Win_delete_attr_function(MPI_Win win, int win_keyval,
           45
                                void *attribute_val, void *extra_state);
           46
           47
                typedef int MPI_Type_copy_attr_function(MPI_Datatype oldtype,
                                int type_keyval, void *extra_state,
```

```
void *attribute_val_in, void *attribute_val_out, int *flag);
typedef int MPI_Type_delete_attr_function(MPI_Datatype type,
              int type_keyval, void *attribute_val, void *extra_state);
typedef void MPI_Comm_errhandler_function(MPI_Comm *, int *, ...);
typedef void MPI_Win_errhandler_function(MPI_Win *, int *, ...);
typedef void MPI_File_errhandler_function(MPI_File *, int *, ...);
typedef int MPI_Grequest_query_function(void *extra_state,
            MPI_Status *status);
typedef int MPI_Grequest_free_function(void *extra_state);
typedef int MPI_Grequest_cancel_function(void *extra_state, int complete);
                                                                                  12
                                                                                  13
typedef int MPI_Datarep_extent_function(MPI_Datatype datatype,
                                                                                  14
                                                                                  15
            MPI_Aint *file_extent, void *extra_state);
                                                                                  16
typedef int MPI_Datarep_conversion_function(void *userbuf,
            MPI_Datatype datatype, int count, void *filebuf,
            MPI_Offset position, void *extra_state);
                                                                                  19
   For Fortran, here are examples of how each of the user-defined subroutines should be
                                                                                  20
declared.
                                                                                  21
   The user-function argument to MPI_OP_CREATE should be declared like this:
                                                                                  22
                                                                                  23
SUBROUTINE USER_FUNCTION(INVEC, INOUTVEC, LEN, TYPE)
                                                                                  24
   <type> INVEC(LEN), INOUTVEC(LEN)
   INTEGER LEN, TYPE
                                                                                  27
   The copy and delete function arguments to MPI_COMM_CREATE_KEYVAL should be
                                                                                  28
declared like these:
                                                                                  29
SUBROUTINE COMM_COPY_ATTR_[ticket250-V.][FN]FUNCTION(OLDCOMM, COMM_KEYVAL, EXTRA STATE,
             ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
                                                                                  32
   INTEGER OLDCOMM, COMM_KEYVAL, IERROR
   INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
                                                                                  34
             ATTRIBUTE_VAL_OUT
                                                                                  35
   LOGICAL FLAG
SUBROUTINE COMM_DELETE_ATTR_[ticket250-V.] [FN] FUNCTION (COMM, COMM_KEYVAL, ATTRIBUTE_VAL,
             EXTRA_STATE, IERROR)
   INTEGER COMM, COMM_KEYVAL, IERROR
   INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
                                                                                  42
   The copy and delete function arguments to MPI_WIN_CREATE_KEYVAL should be
declared like these:
                                                                                  43
                                                                                  44
SUBROUTINE WIN_COPY_ATTR_[ticket250-V.] [FN] FUNCTION(OLDWIN, WIN_KEYVAL, EXTRA_STATE,
             ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
   INTEGER OLDWIN, WIN_KEYVAL, IERROR
                                                                                  47
   INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
```

```
1
                   ATTRIBUTE_VAL_OUT
2
        LOGICAL FLAG
4
     SUBROUTINE WIN_DELETE_ATTR_[ticket250-V.][FN] FUNCTION(WIN, WIN_KEYVAL, ATTRIBUTE_VAL,
5
                   EXTRA_STATE, IERROR)
6
        INTEGER WIN, WIN_KEYVAL, IERROR
        INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
         The copy and delete function arguments to MPI_TYPE_CREATE_KEYVAL should be
9
     declared like these:
10
11
     SUBROUTINE TYPE_COPY_ATTR_[ticket250-V.] [FN] FUNCTION(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE,
12
                    ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT, FLAG, IERROR)
13
        INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
14
        INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE,
15
                    ATTRIBUTE_VAL_IN, ATTRIBUTE_VAL_OUT
16
        LOGICAL FLAG
17
18
     SUBROUTINE TYPE_DELETE_ATTR_[ticket250-V.] [FN] FUNCTION([ticket252-W.]DATATYPE, TYPE_KEYVAL,
19
                    EXTRA_STATE, IERROR)
20
        INTEGER [ticket252-W.]DATATYPE, TYPE_KEYVAL, IERROR
21
        INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
22
23
         The handler-function argument to MPI_COMM_CREATE_ERRHANDLER should be de-
24
     clared like this:
25
26
     SUBROUTINE COMM_ERRHANDLER_FUNCTION(COMM, ERROR_CODE)
27
        INTEGER COMM, ERROR_CODE
28
29
         The handler-function argument to MPI_WIN_CREATE_ERRHANDLER should be de-
30
     clared like this:
31
32
     SUBROUTINE WIN_ERRHANDLER_FUNCTION(WIN, ERROR_CODE)
33
        INTEGER WIN, ERROR_CODE
34
35
         The handler-function argument to MPI_FILE_CREATE_ERRHANDLER should be de-
36
     clared like this:
37
38
     SUBROUTINE FILE_ERRHANDLER_FUNCTION(FILE, ERROR_CODE)
39
        INTEGER FILE, ERROR_CODE
40
41
         The query, free, and cancel function arguments to MPI_GREQUEST_START should be
42
     declared like these:
43
     SUBROUTINE GREQUEST_QUERY_FUNCTION(EXTRA_STATE, STATUS, IERROR)
44
        INTEGER STATUS(MPI_STATUS_SIZE), IERROR
45
        INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
46
47
     SUBROUTINE GREQUEST_FREE_FUNCTION(EXTRA_STATE, IERROR)
```

```
INTEGER IERROR
   INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
SUBROUTINE GREQUEST_CANCEL_FUNCTION(EXTRA_STATE, COMPLETE, IERROR)
   INTEGER IERROR
   INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
   LOGICAL COMPLETE
   The extend and conversion function arguments to MPI_REGISTER_DATAREP should
be declared like these:
SUBROUTINE DATAREP_EXTENT_FUNCTION(DATATYPE, EXTENT, EXTRA_STATE, IERROR)
                                                                                  12
    INTEGER DATATYPE, IERROR
                                                                                  13
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTENT, EXTRA_STATE
                                                                                  14
                                                                                  15
SUBROUTINE DATAREP_CONVERSION_FUNCTION(USERBUF, DATATYPE, COUNT, FILEBUF,
                                                                                  16
             POSITION, EXTRA_STATE, IERROR)
    <TYPE> USERBUF(*), FILEBUF(*)
    INTEGER COUNT, DATATYPE, IERROR
                                                                                  19
    INTEGER(KIND=MPI_OFFSET_KIND) POSITION
                                                                                  20
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                  21
                                                                                  22
    The following are defined C++ typedefs, also included in the file mpi.h.
                                                                                  23
                                                                                  24
namespace MPI {
  typedef void User_function(const void* invec, void *inoutvec,
              int len, const Datatype& datatype);
                                                                                  27
                                                                                  28
  typedef int Comm::Copy_attr_function(const Comm& oldcomm,
                                                                                  29
              int comm_keyval, void* extra_state, void* attribute_val_in,
              void* attribute_val_out, bool& flag);
                                                                                  30
  typedef int Comm::Delete_attr_function(Comm& comm, int
              comm_keyval, void* attribute_val, void* extra_state);
                                                                                  34
  typedef int Win::Copy_attr_function(const Win& oldwin,
                                                                                  35
              int win_keyval, void* extra_state, void* attribute_val_in,
                                                                                  36
              void* attribute_val_out, bool& flag);
                                                                                  37
  typedef int Win::Delete_attr_function(Win& win, int
              win_keyval, void* attribute_val, void* extra_state);
  typedef int Datatype::Copy_attr_function(const Datatype& oldtype,
              int type_keyval, void* extra_state,
                                                                                  42
              const void* attribute_val_in, void* attribute_val_out,
              bool& flag);
                                                                                  43
                                                                                  44
  typedef int Datatype::Delete_attr_function(Datatype& type,
                                                                                  45
              int type_keyval, void* attribute_val, void* extra_state);
                                                                                  46
                                                                                  47
  typedef void Comm::Errhandler_function(Comm &, int *, ...);
  typedef void Win::Errhandler_function(Win &, int *, ...);
```

```
1
                int MPI_Pack(void* inbuf, int incount, MPI_Datatype datatype, void *outbuf,
           2
                              int outsize, int *position, MPI_Comm comm)
           3
                int MPI_Pack_external(char *datarep, void *inbuf, int incount,
                             MPI_Datatype datatype, void *outbuf, MPI_Aint outsize,
           5
                             MPI_Aint *position)
           6
           7
                int MPI_Pack_external_size(char *datarep, int incount,
           8
                             MPI_Datatype datatype, MPI_Aint *size)
           9
                int MPI_Pack_size(int incount, MPI_Datatype datatype, MPI_Comm comm,
           10
                              int *size)
           11
          12
                int MPI_Type_commit(MPI_Datatype *datatype)
           13
                int MPI_Type_contiguous(int count, MPI_Datatype oldtype,
           14
                             MPI_Datatype *newtype)
           15
           16
                int MPI_Type_create_darray(int size, int rank, int ndims,
           17
                              int array_of_gsizes[], int array_of_distribs[], int
           18
                              array_of_dargs[], int array_of_psizes[], int order,
           19
                             MPI_Datatype oldtype, MPI_Datatype *newtype)
          20
                int MPI_Type_create_hindexed(int count, int array_of_blocklengths[],
          21
                             MPI_Aint array_of_displacements[], MPI_Datatype oldtype,
           22
                             MPI_Datatype *newtype)
          23
           24
                int MPI_Type_create_hvector(int count, int blocklength, MPI_Aint stride,
           25
                             MPI_Datatype oldtype, MPI_Datatype *newtype)
           26
                int MPI_Type_create_indexed_block(int count, int blocklength,
          27
                              int array_of_displacements[], MPI_Datatype oldtype,
           28
                             MPI_Datatype *newtype)
           29
           30
                int MPI_Type_create_resized(MPI_Datatype oldtype, MPI_Aint lb, MPI_Aint
           31
                             extent, MPI_Datatype *newtype)
           32
                int MPI_Type_create_struct(int count, int array_of_blocklengths[],
          33
          34
                             MPI_Aint array_of_displacements[],
                             MPI_Datatype array_of_types[], MPI_Datatype *newtype)
          35
           36
                int MPI_Type_create_subarray(int ndims, int array_of_sizes[],
           37
                              int array_of_subsizes[], int array_of_starts[], int order,
           38
                             MPI_Datatype oldtype, MPI_Datatype *newtype)
ticket252-W. 40
                int MPI_Type_dup(MPI_Datatype oldtype, MPI_Datatype *newtype)
           41
                int MPI_Type_free(MPI_Datatype *datatype)
           42
                int MPI_Type_get_contents(MPI_Datatype datatype, int max_integers,
           43
           44
                              int max_addresses, int max_datatypes, int array_of_integers[],
           45
                             MPI_Aint array_of_addresses[],
           46
                             MPI_Datatype array_of_datatypes[])
           47
                int MPI_Type_get_envelope(MPI_Datatype datatype, int *num_integers,
           48
```

A.2. C BINDINGS 613

```
int MPI_Ireduce(void* sendbuf, void* recvbuf, int count,
             MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm,
             MPI_Request* request)
int MPI_Ireduce_scatter(void* sendbuf, void* recvbuf, int [*]recvcounts[],
                                                                                    ticket0.
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
                                                                                    ticket0.
             MPI_Request* request)
                                                                                  7
int MPI_Ireduce_scatter_block(void* sendbuf, void* recvbuf, int recvcount,
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
             MPI_Request* request)
int MPI_Iscan(void* sendbuf, void* recvbuf, int count,
                                                                                  12
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm,
                                                                                  13
             MPI_Request* request)
                                                                                  14
                                                                                  15
int MPI_Iscatter(void* sendbuf, int sendcount, MPI_Datatype sendtype,
                                                                                  16
             void* recvbuf, int recvcount, MPI_Datatype recvtype, int root,
                                                                                  17
             MPI_Comm comm, MPI_Request* request)
int MPI_Iscatterv(void* sendbuf, int [*]sendcounts[], int [*]displs[],
                                                                                  19 ticket0.
                                                                                  20 ticket0.
             MPI_Datatype sendtype, void* recvbuf, int recvcount,
                                                                                  21 ticket0.
             MPI_Datatype recvtype, int root, MPI_Comm comm,
                                                                                  _{22} ticket0.
             MPI_Request* request)
                                                                                  23
int MPI_Op_commutative(MPI_Op op, int *commute)
int MPI_Op_create(MPI_User_function* [function]user_fn, int commute,
                                                                                  25 ticket252-W.
             MPI_Op* op)
                                                                                  27
int MPI_Reduce(void* sendbuf, void* recvbuf, int count,
                                                                                  28
             MPI_Datatype datatype, MPI_Op op, int root, MPI_Comm comm)
                                                                                  29
int MPI_Reduce_local(void* inbuf, void* inoutbuf, int count,
                                                                                  30
             MPI_Datatype datatype, MPI_Op op)
                                                                                  31
int MPI_Reduce_scatter(void* sendbuf, void* recvbuf, int [*]recvcounts[],
                                                                                    ticket0.
                                                                                    ticket0.
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
int MPI_Reduce_scatter_block(void* sendbuf, void* recvbuf, int recvcount,
                                                                                  35
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
                                                                                  36
                                                                                  37
int MPI_Scan(void* sendbuf, void* recvbuf, int count,
                                                                                  38
             MPI_Datatype datatype, MPI_Op op, MPI_Comm comm)
int MPI_Scatter(void* sendbuf, int sendcount, MPI_Datatype sendtype,
             void* recvbuf, int recvcount, MPI_Datatype recvtype, int root,
             MPI_Comm comm)
                                                                                  _{44} ticket0.
int MPI_Scatterv(void* sendbuf, int [*] sendcounts[], int [*] displs[],
             MPI_Datatype sendtype, void* recvbuf, int recvcount,
                                                                                    ticket0.
                                                                                    ticket0.
             MPI_Datatype recvtype, int root, MPI_Comm comm)
                                                                                  ticket0.
int MPI_op_free(MPI_Op *op)
```

A.2. C BINDINGS 615

```
int MPI_Group_incl(MPI_Group group, int n, int *ranks, MPI_Group *newgroup)
int MPI_Group_intersection(MPI_Group group1, MPI_Group group2,
             MPI_Group *newgroup)
int MPI_Group_range_excl(MPI_Group group, int n, int ranges[][3],
             MPI_Group *newgroup)
int MPI_Group_range_incl(MPI_Group group, int n, int ranges[][3],
             MPI_Group *newgroup)
int MPI_Group_rank(MPI_Group group, int *rank)
                                                                                  11
int MPI_Group_size(MPI_Group group, int *size)
                                                                                  12
                                                                                  13
int MPI_Group_translate_ranks (MPI_Group group1, int n, int *ranks1,
                                                                                  14
             MPI_Group group2, int *ranks2)
                                                                                  15
int MPI_Group_union(MPI_Group group1, MPI_Group group2,
                                                                                  16
             MPI_Group *newgroup)
                                                                                   17
                                                                                  18
int MPI_Intercomm_create(MPI_Comm local_comm, int local_leader,
                                                                                  19
             MPI_Comm peer_comm, int remote_leader, int tag,
                                                                                  20
             MPI_Comm *newintercomm)
                                                                                  21
int MPI_Intercomm_merge(MPI_Comm intercomm, int high,
                                                                                  22
             MPI_Comm *newintracomm)
                                                                                  23
                                                                                  24
int MPI_TYPE_DUP_FN(MPI_Datatype oldtype, int type_keyval,
                                                                                  25
             void *extra_state, void *attribute_val_in,
                                                                                  26
             void *attribute_val_out, int *flag)
                                                                                  27
int MPI_TYPE_NULL_COPY_FN(MPI_Datatype oldtype, int type_keyval,
                                                                                  28
             void *extra_state, void *attribute_val_in,
                                                                                  29
             void *attribute_val_out, int *flag)
                                                                                  30
int MPI_TYPE_NULL_DELETE_FN(MPI_Datatype datatype, int type_keyval, void
                                                                                    ticket252-W.
              *attribute_val, void *extra_state)
                                                                                  33
int MPI_Type_create_keyval(MPI_Type_copy_attr_function *type_copy_attr_fn,
                                                                                  34
             MPI_Type_delete_attr_function *type_delete_attr_fn,
                                                                                  35
              int *type_keyval, void *extra_state)
                                                                                  36
                                                                                  _{38} ticket252-W.
int MPI_Type_delete_attr(MPI_Datatype datatype, int type_keyval)
int MPI_Type_free_keyval(int *type_keyval)
                                                                                  _{41} ticket252-W.
int MPI_Type_get_attr(MPI_Datatype datatype, int type_keyval, void
             *attribute_val, int *flag)
                                                                                  ^{43} ticket 252-W.
int MPI_Type_get_name(MPI_Datatype datatype, char *type_name, int
             *resultlen)
                                                                                  _{46} ticket252-W.
int MPI_Type_set_attr(MPI_Datatype datatype, int type_keyval,
             void *attribute_val)
```

47

```
ticket252\text{-W}. <sup>1</sup>
                int MPI_Type_set_name(MPI_Datatype datatype, char *type_name)
                int MPI_WIN_DUP_FN(MPI_Win oldwin, int win_keyval, void *extra_state,
           3
                              void *attribute_val_in, void *attribute_val_out, int *flag)
           4
           5
                int MPI_WIN_NULL_COPY_FN(MPI_Win oldwin, int win_keyval, void *extra_state,
           6
                              void *attribute_val_in, void *attribute_val_out, int *flag)
           7
                int MPI_WIN_NULL_DELETE_FN(MPI_Win win, int win_keyval, void
           8
                              *attribute_val, void *extra_state)
           9
           10
                int MPI_Win_create_keyval(MPI_Win_copy_attr_function *win_copy_attr_fn,
           11
                              MPI_Win_delete_attr_function *win_delete_attr_fn,
           12
                              int *win_keyval, void *extra_state)
           13
                int MPI_Win_delete_attr(MPI_Win win, int win_keyval)
           14
           15
                int MPI_Win_free_keyval(int *win_keyval)
           16
                int MPI_Win_get_attr(MPI_Win win, int win_keyval, void *attribute_val,
           17
                              int *flag)
           18
           19
                int MPI_Win_get_name(MPI_Win win, char *win_name, int *resultlen)
           20
                int MPI_Win_set_attr(MPI_Win win, int win_keyval, void *attribute_val)
           21
           22
                int MPI_Win_set_name(MPI_Win win, char *win_name)
           23
           ^{24}
           25
                A.2.5 Process Topologies C Bindings
           26
                int MPI_Cart_coords(MPI_Comm comm, int rank, int maxdims, int *coords)
           27
           28
                int MPI_Cart_create(MPI_Comm comm_old, int ndims, int *dims, int *periods,
           29
                              int reorder, MPI_Comm *comm_cart)
           30
                int MPI_Cart_get(MPI_Comm comm, int maxdims, int *dims, int *periods,
           31
                              int *coords)
           32
           33
                int MPI_Cart_map(MPI_Comm comm, int ndims, int *dims, int *periods,
           34
                              int *newrank)
           35
                int MPI_Cart_rank(MPI_Comm comm, int *coords, int *rank)
           36
           37
                int MPI_Cart_shift(MPI_Comm comm, int direction, int disp,
           38
                              int *rank_source, int *rank_dest)
           39
                int MPI_Cart_sub(MPI_Comm comm, int *remain_dims, MPI_Comm *newcomm)
           40
           41
                int MPI_Cartdim_get(MPI_Comm comm, int *ndims)
           42
                int MPI_Dims_create(int nnodes, int ndims, int *dims)
           43
           44
                int MPI_Dist_graph_create(MPI_Comm comm_old, int n, int sources[],
           45
                              int degrees[], int destinations[], int weights[],
           46
                              MPI_Info info, int reorder, MPI_Comm *comm_dist_graph)
           47
```

A.2. CBINDINGS 617

```
int MPI_Dist_graph_create_adjacent(MPI_Comm comm_old, int indegree,
             int sources[], int sourceweights[], int outdegree,
             int destinations[], int destweights[], MPI_Info info,
             int reorder, MPI_Comm *comm_dist_graph)
int MPI_Dist_graph_neighbors(MPI_Comm comm, int maxindegree, int sources[],
             int sourceweights[], int maxoutdegree, int destinations[],
             int destweights[])
int MPI_Dist_graph_neighbors_count(MPI_Comm comm, int *indegree,
              int *outdegree, int *weighted)
int MPI_Graph_create(MPI_Comm comm_old, int nnodes, int *index, int *edges,
                                                                                  12
             int reorder, MPI_Comm *comm_graph)
                                                                                  13
                                                                                  14
int MPI_Graph_get(MPI_Comm comm, int maxindex, int maxedges, int *index,
                                                                                  15
             int *edges)
                                                                                  16
int MPI_Graph_map(MPI_Comm comm, int nnodes, int *index, int *edges,
              int *newrank)
                                                                                  18
                                                                                  19
int MPI_Graph_neighbors(MPI_Comm comm, int rank, int maxneighbors,
                                                                                  20
             int *neighbors)
                                                                                  21
int MPI_Graph_neighbors_count(MPI_Comm comm, int rank, int *nneighbors)
                                                                                  22
                                                                                  23
int MPI_Graphdims_get(MPI_Comm comm, int *nnodes, int *nedges)
                                                                                  24
int MPI_Topo_test(MPI_Comm comm, int *status)
                                                                                  25
                                                                                  26
                                                                                  27
A.2.6 MPI Environmental Management C Bindings
                                                                                  28
double MPI_Wtick(void)
                                                                                  29
                                                                                  30
double MPI_Wtime(void)
int MPI_Abort(MPI_Comm comm, int errorcode)
                                                                                  33
int MPI_Add_error_class(int *errorclass)
                                                                                  34
                                                                                  35
int MPI_Add_error_code(int errorclass, int *errorcode)
                                                                                  36
int MPI_Add_error_string(int errorcode, char *string)
                                                                                  37
                                                                                  38
int MPI_Alloc_mem(MPI_Aint size, MPI_Info info, void *baseptr)
                                                                                  39
int MPI_Comm_call_errhandler(MPI_Comm comm, int errorcode)
int MPI_Comm_create_errhandler(MPI_Comm_errhandler_function
                                                                                    ticket252-W.
             *[function]comm_errhandler_fn, MPI_Errhandler *errhandler)
int MPI_Comm_get_errhandler(MPI_Comm comm, MPI_Errhandler *errhandler)
                                                                                  44
                                                                                  45
int MPI_Comm_set_errhandler(MPI_Comm comm, MPI_Errhandler errhandler)
                                                                                  46
int MPI_Errhandler_free(MPI_Errhandler *errhandler)
                                                                                  47
```

```
1
                int MPI_Error_class(int errorcode, int *errorclass)
           2
                int MPI_Error_string(int errorcode, char *string, int *resultlen)
           3
                int MPI_File_call_errhandler(MPI_File fh, int errorcode)
                int MPI_File_create_errhandler(MPI_File_errhandler_function
ticket252-W. <sub>7</sub>
                              *[function]file_errhandler_fn, MPI_Errhandler *errhandler)
                int MPI_File_get_errhandler(MPI_File file, MPI_Errhandler *errhandler)
           9
                int MPI_File_set_errhandler(MPI_File file, MPI_Errhandler errhandler)
           10
           11
                int MPI_Finalize(void)
           12
                int MPI_Finalized(int *flag)
           13
           14
                int MPI_Free_mem(void *base)
           15
                int MPI_Get_processor_name(char *name, int *resultlen)
           16
           17
                int MPI_Get_version(int *version, int *subversion)
           18
                int MPI_Init(int *argc, char ***argv)
           19
           20
                int MPI_Initialized(int *flag)
           21
           22
                int MPI_Win_call_errhandler(MPI_Win win, int errorcode)
           23
                int MPI_Win_create_errhandler(MPI_Win_errhandler_function
ticket252-W. _{25}
                              *[function]win_errhandler_fn, MPI_Errhandler *errhandler)
           26
                int MPI_Win_get_errhandler(MPI_Win win, MPI_Errhandler *errhandler)
           27
                int MPI_Win_set_errhandler(MPI_Win win, MPI_Errhandler errhandler)
           28
           29
           30
                A.2.7 The Info Object C Bindings
           31
                int MPI_Info_create(MPI_Info *info)
           32
           33
                int MPI_Info_delete(MPI_Info info, char *key)
           34
                int MPI_Info_dup(MPI_Info info, MPI_Info *newinfo)
           35
           36
                int MPI_Info_free(MPI_Info *info)
           37
                int MPI_Info_get(MPI_Info info, char *key, int valuelen, char *value,
           38
                              int *flag)
           39
           40
                int MPI_Info_get_nkeys(MPI_Info info, int *nkeys)
           41
           42
                int MPI_Info_get_nthkey(MPI_Info info, int n, char *key)
           43
                int MPI_Info_get_valuelen(MPI_Info info, char *key, int *valuelen,
           44
                              int *flag)
           45
           46
                int MPI_Info_set(MPI_Info info, char *key, char *value)
           47
```

A.2. C BINDINGS 623

```
void *extra_state)
A.2.12 Language Bindings C Bindings
int MPI_Status_f082f(MPI_F_status *f08_status, MPI_Fint *f_status)
int MPI_Status_f2f08(MPI_Fint *f_status, MPI_F_status *f08_status)
int MPI_Type_create_f90_complex(int p, int r, MPI_Datatype *newtype)
int MPI_Type_create_f90_integer(int r, MPI_Datatype *newtype)
int MPI_Type_create_f90_real(int p, int r, MPI_Datatype *newtype)
                                                                                 12
int MPI_Type_match_size(int typeclass, int size, MPI_Datatype *datatype)
                                                                                 13 ticket252-W.
                                                                                 14
MPI_Fint MPI_Comm_c2f(MPI_Comm comm)
                                                                                 15
MPI_Comm MPI_Comm_f2c(MPI_Fint comm)
                                                                                 16
MPI_Fint MPI_Errhandler_c2f(MPI_Errhandler errhandler)
MPI_Errhandler MPI_Errhandler_f2c(MPI_Fint errhandler)
                                                                                 19
                                                                                 20
MPI_Fint MPI_File_c2f(MPI_File file)
                                                                                 21
                                                                                 22
MPI_File MPI_File_f2c(MPI_Fint file)
                                                                                 23
MPI_Fint MPI_Group_c2f(MPI_Group group)
MPI_Group_f2c(MPI_Fint group)
MPI_Fint MPI_Info_c2f(MPI_Info info)
                                                                                 27
                                                                                 28
MPI_Info MPI_Info_f2c(MPI_Fint info)
                                                                                 29
MPI_Fint MPI_Op_c2f(MPI_Op op)
                                                                                 30
MPI_Op MPI_Op_f2c(MPI_Fint op)
MPI_Fint MPI_Request_c2f(MPI_Request request)
                                                                                 34
MPI_Request MPI_Request_f2c(MPI_Fint request)
                                                                                 35
int MPI_Status_c2f(MPI_Status *c_status, MPI_Fint *f_status)
                                                                                 36
                                                                                 37
int MPI_Status_c2f08(MPI_Status *c_status, MPI_F_status *f08_status)
int MPI_Status_f082c(MPI_F_status *f08_status, MPI_Status *c_status)
int MPI_Status_f2c(MPI_Fint *f_status, MPI_Status *c_status)
                                                                                 42
MPI_Fint MPI_Type_c2f(MPI_Datatype datatype)
                                                                                 43
MPI_Datatype MPI_Type_f2c(MPI_Fint datatype)
                                                                                 44
                                                                                 45
MPI_Fint MPI_Win_c2f(MPI_Win win)
                                                                                 46
MPI_Win MPI_Win_f2c(MPI_Fint win)
```

45 46 47

```
1
                A.2.13 Profiling Interface C Bindings
           2
                int MPI_Pcontrol(const int level, ...)
           3
           4
           5
                A.2.14 Deprecated C Bindings
           6
                int MPI_Address(void* location, MPI_Aint *address)
           7
                int MPI_Attr_delete(MPI_Comm comm, int keyval)
           9
                int MPI_Attr_get(MPI_Comm comm, int keyval, void *attribute_val, int *flag)
           10
           11
                int MPI_Attr_put(MPI_Comm comm, int keyval, void* attribute_val)
           12
                int MPI_DUP_FN(MPI_Comm oldcomm, int keyval, void *extra_state,
           13
                              void *attribute_val_in, void *attribute_val_out, int *flag)
           14
ticket252-W.
                int MPI_Errhandler_create(MPI_Handler_function *[function]handler_fn,
                             MPI_Errhandler *errhandler)
           17
           18
                int MPI_Errhandler_get(MPI_Comm comm, MPI_Errhandler *errhandler)
           19
                int MPI_Errhandler_set(MPI_Comm comm, MPI_Errhandler errhandler)
           20
          21
                int MPI_Keyval_create(MPI_Copy_function *copy_fn, MPI_Delete_function
                              *delete_fn, int *keyval, void* extra_state)
           22
          23
                int MPI_Keyval_free(int *keyval)
           24
           25
                int MPI_NULL_COPY_FN(MPI_Comm oldcomm, int keyval, void *extra_state,
           26
                              void *attribute_val_in, void *attribute_val_out, int *flag)
          27
                int MPI_NULL_DELETE_FN(MPI_Comm comm, int keyval, void *attribute_val,
           28
                              void *extra_state)
           29
           30
                int MPI_Type_extent(MPI_Datatype datatype, MPI_Aint *extent)
           31
                int MPI_Type_hindexed(int count, int *array_of_blocklengths,
           32
                              MPI_Aint *array_of_displacements, MPI_Datatype oldtype,
           33
                              MPI_Datatype *newtype)
          34
          35
                int MPI_Type_hvector(int count, int blocklength, MPI_Aint stride,
           36
                              MPI_Datatype oldtype, MPI_Datatype *newtype)
          37
                int MPI_Type_lb(MPI_Datatype datatype, MPI_Aint* displacement)
          38
           39
                int MPI_Type_struct(int count, int *array_of_blocklengths,
           40
                              MPI_Aint *array_of_displacements,
           41
                              MPI_Datatype *array_of_types, MPI_Datatype *newtype)
           42
                int MPI_Type_ub(MPI_Datatype datatype, MPI_Aint* displacement)
           43
           44
```

45

A.3 Fortran Bindings with mpif.h or the mpi Module	1
A.3.1 Point-to-Point Communication Fortran Bindings	2
A.S.1 Tomt-to-Fourt Communication Fortian Dindings	4
MPI_BSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)	5
<type> BUF(*)</type>	6
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR	7
MPI_BSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)	8
<type> BUF(*)</type>	9
INTEGER [REQUEST,] COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR	10 ticket 250-V.
MPI_BUFFER_ATTACH(BUFFER, SIZE, IERROR)	11
<pre><type> BUFFER(*)</type></pre>	12
INTEGER SIZE, IERROR	13
	14
MPI_BUFFER_DETACH(BUFFER_ADDR, SIZE, IERROR)	15
<type> BUFFER_ADDR(*)</type>	16
INTEGER SIZE, IERROR	17 18
MPI_CANCEL(REQUEST, IERROR)	19
INTEGER REQUEST, IERROR	20
MPI_GET_COUNT(STATUS, DATATYPE, COUNT, IERROR)	21
INTEGER STATUS(MPI_STATUS_SIZE), DATATYPE, COUNT, IERROR	22
	23
MPI_IBSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)	24
<type> BUF(*)</type>	25
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR	26
MPI_IPROBE(SOURCE, TAG, COMM, FLAG, STATUS, IERROR)	27
LOGICAL FLAG	28
INTEGER SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR	29
MPI_IRECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR)	30
<pre><type> BUF(*)</type></pre>	31
INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR	32 33
	34
MPI_IRSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)	35
<pre><type> BUF(*) INTEGED COUNT DATATYDE DEST TAC COMM DECLIEST LEDDOD</type></pre>	36
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR	37
MPI_ISEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)	38
<type> BUF(*)</type>	39
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR	40
MPI_ISSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)	41
<type> BUF(*)</type>	42
INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR	43
	44

INTEGER SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR

MPI_RECV(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS, IERROR)

MPI_PROBE(SOURCE, TAG, COMM, STATUS, IERROR)

```
1
                    <type> BUF(*)
           2
                    INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, STATUS(MPI_STATUS_SIZE),
               MPI_RECV_INIT(BUF, COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR)
           5
                    <type> BUF(*)
           6
                    INTEGER COUNT, DATATYPE, SOURCE, TAG, COMM, REQUEST, IERROR
           7
           8
               MPI_REQUEST_FREE(REQUEST, IERROR)
           9
                    INTEGER REQUEST, IERROR
          10
               MPI_REQUEST_GET_STATUS( REQUEST, FLAG, STATUS, IERROR)
          11
                    INTEGER REQUEST, STATUS(MPI_STATUS_SIZE), IERROR
          12
                    LOGICAL FLAG
          13
          14
               MPI_RSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
          15
                    <type> BUF(*)
          16
                    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
          17
               MPI_RSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
          18
                    <type> BUF(*)
          19
                    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
          20
          21
               MPI_SEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
          22
                    <type> BUF(*)
          23
                    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
          24
               MPI_SENDRECV(SENDBUF, SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVBUF,
          25
                             RECVCOUNT, RECVTYPE, SOURCE, RECVTAG, COMM, STATUS, IERROR)
          26
                    <type> SENDBUF(*), RECVBUF(*)
          27
                    INTEGER SENDCOUNT, SENDTYPE, DEST, SENDTAG, RECVCOUNT, RECVTYPE,
          28
                    SOURCE, RECVTAG, COMM, STATUS(MPI_STATUS_SIZE), IERROR
          29
          30
                MPI_SENDRECV_REPLACE(BUF, COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG,
          31
                             COMM, STATUS, IERROR)
          32
                    <type> BUF(*)
          33
                    INTEGER COUNT, DATATYPE, DEST, SENDTAG, SOURCE, RECVTAG, COMM,
          34
                    STATUS(MPI_STATUS_SIZE), IERROR
          35
               MPI_SEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
          36
                    <type> BUF(*)
                    INTEGER [REQUEST, ] COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
ticket250-V. 38
               MPI_SSEND(BUF, COUNT, DATATYPE, DEST, TAG, COMM, IERROR)
          40
                    <type> BUF(*)
          41
                    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, IERROR
          42
               MPI_SSEND_INIT(BUF, COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR)
          43
                    <type> BUF(*)
          44
                    INTEGER COUNT, DATATYPE, DEST, TAG, COMM, REQUEST, IERROR
          45
          46
               MPI_START(REQUEST, IERROR)
          47
                    INTEGER REQUEST, IERROR
```

```
INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_DISPLACEMENTS(*)
MPI_TYPE_CREATE_SUBARRAY(NDIMS, ARRAY_OF_SIZES, ARRAY_OF_SUBSIZES,
              ARRAY_OF_STARTS, ORDER, OLDTYPE, NEWTYPE, IERROR)
    INTEGER NDIMS, ARRAY_OF_SIZES(*), ARRAY_OF_SUBSIZES(*),
    ARRAY_OF_STARTS(*), ORDER, OLDTYPE, NEWTYPE, IERROR
MPI_TYPE_DUP(OLDTYPE, NEWTYPE, IERROR)
                                                                                  <sup>7</sup> ticket252-W.
                                                                                  <sup>8</sup> ticket252-W.
    INTEGER OLDTYPE, NEWTYPE, IERROR
MPI_TYPE_FREE(DATATYPE, IERROR)
    INTEGER DATATYPE, IERROR
                                                                                  11
                                                                                  12
MPI_TYPE_GET_CONTENTS(DATATYPE, MAX_INTEGERS, MAX_ADDRESSES, MAX_DATATYPES,
                                                                                  13
              ARRAY_OF_INTEGERS, ARRAY_OF_ADDRESSES, ARRAY_OF_DATATYPES,
                                                                                  14
              IERROR)
                                                                                  15
    INTEGER DATATYPE, MAX_INTEGERS, MAX_ADDRESSES, MAX_DATATYPES,
                                                                                  16
    ARRAY_OF_INTEGERS(*), ARRAY_OF_DATATYPES(*), IERROR
                                                                                  17
    INTEGER(KIND=MPI_ADDRESS_KIND) ARRAY_OF_ADDRESSES(*)
MPI_TYPE_GET_ENVELOPE(DATATYPE, NUM_INTEGERS, NUM_ADDRESSES, NUM_DATATYPES,
                                                                                  19
              COMBINER, IERROR)
                                                                                  20
    INTEGER DATATYPE, NUM_INTEGERS, NUM_ADDRESSES, NUM_DATATYPES, COMBINER,
    IERROR
                                                                                  23
MPI_TYPE_GET_EXTENT(DATATYPE, LB, EXTENT, IERROR)
                                                                                  24
    INTEGER DATATYPE, IERROR
    INTEGER(KIND = MPI_ADDRESS_KIND) LB, EXTENT
                                                                                  26
MPI_TYPE_GET_TRUE_EXTENT(DATATYPE, TRUE_LB, TRUE_EXTENT, IERROR)
                                                                                  27
    INTEGER DATATYPE, IERROR
                                                                                  28
    INTEGER(KIND = MPI_ADDRESS_KIND) TRUE_LB, TRUE_EXTENT
                                                                                  29
MPI_TYPE_INDEXED(COUNT, ARRAY_OF_BLOCKLENGTHS, ARRAY_OF_DISPLACEMENTS,
              OLDTYPE, NEWTYPE, IERROR)
    INTEGER COUNT, ARRAY_OF_BLOCKLENGTHS(*), ARRAY_OF_DISPLACEMENTS(*),
    OLDTYPE, NEWTYPE, IERROR
                                                                                  34
MPI_TYPE_SIZE(DATATYPE, SIZE, IERROR)
                                                                                  35
    INTEGER DATATYPE, SIZE, IERROR
                                                                                  36
                                                                                  37
MPI_TYPE_VECTOR(COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR)
    INTEGER COUNT, BLOCKLENGTH, STRIDE, OLDTYPE, NEWTYPE, IERROR
MPI_UNPACK(INBUF, INSIZE, POSITION, OUTBUF, OUTCOUNT, DATATYPE, COMM,
              IERROR)
    <type> INBUF(*), OUTBUF(*)
                                                                                  42
    INTEGER INSIZE, POSITION, OUTCOUNT, DATATYPE, COMM, IERROR
                                                                                  43
                                                                                  44
MPI_UNPACK_EXTERNAL(DATAREP, INBUF, INSIZE, POSITION, OUTBUF, OUTCOUNT,
                                                                                  45
              DATATYPE, IERROR)
    INTEGER OUTCOUNT, DATATYPE, IERROR
    INTEGER(KIND=MPI_ADDRESS_KIND) INSIZE, POSITION
```

```
1
                    <type> SENDBUF(*), RECVBUF(*)
           2
                    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,
                    IERROR
                MPI_IGATHERV(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNTS, DISPLS,
                             RECVTYPE, ROOT, COMM, REQUEST, IERROR)
           6
                    <type> SENDBUF(*), RECVBUF(*)
                    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNTS(*), DISPLS(*), RECVTYPE, ROOT,
                    COMM, REQUEST, IERROR
           9
           10
               MPI_IREDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, REQUEST,
           11
                              IERROR)
           12
                    <type> SENDBUF(*), RECVBUF(*)
           13
                    INTEGER COUNT, DATATYPE, OP, ROOT, COMM, REQUEST, IERROR
           14
               MPI_IREDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
           15
                             REQUEST, IERROR)
           16
                    <type> SENDBUF(*), RECVBUF(*)
           17
                    INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, REQUEST, IERROR
           18
           19
                MPI_IREDUCE_SCATTER_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM,
           20
                             REQUEST, IERROR)
           21
                    <type> SENDBUF(*), RECVBUF(*)
           22
                    INTEGER RECVCOUNT, DATATYPE, OP, COMM, REQUEST, IERROR
          23
               MPI_ISCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, REQUEST, IERROR)
           24
                    <type> SENDBUF(*), RECVBUF(*)
                    INTEGER COUNT, DATATYPE, OP, COMM, REQUEST, IERROR
           26
          27
               MPI_ISCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
           28
                             ROOT, COMM, REQUEST, IERROR)
           29
                    <type> SENDBUF(*), RECVBUF(*)
           30
                    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, REQUEST,
                    IERROR
               MPI_ISCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT,
           33
                             RECVTYPE, ROOT, COMM, REQUEST, IERROR)
           34
                    <type> SENDBUF(*), RECVBUF(*)
           35
                    INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
           36
                    COMM, REQUEST, IERROR
          37
           38
               MPI_OP_COMMUTATIVE(OP, COMMUTE, IERROR)
                    LOGICAL COMMUTE
                    INTEGER OP, IERROR
ticket252-W. 42
               MPI_OP_CREATE( [FUNCTION] USER_FN, COMMUTE, OP, IERROR)
ticket252-W. 43
                    EXTERNAL [FUNCTION] USER_FN
                    LOGICAL COMMUTE
           44
                    INTEGER OP, IERROR
           45
               MPI_OP_FREE(OP, IERROR)
           47
                    INTEGER OP, IERROR
```

```
MPI_REDUCE(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, ROOT, COMM, IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER COUNT, DATATYPE, OP, ROOT, COMM, IERROR
                                                                                 5 ticket250-V.
MPI_REDUCE_LOCAL(INBUF, INOUTBUF, COUNT, DATATYPE, OP, IERROR)
    <type> INBUF(*), INOUTBUF(*)
    INTEGER COUNT, DATATYPE, OP, IERROR
MPI_REDUCE_SCATTER(SENDBUF, RECVBUF, RECVCOUNTS, DATATYPE, OP, COMM,
              IERROR)
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER RECVCOUNTS(*), DATATYPE, OP, COMM, IERROR
                                                                                 12
MPI_REDUCE_SCATTER_BLOCK(SENDBUF, RECVBUF, RECVCOUNT, DATATYPE, OP, COMM,
                                                                                 13
              IERROR)
                                                                                 14
    <type> SENDBUF(*), RECVBUF(*)
                                                                                 15
    INTEGER RECVCOUNT, DATATYPE, OP, COMM, IERROR
                                                                                 16
MPI_SCAN(SENDBUF, RECVBUF, COUNT, DATATYPE, OP, COMM, IERROR)
                                                                                 18
    <type> SENDBUF(*), RECVBUF(*)
                                                                                 19
    INTEGER COUNT, DATATYPE, OP, COMM, IERROR
                                                                                 20
MPI_SCATTER(SENDBUF, SENDCOUNT, SENDTYPE, RECVBUF, RECVCOUNT, RECVTYPE,
                                                                                 21
             ROOT, COMM, IERROR)
                                                                                 22
    <type> SENDBUF(*), RECVBUF(*)
    INTEGER SENDCOUNT, SENDTYPE, RECVCOUNT, RECVTYPE, ROOT, COMM, IERROR
                                                                                 24
MPI_SCATTERV(SENDBUF, SENDCOUNTS, DISPLS, SENDTYPE, RECVBUF, RECVCOUNT,
                                                                                 26
             RECVTYPE, ROOT, COMM, IERROR)
                                                                                 27
    <type> SENDBUF(*), RECVBUF(*)
                                                                                 28
    INTEGER SENDCOUNTS(*), DISPLS(*), SENDTYPE, RECVCOUNT, RECVTYPE, ROOT,
                                                                                 29
    COMM, IERROR
A.3.4 Groups, Contexts, Communicators, and Caching Fortran Bindings
MPI_COMM_COMPARE(COMM1, COMM2, RESULT, IERROR)
                                                                                 34
    INTEGER COMM1, COMM2, RESULT, IERROR
                                                                                 35
MPI_COMM_CREATE(COMM, GROUP, NEWCOMM, IERROR)
                                                                                 36
    INTEGER COMM, GROUP, NEWCOMM, IERROR
MPI_COMM_CREATE_KEYVAL(COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN, COMM_KEYVAL,
             EXTRA_STATE, IERROR)
    EXTERNAL COMM_COPY_ATTR_FN, COMM_DELETE_ATTR_FN
    INTEGER COMM_KEYVAL, IERROR
                                                                                 42
    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
                                                                                 43
MPI_COMM_DELETE_ATTR(COMM, COMM_KEYVAL, IERROR)
                                                                                 44
    INTEGER COMM, COMM_KEYVAL, IERROR
                                                                                 45
MPI_COMM_DUP(COMM, NEWCOMM, IERROR)
```

INTEGER COMM, NEWCOMM, IERROR

MPI_COMM_SIZE(COMM, SIZE, IERROR) INTEGER COMM, SIZE, IERROR	1 2
MPI_COMM_SPLIT(COMM, COLOR, KEY, NEWCOMM, IERROR) INTEGER COMM, COLOR, KEY, NEWCOMM, IERROR	3 4 5
MPI_COMM_TEST_INTER(COMM, FLAG, IERROR) INTEGER COMM, IERROR LOGICAL FLAG	6 7 8
MPI_GROUP_COMPARE(GROUP1, GROUP2, RESULT, IERROR) INTEGER GROUP1, GROUP2, RESULT, IERROR	9 10 11
MPI_GROUP_DIFFERENCE(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR	12
MPI_GROUP_EXCL(GROUP, N, RANKS, NEWGROUP, IERROR) INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR	14 15 16
MPI_GROUP_FREE(GROUP, IERROR) INTEGER GROUP, IERROR	17 18 19
MPI_GROUP_INCL(GROUP, N, RANKS, NEWGROUP, IERROR) INTEGER GROUP, N, RANKS(*), NEWGROUP, IERROR	20 21
MPI_GROUP_INTERSECTION(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR	22 23 24
MPI_GROUP_RANGE_EXCL(GROUP, N, RANGES, NEWGROUP, IERROR) INTEGER GROUP, N, RANGES(3,*), NEWGROUP, IERROR	25 26
MPI_GROUP_RANGE_INCL(GROUP, N, RANGES, NEWGROUP, IERROR) INTEGER GROUP, N, RANGES(3,*), NEWGROUP, IERROR	27 28 29
MPI_GROUP_RANK(GROUP, RANK, IERROR) INTEGER GROUP, RANK, IERROR	30 31
MPI_GROUP_SIZE(GROUP, SIZE, IERROR) INTEGER GROUP, SIZE, IERROR	32 33 34
MPI_GROUP_TRANSLATE_RANKS(GROUP1, N, RANKS1, GROUP2, RANKS2, IERROR) INTEGER GROUP1, N, RANKS1(*), GROUP2, RANKS2(*), IERROR	35 36
MPI_GROUP_UNION(GROUP1, GROUP2, NEWGROUP, IERROR) INTEGER GROUP1, GROUP2, NEWGROUP, IERROR	37 38 39
MPI_INTERCOMM_CREATE(LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG, NEWINTERCOMM, IERROR) INTEGER LOCAL_COMM, LOCAL_LEADER, PEER_COMM, REMOTE_LEADER, TAG,	40 41 42
NEWINTERCOMM, IERROR MPI_INTERCOMM_MERGE(INTERCOMM, HIGH, NEWINTRACOMM, IERROR)	43 44 45 ticket250-
INTEGER NEWINTERCOMM, INTRACOMM, IERROR LOGICAL HIGH	45 ticket250-1

```
MPI_TYPE_CREATE_KEYVAL(TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN, TYPE_KEYVAL,
           2
                              EXTRA_STATE, IERROR)
                    EXTERNAL TYPE_COPY_ATTR_FN, TYPE_DELETE_ATTR_FN
                    INTEGER TYPE_KEYVAL, IERROR
                    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
ticket252-W. 7
                MPI TYPE DELETE ATTR(DATATYPE, TYPE KEYVAL, IERROR)
ticket252-W. 8
                    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                MPI_TYPE_DUP_FN(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
           10
                              ATTRIBUTE_VAL_OUT, FLAG, IERROR)
           11
                    INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
           12
                    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
           13
                        ATTRIBUTE_VAL_OUT
           14
                    LOGICAL FLAG
           15
                MPI_TYPE_FREE_KEYVAL(TYPE_KEYVAL, IERROR)
           16
                    INTEGER TYPE_KEYVAL, IERROR
ticket 252-W. <sup>18</sup>
                MPI_TYPE_GET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)
ticket 252-W. <sup>19</sup>
                    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
           21
                    LOGICAL FLAG
                MPI_TYPE_GET_NAME(DATATYPE, TYPE_NAME, RESULTLEN, IERROR)
ticket 252-W._{23}
ticket 252-W._{24}
                    INTEGER DATATYPE, RESULTLEN, IERROR
                    CHARACTER*(*) TYPE_NAME
           26
                MPI_TYPE_NULL_COPY_FN(OLDTYPE, TYPE_KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,
           ^{27}
                              ATTRIBUTE_VAL_OUT, FLAG, IERROR)
           28
                    INTEGER OLDTYPE, TYPE_KEYVAL, IERROR
                    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE, ATTRIBUTE_VAL_IN,
           30
                         ATTRIBUTE_VAL_OUT
                    LOGICAL FLAG
                MPI_TYPE_NULL_DELETE_FN(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE,
ticket252-W. 33
                              IERROR)
                    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
ticket252-W. <sub>35</sub>
                    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL, EXTRA_STATE
ticket252-W. ^{37}
                MPI_TYPE_SET_ATTR(DATATYPE, TYPE_KEYVAL, ATTRIBUTE_VAL, IERROR)
ticket252-W. ^{38}
                    INTEGER DATATYPE, TYPE_KEYVAL, IERROR
                    INTEGER(KIND=MPI_ADDRESS_KIND) ATTRIBUTE_VAL
ticket252-W. 41
                MPI_TYPE_SET_NAME(DATATYPE, TYPE_NAME, IERROR)
ticket252-W. 42
                    INTEGER DATATYPE, IERROR
                    CHARACTER*(*) TYPE_NAME
           43
           44
                MPI_WIN_CREATE_KEYVAL(WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN, WIN_KEYVAL,
           45
                              EXTRA_STATE, IERROR)
           46
                    EXTERNAL WIN_COPY_ATTR_FN, WIN_DELETE_ATTR_FN
           47
                    INTEGER WIN_KEYVAL, IERROR
```

<pre>INTEGER COMM, MAXINDEX, MAXEDGES, INDEX(*), EDGES(*), IERROR</pre>	1
MPI_GRAPH_MAP(COMM, NNODES, INDEX, EDGES, NEWRANK, IERROR)	2
INTEGER COMM, NNODES, INDEX(*), EDGES(*), NEWRANK, IERROR	3 4
MDI GDADU NEIGUDODG/GOMM DANW MAYNEIGUDODG NEIGUDODG IEDDOD)	5
MPI_GRAPH_NEIGHBORS(COMM, RANK, MAXNEIGHBORS, NEIGHBORS, IERROR) INTEGER COMM, RANK, MAXNEIGHBORS, NEIGHBORS(*), IERROR	6
INTEGER COMM, RANK, MAKNEIGHDORS, NEIGHDORS(*), IERROR	7
MPI_GRAPH_NEIGHBORS_COUNT(COMM, RANK, NNEIGHBORS, IERROR)	8
INTEGER COMM, RANK, NNEIGHBORS, IERROR	9
MPI_TOPO_TEST(COMM, STATUS, IERROR)	10
INTEGER COMM, STATUS, IERROR	11
	12
A.3.6 MPI Environmental Management Fortran Bindings	13
A.3.0 WET Environmental Management Fortran bindings	14 15
DOUBLE PRECISION MPI_WTICK()	16
DOUBLE PRECISION MPI_WTIME()	17
	18
MPI_ABORT(COMM, ERRORCODE, IERROR)	19
INTEGER COMM, ERRORCODE, IERROR	20
MPI_ADD_ERROR_CLASS(ERRORCLASS, IERROR)	21
INTEGER ERRORCLASS, IERROR	22
MPI_ADD_ERROR_CODE(ERRORCLASS, ERRORCODE, IERROR)	23
INTEGER ERRORCLASS, ERRORCODE, IERROR	24
	25 26
MPI_ADD_ERROR_STRING(ERRORCODE, STRING, IERROR)	27
INTEGER ERRORCODE, IERROR CHARACTER*(*) STRING	28
	29
MPI_ALLOC_MEM(SIZE, INFO, BASEPTR, IERROR)	30
INTEGER INFO, IERROR	31
INTEGER(KIND=MPI_ADDRESS_KIND) SIZE, BASEPTR	32
MPI_COMM_CALL_ERRHANDLER(COMM, ERRORCODE, IERROR)	33
INTEGER COMM, ERRORCODE, IERROR	34
MPI_COMM_CREATE_ERRHANDLER([FUNCTION]COMM_ERRHANDLER_FN, ERRHANDLER,	$_{ m 36}^{ m 35}$ ticket252-W.
IERROR)	37
EXTERNAL [FUNCTION] COMM_ERRHANDLER_FN	38 ticket252-W
INTEGER ERRHANDLER, IERROR	39
MPI_COMM_GET_ERRHANDLER(COMM, ERRHANDLER, IERROR)	40
INTEGER COMM, ERRHANDLER, IERROR	41
	42
MPI_COMM_SET_ERRHANDLER(COMM, ERRHANDLER, IERROR)	43
INTEGER COMM, ERRHANDLER, IERROR	44
MPI_ERRHANDLER_FREE(ERRHANDLER, IERROR)	45
INTEGER ERRHANDLER, IERROR	46

MPI_ERROR_CLASS(ERRORCODE, ERRORCLASS, IERROR)

```
1
                    INTEGER ERRORCODE, ERRORCLASS, IERROR
           2
                MPI_ERROR_STRING(ERRORCODE, STRING, RESULTLEN, IERROR)
           3
                    INTEGER ERRORCODE, RESULTLEN, IERROR
                    CHARACTER*(*) STRING
           5
           6
                MPI_FILE_CALL_ERRHANDLER(FH, ERRORCODE, IERROR)
                    INTEGER FH, ERRORCODE, IERROR
ticket252-W. a
                MPI_FILE_CREATE_ERRHANDLER([FUNCTION]FILE_ERRHANDLER_FN, ERRHANDLER,
                              IERROR)
ticket252-W. 11
                    EXTERNAL [FUNCTION] FILE_ERRHANDLER_FN
                    INTEGER ERRHANDLER, IERROR
           12
           13
                MPI_FILE_GET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
           14
                    INTEGER FILE, ERRHANDLER, IERROR
           15
                MPI_FILE_SET_ERRHANDLER(FILE, ERRHANDLER, IERROR)
           16
                    INTEGER FILE, ERRHANDLER, IERROR
           17
           18
                MPI_FINALIZE(IERROR)
           19
                    INTEGER IERROR
           20
                MPI_FINALIZED(FLAG, IERROR)
           21
                    LOGICAL FLAG
           22
                    INTEGER IERROR
           23
           ^{24}
                MPI_FREE_MEM(BASE, IERROR)
                    <type> BASE(*)
           26
                    INTEGER IERROR
           27
                MPI_GET_PROCESSOR_NAME( NAME, RESULTLEN, IERROR)
           28
                    CHARACTER*(*) NAME
           29
                    INTEGER RESULTLEN, IERROR
           30
           31
                MPI_GET_VERSION(VERSION, SUBVERSION, IERROR)
           32
                    INTEGER VERSION, SUBVERSION, IERROR
           33
           34
                MPI_INIT(IERROR)
                    INTEGER IERROR
           35
           36
                MPI_INITIALIZED(FLAG, IERROR)
           37
                    LOGICAL FLAG
           38
                    INTEGER IERROR
           39
                MPI_WIN_CALL_ERRHANDLER(WIN, ERRORCODE, IERROR)
                    INTEGER WIN, ERRORCODE, IERROR
ticket252-W.
                MPI_WIN_CREATE_ERRHANDLER([FUNCTION]WIN_ERRHANDLER_FN, ERRHANDLER, IERROR)
ticket252-W. _{44}
                    EXTERNAL [FUNCTION] WIN_ERRHANDLER_FN
                    INTEGER ERRHANDLER, IERROR
           45
           ^{46}
                MPI_WIN_GET_ERRHANDLER(WIN, ERRHANDLER, IERROR)
           47
                    INTEGER WIN, ERRHANDLER, IERROR
```

```
1
                MPI_FILE_WRITE_ORDERED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
           2
                    <type> BUF(*)
                    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
                MPI_FILE_WRITE_ORDERED_BEGIN(FH, BUF, COUNT, DATATYPE, IERROR)
           5
                    <type> BUF(*)
           6
                    INTEGER FH, COUNT, DATATYPE, IERROR
           7
           8
                MPI_FILE_WRITE_ORDERED_END(FH, BUF, STATUS, IERROR)
           9
                    <type> BUF(*)
           10
                    INTEGER FH, STATUS(MPI_STATUS_SIZE), IERROR
           11
                MPI_FILE_WRITE_SHARED(FH, BUF, COUNT, DATATYPE, STATUS, IERROR)
           12
                    <type> BUF(*)
           13
                    INTEGER FH, COUNT, DATATYPE, STATUS(MPI_STATUS_SIZE), IERROR
           14
           15
                MPI_REGISTER_DATAREP(DATAREP, READ_CONVERSION_FN, WRITE_CONVERSION_FN,
           16
                              DTYPE_FILE_EXTENT_FN, EXTRA_STATE, IERROR)
           17
                    CHARACTER*(*) DATAREP
           18
                    EXTERNAL READ_CONVERSION_FN, WRITE_CONVERSION_FN, DTYPE_FILE_EXTENT_FN
           19
                    INTEGER(KIND=MPI_ADDRESS_KIND) EXTRA_STATE
           20
                    INTEGER IERROR
           21
           22
                A.3.12 Language Bindings Fortran Bindings
           23
           ^{24}
                MPI_F_SYNC_REG(buf)
           25
                    <type> buf(*)
           26
                MPI_SIZEOF(X, SIZE, IERROR)
           27
                    <type> X
           28
                    INTEGER SIZE, IERROR
           29
           30
                MPI_STATUS_F082F(F08_STATUS, F_STATUS, IERROR)
           31
                    TYPE(MPI_Status) :: F08_STATUS
           32
                    INTEGER F_STATUS(MPI_STATUS_SIZE)
           33
                    INTEGER IERROR
           34
                MPI_STATUS_F2F08(F_STATUS, F08_STATUS, IERROR)
           35
                    INTEGER F_STATUS(MPI_STATUS_SIZE)
           36
           37
                    TYPE(MPI_Status) :: F08_STATUS
           38
                    INTEGER IERROR
                MPI_TYPE_CREATE_F90_COMPLEX(P, R, NEWTYPE, IERROR)
           40
                    INTEGER P, R, NEWTYPE, IERROR
           41
           42
                MPI_TYPE_CREATE_F90_INTEGER(R, NEWTYPE, IERROR)
                    INTEGER R, NEWTYPE, IERROR
           43
           44
                MPI_TYPE_CREATE_F90_REAL(P, R, NEWTYPE, IERROR)
           45
                    INTEGER P, R, NEWTYPE, IERROR
ticket252-W. <sup>47</sup>
                MPI_TYPE_MATCH_SIZE(TYPECLASS, SIZE, DATATYPE, IERROR)
ticket 252-W. <sup>48</sup>
                    INTEGER TYPECLASS, SIZE, DATATYPE, IERROR
```

A.3.13 Profiling Interface Fortran Bindings	1
MPI_PCONTROL(LEVEL)	2
INTEGER LEVEL	3
	4 5
A 0.14 B I.E B'. I'	6
A.3.14 Deprecated Fortran Bindings	7
MPI_ADDRESS(LOCATION, ADDRESS, IERROR)	8
<type> LOCATION(*)</type>	9
INTEGER ADDRESS, IERROR	10
MPI_ATTR_DELETE(COMM, KEYVAL, IERROR)	11
INTEGER COMM, KEYVAL, IERROR	12
	13
MPI_ATTR_GET(COMM, KEYVAL, ATTRIBUTE_VAL, FLAG, IERROR)	14
INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, IERROR LOGICAL FLAG	15
LUGICAL FLAG	16 17
MPI_ATTR_PUT(COMM, KEYVAL, ATTRIBUTE_VAL, IERROR)	18
INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, IERROR	19
MPI_DUP_FN(OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	20
ATTRIBUTE_VAL_OUT, FLAG, IERR)	21
INTEGER OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	22
ATTRIBUTE_VAL_OUT, IERR	23
LOGICAL FLAG	24
MPI_ERRHANDLER_CREATE([FUNCTION]HANDLER_FN, ERRHANDLER, IERROR)	25 ticket $252 ext{-W}$.
EXTERNAL [FUNCTION] HANDLER_FN	ticket252-W.
INTEGER ERRHANDLER, IERROR	27
MDI EDDUANDI ED GET/GOMM EDDUANDI ED TEDDOD	28 29
MPI_ERRHANDLER_GET(COMM, ERRHANDLER, IERROR) INTEGER COMM, ERRHANDLER, IERROR	30
INTEGER COMM, ERRHANDLER, TERROR	31
MPI_ERRHANDLER_SET(COMM, ERRHANDLER, IERROR)	32
INTEGER COMM, ERRHANDLER, IERROR	33
MPI_KEYVAL_CREATE(COPY_FN, DELETE_FN, KEYVAL, EXTRA_STATE, IERROR)	34
EXTERNAL COPY_FN, DELETE_FN	35
INTEGER KEYVAL, EXTRA_STATE, IERROR	36
MPI_KEYVAL_FREE(KEYVAL, IERROR)	37
INTEGER KEYVAL, IERROR	38
	39
MPI_NULL_COPY_FN(OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	40
ATTRIBUTE_VAL_OUT, FLAG, IERR)	41 42
INTEGER OLDCOMM, KEYVAL, EXTRA_STATE, ATTRIBUTE_VAL_IN,	43
ATTRIBUTE_VAL_OUT, IERR LOGICAL FLAG	44
DOUTORD FERM	45
MPI_NULL_DELETE_FN(COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERROR)	46

INTEGER COMM, KEYVAL, ATTRIBUTE_VAL, EXTRA_STATE, IERROR

```
<sub>2</sub> ticket247-S.
A.4 Fortran 2008 Bindings with the mpi_f08 Module
A.4.1 Point-to-Point Communication Fortran 2008 Bindings
                                                                                  ^{6} ticket-248T.
MPI_Bsend(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _{13} ticket-248T.
MPI_Bsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                                                                                  14
    TYPE(*), DIMENSION(..) :: buf
                                                                                  15
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                  16
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  18
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  19
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{20} ticket-248T.
MPI_Buffer_attach(buffer, size, ierror)
    TYPE(*), DIMENSION(..) :: buffer
    INTEGER, INTENT(IN) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _{25} ticket-248T.
MPI_Buffer_detach(buffer_addr, size, ierror)
    TYPE(*), DIMENSION(..) :: buffer_addr
                                                                                  27
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{29} ticket-248T.
MPI_Cancel(request, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _{33} ticket-248T.
MPI_Get_count(status, datatype, count, ierror)
    TYPE(MPI_Status), INTENT(IN) :: status
                                                                                  35
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                  36
    INTEGER, INTENT(OUT) :: count
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{38} ticket-248T.
MPI_Ibsend(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                  43
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  44
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  46 ticket-248T.
MPI_Iprobe(source, tag, comm, flag, status, ierror)
                                                                                  47
    INTEGER, INTENT(IN) :: source, tag
```

```
1
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          2
                   LOGICAL, INTENT(OUT) :: flag
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 5
               MPI_Irecv(buf, count, datatype, source, tag, comm, request, ierror)
                   TYPE(*), DIMENSION(..) :: buf
                   INTEGER, INTENT(IN) :: count, source, tag
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          9
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          10
                   TYPE(MPI_Request), INTENT(OUT) :: request
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{12}
          13
               MPI_Irsend(buf, count, datatype, dest, tag, comm, request, ierror)
          14
                   TYPE(*), DIMENSION(..) :: buf
          15
                   INTEGER, INTENT(IN) :: count, dest, tag
          16
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Request), INTENT(OUT) :: request
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 20
               MPI_Isend(buf, count, datatype, dest, tag, comm, request, ierror)
          21
                   TYPE(*), DIMENSION(..) :: buf
          22
                   INTEGER, INTENT(IN) :: count, dest, tag
          23
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          24
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Request), INTENT(OUT) :: request
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          28
               MPI_Issend(buf, count, datatype, dest, tag, comm, request, ierror)
          29
                   TYPE(*), DIMENSION(..) :: buf
          30
                   INTEGER, INTENT(IN) :: count, dest, tag
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Request), INTENT(OUT) :: request
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 35
               MPI_Probe(source, tag, comm, status, ierror)
          36
                   INTEGER, INTENT(IN) :: source, tag
          37
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Recv(buf, count, datatype, source, tag, comm, status, ierror)
          42
                   TYPE(*), DIMENSION(..) :: buf
          43
                   INTEGER, INTENT(IN) :: count, source, tag
          44
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          45
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Status), INTENT(OUT) :: status !
                                                                optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 48
```

```
MPI_Recv_init(buf, count, datatype, source, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, source, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>8</sub> ticket-248T.
MPI_Request_free(request, ierror)
    TYPE(MPI_Request), INTENT(INOUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_Request_get_status( request, flag, status, ierror)
                                                                                13
    TYPE(MPI_Request), INTENT(IN) :: request
                                                                                14
    LOGICAL, INTENT(OUT) :: flag
                                                                                15
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                <sub>17</sub> ticket-248T.
MPI_Rsend(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..) :: buf
                                                                                19
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                20
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                21
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_Rsend_init(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..) :: buf
                                                                                26
    INTEGER, INTENT(IN) :: count, dest, tag
                                                                                27
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                28
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                зı ticket-248Т.
MPI_Send(buf, count, datatype, dest, tag, comm, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                35
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_Send_init(buf, count, datatype, dest, tag, comm, request, ierror)
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count, dest, tag
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                42
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                43
    TYPE(MPI_Request), INTENT(OUT) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                45 ticket-248T.
MPI_Sendrecv(sendbuf, sendcount, sendtype, dest, sendtag, recvbuf,
             recvcount, recvtype, source, recvtag, comm, status, ierror)
                                                                                 47
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
```

```
1
                   INTEGER, INTENT(IN) :: sendcount, dest, sendtag, recvcount, source,
          2
                   recvtag
                   TYPE(MPI_Datatype), INTENT(IN) :: sendtype, recvtype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 7
               MPI_Sendrecv_replace(buf, count, datatype, dest, sendtag, source, recvtag,
                             comm, status, ierror)
          9
                   TYPE(*), DIMENSION(..) :: buf
          10
                   INTEGER, INTENT(IN) :: count, dest, sendtag, source, recvtag
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          12
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          13
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          14
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{15}
               MPI_Ssend(buf, count, datatype, dest, tag, comm, ierror)
                   TYPE(*), DIMENSION(..) :: buf
          18
                   INTEGER, INTENT(IN) :: count, dest, tag
          19
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          20
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 22
               MPI_Ssend_init(buf, count, datatype, dest, tag, comm, request, ierror)
                   TYPE(*), DIMENSION(..) :: buf
          24
                   INTEGER, INTENT(IN) :: count, dest, tag
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          27
                   TYPE(MPI_Request), INTENT(OUT) :: request
          28
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{^{29}}
               MPI_Start(request, ierror)
                   TYPE(MPI_Request), INTENT(INOUT) :: request
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 33
               MPI_Startall(count, array_of_requests, ierror)
                   INTEGER, INTENT(IN) :: count
          35
                   TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
          36
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Test(request, flag, status, ierror)
                   LOGICAL, INTENT(OUT) :: flag
                   TYPE(MPI_Request), INTENT(INOUT) :: request
          41
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 43
               MPI_Test_cancelled(status, flag, ierror)
          44
                   TYPE(MPI_Status), INTENT(IN) :: status
          45
                   LOGICAL, INTENT(OUT) :: flag
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
```

```
MPI_Testall(count, array_of_requests, flag, array_of_statuses, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Status), INTENT(OUT) :: array_of_statuses(*) ! optional by
    overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>8</sub> ticket-248T.
MPI_Testany(count, array_of_requests, index, flag, status, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
    INTEGER, INTENT(OUT) :: index
                                                                                 12
    LOGICAL, INTENT(OUT) :: flag
                                                                                 13
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sup>15</sup> ticket-248T.
MPI_Testsome(incount, array_of_requests, outcount, array_of_indices,
                                                                                 17
             array_of_statuses, ierror)
    INTEGER, INTENT(IN) :: incount
                                                                                 19
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
    INTEGER, INTENT(OUT) :: outcount, array_of_indices(*)
                                                                                 20
                                                                                 21
    TYPE(MPI_Status), INTENT(OUT) :: array_of_statuses(*) ! optional by
                                                                                 22
    overloading
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>24</sub> ticket-248T.
MPI_Wait(request, status, ierror)
    TYPE(MPI_Request), INTENT(INOUT) :: request
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                                                                                 27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{28} ticket-248T.
MPI_Waitall(count, array_of_requests, array_of_statuses, ierror)
                                                                                 30
    INTEGER, INTENT(IN) :: count
    INTEGER, INTENT(INOUT) :: array_of_requests(*)
    TYPE(MPI_Status), INTENT(OUT) :: array_of_statuses(*) ! optional by
    overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 з5 ticket-248T.
MPI_Waitany(count, array_of_requests, index, status, ierror)
                                                                                 36
    INTEGER, INTENT(IN) :: count
                                                                                 37
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
    INTEGER, INTENT(OUT) :: index
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Waitsome(incount, array_of_requests, outcount, array_of_indices,
                                                                                 43
             array_of_statuses, ierror)
                                                                                 44
    INTEGER, INTENT(IN) :: incount
                                                                                 45
    TYPE(MPI_Request), INTENT(INOUT) :: array_of_requests(*)
    INTEGER, INTENT(OUT) :: outcount, array_of_indices(*)
                                                                                 47
    TYPE(MPI_Status), INTENT(OUT) :: array_of_statuses(*) ! optional by
```

```
1
                   overloading
           2
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
               A.4.2 Datatypes Fortran 2008 Bindings
ticket-248T.
               MPI_Get_address(location, address, ierror)
                   TYPE(*), DIMENSION(..) :: location
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: address
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 10
               MPI_Get_elements(status, datatype, count, ierror)
                   TYPE(MPI_Status), INTENT(IN) :: status
          12
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          13
                   INTEGER, INTENT(OUT) :: count
          14
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Pack(inbuf, incount, datatype, outbuf, outsize, position, comm, ierror)
          17
                   TYPE(*), DIMENSION(..) :: inbuf, outbuf
                   INTEGER, INTENT(IN) :: incount, outsize
          19
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          20
                   INTEGER, INTENT(INOUT) :: position
          21
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. <sup>23</sup>
               MPI_Pack_external(datarep, inbuf, incount, datatype, outbuf, outsize,
          24
                             position, ierror)
                   CHARACTER(LEN=*), INTENT(IN) :: datarep
          26
                   TYPE(*), DIMENSION(..) :: inbuf, outbuf
          27
                   INTEGER, INTENT(IN) :: incount
          28
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: outsize
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{33}
               MPI_Pack_external_size(datarep, incount, datatype, size, ierror)
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          35
                   INTEGER, INTENT(IN) :: incount
          36
                   CHARACTER(LEN=*), INTENT(IN) :: datarep
          37
                    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: size
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 39
               MPI_Pack_size(incount, datatype, comm, size, ierror)
                    INTEGER, INTENT(IN) :: incount
          42
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          43
                    INTEGER, INTENT(OUT) :: size
          44
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{46}
               MPI_Type_commit(datatype, ierror)
          47
                   TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>2</sub> ticket-248T.
MPI_Type_contiguous(count, oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Type_create_darray(size, rank, ndims, array_of_gsizes,
             array_of_distribs, array_of_dargs, array_of_psizes, order,
             oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: size, rank, ndims, array_of_gsizes(*),
    array_of_distribs(*), array_of_dargs(*), array_of_psizes(*), order
                                                                                 12
                                                                                 13
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 14
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>16</sub> ticket-248T.
MPI_Type_create_hindexed(count, array_of_blocklengths,
                                                                                 17
             array_of_displacements, oldtype, newtype, ierror)
                                                                                 18
    INTEGER, INTENT(IN) :: count, array_of_blocklengths(*)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
                                                                                 20
    array_of_displacements(*)
                                                                                 21
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 22
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{24} ticket-248T.
MPI_Type_create_hvector(count, blocklength, stride, oldtype, newtype,
                                                                                 26
              ierror)
                                                                                 27
    INTEGER, INTENT(IN) :: count, blocklength
                                                                                 28
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: stride
                                                                                 29
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 30
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 32 ticket-248T.
MPI_Type_create_indexed_block(count, blocklength, array_of_displacements,
             oldtype, newtype, ierror)
    INTEGER, INTENT(IN) :: count, blocklength, array_of_displacements(*)
                                                                                 35
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 36
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 37
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Type_create_resized(oldtype, lb, extent, newtype, ierror)
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: lb, extent
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 44 ticket-248T.
MPI_Type_create_struct(count, array_of_blocklengths,
             array_of_displacements, array_of_types, newtype, ierror)
    INTEGER, INTENT(IN) :: count, array_of_blocklengths(*)
                                                                                  47
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) ::
```

```
1
                   array_of_displacements(*)
           2
                   TYPE(MPI_Datatype), INTENT(IN) :: array_of_types(*)
                   TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 5
               MPI_Type_create_subarray(ndims, array_of_sizes, array_of_subsizes,
                             array_of_starts, order, oldtype, newtype, ierror)
           7
                   INTEGER, INTENT(IN) :: ndims, array_of_sizes(*), array_of_subsizes(*),
                   array_of_starts(*), order
           9
                   TYPE(MPI_Datatype), INTENT(IN) :: oldtype
          10
                   TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{12}
          13
               MPI_Type_dup(oldtype, newtype, ierror)
          14
                   TYPE(MPI_Datatype), INTENT(IN) :: oldtype
          15
                   TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 17
               MPI_Type_free(datatype, ierror)
                   TYPE(MPI_Datatype), INTENT(INOUT) :: datatype
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          20
ticket-248T.
          21
               MPI_Type_get_contents(datatype, max_integers, max_addresses, max_datatypes,
          22
                             array_of_integers, array_of_addresses, array_of_datatypes,
          23
                             ierror)
          24
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER, INTENT(IN) :: max_integers, max_addresses, max_datatypes
          26
                   INTEGER, INTENT(OUT) :: array_of_integers(*)
          27
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: array_of_addresses(*)
          28
                   TYPE(MPI_Datatype), INTENT(OUT) :: array_of_datatypes(*)
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 30
               MPI_Type_get_envelope(datatype, num_integers, num_addresses, num_datatypes,
          31
                             combiner, ierror)
          32
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER, INTENT(OUT) :: num_integers, num_addresses, num_datatypes,
          34
                   combiner
          35
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          37
               MPI_Type_get_extent(datatype, lb, extent, ierror)
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          39
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: lb, extent
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 41
               MPI_Type_get_true_extent(datatype, true_lb, true_extent, ierror)
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          43
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: true_lb, true_extent
          44
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Type_indexed(count, array_of_blocklengths, array_of_displacements,
          47
                             oldtype, newtype, ierror)
```

```
1
    INTEGER, INTENT(IN) :: count, array_of_blocklengths(*),
                                                                                  2
    array_of_displacements(*)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  6 ticket-248T.
MPI_Type_size(datatype, size, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{10} ticket-248T.
MPI_Type_vector(count, blocklength, stride, oldtype, newtype, ierror)
                                                                                 12
    INTEGER, INTENT(IN) :: count, blocklength, stride
                                                                                 13
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                 14
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                                                                                  15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>16</sub> ticket-248T.
MPI_Unpack(inbuf, insize, position, outbuf, outcount, datatype, comm,
                                                                                  17
             ierror)
                                                                                 18
    TYPE(*), DIMENSION(..) :: inbuf, outbuf
                                                                                  19
    INTEGER, INTENT(IN) :: insize, outcount
                                                                                 20
    INTEGER, INTENT(INOUT) :: position
                                                                                 21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                 22
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{24} ticket-248T.
MPI_Unpack_external(datarep, inbuf, insize, position, outbuf, outcount,
                                                                                 26
             datatype, ierror)
                                                                                 27
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                 28
    TYPE(*), DIMENSION(..) :: inbuf, outbuf
                                                                                 29
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: insize
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(INOUT) :: position
    INTEGER, INTENT(IN) :: outcount
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 34
                                                                                 35
A.4.3 Collective Communication Fortran 2008 Bindings
                                                                                 _{37} ticket-248T.
MPI_Allgather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
             comm, ierror)
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype
                                                                                  42
    TYPE(MPI_Datatype), INTENT(IN) :: recvtype
                                                                                  43
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sup>45</sup> ticket-248T.
MPI_Allgatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
             recvtype, comm, ierror)
                                                                                  47
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
```

```
1
                   INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*)
           2
                   TYPE(MPI_Datatype), INTENT(IN) :: sendtype
                   TYPE(MPI_Datatype), INTENT(IN) :: recvtype
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _6
               MPI_Allreduce(sendbuf, recvbuf, count, datatype, op, comm, ierror)
                   TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
                   INTEGER, INTENT(IN) :: count
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          10
                   TYPE(MPI_Op), INTENT(IN) :: op
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          12
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{13}
          14
               MPI_Alltoall(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
          15
                             comm, ierror)
          16
                   TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
          17
                   INTEGER, INTENT(IN) :: sendcount, recvcount
          18
                   TYPE(MPI_Datatype), INTENT(IN) :: sendtype
          19
                   TYPE(MPI_Datatype), INTENT(IN) :: recvtype
          20
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 22
               MPI_Alltoallv(sendbuf, sendcounts, sdispls, sendtype, recvbuf, recvcounts,
          23
                             rdispls, recvtype, comm, ierror)
          24
                   TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
                   INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
          26
                   rdispls(*)
          27
                   TYPE(MPI_Datatype), INTENT(IN) :: sendtype
          28
                   TYPE(MPI_Datatype), INTENT(IN) :: recvtype
          29
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{^{31}}
               MPI_Alltoallw(sendbuf, sendcounts, sdispls, sendtypes, recvbuf, recvcounts,
          33
                             rdispls, recvtypes, comm, ierror)
          34
                   TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
          35
                   INTEGER, INTENT(IN) :: sendcounts(*), sdispls(*), recvcounts(*),
          36
                   rdispls(*)
          37
                   TYPE(MPI_Datatype), INTENT(IN) :: sendtypes(*)
                   TYPE(MPI_Datatype), INTENT(IN) :: recvtypes(*)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 41
               MPI_Barrier(comm, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          43
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          45
               MPI_Bcast(buffer, count, datatype, root, comm, ierror)
                   TYPE(*), DIMENSION(..) :: buffer
          47
                   INTEGER, INTENT(IN) :: count, root
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                      2
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      4 ticket-248T.
MPI_Exscan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      ^{11} ticket-248T.
MPI_Gather(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                      13
              root, comm, ierror)
                                                                                      14
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
                                                                                      15
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
                                                                                      16
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype
                                                                                      17
    TYPE(MPI_Datatype), INTENT(IN) :: recvtype
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      <sub>20</sub> ticket-248T.
MPI_Gatherv(sendbuf, sendcount, sendtype, recvbuf, recvcounts, displs,
              recvtype, root, comm, ierror)
                                                                                      22
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
                                                                                      23
    INTEGER, INTENT(IN) :: sendcount, recvcounts(*), displs(*), root
                                                                                      24
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype
    TYPE(MPI_Datatype), INTENT(IN) :: recvtype
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                      27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                      ^{28} ticket-248T.
MPI_Iallgather( -- Fortran 2008 -- to be done -- )
                                                                                      30 ticket-248T.
MPI_Iallgatherv( -- Fortran 2008 -- to be done -- )
                                                                                      \frac{31}{32} ticket-248T.
MPI_Iallreduce( -- Fortran 2008 -- to be done -- )
                                                                                      зз ticket-248T.
MPI_Ialltoall( -- Fortran 2008 -- to be done -- )
                                                                                      _{35}^{34} ticket-248T.
MPI_Ialltoallv( -- Fortran 2008 -- to be done -- )
                                                                                      36 ticket-248T.
MPI_Ialltoallw( -- Fortran 2008 -- to be done -- )
                                                                                      \frac{1}{38} ticket-248T.
MPI_Ibarrier( -- Fortran 2008 -- to be done -- )
                                                                                      <sup>39</sup> ticket-248T.
MPI_Ibcast( -- Fortran 2008 -- to be done -- )
                                                                                      <sub>41</sub> ticket-248T.
MPI_Iexscan( -- Fortran 2008 -- to be done -- )
                                                                                      <sup>42</sup> ticket-248T.
MPI_Igather( -- Fortran 2008 -- to be done -- )
                                                                                      <sub>44</sub> ticket-248T.
MPI_Igatherv( -- Fortran 2008 -- to be done -- )
                                                                                      <sup>45</sup> ticket-248T.
MPI_Ireduce( -- Fortran 2008 -- to be done -- )
                                                                                      <sub>47</sub> ticket-248T.
MPI_Ireduce_scatter( -- Fortran 2008 -- to be done -- )
```

```
ticket-248T.
               MPI_Ireduce_scatter_block( -- Fortran 2008 -- to be done -- )
ticket-248T. 3
               MPI_Iscan( -- Fortran 2008 -- to be done -- )
ticket-248T. 4
               MPI_Iscatter( -- Fortran 2008 -- to be done -- )
ticket-248T. _6
               MPI_Iscatterv( -- Fortran 2008 -- to be done -- )
ticket-248
T. ^{\rm 7}
               MPI_Op_commutative(op, commute, ierror)
           9
                    TYPE(MPI_Op), INTENT(IN) :: op
           10
                    LOGICAL, INTENT(OUT) :: commute
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 12
               MPI_Op_create(user_fn, commute, op, ierror)
           13
                    EXTERNAL :: user_fn
          14
                    LOGICAL, INTENT(IN) :: commute
          15
                    TYPE(MPI_Op), INTENT(OUT) :: op
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{17}
               MPI_Op_free(op, ierror)
           19
                    TYPE(MPI_Op), INTENT(INOUT) :: op
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 21
               MPI_Reduce(sendbuf, recvbuf, count, datatype, op, root, comm, ierror)
          22
                    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
          23
                    INTEGER, INTENT(IN) :: count, root
          24
                    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                    TYPE(MPI_Op), INTENT(IN) :: op
                    TYPE(MPI_Comm), INTENT(IN) :: comm
          27
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Reduce_local(inbuf, inoutbuf, count, datatype, op, ierror)
           30
                    TYPE(*), DIMENSION(..) :: inbuf, inoutbuf
          31
                    INTEGER, INTENT(IN) :: count
          32
                    TYPE(MPI_Datatype), INTENT(IN) ::
          33
                    TYPE(MPI_Op), INTENT(IN) :: op
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 35
                MPI_Reduce_scatter(sendbuf, recvbuf, recvcounts, datatype, op, comm,
          36
                             ierror)
          37
                    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
          38
                    INTEGER, INTENT(IN) :: recvcounts(*)
                    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                    TYPE(MPI_Op), INTENT(IN) :: op
                    TYPE(MPI_Comm), INTENT(IN) :: comm
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          43
ticket-248T.
           44
               MPI_Reduce_scatter_block(sendbuf, recvbuf, recvcount, datatype, op, comm,
          45
                             ierror)
          46
                    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
           47
                    INTEGER, INTENT(IN) :: recvcount
```

```
TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>5</sub> ticket-248T.
MPI_Scan(sendbuf, recvbuf, count, datatype, op, comm, ierror)
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Op), INTENT(IN) :: op
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{12} ticket-248T.
MPI_Scatter(sendbuf, sendcount, sendtype, recvbuf, recvcount, recvtype,
                                                                                 14
             root, comm, ierror)
                                                                                 15
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
    INTEGER, INTENT(IN) :: sendcount, recvcount, root
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype
    TYPE(MPI_Datatype), INTENT(IN) :: recvtype
                                                                                 19
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>21</sub> ticket-248T.
MPI_Scatterv(sendbuf, sendcounts, displs, sendtype, recvbuf, recvcount,
                                                                                 22
             recvtype, root, comm, ierror)
                                                                                 23
    TYPE(*), DIMENSION(..) :: sendbuf, recvbuf
                                                                                 24
    INTEGER, INTENT(IN) :: sendcounts(*), displs(*), recvcount, root
    TYPE(MPI_Datatype), INTENT(IN) :: sendtype
                                                                                 26
    TYPE(MPI_Datatype), INTENT(IN) :: recvtype
                                                                                 27
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 28
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 29
                                                                                 30
A.4.4 Groups, Contexts, Communicators, and Caching Fortran 2008 Bindings
                                                                                 ^{32} ticket-248T.
MPI_COMM_DUP_FN(oldcomm, comm_keyval, extra_state, attribute_val_in,
             attribute_val_out, flag, ierror)
                                                                                 34
    TYPE(MPI_Comm), INTENT(IN) :: oldcomm
                                                                                 35
    INTEGER, INTENT(IN) :: comm_keyval
                                                                                 36
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
                                                                                 37
    attribute_val_in
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, INTENT(OUT) :: ierror
                                                                                 _{42} ticket-248T.
MPI_COMM_NULL_COPY_FN(oldcomm, comm_keyval, extra_state, attribute_val_in,
             attribute_val_out, flag, ierror)
                                                                                 44
    TYPE(MPI_Comm), INTENT(IN) :: oldcomm
                                                                                 45
    INTEGER, INTENT(IN) :: comm_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
    attribute_val_in
```

```
1
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
                   LOGICAL, INTENT(OUT) :: flag
                   INTEGER, INTENT(OUT) :: ierror
ticket-248T. 4
               MPI_COMM_NULL_DELETE_FN(comm, comm_keyval, attribute_val, extra_state,
                             ierror)
           6
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, INTENT(IN) :: comm_keyval
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val,
                   extra_state
                   INTEGER, INTENT(OUT) :: ierror
ticket-248T.
          12
               MPI_Comm_compare(comm1, comm2, result, ierror)
          13
                   TYPE(MPI_Comm), INTENT(IN) :: comm1
          14
                   TYPE(MPI_Comm), INTENT(IN) :: comm2
          15
                   INTEGER, INTENT(OUT) :: result
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 17
               MPI_Comm_create(comm, group, newcomm, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          19
                   TYPE(MPI_Group), INTENT(IN) :: group
          20
                   TYPE(MPI_Comm), INTENT(OUT) :: newcomm
          21
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{^{22}}
          23
               MPI_Comm_create_keyval(comm_copy_attr_fn, comm_delete_attr_fn, comm_keyval,
          ^{24}
                             extra_state, ierror)
                   EXTERNAL :: comm_copy_attr_fn, comm_delete_attr_fn
          26
                   INTEGER, INTENT(OUT) :: comm_keyval
          27
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 29
               MPI_Comm_delete_attr(comm, comm_keyval, ierror)
          30
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          31
                    INTEGER, INTENT(IN) :: comm_keyval
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          33
ticket-248T.
               MPI_Comm_dup(comm, newcomm, ierror)
          35
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          36
                   TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 38
               MPI_Comm_free(comm, ierror)
                   TYPE(MPI_Comm), INTENT(INOUT) :: comm
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Comm_free_keyval(comm_keyval, ierror)
          43
                   INTEGER, INTENT(INOUT) :: comm_keyval
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 45
               MPI_Comm_get_attr(comm, comm_keyval, attribute_val, flag, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          47
                   INTEGER, INTENT(IN) :: comm_keyval
```

```
INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
                                                                                  2
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  4 ticket-248T.
MPI_Comm_get_name(comm, comm_name, resultlen, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    CHARACTER(LEN=*), INTENT(OUT) :: comm_name
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_group(comm, group, ierror)
                                                                                  11
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 12
    TYPE(MPI_Group), INTENT(OUT) :: group
                                                                                  13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>14</sub> ticket-248T.
MPI_Comm_rank(comm, rank, ierror)
                                                                                  15
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                  16
    INTEGER, INTENT(OUT) :: rank
                                                                                  17
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ticket-248T.
MPI_Comm_remote_group(comm, group, ierror)
                                                                                 20
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 21
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 23 ticket-248T.
MPI_Comm_remote_size(comm, size, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_set_attr(comm, comm_keyval, attribute_val, ierror)
                                                                                 29
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 30
    INTEGER, INTENT(IN) :: comm_keyval
                                                                                 31
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 33 ticket-248T.
MPI_Comm_set_name(comm, comm_name, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 35
    CHARACTER(LEN=*), INTENT(IN) :: comm_name
                                                                                 36
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_size(comm, size, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sup>42</sup> ticket-248T.
MPI_Comm_split(comm, color, key, newcomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: color, key
                                                                                  45
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  48 ticket-248T.
```

```
1
               MPI_Comm_test_inter(comm, flag, ierror)
           2
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   LOGICAL, INTENT(OUT) :: flag
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _5
               MPI_Group_compare(group1, group2, result, ierror)
                   TYPE(MPI_Group), INTENT(IN) :: group1, group2
           7
                   INTEGER, INTENT(OUT) :: result
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Group_difference(group1, group2, newgroup, ierror)
          11
                   TYPE(MPI_Group), INTENT(IN) :: group1, group2
          12
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
          13
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 14
               MPI_Group_excl(group, n, ranks, newgroup, ierror)
          15
                   TYPE(MPI_Group), INTENT(IN) :: group
          16
                   INTEGER, INTENT(IN) :: n, ranks(*)
          17
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          19
ticket-248T.
          20
               MPI_Group_free(group, ierror)
          21
                   TYPE(MPI_Group), INTENT(INOUT) ::
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 23
               MPI_Group_incl(group, n, ranks, newgroup, ierror)
          24
                   INTEGER, INTENT(IN) :: n, ranks(*)
                   TYPE(MPI_Group), INTENT(IN) :: group
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
          27
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Group_intersection(group1, group2, newgroup, ierror)
          30
                   TYPE(MPI_Group), INTENT(IN) :: group1, group2
          31
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 33
               MPI_Group_range_excl(group, n, ranges, newgroup, ierror)
                   TYPE(MPI_Group), INTENT(IN) :: group
          35
                   INTEGER, INTENT(IN) :: n, ranges(3,*)
          36
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
          37
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Group_range_incl(group, n, ranges, newgroup, ierror)
                   TYPE(MPI_Group), INTENT(IN) :: group
          41
                   INTEGER, INTENT(IN) :: n, ranges(3,*)
          42
                   TYPE(MPI_Group), INTENT(OUT) :: newgroup
          43
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 44
               MPI_Group_rank(group, rank, ierror)
          45
                   TYPE(MPI_Group), INTENT(IN) :: group
                   INTEGER, INTENT(OUT) :: rank
          47
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
<sub>2</sub> ticket-248T.
MPI_Group_size(group, size, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   _{6} ticket-248T.
MPI_Group_translate_ranks(group1, n, ranks1, group2, ranks2, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
    INTEGER, INTENT(IN) :: n, ranks1(*)
    INTEGER, INTENT(OUT) :: ranks2(*)
                                                                                  10
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sup>11</sup> ticket-248T.
MPI_Group_union(group1, group2, newgroup, ierror)
                                                                                  13
    TYPE(MPI_Group), INTENT(IN) :: group1, group2
    TYPE(MPI_Group), INTENT(OUT) :: newgroup
                                                                                  14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  15
                                                                                  <sub>16</sub> ticket-248T.
MPI_Intercomm_create(local_comm, local_leader, peer_comm, remote_leader,
             tag, newintercomm, ierror)
                                                                                  18
    TYPE(MPI_Comm), INTENT(IN) :: local_comm, peer_comm
                                                                                  19
    INTEGER, INTENT(IN) :: local_leader, remote_leader, tag
                                                                                  20
    TYPE(MPI_Comm), INTENT(OUT) :: newintercomm
                                                                                  21
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{22} ticket-248T.
MPI_Intercomm_merge(intercomm, high, newintracomm, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: intercomm
    LOGICAL, INTENT(IN) :: high
    TYPE(MPI_Comm), INTENT(OUT) :: newintracomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>28</sub> ticket-248T.
MPI_TYPE_DUP_FN(oldtype, type_keyval, extra_state, attribute_val_in,
              attribute_val_out, flag, ierror)
                                                                                  30
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
                                                                                  31
    INTEGER, INTENT(IN) :: type_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
    attribute_val_in
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
                                                                                  35
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, INTENT(OUT) :: ierror
                                                                                  ^{37} ticket-248T.
MPI_TYPE_NULL_COPY_FN(oldtype, type_keyval, extra_state, attribute_val_in,
              attribute_val_out, flag, ierror)
    TYPE(MPI_Datatype), INTENT(IN) :: oldtype
    INTEGER, INTENT(IN) :: type_keyval
                                                                                  42
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
                                                                                  43
    attribute_val_in
                                                                                  44
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
                                                                                  45
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, INTENT(OUT) :: ierror
                                                                                  47 ticket-248T.
MPI_TYPE_NULL_DELETE_FN(datatype, type_keyval, attribute_val, extra_state,
```

```
1
                             ierror)
           2
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER, INTENT(IN) :: type_keyval
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val,
                   extra_state
                   INTEGER, INTENT(OUT) :: ierror
ticket-248T. 7
               MPI_Type_create_keyval(type_copy_attr_fn, type_delete_attr_fn, type_keyval,
                             extra_state, ierror)
           9
                   EXTERNAL :: type_copy_attr_fn, type_delete_attr_fn
          10
                   INTEGER, INTENT(OUT) :: type_keyval
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
          12
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{13}
          14
               MPI_Type_delete_attr(datatype, type_keyval, ierror)
          15
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          16
                   INTEGER, INTENT(IN) :: type_keyval
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 18
               MPI_Type_free_keyval(type_keyval, ierror)
                    INTEGER, INTENT(INOUT) :: type_keyval
          20
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{21}
          22
               MPI_Type_get_attr(datatype, type_keyval, attribute_val, flag, ierror)
          23
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          24
                   INTEGER, INTENT(IN) :: type_keyval
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
          26
                   LOGICAL, INTENT(OUT) :: flag
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 28
               MPI_Type_get_name(datatype, type_name, resultlen, ierror)
          29
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          30
                   CHARACTER(LEN=*), INTENT(OUT) :: type_name
          31
                   INTEGER, INTENT(OUT) :: resultlen
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          33
ticket-248T.
               MPI_Type_set_attr(datatype, type_keyval, attribute_val, ierror)
          35
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          36
                   INTEGER, INTENT(IN) :: type_keyval
          37
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 39
               MPI_Type_set_name(datatype, type_name, ierror)
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          41
                   CHARACTER(LEN=*), INTENT(IN) :: type_name
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          44
               MPI_WIN_DUP_FN(oldwin, win_keyval, extra_state, attribute_val_in,
          45
                             attribute_val_out, flag, ierror)
          46
                    INTEGER, INTENT(IN) :: oldwin, win_keyval
          47
                    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
```

```
attribute_val_in
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, INTENT(OUT) :: ierror
                                                                                  <sub>5</sub> ticket-248T.
MPI_WIN_NULL_COPY_FN(oldwin, win_keyval, extra_state, attribute_val_in,
             attribute_val_out, flag, ierror)
    INTEGER, INTENT(IN) :: oldwin, win_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state,
    attribute_val_in
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val_out
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, INTENT(OUT) :: ierror
                                                                                 ^{13} ticket-248T.
                                                                                 14
MPI_WIN_NULL_DELETE_FN(win, win_keyval, attribute_val, extra_state, ierror)
                                                                                 15
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 16
    INTEGER, INTENT(IN) :: win_keyval
                                                                                 17
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val,
                                                                                 18
    extra_state
    INTEGER, INTENT(OUT) :: ierror
                                                                                 <sub>20</sub> ticket-248T.
MPI_Win_create_keyval(win_copy_attr_fn, win_delete_attr_fn, win_keyval,
                                                                                 21
             extra_state, ierror)
                                                                                 22
    EXTERNAL :: win_copy_attr_fn, win_delete_attr_fn
                                                                                 23
    INTEGER, INTENT(OUT) :: win_keyval
                                                                                 24
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{26} ticket-248T.
MPI_Win_delete_attr(win, win_keyval, ierror)
                                                                                 28
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: win_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 зı ticket-248T.
MPI_Win_free_keyval(win_keyval, ierror)
    INTEGER, INTENT(INOUT) :: win_keyval
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Win_get_attr(win, win_keyval, attribute_val, flag, ierror)
                                                                                 36
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 37
    INTEGER, INTENT(IN) :: win_keyval
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: attribute_val
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 41 ticket-248T.
MPI_Win_get_name(win, win_name, resultlen, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                 43
    CHARACTER(LEN=*), INTENT(OUT) :: win_name
                                                                                 44
    INTEGER, INTENT(OUT) :: resultlen
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ii ticket-248T.
MPI_Win_set_attr(win, win_keyval, attribute_val, ierror)
```

```
1
                   TYPE(MPI_Win), INTENT(IN) :: win
           2
                   INTEGER, INTENT(IN) :: win_keyval
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: attribute_val
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _5
               MPI_Win_set_name(win, win_name, ierror)
                   TYPE(MPI_Win), INTENT(IN) :: win
           7
                   CHARACTER(LEN=*), INTENT(IN) :: win_name
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           9
          10
          11
               A.4.5 Process Topologies Fortran 2008 Bindings
ticket-248T. 12
               MPI_Cart_coords(comm, rank, maxdims, coords, ierror)
          13
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          14
                   INTEGER, INTENT(IN) :: rank, maxdims
          15
                   INTEGER, INTENT(OUT) :: coords(*)
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Cart_create(comm_old, ndims, dims, periods, reorder, comm_cart, ierror)
          19
                   TYPE(MPI_Comm), INTENT(IN) :: comm_old
          20
                   INTEGER, INTENT(IN) :: ndims, dims(*)
          21
                   LOGICAL, INTENT(IN) :: periods(*), reorder
          22
                   TYPE(MPI_Comm), INTENT(OUT) :: comm_cart
          23
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 24
               MPI_Cart_get(comm, maxdims, dims, periods, coords, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          26
                   INTEGER, INTENT(IN) :: maxdims
          27
                   INTEGER, INTENT(OUT) :: dims(*), coords(*)
          28
                   LOGICAL, INTENT(OUT) :: periods(*)
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          31
               MPI_Cart_map(comm, ndims, dims, periods, newrank, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          33
                   INTEGER, INTENT(IN) :: ndims, dims(*)
          34
                   LOGICAL, INTENT(IN) :: periods(*)
          35
                   INTEGER, INTENT(OUT) :: newrank
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 37
               MPI_Cart_rank(comm, coords, rank, ierror)
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   INTEGER, INTENT(IN) :: coords(*)
                   INTEGER, INTENT(OUT) :: rank
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248
T. _{\rm 43}
               MPI_Cart_shift(comm, direction, disp, rank_source, rank_dest, ierror)
          44
                   TYPE(MPI_Comm), INTENT(IN) :: comm
          45
                   INTEGER, INTENT(IN) :: direction, disp
                   INTEGER, INTENT(OUT) :: rank_source, rank_dest
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 48
```

```
MPI_Cart_sub(comm, remain_dims, newcomm, ierror)
                                                                                 2
    TYPE(MPI_Comm), INTENT(IN) :: comm
    LOGICAL, INTENT(IN) :: remain_dims(*)
    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 6 ticket-248T.
MPI_Cartdim_get(comm, ndims, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: ndims
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                ^{10} ticket-248T.
MPI_Dims_create(nnodes, ndims, dims, ierror)
                                                                                12
    INTEGER, INTENT(IN) :: nnodes, ndims
                                                                                13
    INTEGER, INTENT(INOUT) :: dims(*)
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                <sub>15</sub> ticket-248T.
MPI_Dist_graph_create(comm_old, n, sources, degrees, destinations, weights,
             info, reorder, comm_dist_graph, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
    INTEGER, INTENT(IN) :: n, sources(*), degrees(*), destinations(*)
                                                                                19
    INTEGER, INTENT(IN) :: weights(*) ! optional by overloading
                                                                                20
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                21
    LOGICAL, INTENT(IN) :: reorder
                                                                                22
    TYPE(MPI_Comm), INTENT(OUT) :: comm_dist_graph
                                                                                23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                ^{24} ticket-248T.
MPI_Dist_graph_create_adjacent(comm_old, indegree, sources, sourceweights,
                                                                                26
             outdegree, destinations, destweights, info, reorder,
                                                                                27
             comm_dist_graph, ierror)
                                                                                28
    TYPE(MPI_Comm), INTENT(IN) :: comm_old
                                                                                29
    INTEGER, INTENT(IN) :: indegree, sources(*), outdegree,
    destinations(*)
    INTEGER, INTENT(IN) :: sourceweights(*), destweights(*) ! optional by
    overloading
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                34
    LOGICAL, INTENT(IN) :: reorder
                                                                                35
    TYPE(MPI_Comm), INTENT(OUT) :: comm_dist_graph
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                37 ticket-248T.
MPI_Dist_graph_neighbors(comm, maxindegree, sources, sourceweights,
             maxoutdegree, destinations, destweights, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: maxindegree, maxoutdegree
    INTEGER, INTENT(OUT) :: sources(*), destinations(*)
    INTEGER :: sourceweights(*), destweights(*) ! optional by overloading
                                                                                43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_Dist_graph_neighbors_count(comm, indegree, outdegree, weighted, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(OUT) :: indegree, outdegree
```

```
LOGICAL, INTENT(OUT) :: weighted
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 3
               MPI_Graph_create(comm_old, nnodes, index, edges, reorder, comm_graph,
                             ierror)
                    TYPE(MPI_Comm), INTENT(IN) :: comm_old
           6
                    INTEGER, INTENT(IN) :: nnodes, index(*), edges(*)
                    LOGICAL, INTENT(IN) :: reorder
                    TYPE(MPI_Comm), INTENT(OUT) :: comm_graph
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{10}
          11
               MPI_Graph_get(comm, maxindex, maxedges, index, edges, ierror)
          12
                    TYPE(MPI_Comm), INTENT(IN) :: comm
          13
                    INTEGER, INTENT(IN) :: maxindex, maxedges
          14
                    INTEGER, INTENT(OUT) :: index(*), edges(*)
           15
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 16
               MPI_Graph_map(comm, nnodes, index, edges, newrank, ierror)
          17
                    TYPE(MPI_Comm), INTENT(IN) :: comm
                    INTEGER, INTENT(IN) :: nnodes, index(*), edges(*)
          19
                    INTEGER, INTENT(OUT) :: newrank
          20
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          21
ticket-248T.
          22
                MPI_Graph_neighbors(comm, rank, maxneighbors, neighbors, ierror)
          23
                    TYPE(MPI_Comm), INTENT(IN) :: comm
          ^{24}
                    INTEGER, INTENT(IN) :: rank, maxneighbors
                    INTEGER, INTENT(OUT) :: neighbors(*)
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 27
               MPI_Graph_neighbors_count(comm, rank, nneighbors, ierror)
          28
                    TYPE(MPI_Comm), INTENT(IN) :: comm
          29
                    INTEGER, INTENT(IN) :: rank
                    INTEGER, INTENT(OUT) :: nneighbors
          31
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
           33
                MPI_Graphdims_get(comm, nnodes, nedges, ierror)
          34
                    TYPE(MPI_Comm), INTENT(IN) :: comm
          35
                    INTEGER, INTENT(OUT) :: nnodes, nedges
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 37
               MPI_Topo_test(comm, status, ierror)
          38
                    TYPE(MPI_Comm), INTENT(IN) :: comm
                    INTEGER, INTENT(OUT) :: status
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                A.4.6 MPI Environmental Management Fortran 2008 Bindings
ticket-248T. ^{44}
               DOUBLE PRECISION MPI_Wtick()
ticket-248T. _{46}
               DOUBLE PRECISION MPI_Wtime()
ticket-248T. ^{47}
               MPI_Abort(comm, errorcode, ierror)
```

```
1
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _4 ticket-248T.
MPI_Add_error_class(errorclass, ierror)
    INTEGER, INTENT(OUT) :: errorclass
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{7} ticket-248T.
MPI_Add_error_code(errorclass, errorcode, ierror)
    INTEGER, INTENT(IN) :: errorclass
    INTEGER, INTENT(OUT) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>12</sub> ticket-248T.
MPI_Add_error_string(errorcode, string, ierror)
                                                                                 13
    INTEGER, INTENT(IN) :: errorcode
                                                                                 14
    CHARACTER(LEN=*), INTENT(IN) :: string
                                                                                 15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Alloc_mem(size, info, baseptr, ierror)
    USE, INTRINSIC :: ISO_C_BINDING
                                                                                 19
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
                                                                                 20
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 21
    TYPE(C_PTR), INTENT(OUT) :: baseptr
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 23 ticket-248T.
MPI_Comm_call_errhandler(comm, errorcode, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_create_errhandler(comm_errhandler_fn, errhandler, ierror)
                                                                                 29
    EXTERNAL :: comm_errhandler_fn
                                                                                 30
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sup>32</sup> ticket-248T.
MPI_Comm_get_errhandler(comm, errhandler, ierror)
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
                                                                                 35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_set_errhandler(comm, errhandler, ierror)
                                                                                 38
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 41 ticket-248T.
MPI_Errhandler_free(errhandler, ierror)
    TYPE(MPI_Errhandler), INTENT(INOUT) :: errhandler
                                                                                 43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 _{45} ticket-248T.
MPI_Error_class(errorcode, errorclass, ierror)
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, INTENT(OUT) :: errorclass
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 2
                MPI_Error_string(errorcode, string, resultlen, ierror)
                    INTEGER, INTENT(IN) :: errorcode
                    CHARACTER(LEN=*), INTENT(OUT) :: string
           5
                    INTEGER, INTENT(OUT) :: resultlen
           6
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
                MPI_File_call_errhandler(fh, errorcode, ierror)
                    TYPE(MPI_File), INTENT(IN) :: fh
           10
                    INTEGER, INTENT(IN) :: errorcode
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 12
                MPI_File_create_errhandler(file_errhandler_fn, errhandler, ierror)
           13
                    EXTERNAL :: file_errhandler_fn
           14
                    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
           15
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{^{16}}
                MPI_File_get_errhandler(file, errhandler, ierror)
                    TYPE(MPI_File), INTENT(IN) :: file
           19
                    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
           20
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 21
                MPI_File_set_errhandler(file, errhandler, ierror)
           22
                    TYPE(MPI_File), INTENT(IN) :: file
           23
                    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
           24
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
                MPI_Finalize(ierror)
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 28
                MPI_Finalized(flag, ierror)
                    LOGICAL, INTENT(OUT) :: flag
           30
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{_{32}}^{\circ}
                MPI_Free_mem(base, ierror)
           33
                    USE, INTRINSIC :: ISO_C_BINDING
           34
                    TYPE(C_PTR), INTENT(IN) :: base
           35
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. <sup>36</sup>
                MPI_Get_processor_name( name, resultlen, ierror)
                    CHARACTER(LEN=*), INTENT(OUT) :: name
                    INTEGER, INTENT(OUT) :: resultlen
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
                MPI_Get_version(version, subversion, ierror)
                    INTEGER, INTENT(OUT) :: version, subversion
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 44
                MPI_Init(ierror)
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{47}
                MPI_Initialized(flag, ierror)
```

```
1
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    <sub>3</sub> ticket-248T.
MPI_Win_call_errhandler(win, errorcode, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, INTENT(IN) :: errorcode
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ^{7} ticket-248T.
MPI_Win_create_errhandler(win_errhandler_fn, errhandler, ierror)
    EXTERNAL :: win_errhandler_fn
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    <sub>12</sub> ticket-248T.
MPI_Win_get_errhandler(win, errhandler, ierror)
                                                                                   13
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                   14
    TYPE(MPI_Errhandler), INTENT(OUT) :: errhandler
                                                                                    15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     ticket-248T.
MPI_Win_set_errhandler(win, errhandler, ierror)
                                                                                    18
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                   19
    TYPE(MPI_Errhandler), INTENT(IN) :: errhandler
                                                                                   20
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   21
A.4.7 The Info Object Fortran 2008 Bindings
                                                                                    _{24} ticket-248T.
MPI_Info_create(info, ierror)
    TYPE(MPI_Info), INTENT(OUT) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   <sup>27</sup> ticket-248T.
MPI_Info_delete(info, key, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    _{32} ticket-248T.
MPI_Info_dup(info, newinfo, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Info), INTENT(OUT) :: newinfo
                                                                                   35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ^{36} ticket-248T.
MPI_Info_free(info, ierror)
    TYPE(MPI_Info), INTENT(INOUT) :: info
                                                                                   38
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    _{40} ticket-248T.
MPI_Info_get(info, key, valuelen, value, flag, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: key
                                                                                    43
    INTEGER, INTENT(IN) :: valuelen
                                                                                    44
    CHARACTER(LEN=*), INTENT(OUT) :: value
                                                                                    45
    LOGICAL, INTENT(OUT) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   <sup>47</sup> ticket-248T.
MPI_Info_get_nkeys(info, nkeys, ierror)
```

```
1
                    TYPE(MPI_Info), INTENT(IN) :: info
                    INTEGER, INTENT(OUT) :: nkeys
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 4
                MPI_Info_get_nthkey(info, n, key, ierror)
                    TYPE(MPI_Info), INTENT(IN) :: info
           6
                    INTEGER, INTENT(IN) :: n
                    CHARACTER(LEN=*), INTENT(OUT) :: key
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_Info_get_valuelen(info, key, valuelen, flag, ierror)
          11
                    TYPE(MPI_Info), INTENT(IN) :: info
          12
                    CHARACTER(LEN=*), INTENT(IN) :: key
          13
                    INTEGER, INTENT(OUT) :: valuelen
          14
                    LOGICAL, INTENT(OUT) :: flag
           15
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 16
               MPI_Info_set(info, key, value, ierror)
           17
                    TYPE(MPI_Info), INTENT(IN) :: info
                    CHARACTER(LEN=*), INTENT(IN) :: key, value
          19
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
          20
          21
                A.4.8 Process Creation and Management Fortran 2008 Bindings
ticket-248T. <sup>23</sup>
               MPI_Close_port(port_name, ierror)
                    CHARACTER(LEN=*), INTENT(IN) :: port_name
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
                MPI_Comm_accept(port_name, info, root, comm, newcomm, ierror)
          28
                    CHARACTER(LEN=*), INTENT(IN) :: port_name
          29
                    TYPE(MPI_Info), INTENT(IN) :: info
          30
                    INTEGER, INTENT(IN) :: root
                    TYPE(MPI_Comm), INTENT(IN) :: comm
                    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 34
               MPI_Comm_connect(port_name, info, root, comm, newcomm, ierror)
          35
                    CHARACTER(LEN=*), INTENT(IN) :: port_name
          36
          37
                    TYPE(MPI_Info), INTENT(IN) :: info
                    INTEGER, INTENT(IN) :: root
                    TYPE(MPI_Comm), INTENT(IN) :: comm
                    TYPE(MPI_Comm), INTENT(OUT) :: newcomm
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{42}
               MPI_Comm_disconnect(comm, ierror)
           43
                    TYPE(MPI_Comm), INTENT(INOUT) :: comm
          44
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{45}
               MPI_Comm_get_parent(parent, ierror)
          47
                    TYPE(MPI_Comm), INTENT(OUT) :: parent
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
_2 ticket-248T.
MPI_Comm_join(fd, intercomm, ierror)
    INTEGER, INTENT(IN) :: fd
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_Comm_spawn(command, argv, maxprocs, info, root, comm, intercomm,
             array_of_errcodes, ierror)
    CHARACTER(LEN=*), INTENT(IN) :: command, argv(*)
    INTEGER, INTENT(IN) :: maxprocs, root
    TYPE(MPI_Info), INTENT(IN) :: info
    TYPE(MPI_Comm), INTENT(IN) :: comm
                                                                                 12
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
                                                                                 13
    INTEGER, INTENT(OUT) :: array_of_errcodes(*) ! optional by
                                                                                 14
    overloading
                                                                                  15
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{16} ticket-248T.
MPI_Comm_spawn_multiple(count, array_of_commands, array_of_argv,
             array_of_maxprocs, array_of_info, root, comm, intercomm,
                                                                                 18
             array_of_errcodes, ierror)
                                                                                 19
    INTEGER, INTENT(IN) :: count, array_of_maxprocs(*), root
                                                                                 20
    CHARACTER(LEN=*), INTENT(IN) :: array_of_commands(*),
                                                                                 21
    array_of_argv(count, *)
                                                                                 22
    TYPE(MPI_Info), INTENT(IN) :: array_of_info(*)
                                                                                 23
                                                                                  24
    TYPE(MPI_Comm), INTENT(IN) :: comm
    TYPE(MPI_Comm), INTENT(OUT) :: intercomm
    INTEGER, INTENT(OUT) :: array_of_errcodes(*) ! optional by
    overloading
                                                                                 27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 28
                                                                                 <sub>29</sub> ticket-248T.
MPI_Lookup_name(service_name, info, port_name, ierror)
                                                                                 30
    CHARACTER(LEN=*), INTENT(IN) :: service_name
                                                                                 31
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  32
    CHARACTER(LEN=*), INTENT(OUT) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{34} ticket-248T.
MPI_Open_port(info, port_name, ierror)
                                                                                 36
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                 37
    CHARACTER(LEN=*), INTENT(OUT) :: port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>39</sub> ticket-248T.
MPI_Publish_name(service_name, info, port_name, ierror)
    TYPE(MPI_Info), INTENT(IN) :: info
    CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ^{43} ticket-248T.
MPI_Unpublish_name(service_name, info, port_name, ierror)
                                                                                 45
    CHARACTER(LEN=*), INTENT(IN) :: service_name, port_name
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                  47
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
A.4.9 One-Sided Communications Fortran 2008 Bindings
ticket-248T.
               MPI_Accumulate(origin_addr, origin_count, origin_datatype, target_rank,
                             target_disp, target_count, target_datatype, op, win, ierror)
                   TYPE(*), DIMENSION(..) :: origin_addr
          5
                   INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
          6
                   TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
                   TYPE(MPI_Datatype), INTENT(IN) :: target_datatype
          9
                   TYPE(MPI_Op), INTENT(IN) :: op
                   TYPE(MPI_Win), INTENT(IN) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{12}
          13
               MPI_Get(origin_addr, origin_count, origin_datatype, target_rank,
          14
                             target_disp, target_count, target_datatype, win, ierror)
          15
                   TYPE(*), DIMENSION(..) :: origin_addr
          16
                   INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
                   TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
          19
                   TYPE(MPI_Datatype), INTENT(IN) :: target_datatype
          20
                   TYPE(MPI_Win), INTENT(IN) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) ::
                                                       ierror
ticket-248T. 22
               MPI_Put(origin_addr, origin_count, origin_datatype, target_rank,
                             target_disp, target_count, target_datatype, win, ierror)
          24
                   TYPE(*), DIMENSION(..) :: origin_addr
                   INTEGER, INTENT(IN) :: origin_count, target_rank, target_count
          26
                   TYPE(MPI_Datatype), INTENT(IN) :: origin_datatype
          27
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: target_disp
          28
                   TYPE(MPI_Datatype), INTENT(IN) :: target_datatype
                   TYPE(MPI_Win), INTENT(IN) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) ::
                                                       ierror
ticket-248T. ^{^{31}}
               MPI_Win_complete(win, ierror)
                   TYPE(MPI_Win), INTENT(IN) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 35
               MPI_Win_create(base, size, disp_unit, info, comm, win, ierror)
          36
                   TYPE(*), DIMENSION(..) :: base
          37
                   INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: size
                   INTEGER, INTENT(IN) :: disp_unit
                   TYPE(MPI_Info), INTENT(IN) :: info
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   TYPE(MPI_Win), INTENT(OUT) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{43}
               MPI_Win_fence(assert, win, ierror)
                   INTEGER, INTENT(IN) :: assert
                   TYPE(MPI_Win), INTENT(IN) :: win
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 48
```

```
1
MPI_Win_free(win, ierror)
                                                                                  2
    TYPE(MPI_Win), INTENT(INOUT) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  4 ticket-248T.
MPI_Win_get_group(win, group, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ticket-248T.
MPI_Win_lock(lock_type, rank, assert, win, ierror)
                                                                                  10
    INTEGER, INTENT(IN) :: lock_type, rank, assert
    TYPE(MPI_Win), INTENT(IN) :: win
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>13</sub> ticket-248T.
MPI_Win_post(group, assert, win, ierror)
    TYPE(MPI_Group), INTENT(IN) :: group
                                                                                  15
    INTEGER, INTENT(IN) :: assert
                                                                                  16
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  17
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ticket-248T.
MPI_Win_start(group, assert, win, ierror)
                                                                                  20
    TYPE(MPI_Group), INTENT(IN) :: group
                                                                                  21
    INTEGER, INTENT(IN) :: assert
                                                                                  22
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  24 ticket-248T.
MPI_Win_test(win, flag, ierror)
    LOGICAL, INTENT(OUT) :: flag
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  27
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ticket-248T.
MPI_Win_unlock(rank, win, ierror)
                                                                                  30
    INTEGER, INTENT(IN) :: rank
                                                                                  31
    TYPE(MPI_Win), INTENT(IN) ::
    INTEGER, OPTIONAL, INTENT(OUT) ::
                                                                                  33 ticket-248T.
MPI_Win_wait(win, ierror)
    TYPE(MPI_Win), INTENT(IN) :: win
                                                                                  35
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  36
A.4.10 External Interfaces Fortran 2008 Bindings
                                                                                  ^{39} ticket-248T.
MPI_Grequest_complete(request, ierror)
    TYPE(MPI_Request), INTENT(IN) :: request
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _{43} ticket-248T.
MPI_Grequest_start(query_fn, free_fn, cancel_fn, extra_state, request,
                                                                                  44
             ierror)
                                                                                  45
    EXTERNAL :: query_fn, free_fn, cancel_fn
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                                                                                  47
    TYPE(MPI_Request), INTENT(OUT) :: request
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 2
                MPI_Init_thread(required, provided, ierror)
                    INTEGER, INTENT(IN) :: required
                    INTEGER, INTENT(OUT) :: provided
           5
                    INTEGER, OPTIONAL, INTENT(OUT) ::
ticket-248T.
                MPI_Is_thread_main(flag, ierror)
                    LOGICAL, INTENT(OUT) :: flag
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 10
                MPI_Query_thread(provided, ierror)
                    INTEGER, INTENT(OUT) :: provided
           12
                    INTEGER, OPTIONAL, INTENT(OUT) ::
                                                        ierror
ticket-248T. ^{^{13}}
           14
                MPI_Status_set_cancelled(status, flag, ierror)
           15
                    TYPE(MPI_Status), INTENT(INOUT) :: status
                    LOGICAL, INTENT(OUT) :: flag
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 18
               MPI_Status_set_elements(status, datatype, count, ierror)
           19
                    TYPE(MPI_Status), INTENT(INOUT) :: status
           20
                    TYPE(MPI_Datatype), INTENT(IN) :: datatype
           21
                    INTEGER, INTENT(IN) :: count
           22
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           23
           24
                A.4.11 I/O Fortran 2008 Bindings
ticket-248T. ^{26}
               MPI_File_close(fh, ierror)
           27
                    TYPE(MPI_File), INTENT(INOUT) :: fh
           28
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _{30}
                MPI_File_delete(filename, info, ierror)
                    CHARACTER(LEN=*), INTENT(IN) :: filename
                    TYPE(MPI_Info), INTENT(IN) :: info
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. <sup>34</sup>
                MPI_File_get_amode(fh, amode, ierror)
           36
                    TYPE(MPI_File), INTENT(IN) :: fh
           37
                    INTEGER, INTENT(OUT) :: amode
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 39
                MPI_File_get_atomicity(fh, flag, ierror)
                    TYPE(MPI_File), INTENT(IN) :: fh
           41
                    LOGICAL, INTENT(OUT) :: flag
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{43}
           44
                MPI_File_get_byte_offset(fh, offset, disp, ierror)
           45
                    TYPE(MPI_File), INTENT(IN) :: fh
           46
                    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
           47
                    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
```

```
_2 ticket-248T.
MPI_File_get_group(fh, group, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Group), INTENT(OUT) :: group
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  _{6} ticket-248T.
MPI_File_get_info(fh, info_used, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Info), INTENT(OUT) :: info_used
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{10} ticket-248T.
MPI_File_get_position(fh, offset, ierror)
                                                                                  12
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
                                                                                  13
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>15</sub> ticket-248T.
MPI_File_get_position_shared(fh, offset, ierror)
                                                                                  16
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                  17
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: offset
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{19} ticket-248T.
MPI_File_get_size(fh, size, ierror)
                                                                                  21
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: size
                                                                                  22
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  <sub>24</sub> ticket-248T.
MPI_File_get_type_extent(fh, datatype, extent, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                  27
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(OUT) :: extent
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ^{29} ticket-248T.
MPI_File_get_view(fh, disp, etype, filetype, datarep, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(OUT) :: disp
    TYPE(MPI_Datatype), INTENT(OUT) :: etype
                                                                                  34
    TYPE(MPI_Datatype), INTENT(OUT) :: filetype
                                                                                  35
    CHARACTER(LEN=*), INTENT(OUT) :: datarep
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  37 ticket-248T.
MPI_File_iread(fh, buf, count, datatype, request, ierror)
                                                                                  38
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Request), INTENT(OUT) :: request
                                                                                  43
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                    ticket-248T.
MPI_File_iread_at(fh, offset, buf, count, datatype, request, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
```

```
1
                   TYPE(*), DIMENSION(..) :: buf
           2
                   INTEGER, INTENT(IN) :: count
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   TYPE(MPI_Request), INTENT(OUT) ::
                   INTEGER, OPTIONAL, INTENT(OUT) ::
ticket-248T. _6
               MPI_File_iread_shared(fh, buf, count, datatype, request, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   TYPE(*), DIMENSION(..) :: buf
                   INTEGER, INTENT(IN) :: count
          10
                   TYPE(MPI_Datatype), INTENT(IN) ::
                                                       datatype
                   TYPE(MPI_Request), INTENT(OUT) :: request
          12
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. ^{13}
          14
               MPI_File_iwrite(fh, buf, count, datatype, request, ierror)
          15
                   TYPE(MPI_File), INTENT(IN) :: fh
          16
                   TYPE(*), DIMENSION(..) :: buf
          17
                   INTEGER, INTENT(IN) :: count
          18
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          19
                   TYPE(MPI_Request), INTENT(OUT) :: request
          20
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 21
               MPI_File_iwrite_at(fh, offset, buf, count, datatype, request, ierror)
          22
                   TYPE(MPI_File), INTENT(IN) :: fh
          23
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          24
                   TYPE(*), DIMENSION(..) :: buf
                   INTEGER, INTENT(IN) :: count
          26
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          27
                   TYPE(MPI_Request), INTENT(OUT) :: request
          28
                   INTEGER, OPTIONAL, INTENT(OUT) ::
ticket-248T. ^{^{29}}
               MPI_File_iwrite_shared(fh, buf, count, datatype, request, ierror)
                   TYPE(*), DIMENSION(..) :: buf
                   TYPE(MPI_File), INTENT(IN) :: fh
          33
                   INTEGER, INTENT(IN) :: count
          34
                   TYPE(MPI_Datatype), INTENT(IN) ::
          35
                   TYPE(MPI_Request), INTENT(OUT) ::
                   INTEGER, OPTIONAL, INTENT(OUT) ::
ticket-248T. 37
               MPI_File_open(comm, filename, amode, info, fh, ierror)
          38
                   TYPE(MPI_Comm), INTENT(IN) :: comm
                   CHARACTER(LEN=*), INTENT(IN) :: filename
                   INTEGER, INTENT(IN) :: amode
                   TYPE(MPI_Info), INTENT(IN) :: info
                   TYPE(MPI_File), INTENT(OUT) :: fh
          43
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          45
               MPI_File_preallocate(fh, size, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
          47
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                <sub>2</sub> ticket-248T.
MPI_File_read(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 ticket-248T.
MPI_File_read_all(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
                                                                                12
                                                                                13
    INTEGER, INTENT(IN) :: count
                                                                                14
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                15
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                <sub>17</sub> ticket-248T.
MPI_File_read_all_begin(fh, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                19
    TYPE(*), DIMENSION(..) :: buf
                                                                                20
    INTEGER, INTENT(IN) :: count
                                                                                21
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                               ^{23} ticket-248T.
MPI_File_read_all_end(fh, buf, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
                                                                                27
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                29 ticket-248T.
MPI_File_read_at(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                35
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_File_read_at_all(fh, offset, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
                                                                                43
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                46 ticket-248T.
MPI_File_read_at_all_begin(fh, offset, buf, count, datatype, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
```

```
1
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          2
                   TYPE(*), DIMENSION(..) :: buf
                   INTEGER, INTENT(IN) :: count
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER, OPTIONAL, INTENT(OUT) ::
ticket-248T. _6
               MPI_File_read_at_all_end(fh, buf, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   TYPE(*), DIMENSION(..) :: buf
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          10
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          12
               MPI_File_read_ordered(fh, buf, count, datatype, status, ierror)
          13
                   TYPE(MPI_File), INTENT(IN) :: fh
          14
                   TYPE(*), DIMENSION(..) :: buf
          15
                   INTEGER, INTENT(IN) :: count
          16
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          17
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 19
               MPI_File_read_ordered_begin(fh, buf, count, datatype, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
          21
                   TYPE(*), DIMENSION(..) :: buf
          22
                   INTEGER, INTENT(IN) :: count
          23
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          24
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
          26
               MPI_File_read_ordered_end(fh, buf, status, ierror)
          27
                   TYPE(MPI_File), INTENT(IN) :: fh
          28
                   TYPE(*), DIMENSION(..) :: buf
          29
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 31
               MPI_File_read_shared(fh, buf, count, datatype, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   TYPE(*), DIMENSION(..) :: buf
          34
                   INTEGER, INTENT(IN) :: count
          35
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          36
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          37
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_File_seek(fh, offset, whence, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
                   INTEGER, INTENT(IN) :: whence
          43
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 44
               MPI_File_seek_shared(fh, offset, whence, ierror)
          45
                   TYPE(MPI_File), INTENT(IN) :: fh
          46
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          47
                   INTEGER, INTENT(IN) :: whence
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 <sub>2</sub> ticket-248T.
MPI_File_set_atomicity(fh, flag, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    LOGICAL, INTENT(IN) :: flag
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_File_set_info(fh, info, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(MPI_Info), INTENT(IN) :: info
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                 11 ticket-248T.
MPI_File_set_size(fh, size, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                13
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: size
                                                                                14
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                ^{^{15}} ticket-248T.
MPI_File_set_view(fh, disp, etype, filetype, datarep, info, ierror)
                                                                                 17
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: disp
                                                                                 19
    TYPE(MPI_Datatype), INTENT(IN) :: etype
                                                                                20
    TYPE(MPI_Datatype), INTENT(IN) :: filetype
                                                                                21
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                22
    TYPE(MPI_Info), INTENT(IN) :: info
                                                                                23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                24 ticket-248T.
MPI_File_sync(fh, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                  ticket-248T.
MPI_File_write(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                35 ticket-248T.
MPI_File_write_all(fh, buf, count, datatype, status, ierror)
                                                                                36
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                37
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   ticket-248T.
MPI_File_write_all_begin(fh, buf, count, datatype, ierror)
                                                                                44
    TYPE(MPI_File), INTENT(IN) :: fh
                                                                                 45
    TYPE(*), DIMENSION(..) :: buf
    INTEGER, INTENT(IN) :: count
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
```

```
INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 2
               MPI_File_write_all_end(fh, buf, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   TYPE(*), DIMENSION(..) :: buf
          5
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_File_write_at(fh, offset, buf, count, datatype, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
          10
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          11
                   TYPE(*), DIMENSION(..) :: buf
          12
                   INTEGER, INTENT(IN) :: count
          13
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          14
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          15
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 16
               MPI_File_write_at_all(fh, offset, buf, count, datatype, status, ierror)
          17
                   TYPE(MPI_File), INTENT(IN) :: fh
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          19
                   TYPE(*), DIMENSION(..) :: buf
          20
                   INTEGER, INTENT(IN) :: count
          21
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          22
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          23
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_File_write_at_all_begin(fh, offset, buf, count, datatype, ierror)
          26
                   TYPE(MPI_File), INTENT(IN) :: fh
          27
                   INTEGER(KIND=MPI_OFFSET_KIND), INTENT(IN) :: offset
          28
                   TYPE(*), DIMENSION(..) :: buf
                   INTEGER, INTENT(IN) :: count
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 32
               MPI_File_write_at_all_end(fh, buf, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
          34
                   TYPE(*), DIMENSION(..) :: buf
          35
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
          36
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
               MPI_File_write_ordered(fh, buf, count, datatype, status, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
                   TYPE(*), DIMENSION(..) :: buf
          41
                   INTEGER, INTENT(IN) :: count
          42
                   TYPE(MPI_Datatype), INTENT(IN) :: datatype
          43
                   TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
                   INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. 45
               MPI_File_write_ordered_begin(fh, buf, count, datatype, ierror)
                   TYPE(MPI_File), INTENT(IN) :: fh
          47
                   TYPE(*), DIMENSION(..) :: buf
```

```
INTEGER, INTENT(IN) :: count
                                                                                   2
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   _4 ticket-248T.
MPI_File_write_ordered_end(fh, buf, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                     ticket-248T.
MPI_File_write_shared(fh, buf, count, datatype, status, ierror)
    TYPE(MPI_File), INTENT(IN) :: fh
    TYPE(*), DIMENSION(..) :: buf
                                                                                   12
                                                                                   13
    INTEGER, INTENT(IN) :: count
                                                                                   14
    TYPE(MPI_Datatype), INTENT(IN) :: datatype
                                                                                   15
    TYPE(MPI_Status), INTENT(OUT) :: status ! optional by overloading
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   <sub>17</sub> ticket-248T.
MPI_Register_datarep(datarep, read_conversion_fn, write_conversion_fn,
              dtype_file_extent_fn, extra_state, ierror)
                                                                                   19
    CHARACTER(LEN=*), INTENT(IN) :: datarep
                                                                                   20
    EXTERNAL :: read_conversion_fn, write_conversion_fn,
                                                                                   21
    dtype_file_extent_fn
                                                                                   22
    INTEGER(KIND=MPI_ADDRESS_KIND), INTENT(IN) :: extra_state
                                                                                   23
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   24
                                                                                   25
A.4.12 Language Bindings Fortran 2008 Bindings
                                                                                   <sup>27</sup> ticket-248T.
MPI_F_sync_reg(buf)
                                                                                   28
    TYPE(*), DIMENSION(..) :: buf
                                                                                     ticket-248T.
MPI_Sizeof(x, size, ierror)
                                                                                   31
    TYPE(*) :: x
                                                                                   32
    INTEGER, INTENT(OUT) :: size
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   <sup>34</sup> ticket-248T.
MPI_Status_f082f(f08_status, f_status, ierror)
    TYPE(MPI_Status) :: f08_status
                                                                                   36
    INTEGER :: f_status(MPI_STATUS_SIZE)
    INTEGER, OPTIONAL :: ierror
                                                                                   _{39} ticket-248T.
MPI_Status_f2f08(f_status, f08_status, ierror)
    INTEGER f_status(MPI_STATUS_SIZE)
    TYPE(MPI_Status) :: f08_status
    INTEGER, OPTIONAL :: ierror
                                                                                   <sup>43</sup> ticket-248T.
MPI_Type_create_f90_complex(p, r, newtype, ierror)
    INTEGER, INTENT(IN) :: p, r
                                                                                   45
    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
                                                                                   _{48} ticket-248T.
```

```
1
               MPI_Type_create_f90_integer(r, newtype, ierror)
           2
                    INTEGER, INTENT(IN) :: r
           3
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T. _5
               MPI_Type_create_f90_real(p, r, newtype, ierror)
                    INTEGER, INTENT(IN) :: p, r
           7
                    TYPE(MPI_Datatype), INTENT(OUT) :: newtype
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
ticket-248T.
                MPI_Type_match_size(typeclass, size, datatype, ierror)
           11
                    INTEGER, INTENT(IN) :: typeclass, size
          12
                    TYPE(MPI_Datatype), INTENT(OUT) :: datatype
           13
                    INTEGER, OPTIONAL, INTENT(OUT) :: ierror
           14
           15
                A.4.13 Profiling Interface Fortran 2008 Bindings
ticket-248T.
           17
               MPI_Pcontrol(level)
                    INTEGER, INTENT(IN) :: level
           19
          20
          21
                A.4.14
                        Deprecated Fortran 2008 Bindings
          22
          23
          24
           26
```

```
ticket 252-W. <sup>1</sup>
                  {void Op::Init(User_function* [function]user_fn, bool commute)(binding
                               deprecated, see Section 15.2) }
                   {Request Comm::Ireduce(const void* sendbuf, void* recvbuf, int count,
                               const Datatype& datatype, const Op& op, int root)
                               const = 0(binding deprecated, see Section 15.2) }
           6
                   {Request Comm:: Ireduce_scatter(const void* sendbuf, void* recvbuf,
                               int recvcounts[], const Datatype& datatype, const Op& op)
           9
                               const = 0(binding deprecated, see Section 15.2) }
           10
                   {Request Comm::Ireduce_scatter_block(const void* sendbuf, void* recvbuf,
           11
                               int recvcount, const Datatype& datatype, const Op& op)
           12
                               const = 0(binding deprecated, see Section 15.2) }
           13
           14
                  {bool Op::Is_commutative() const(binding deprecated, see Section 15.2)}
           15
                   {Request Intracomm::Iscan(const void* sendbuf, void* recvbuf, int count,
           16
                               const Datatype& datatype, const Op& op) const(binding deprecated,
                               see Section 15.2)
           18
           19
                   {Request Comm::Iscatter(const void* sendbuf, int sendcount, const
           20
                               Datatype& sendtype, void* recvbuf, int recvcount,
           21
                               const Datatype& recvtype, int root) const = 0(binding deprecated,
           22
                               see Section 15.2) }
           23
                  {Request Comm::Iscatterv(const void* sendbuf, const int sendcounts[],
           24
                               const int displs[], const Datatype& sendtype, void* recvbuf,
                               int recvcount, const Datatype& recvtype, int root)
           26
                               const = 0(binding deprecated, see Section 15.2) }
           27
           28
                   {void Comm::Reduce(const void* sendbuf, void* recvbuf, int count,
           29
                               const Datatype& datatype, const Op& op, int root)
           30
                               const = 0(binding deprecated, see Section 15.2) }
           31
                  {void Op::Reduce_local(const void* inbuf, void* inoutbuf, int count,
                               const Datatype& datatype) const(binding deprecated, see
           33
                               Section 15.2) }
           34
           35
                   {void Comm::Reduce_scatter(const void* sendbuf, void* recvbuf,
           36
                               int recvcounts[], const Datatype& datatype, const Op& op)
           37
                               const = 0(binding deprecated, see Section 15.2) }
                  {void Comm::Reduce_scatter_block(const void* sendbuf, void* recvbuf,
           39
                               int recvcount, const Datatype& datatype, const Op& op)
                               const = 0(binding deprecated, see Section 15.2) }
           41
           42
                  {void Intracomm::Scan(const void* sendbuf, void* recvbuf, int count,
           43
                               const Datatype& datatype, const Op& op) const(binding deprecated,
           44
                               see Section 15.2) }
           45
                  {void Comm::Scatter(const void* sendbuf, int sendcount, const
           46
           47
                               Datatype& sendtype, void* recvbuf, int recvcount,
                               const Datatype& recvtype, int root) const = 0(binding deprecated,
```

```
{static Errhandler Comm::Create_errhandler(Comm::Errhandler_function*
ticket252-W. <sup>2</sup>
                                 [function] comm_errhandler_fn) (binding deprecated, see Section 15.2) }
                    {static Errhandler File::Create_errhandler(File::Errhandler_function*
ticket252-W.
                                 [function] file_errhandler_fn) (binding deprecated, see Section 15.2) }
                    {static Errhandler Win::Create_errhandler(Win::Errhandler_function*
ticket252-W.
                                 [function]win_errhandler_fn) (binding deprecated, see Section 15.2) }
                    {void Finalize() (binding deprecated, see Section 15.2) }
            10
                    {void Errhandler::Free()(binding deprecated, see Section 15.2)}
            11
                    {void Free_mem(void *base) (binding deprecated, see Section 15.2) }
            12
            13
                    \{ \texttt{Errhandler Comm::Get\_errhandler() const}(binding deprecated, see Section 15.2) \}
            14
                    {Errhandler File::Get_errhandler() const(binding deprecated, see Section 15.2)}
            15
            16
                    \{\text{Errhandler Win}: \text{Get\_errhandler}() \ \text{const}(binding \ deprecated, see \ Section \ 15.2) \}
            17
                    {int Get_error_class(int errorcode)(binding deprecated, see Section 15.2)}
            18
            19
                    {void Get_error_string(int errorcode, char* name, int& resultlen)(binding
            20
                                 deprecated, see Section 15.2) }
            21
                    {void Get_processor_name(char* name, int& resultlen)(binding deprecated, see
            22
                                 Section 15.2) }
            23
            24
                    {void Get_version(int& version, int& subversion)(binding deprecated, see
            25
                                 Section 15.2) }
            26
                    {void Init()(binding deprecated, see Section 15.2)}
            27
            28
                    {void Init(int& argc, char**& argv)(binding deprecated, see Section 15.2)}
            29
            30
                    {bool Is_finalized() (binding deprecated, see Section 15.2) }
            31
                    {bool Is_initialized()(binding deprecated, see Section 15.2)}
            32
            33
                    {void Comm::Set_errhandler(const Errhandler& errhandler)(binding deprecated,
            34
                                 see Section 15.2) }
            35
                    {void File::Set_errhandler(const Errhandler& errhandler)(binding deprecated,
            36
                                 see Section 15.2) }
            37
                    {void Win::Set_errhandler(const Errhandler& errhandler)(binding deprecated,
            39
                                 see Section 15.2) }
                    {double Wtick() (binding deprecated, see Section 15.2) }
            41
            42
                    {double Wtime() (binding deprecated, see Section 15.2) }
            43
            44
                  };
            45
            46
                         The Info Object C++ Bindings
            47
            48
                  namespace MPI {
```