MPI for Python

Release 4.0.1

Lisandro Dalcin

Oct 11, 2024

Contents

1	Introduction 1.1 What is MPI? 1.2 What is Python? 1.3 Related Projects	3 4 4 4
2	Overview 2.1 Communicating Python Objects and Array Data 2.2 Communicators 2.3 Point-to-Point Communications 2.4 Collective Communications 2.5 Support for GPU-aware MPI	5 6 6 7 8 8
	2.9 Environmental Management	9 10 10
3	3.1 Running Python scripts with MPI 3.2 Point-to-Point Communication 3.3 Collective Communication 3.4 Input/Output (MPI-IO) 3.5 Dynamic Process Management 3.6 GPU-aware MPI + Python GPU arrays 3.7 One-Sided Communication (RMA) 3.8 Wrapping with SWIG	11 13 14 16 17 18 18 20 20
4	4.1 Runtime configuration options	21 21 24 27
5	5.1 Classes 5.2 Functions	28 28 29

6	mpi4py.typing	37
7	mpi4py.futures 7.1 MPIPoolExecutor 7.2 MPICommExecutor 7.3 Command line 7.4 Parallel tasks 7.5 Utilities 7.6 Examples 7.7 Citation	40 41 44 45 46 46 47 50
8	mpi4py.util 8.1 mpi4py.util.dtlib 8.2 mpi4py.util.pkl5 8.3 mpi4py.util.pool 8.4 mpi4py.util.sync	50 50 51 58 62
9	mpi4py.run 9.1 Exceptions and deadlocks	70 70 71
10	mpi4py.bench	71
11	Reference11.1 mpi4py.MPI	71 71
12	Citation	243
13	Installation 13.1 Build backends	246 246 247 248
	14.1 Prerequisites	249 250
13		250 250
16	LICENSE	252
17		254 255 255 255 255

17.9 Release 3.1.0 [2021-08-12]	256
17.10Release 3.0.3 [2019-11-04]	257
17.11Release 3.0.2 [2019-06-11]	257
17.12Release 3.0.1 [2019-02-15]	257
17.13Release 3.0.0 [2017-11-08]	257
17.14Release 2.0.0 [2015-10-18]	258
17.15Release 1.3.1 [2013-08-07]	259
17.16Release 1.3 [2012-01-20]	259
17.17Release 1.2.2 [2010-09-13]	260
17.18Release 1.2.1 [2010-02-26]	260
17.19Release 1.2 [2009-12-29]	260
17.20Release 1.1.0 [2009-06-06]	261
17.21Release 1.0.0 [2009-03-20]	261
References	262
Python Module Index	263
Index	264

Abstract

MPI for Python provides Python bindings for the Message Passing Interface (MPI) standard, allowing Python applications to exploit multiple processors on workstations, clusters and supercomputers.

This package builds on the MPI specification and provides an object oriented interface resembling the MPI-2 C++ bindings. It supports point-to-point (sends, receives) and collective (broadcasts, scatters, gathers) communication of any *picklable* Python object, as well as efficient communication of Python objects exposing the Python buffer interface (e.g. NumPy arrays and builtin bytes/array/memoryview objects).

1 Introduction

Over the last years, high performance computing has become an affordable resource to many more researchers in the scientific community than ever before. The conjunction of quality open source software and commodity hardware strongly influenced the now widespread popularity of Beowulf class clusters and cluster of workstations.

Among many parallel computational models, message-passing has proven to be an effective one. This paradigm is specially suited for (but not limited to) distributed memory architectures and is used in today's most demanding scientific and engineering application related to modeling, simulation, design, and signal processing. However, portable message-passing parallel programming used to be a nightmare in the past because of the many incompatible options developers were faced to. Fortunately, this situation definitely changed after the MPI Forum released its standard specification.

High performance computing is traditionally associated with software development using compiled languages. However, in typical applications programs, only a small part of the code is time-critical enough to require the efficiency of compiled languages. The rest of the code is generally related to memory management, error handling, input/output, and user interaction, and those are usually the most error prone and time-consuming lines of code to write and debug in the whole development process. Interpreted high-level languages can be really advantageous for this kind of tasks.

For implementing general-purpose numerical computations, MATLAB¹ is the dominant interpreted programming language. In the open source side, Octave and Scilab are well known, freely distributed software packages providing compatibility with the MATLAB language. In this work, we present MPI for Python, a new package enabling applications to exploit multiple processors using standard MPI "look and feel" in Python scripts.

1.1 What is MPI?

MPI, [mpi-using] [mpi-ref] the *Message Passing Interface*, is a standardized and portable message-passing system designed to function on a wide variety of parallel computers. The standard defines the syntax and semantics of library routines and allows users to write portable programs in the main scientific programming languages (Fortran, C, or C++).

Since its release, the MPI specification [mpi-std1] [mpi-std2] has become the leading standard for message-passing libraries for parallel computers. Implementations are available from vendors of high-performance computers and from well known open source projects like MPICH [mpi-mpich] and Open MPI [mpi-openmpi].

1.2 What is Python?

Python is a modern, easy to learn, powerful programming language. It has efficient high-level data structures and a simple but effective approach to object-oriented programming with dynamic typing and dynamic binding. It supports modules and packages, which encourages program modularity and code reuse. Python's elegant syntax, together with its interpreted nature, make it an ideal language for scripting and rapid application development in many areas on most platforms.

The Python interpreter and the extensive standard library are available in source or binary form without charge for all major platforms, and can be freely distributed. It is easily extended with new functions and data types implemented in C or C++. Python is also suitable as an extension language for customizable applications.

Python is an ideal candidate for writing the higher-level parts of large-scale scientific applications [Hinsen97] and driving simulations in parallel architectures [Beazley97] like clusters of PC's or SMP's. Python codes are quickly developed, easily maintained, and can achieve a high degree of integration with other libraries written in compiled languages.

1.3 Related Projects

As this work started and evolved, some ideas were borrowed from well known MPI and Python related open source projects from the Internet.

• OOMPI

- It has no relation with Python, but is an excellent object oriented approach to MPI.
- It is a C++ class library specification layered on top of the C bindings that encapsulates MPI into a functional class hierarchy.
- It provides a flexible and intuitive interface by adding some abstractions, like *Ports* and *Messages*, which enrich and simplify the syntax.

• Pypar

- Its interface is rather minimal. There is no support for communicators or process topologies.
- It does not require the Python interpreter to be modified or recompiled, but does not permit interactive parallel runs.

¹ MATLAB is a registered trademark of The MathWorks, Inc.

- General (*picklable*) Python objects of any type can be communicated. There is good support for numeric arrays, practically full MPI bandwidth can be achieved.

• pyMPI

- It rebuilds the Python interpreter providing a built-in module for message passing. It does permit interactive parallel runs, which are useful for learning and debugging.
- It provides an interface suitable for basic parallel programming. There is not full support for defining new communicators or process topologies.
- General (picklable) Python objects can be messaged between processors. There is native support for numeric arrays.

· Scientific Python

- It provides a collection of Python modules that are useful for scientific computing.
- There is an interface to MPI and BSP (Bulk Synchronous Parallel programming).
- The interface is simple but incomplete and does not resemble the MPI specification. There is support for numeric arrays.

Additionally, we would like to mention some available tools for scientific computing and software development with Python.

- NumPy is a package that provides array manipulation and computational capabilities similar to those found in IDL, MATLAB, or Octave. Using NumPy, it is possible to write many efficient numerical data processing applications directly in Python without using any C, C++ or Fortran code.
- SciPy is an open source library of scientific tools for Python, gathering a variety of high level science and engineering modules together as a single package. It includes modules for graphics and plotting, optimization, integration, special functions, signal and image processing, genetic algorithms, ODE solvers, and others.
- Cython is a language that makes writing C extensions for the Python language as easy as Python itself. The Cython language is very close to the Python language, but Cython additionally supports calling C functions and declaring C types on variables and class attributes. This allows the compiler to generate very efficient C code from Cython code. This makes Cython the ideal language for wrapping for external C libraries, and for fast C modules that speed up the execution of Python code.
- SWIG is a software development tool that connects programs written in C and C++ with a variety of high-level programming languages like Perl, Tcl/Tk, Ruby and Python. Issuing header files to SWIG is the simplest approach to interfacing C/C++ libraries from a Python module.

2 Overview

MPI for Python provides an object oriented approach to message passing which grounds on the standard MPI-2 C++ bindings. The interface was designed with focus in translating MPI syntax and semantics of standard MPI-2 bindings for C++ to Python. Any user of the standard C/C++ MPI bindings should be able to use this module without need of learning a new interface.

2.1 Communicating Python Objects and Array Data

The Python standard library supports different mechanisms for data persistence. Many of them rely on disk storage, but *pickling* and *marshaling* can also work with memory buffers.

The pickle modules provide user-extensible facilities to serialize general Python objects using ASCII or binary formats. The marshal module provides facilities to serialize built-in Python objects using a binary format specific to Python, but independent of machine architecture issues.

MPI for Python can communicate any built-in or user-defined Python object taking advantage of the features provided by the pickle module. These facilities will be routinely used to build binary representations of objects to communicate (at sending processes), and restoring them back (at receiving processes).

Although simple and general, the serialization approach (i.e., *pickling* and *unpickling*) previously discussed imposes important overheads in memory as well as processor usage, especially in the scenario of objects with large memory footprints being communicated. Pickling general Python objects, ranging from primitive or container built-in types to user-defined classes, necessarily requires computer resources. Processing is also needed for dispatching the appropriate serialization method (that depends on the type of the object) and doing the actual packing. Additional memory is always needed, and if its total amount is not known *a priori*, many reallocations can occur. Indeed, in the case of large numeric arrays, this is certainly unacceptable and precludes communication of objects occupying half or more of the available memory resources.

MPI for Python supports direct communication of any object exporting the single-segment buffer interface. This interface is a standard Python mechanism provided by some types (e.g., strings and numeric arrays), allowing access in the C side to a contiguous memory buffer (i.e., address and length) containing the relevant data. This feature, in conjunction with the capability of constructing user-defined MPI datatypes describing complicated memory layouts, enables the implementation of many algorithms involving multidimensional numeric arrays (e.g., image processing, fast Fourier transforms, finite difference schemes on structured Cartesian grids) directly in Python, with negligible overhead, and almost as fast as compiled Fortran, C, or C++ codes.

2.2 Communicators

In MPI for Python, Comm is the base class of communicators. The Intracomm and Intercomm classes are subclasses of the Comm class. The Comm. Is_inter method (and Comm. Is_intra, provided for convenience but not part of the MPI specification) is defined for communicator objects and can be used to determine the particular communicator class.

The two predefined intracommunicator instances are available: COMM_SELF and COMM_WORLD. From them, new communicators can be created as needed.

The number of processes in a communicator and the calling process rank can be respectively obtained with methods <code>Comm.Get_size</code> and <code>Comm.Get_rank</code>. The associated process group can be retrieved from a communicator by calling the <code>Comm.Get_group</code> method, which returns an instance of the <code>Group</code> class. Set operations with <code>Group</code> objects like <code>like Group.Union</code>, <code>Group.Intersection</code> and <code>Group.Difference</code> are fully supported, as well as the creation of new communicators from these groups using <code>Comm.Create</code> and <code>Intracomm.Create_group</code>.

New communicator instances can be obtained with the *Comm.Clone*, *Comm.Dup* and *Comm.Split* methods, as well methods *Intracomm.Create_intercomm* and *Intercomm.Merge*.

Virtual topologies (*Cartcomm*, *Graphcomm* and *Distgraphcomm* classes, which are specializations of the *Intracomm* class) are fully supported. New instances can be obtained from intracommunicator instances with factory methods *Intracomm.Create_cart* and *Intracomm.Create_graph*.

2.3 Point-to-Point Communications

Point to point communication is a fundamental capability of message passing systems. This mechanism enables the transmission of data between a pair of processes, one side sending, the other receiving.

MPI provides a set of *send* and *receive* functions allowing the communication of *typed* data with an associated *tag*. The type information enables the conversion of data representation from one architecture to another in the case of heterogeneous computing environments; additionally, it allows the representation of non-contiguous data layouts and user-defined datatypes, thus avoiding the overhead of (otherwise unavoidable) packing/unpacking operations. The tag information allows selectivity of messages at the receiving end.

Blocking Communications

MPI provides basic send and receive functions that are *blocking*. These functions block the caller until the data buffers involved in the communication can be safely reused by the application program.

In MPI for Python, the Comm.Send, Comm.Recv and Comm.Sendrecv methods of communicator objects provide support for blocking point-to-point communications within Intracomm and Intercomm instances. These methods can communicate memory buffers. The variants Comm.send, Comm.recv and Comm.sendrecv can communicate general Python objects.

Nonblocking Communications

On many systems, performance can be significantly increased by overlapping communication and computation. This is particularly true on systems where communication can be executed autonomously by an intelligent, dedicated communication controller.

MPI provides *nonblocking* send and receive functions. They allow the possible overlap of communication and computation. Non-blocking communication always come in two parts: posting functions, which begin the requested operation; and test-for-completion functions, which allow to discover whether the requested operation has completed.

In MPI for Python, the Comm. Isend and Comm. Irecv methods initiate send and receive operations, respectively. These methods return a Request instance, uniquely identifying the started operation. Its completion can be managed using the Request. Test, Request. Wait and Request. Cancel methods. The management of Request objects and associated memory buffers involved in communication requires a careful, rather low-level coordination. Users must ensure that objects exposing their memory buffers are not accessed at the Python level while they are involved in nonblocking message-passing operations.

Persistent Communications

Often a communication with the same argument list is repeatedly executed within an inner loop. In such cases, communication can be further optimized by using persistent communication, a particular case of nonblocking communication allowing the reduction of the overhead between processes and communication controllers. Furthermore, this kind of optimization can also alleviate the extra call overheads associated to interpreted, dynamic languages like Python.

In MPI for Python, the Comm.Send_init and Comm.Recv_init methods create persistent requests for a send and receive operation, respectively. These methods return an instance of the Prequest class, a subclass of the Request class. The actual communication can be effectively started using the Prequest.Start method, and its completion can be managed as previously described.

2.4 Collective Communications

Collective communications allow the transmittal of data between multiple processes of a group simultaneously. The syntax and semantics of collective functions is consistent with point-to-point communication. Collective functions communicate *typed* data, but messages are not paired with an associated *tag*; selectivity of messages is implied in the calling order. Additionally, collective functions come in blocking versions only.

The more commonly used collective communication operations are the following.

- Barrier synchronization across all group members.
- Global communication functions
 - Broadcast data from one member to all members of a group.
 - Gather data from all members to one member of a group.
 - Scatter data from one member to all members of a group.
- Global reduction operations such as sum, maximum, minimum, etc.

In MPI for Python, the Comm.Bcast, Comm.Scatter, Comm.Gather, Comm.Allgather, Comm.Alltoall methods provide support for collective communications of memory buffers. The lower-case variants Comm.bcast, Comm. scatter, Comm.gather, Comm.allgather and Comm.alltoall can communicate general Python objects. The vector variants (which can communicate different amounts of data to each process) Comm.Scatterv, Comm.Gatherv, Comm.Alltoallv and Comm.Alltoallw are also supported, they can only communicate objects exposing memory buffers.

Global reduction operations on memory buffers are accessible through the <code>Comm.Reduce</code>, <code>Comm.Reduce</code>, <code>Comm.Reduce</code>, <code>Intracomm.Scan</code> and <code>Intracomm.Exscan</code> methods. The lower-case variants <code>Comm.reduce</code>, <code>Comm.allreduce</code>, <code>Intracomm.scan</code> and <code>Intracomm.exscan</code> can communicate general Python objects; however, the actual required reduction computations are performed sequentially at some process. All the predefined (i.e., <code>SUM</code>, <code>PROD</code>, <code>MAX</code>, etc.) reduction operations can be applied.

2.5 Support for GPU-aware MPI

Several MPI implementations, including Open MPI and MVAPICH, support passing GPU pointers to MPI calls to avoid explicit data movement between host and device. On the Python side, support for handling GPU arrays have been implemented in many libraries related GPU computation such as CuPy, Numba, PyTorch, and PyArrow. To maximize interoperability across library boundaries, two kinds of zero-copy data exchange protocols have been defined and agreed upon: DLPack and CUDA Array Interface (CAI).

MPI for Python provides an experimental support for GPU-aware MPI. This feature requires:

- 1. mpi4py is built against a GPU-aware MPI library.
- 2. The Python GPU arrays are compliant with either of the protocols.

See the *Tutorial* section for further information. We note that

- Whether or not a MPI call can work for GPU arrays depends on the underlying MPI implementation, not on mpi4py.
- This support is currently experimental and subject to change in the future.

2.6 Dynamic Process Management

In the context of the MPI-1 specification, a parallel application is static; that is, no processes can be added to or deleted from a running application after it has been started. Fortunately, this limitation was addressed in MPI-2. The new specification added a process management model providing a basic interface between an application and external resources and process managers.

This MPI-2 extension can be really useful, especially for sequential applications built on top of parallel modules, or parallel applications with a client/server model. The MPI-2 process model provides a mechanism to create new processes and establish communication between them and the existing MPI application. It also provides mechanisms to establish communication between two existing MPI applications, even when one did not *start* the other.

In MPI for Python, new independent process groups can be created by calling the Intracomm. Spawn method within an intracommunicator. This call returns a new intercommunicator (i.e., an Intercomm instance) at the parent process group. The child process group can retrieve the matching intercommunicator by calling the Comm. Get_parent class method. At each side, the new intercommunicator can be used to perform point to point and collective communications between the parent and child groups of processes.

Alternatively, disjoint groups of processes can establish communication using a client/server approach. Any server application must first call the <code>Open_port</code> function to open a <code>port</code> and the <code>Publish_name</code> function to publish a provided <code>service</code>, and next call the <code>Intracomm.Accept</code> method. Any client applications can first find a published <code>service</code> by calling the <code>Lookup_name</code> function, which returns the <code>port</code> where a server can be contacted; and next call the <code>Intracomm.Connect</code> method. Both <code>Intracomm.Accept</code> and <code>Intracomm.Connect</code> methods return an <code>Intercomm</code> instance. When connection between client/server processes is no longer needed, all of them must cooperatively call the <code>Comm.Disconnect</code> method. Additionally, server applications should release resources by calling the <code>Unpublish_name</code> and <code>Close_port</code> functions.

2.7 One-Sided Communications

One-sided communications (also called *Remote Memory Access*, *RMA*) supplements the traditional two-sided, send/receive based MPI communication model with a one-sided, put/get based interface. One-sided communication that can take advantage of the capabilities of highly specialized network hardware. Additionally, this extension lowers latency and software overhead in applications written using a shared-memory-like paradigm.

The MPI specification revolves around the use of objects called *windows*; they intuitively specify regions of a process's memory that have been made available for remote read and write operations. The published memory blocks can be accessed through three functions for put (remote send), get (remote write), and accumulate (remote update or reduction) data items. A much larger number of functions support different synchronization styles; the semantics of these synchronization operations are fairly complex.

In MPI for Python, one-sided operations are available by using instances of the Win class. New window objects are created by calling the Win. Create method at all processes within a communicator and specifying a memory buffer . When a window instance is no longer needed, the Win. Free method should be called.

The three one-sided MPI operations for remote write, read and reduction are available through calling the methods *Win.Put*, *Win.Get*, and *Win.Accumulate* respectively within a *Win* instance. These methods need an integer rank identifying the target process and an integer offset relative the base address of the remote memory block being accessed.

The one-sided operations read, write, and reduction are implicitly nonblocking, and must be synchronized by using two primary modes. Active target synchronization requires the origin process to call the <code>Win.Start</code> and <code>Win.Complete</code> methods at the origin process, and target process cooperates by calling the <code>Win.Post</code> and <code>Win.Wait</code> methods. There is also a collective variant provided by the <code>Win.Fence</code> method. Passive target synchronization is more lenient, only the origin process calls the <code>Win.Lock</code> and <code>Win.Unlock</code> methods. Locks are used to protect remote accesses to the locked remote window and to protect local load/store accesses to a locked local window.

2.8 Parallel Input/Output

The POSIX standard provides a model of a widely portable file system. However, the optimization needed for parallel input/output cannot be achieved with this generic interface. In order to ensure efficiency and scalability, the underlying parallel input/output system must provide a high-level interface supporting partitioning of file data among processes and a collective interface supporting complete transfers of global data structures between process memories and files. Additionally, further efficiencies can be gained via support for asynchronous input/output, strided accesses to data, and control over physical file layout on storage devices. This scenario motivated the inclusion in the MPI-2 standard of a custom interface in order to support more elaborated parallel input/output operations.

The MPI specification for parallel input/output revolves around the use objects called *files*. As defined by MPI, files are not just contiguous byte streams. Instead, they are regarded as ordered collections of *typed* data items. MPI supports sequential or random access to any integral set of these items. Furthermore, files are opened collectively by a group of processes.

The common patterns for accessing a shared file (broadcast, scatter, gather, reduction) is expressed by using user-defined datatypes. Compared to the communication patterns of point-to-point and collective communications, this approach has the advantage of added flexibility and expressiveness. Data access operations (read and write) are defined for different kinds of positioning (using explicit offsets, individual file pointers, and shared file pointers), coordination (non-collective and collective), and synchronism (blocking, nonblocking, and split collective with begin/end phases).

In *MPI for Python*, all MPI input/output operations are performed through instances of the *File* class. File handles are obtained by calling the *File.Open* method at all processes within a communicator and providing a file name and the intended access mode. After use, they must be closed by calling the *File.Close* method. Files even can be deleted by calling method *File.Delete*.

After creation, files are typically associated with a per-process *view*. The view defines the current set of data visible and accessible from an open file as an ordered set of elementary datatypes. This data layout can be set and queried with the *File.Set_view* and *File.Get_view* methods respectively.

Actual input/output operations are achieved by many methods combining read and write calls with different behavior regarding positioning, coordination, and synchronism. Summing up, *MPI for Python* provides the thirty (30) methods defined in MPI-2 for reading from or writing to files using explicit offsets or file pointers (individual or shared), in blocking or nonblocking and collective or noncollective versions.

2.9 Environmental Management

Initialization and Exit

Module functions *Init* or *Init_thread* and *Finalize* provide MPI initialization and finalization respectively. Module functions *Is_initialized* and *Is_finalized* provide the respective tests for initialization and finalization.

Note

MPI_Init() or MPI_Init_thread() is actually called when you import the MPI module from the mpi4py package, but only if MPI is not already initialized. In such case, calling Init or Init_thread from Python is expected to generate an MPI error, and in turn an exception will be raised.

Note

MPI_Finalize() is registered (by using Python C/API function Py_AtExit()) for being automatically called when Python processes exit, but only if *mpi4py* actually initialized MPI. Therefore, there is no need to call *Finalize* from Python to ensure MPI finalization.

Implementation Information

- The MPI version number can be retrieved from module function *Get_version*. It returns a two-integer tuple (version, subversion).
- The Get_processor_name function can be used to access the processor name.
- The values of predefined attributes attached to the world communicator can be obtained by calling the Comm.
 Get_attr method within the COMM_WORLD instance.

Timers

MPI timer functionalities are available through the *Wtime* and *Wtick* functions.

Error Handling

In order to facilitate handle sharing with other Python modules interfacing MPI-based parallel libraries, the predefined MPI error handlers <code>ERRORS_RETURN</code> and <code>ERRORS_ARE_FATAL</code> can be assigned to and retrieved from communicators using methods <code>Comm.Set_errhandler</code> and <code>Comm.Get_errhandler</code>, and similarly for windows and files. New custom error handlers can be created with <code>Comm.Create_errhandler</code>.

When the predefined error handler *ERRORS_RETURN* is set, errors returned from MPI calls within Python code will raise an instance of the exception class *Exception*, which is a subclass of the standard Python exception RuntimeError.

Note

After import, mpi4py overrides the default MPI rules governing inheritance of error handlers. The *ERRORS_RETURN* error handler is set in the predefined *COMM_SELF* and *COMM_WORLD* communicators, as well as any new *Comm*, *Win*, or *File* instance created through mpi4py. If you ever pass such handles to C/C++/Fortran library code, it is recommended to set the *ERRORS_ARE_FATAL* error handler on them to ensure MPI errors do not pass silently.

Warning

Importing with from mpi4py.MPI import * will cause a name clashing with the standard Python Exception base class.

3 Tutorial

Warning

Under construction. Contributions very welcome!

Tip

Rolf Rabenseifner at HLRS developed a comprehensive MPI-3.1/4.0 course with slides and a large set of exercises including solutions. This material is available online for self-study. The slides and exercises show the C,

Fortran, and Python (mpi4py) interfaces. For performance reasons, most Python exercises use NumPy arrays and communication routines involving buffer-like objects.

Tip

Victor Eijkhout at TACC authored the book *Parallel Programming for Science and Engineering*. This book is available online in PDF and HTML formats. The book covers parallel programming with MPI and OpenMP in C/C++ and Fortran, and MPI in Python using mpi4py.

MPI for Python supports convenient, pickle-based communication of generic Python object as well as fast, near C-speed, direct array data communication of buffer-provider objects (e.g., NumPy arrays).

· Communication of generic Python objects

You have to use methods with **all-lowercase** names, like *Comm.send*, *Comm.recv*, *Comm.bcast*, *Comm. scatter*, *Comm.gather*. An object to be sent is passed as a parameter to the communication call, and the received object is simply the return value.

The *Comm.isend* and *Comm.irecv* methods return *Request* instances; completion of these methods can be managed using the *Request.test* and *Request.wait* methods.

The Comm. recv and Comm. irecv methods may be passed a buffer object that can be repeatedly used to receive messages avoiding internal memory allocation. This buffer must be sufficiently large to accommodate the transmitted messages; hence, any buffer passed to Comm. recv or Comm. irecv must be at least as long as the pickled data transmitted to the receiver.

Collective calls like *Comm.scatter*, *Comm.gather*, *Comm.allgather*, *Comm.alltoall* expect a single value or a sequence of *Comm.size* elements at the root or all process. They return a single value, a list of *Comm.size* elements, or None.

Note

MPI for Python uses the **highest** protocol version available in the Python runtime (see the HIGHEST_PROTOCOL constant in the pickle module). The default protocol can be changed at import time by setting the MPI4PY_PICKLE_PROTOCOL environment variable, or at runtime by assigning a different value to the PROTOCOL attribute of the pickle object within the MPI module.

· Communication of buffer-like objects

You have to use method names starting with an **upper-case** letter, like *Comm. Send*, *Comm. Recv*, *Comm. Bcast*, *Comm. Scatter*, *Comm. Gather*.

In general, buffer arguments to these calls must be explicitly specified by using a 2/3-list/tuple like [data, MPI. DOUBLE], or [data, count, MPI.DOUBLE] (the former one uses the byte-size of data and the extent of the MPI datatype to define count).

For vector collectives communication operations like *Comm. Scatterv* and *Comm. Gatherv*, buffer arguments are specified as [data, count, displ, datatype], where count and displ are sequences of integral values.

Automatic MPI datatype discovery for NumPy/GPU arrays and PEP-3118 buffers is supported, but limited to basic C types (all C/C99-native signed/unsigned integral types and single/double precision real/complex floating types) and availability of matching datatypes in the underlying MPI implementation. In this case, the buffer-provider object can be passed directly as a buffer argument, the count and MPI datatype will be inferred.

If mpi4py is built against a GPU-aware MPI implementation, GPU arrays can be passed to uppercase methods as long as they have either the <code>__dlpack__</code> and <code>__dlpack__device__</code> methods or the <code>__cuda_array_interface__</code> attribute that are compliant with the respective standard specifications. Moreover, only C-contiguous or Fortran-contiguous GPU arrays are supported. It is important to note that GPU buffers must be fully ready before any MPI routines operate on them to avoid race conditions. This can be ensured by using the synchronization API of your array library. mpi4py does not have access to any GPU-specific functionality and thus cannot perform this operation automatically for users.

3.1 Running Python scripts with MPI

Most MPI programs can be run with the command **mpiexec**. In practice, running Python programs looks like:

```
$ mpiexec -n 4 python script.py
```

to run the program with 4 processors.

3.2 Point-to-Point Communication

• Python objects (pickle under the hood):

```
from mpi4py import MPI

comm = MPI.COMM_WORLD

rank = comm.Get_rank()

if rank == 0:
    data = {'a': 7, 'b': 3.14}
    comm.send(data, dest=1, tag=11)

elif rank == 1:
    data = comm.recv(source=0, tag=11)
```

• Python objects with non-blocking communication:

```
from mpi4py import MPI

comm = MPI.COMM_WORLD
rank = comm.Get_rank()

if rank == 0:
    data = {'a': 7, 'b': 3.14}
    req = comm.isend(data, dest=1, tag=11)
    req.wait()

elif rank == 1:
    req = comm.irecv(source=0, tag=11)
    data = req.wait()
```

• NumPy arrays (the fast way!):

```
from mpi4py import MPI
import numpy

comm = MPI.COMM_WORLD
```

```
rank = comm.Get_rank()

# passing MPI datatypes explicitly
if rank == 0:
    data = numpy.arange(1000, dtype='i')
    comm.Send([data, MPI.INT], dest=1, tag=77)
elif rank == 1:
    data = numpy.empty(1000, dtype='i')
    comm.Recv([data, MPI.INT], source=0, tag=77)

# automatic MPI datatype discovery
if rank == 0:
    data = numpy.arange(100, dtype=numpy.float64)
    comm.Send(data, dest=1, tag=13)
elif rank == 1:
    data = numpy.empty(100, dtype=numpy.float64)
    comm.Recv(data, source=0, tag=13)
```

3.3 Collective Communication

• Broadcasting a Python dictionary:

• Scattering Python objects:

```
from mpi4py import MPI

comm = MPI.COMM_WORLD
size = comm.Get_size()
rank = comm.Get_rank()

if rank == 0:
    data = [(i+1)**2 for i in range(size)]
else:
    data = None
data = comm.scatter(data, root=0)
assert data == (rank+1)**2
```

• Gathering Python objects:

```
from mpi4py import MPI

comm = MPI.COMM_WORLD
size = comm.Get_size()
rank = comm.Get_rank()

data = (rank+1)**2
data = comm.gather(data, root=0)
if rank == 0:
    for i in range(size):
        assert data[i] == (i+1)**2

else:
    assert data is None
```

• Broadcasting a NumPy array:

```
from mpi4py import MPI
import numpy as np

comm = MPI.COMM_WORLD
rank = comm.Get_rank()

if rank == 0:
    data = np.arange(100, dtype='i')
else:
    data = np.empty(100, dtype='i')
comm.Bcast(data, root=0)
for i in range(100):
    assert data[i] == i
```

• Scattering NumPy arrays:

```
from mpi4py import MPI
import numpy as np

comm = MPI.COMM_WORLD
size = comm.Get_size()
rank = comm.Get_rank()

sendbuf = None
if rank == 0:
    sendbuf = np.empty([size, 100], dtype='i')
    sendbuf.T[:,:] = range(size)
recvbuf = np.empty(100, dtype='i')
comm.Scatter(sendbuf, recvbuf, root=0)
assert np.allclose(recvbuf, rank)
```

• Gathering NumPy arrays:

```
from mpi4py import MPI
import numpy as np

comm = MPI.COMM_WORLD
```

```
size = comm.Get_size()
rank = comm.Get_rank()

sendbuf = np.zeros(100, dtype='i') + rank
recvbuf = None
if rank == 0:
    recvbuf = np.empty([size, 100], dtype='i')
comm.Gather(sendbuf, recvbuf, root=0)
if rank == 0:
    for i in range(size):
        assert np.allclose(recvbuf[i,:], i)
```

• Parallel matrix-vector product:

3.4 Input/Output (MPI-IO)

• Collective I/O with NumPy arrays:

```
from mpi4py import MPI
import numpy as np

amode = MPI.MODE_WRONLY|MPI.MODE_CREATE
comm = MPI.COMM_WORLD
fh = MPI.File.Open(comm, "./datafile.contig", amode)

buffer = np.empty(10, dtype=np.int)
buffer[:] = comm.Get_rank()

offset = comm.Get_rank()*buffer.nbytes
fh.Write_at_all(offset, buffer)

fh.Close()
```

• Non-contiguous Collective I/O with NumPy arrays and datatypes:

```
from mpi4py import MPI
import numpy as np

comm = MPI.COMM_WORLD
```

```
rank = comm.Get_rank()
size = comm.Get_size()

amode = MPI.MODE_WRONLY|MPI.MODE_CREATE
fh = MPI.File.Open(comm, "./datafile.noncontig", amode)

item_count = 10

buffer = np.empty(item_count, dtype='i')
buffer[:] = rank

filetype = MPI.INT.Create_vector(item_count, 1, size)
filetype.Commit()

displacement = MPI.INT.Get_size()*rank
fh.Set_view(displacement, filetype=filetype)

fh.Write_all(buffer)
filetype.Free()
fh.Close()
```

3.5 Dynamic Process Management

• Compute Pi - Master (or parent, or client) side:

• Compute Pi - Worker (or child, or server) side:

```
#!/usr/bin/env python
from mpi4py import MPI
import numpy

comm = MPI.Comm.Get_parent()
size = comm.Get_size()

(continues on next page)
```

3.6 GPU-aware MPI + Python GPU arrays

• Reduce-to-all CuPy arrays:

```
from mpi4py import MPI
import cupy as cp

comm = MPI.COMM_WORLD
size = comm.Get_size()
rank = comm.Get_rank()

sendbuf = cp.arange(10, dtype='i')
recvbuf = cp.empty_like(sendbuf)
cp.cuda.get_current_stream().synchronize()
comm.Allreduce(sendbuf, recvbuf)

assert cp.allclose(recvbuf, sendbuf*size)
```

3.7 One-Sided Communication (RMA)

• Read from (write to) the entire RMA window:

```
import numpy as np
from mpi4py import MPI
from mpi4py.util import dtlib

comm = MPI.COMM_WORLD
    rank = comm.Get_rank()

datatype = MPI.FLOAT
    np_dtype = dtlib.to_numpy_dtype(datatype)
    itemsize = datatype.Get_size()

N = 10
win_size = N * itemsize if rank == 0 else 0
win = MPI.Win.Allocate(win_size, comm=comm)
```

```
buf = np.empty(N, dtype=np_dtype)
if rank == 0:
    buf.fill(42)
    win.Lock(rank=0)
    win.Put(buf, target_rank=0)
    win.Unlock(rank=0)
    comm.Barrier()
else:
    comm.Barrier()
    win.Lock(rank=0)
    win.Get(buf, target_rank=0)
    win.Get(buf, target_rank=0)
    win.Unlock(rank=0)
    assert np.all(buf == 42)
```

Accessing a part of the RMA window using the target argument, which is defined as (offset, count, datatype):

```
import numpy as np
from mpi4py import MPI
from mpi4py.util import dtlib
comm = MPI.COMM_WORLD
rank = comm.Get_rank()
datatype = MPI.FLOAT
np_dtype = dtlib.to_numpy_dtype(datatype)
itemsize = datatype.Get_size()
N = comm.Get_size() + 1
win_size = N * itemsize if rank == 0 else 0
win = MPI.Win.Allocate(
    size=win_size,
    disp_unit=itemsize,
    comm=comm.
if rank == 0:
   mem = np.frombuffer(win, dtype=np_dtype)
   mem[:] = np.arange(len(mem), dtype=np_dtype)
comm.Barrier()
buf = np.zeros(3, dtype=np_dtype)
target = (rank, 2, datatype)
win.Lock(rank=0)
win.Get(buf, target_rank=0, target=target)
win.Unlock(rank=0)
assert np.all(buf == [rank, rank+1, 0])
```

3.8 Wrapping with SWIG

• C source:

• SWIG interface file:

```
// file: helloworld.i
%module helloworld
%{
    #include <mpi.h>
    #include "helloworld.c"
}%

%include mpi4py/mpi4py.i
%mpi4py_typemap(Comm, MPI_Comm);
void sayhello(MPI_Comm comm);
```

• Try it in the Python prompt:

```
>>> from mpi4py import MPI
>>> import helloworld
>>> helloworld.sayhello(MPI.COMM_WORLD)
Hello, World! I am process 0 of 1.
```

3.9 Wrapping with F2Py

• Fortran 90 source:

```
! file: helloworld.f90
subroutine sayhello(comm)
  use mpi
  implicit none
  integer :: comm, rank, size, ierr
  call MPI_Comm_size(comm, size, ierr)
  call MPI_Comm_rank(comm, rank, ierr)
  print *, 'Hello, World! I am process ',rank,' of ',size,'.'
end subroutine sayhello
```

• Compiling example using f2py

```
$ f2py -c --f90exec=mpif90 helloworld.f90 -m helloworld
```

• Try it in the Python prompt:

```
>>> from mpi4py import MPI
>>> import helloworld
>>> fcomm = MPI.COMM_WORLD.py2f()
>>> helloworld.sayhello(fcomm)
Hello, World! I am process 0 of 1.
```

4 mpi4py

The MPI for Python package.

The *Message Passing Interface* (MPI) is a standardized and portable message-passing system designed to function on a wide variety of parallel computers. The MPI standard defines the syntax and semantics of library routines and allows users to write portable programs in the main scientific programming languages (Fortran, C, or C++). Since its release, the MPI specification has become the leading standard for message-passing libraries for parallel computers.

MPI for Python provides MPI bindings for the Python programming language, allowing any Python program to exploit multiple processors. This package build on the MPI specification and provides an object oriented interface which closely follows MPI-2 C++ bindings.

4.1 Runtime configuration options

mpi4py.rc

This object has attributes exposing runtime configuration options that become effective at import time of the MPI module.

Attributes Summary

initialize	Automatic MPI initialization at import
threads	Request initialization with thread support
thread_level	Level of thread support to request
finalize	Automatic MPI finalization at exit
fast_reduce	Use tree-based reductions for objects
recv_mprobe	Use matched probes to receive objects
irecv_bufsz	Default buffer size in bytes for <i>irecv()</i>
errors	Error handling policy

Attributes Documentation

mpi4py.rc.initialize

Automatic MPI initialization at import.

Type
bool
Default
True

```
See also
```

MPI4PY_RC_INITIALIZE

mpi4py.rc.threads

Request initialization with thread support.

Type

bool

Default

True

See also

MPI4PY_RC_THREADS

mpi4py.rc.thread_level

Level of thread support to request.

Type

str

Default

"multiple"

Choices

"multiple", "serialized", "funneled", "single"

See also

MPI4PY_RC_THREAD_LEVEL

mpi4py.rc.finalize

Automatic MPI finalization at exit.

Type

None or bool

Default

None

See also

MPI4PY_RC_FINALIZE

mpi4py.rc.fast_reduce

Use tree-based reductions for objects.

Type

bool

Default

True

```
See also
```

MPI4PY_RC_FAST_REDUCE

mpi4py.rc.recv_mprobe

Use matched probes to receive objects.

Type

bool

Default

True

See also

MPI4PY_RC_RECV_MPROBE

mpi4py.rc.irecv_bufsz

Default buffer size in bytes for *irecv()*.

Type

int

Default

32768

See also

MPI4PY_RC_IRECV_BUFSZ

Added in version 4.0.0.

mpi4py.rc.errors

Error handling policy.

Type

str

Default

"exception"

Choices

"exception", "default", "abort", "fatal"

See also

MPI4PY_RC_ERRORS

Example

MPI for Python features automatic initialization and finalization of the MPI execution environment. By using the mpi4py.rc object, MPI initialization and finalization can be handled programmatically:

```
import mpi4py
mpi4py.rc.initialize = False  # do not initialize MPI automatically
mpi4py.rc.finalize = False  # do not finalize MPI automatically

from mpi4py import MPI # import the 'MPI' module

MPI.Init()  # manual initialization of the MPI environment
...  # your finest code here ...
MPI.Finalize() # manual finalization of the MPI environment
```

4.2 Environment variables

The following environment variables override the corresponding attributes of the *mpi4py.rc* and *MPI.pickle* objects at import time of the *MPI* module.

Note

For variables of boolean type, accepted values are 0 and 1 (interpreted as False and True, respectively), and strings specifying a YAML boolean value (case-insensitive).

MPI4PY_RC_INITIALIZE

Type

bool

Default

True

Whether to automatically initialize MPI at import time of the mpi4py.MPI module.

```
See also

mpi4py.rc.initialize
```

Added in version 4.0.0.

MPI4PY_RC_FINALIZE

Type

None | bool

Default

None

Choices

None, True, False

Whether to automatically finalize MPI at exit time of the Python process.

See also

```
mpi4py.rc.finalize
```

Added in version 4.0.0.

MPI4PY_RC_THREADS

Type

bool

Default

True

Whether to initialize MPI with thread support.

See also

```
mpi4py.rc.threads
```

Added in version 3.1.0.

MPI4PY_RC_THREAD_LEVEL

Default

"multiple"

Choices

"single", "funneled", "serialized", "multiple"

The level of required thread support.

See also

```
mpi4py.rc.thread_level
```

Added in version 3.1.0.

MPI4PY_RC_FAST_REDUCE

Type

bool

Default

True

Whether to use tree-based reductions for objects.

See also

mpi4py.rc.fast_reduce

Added in version 3.1.0.

MPI4PY_RC_RECV_MPROBE

```
Type
```

bool

Default

True

Whether to use matched probes to receive objects.

```
See also
```

```
mpi4py.rc.recv_mprobe
```

MPI4PY_RC_IRECV_BUFSZ

Type

bool

Default

True

Default buffer size in bytes for *irecv()*.

See also

```
mpi4py.rc.irecv_bufsz
```

Added in version 4.0.0.

MPI4PY_RC_ERRORS

Default

"exception"

Choices

"exception", "default", "abort", "fatal"

Controls default MPI error handling policy.

See also

```
mpi4py.rc.errors
```

Added in version 3.1.0.

MPI4PY_PICKLE_PROTOCOL

Type

int

Default

```
pickle.HIGHEST_PROTOCOL
```

Controls the default pickle protocol to use when communicating Python objects.

See also

PROTOCOL attribute of the MPI.pickle object within the MPI module.

Added in version 3.1.0.

MPI4PY_PICKLE_THRESHOLD

```
Type int

Default
```

262144

Controls the default buffer size threshold for switching from in-band to out-of-band buffer handling when using pickle protocol version 5 or higher.

See also

THRESHOLD attribute of the MPI.pickle object within the MPI module.

Added in version 3.1.2.

4.3 Miscellaneous functions

```
mpi4py.profile(name, *, path=None)
```

Support for the MPI profiling interface.

Parameters

- name (str) Name of the profiler library to load.
- path (sequence of str, optional) Additional paths to search for the profiler.

Return type

None

mpi4py.get_include()

Return the directory in the package that contains header files.

Extension modules that need to compile against mpi4py should use this function to locate the appropriate include directory. Using Python distutils (or perhaps NumPy distutils):

```
import mpi4py
Extension('extension_name', ...
    include_dirs=[..., mpi4py.get_include()])
```

Return type

stı

mpi4py.get_config()

Return a dictionary with information about MPI.

Changed in version 4.0.0: By default, this function returns an empty dictionary. However, downstream packagers and distributors may alter such behavior. To that end, MPI information must be provided under an mpi section

within a UTF-8 encoded INI-style configuration file mpi.cfg located at the top-level package directory. The configuration file is read and parsed using the configurater module.

Return type

dict[str, str]

5 mpi4py.MPI

5.1 Classes

Ancillary

Datatype	Datatype object.
Status	Status object.
Request	Request handler.
Prequest	Persistent request handler.
Grequest	Generalized request handler.
0p	Reduction operation.
Group	Group of processes.
Info	Info object.
Session	Session context.

Communication

Comm	Communication context.
Intracomm	Intracommunicator.
Topocomm	Topology intracommunicator.
Cartcomm	Cartesian topology intracommunicator.
Graphcomm	General graph topology intracommunicator.
Distgraphcomm	Distributed graph topology intracommunicator.
Intercomm	Intercommunicator.
Message	Matched message.

One-sided operations

Win	Remote memory access context.
-----	-------------------------------

Input/Output

Error handling

Errhandler	Error handler.
Exception	Exception class.

Auxiliary

Pickle	Pickle/unpickle Python objects.
buffer	Buffer.

5.2 Functions

Version inquiry

<pre>Get_version()</pre>	Obtain the version number of the MPI standard.
<pre>Get_library_version()</pre>	Obtain the version string of the MPI library.

Initialization and finalization

Init()	Initialize the MPI execution environment.
<pre>Init_thread([required])</pre>	Initialize the MPI execution environment.
Finalize()	Terminate the MPI execution environment.
<pre>Is_initialized()</pre>	Indicate whether <i>Init</i> has been called.
<pre>Is_finalized()</pre>	Indicate whether Finalize has completed.
Query_thread()	Return the level of thread support provided by the MPI library.
<pre>Is_thread_main()</pre>	Indicate whether this thread called <i>Init</i> or <i>Init_thread</i> .

Memory allocation

Alloc_mem(size[, info])	Allocate memory for message passing and remote mem-
	ory access.
Free_mem(mem)	Free memory allocated with <i>Alloc_mem</i> .

Address manipulation

Get_address(location)	Get the address of a location in memory.
Aint_add(base, disp)	Return the sum of base address and displacement.
Aint_diff(addr1, addr2)	Return the difference between absolute addresses.

Timer

Wtick()	Return the resolution of Wtime.
Wtime()	Return an elapsed time on the calling processor.

Error handling

Get_error_class(errorcode)	Convert an error code into an error class.
<pre>Get_error_string(errorcode)</pre>	Return the <i>error string</i> for a given <i>error class</i> or <i>error code</i> .
Add_error_class()	Add an error class to the known error classes.
Add_error_code(errorclass)	Add an error code to an error class.
Add_error_string(errorcode, string)	Associate an <i>error string</i> with an <i>error class</i> or <i>error code</i> .
Remove_error_class(errorclass)	Remove an error class from the known error classes.
Remove_error_code(errorcode)	Remove an <i>error code</i> from the known error codes.
Remove_error_string(errorcode)	Remove <i>error string</i> association from <i>error class</i> or <i>error code</i> .

Dynamic process management

Open_port([info])	Return an address used to connect group of processes.
Close_port(port_name)	Close a port.
<pre>Publish_name(service_name, port_name[, info])</pre>	Publish a service name.
<pre>Unpublish_name(service_name, port_name[, info])</pre>	Unpublish a service name.
Lookup_name(service_name[, info])	Lookup a port name given a service name.

Miscellanea

Attach_buffer(buf)	Attach a user-provided buffer for sending in buffered mode.
<pre>Detach_buffer()</pre>	Remove an existing attached buffer.
Flush_buffer()	Block until all buffered messages have been transmitted.
Iflush_buffer()	Nonblocking flush for buffered messages.
<pre>Compute_dims(nnodes, dims)</pre>	Return a balanced distribution of processes per coordinate direction.
<pre>Get_processor_name()</pre>	Obtain the name of the calling processor.
Register_datarep(datarep, read_fn, write_fn,)	Register user-defined data representations.
Pcontrol(level)	Control profiling.

Utilities

<pre>get_vendor()</pre>	Information about the underlying MPI implementation.
-------------------------	--

5.3 Attributes

UNDEFINED	Constant UNDEFINED of type int
ANY_SOURCE	Constant ANY_SOURCE of type int
ANY_TAG	Constant ANY_TAG of type int
PROC_NULL	Constant PROC_NULL of type int
ROOT	Constant ROOT of type int
BOTTOM	Constant BOTTOM of type BottomType
IN_PLACE	Constant IN_PLACE of type InPlaceType
BUFFER_AUTOMATIC	Constant BUFFER_AUTOMATIC of type
	BufferAutomaticType
KEYVAL_INVALID	Constant KEYVAL_INVALID of type int
TAG_UB	Constant TAG_UB of type int
IO	Constant IO of type int
WTIME_IS_GLOBAL	Constant WTIME_IS_GLOBAL of type int
UNIVERSE_SIZE	Constant UNIVERSE_SIZE of type int
APPNUM	Constant APPNUM of type int
LASTUSEDCODE	Constant LASTUSEDCODE of type int
WIN_BASE	Constant WIN_BASE of type int
WIN_SIZE	Constant WIN_SIZE of type int
WIN_DISP_UNIT	Constant WIN_DISP_UNIT of type int
WIN_CREATE_FLAVOR	Constant WIN_CREATE_FLAVOR of type int
WIN_FLAVOR	Constant WIN_FLAVOR of type int
WIN_MODEL	Constant WIN_MODEL of type int
SUCCESS	Constant SUCCESS of type int
ERR_LASTCODE	Constant ERR_LASTCODE of type int
ERR_COMM	Constant ERR_COMM of type int
ERR_GROUP	Constant ERR_GROUP of type int
ERR_TYPE	Constant ERR_TYPE of type int
ERR_REQUEST	Constant ERR_REQUEST of type int
	continues on next nage

Table 1 – continued from previous page

Table 1 – Co	nunued from previous page
ERR_OP	Constant ERR_OP of type int
ERR_ERRHANDLER	Constant ERR_ERRHANDLER of type int
ERR_BUFFER	Constant ERR_BUFFER of type int
ERR_COUNT	Constant ERR_COUNT of type int
ERR_TAG	Constant ERR_TAG of type int
ERR_RANK	Constant ERR_RANK of type int
ERR_ROOT	Constant ERR_ROOT of type int
ERR_TRUNCATE	Constant ERR_TRUNCATE of type int
ERR_IN_STATUS	Constant ERR_IN_STATUS of type int
ERR_PENDING	Constant ERR_PENDING of type int
ERR_TOPOLOGY	Constant ERR_TOPOLOGY of type int
ERR_DIMS	Constant ERR_DIMS of type int
ERR_ARG	Constant ERR_ARG of type int
ERR_OTHER	Constant ERR_OTHER of type int
ERR_UNKNOWN	Constant ERR_UNKNOWN of type int
ERR_INTERN	Constant ERR_INTERN of type int
_	
ERR_INFO	Constant ERR_INFO of type int Constant ERR_FILE of type int
ERR_FILE	√1
ERR_WIN	Constant ERR_WIN of type int
ERR_KEYVAL	Constant ERR_KEYVAL of type int
ERR_INFO_KEY	Constant ERR_INFO_KEY of type int
ERR_INFO_VALUE	Constant ERR_INFO_VALUE of type int
ERR_INFO_NOKEY	Constant ERR_INFO_NOKEY of type int
ERR_ACCESS	Constant ERR_ACCESS of type int
ERR_AMODE	Constant ERR_AMODE of type int
ERR_BAD_FILE	Constant ERR_BAD_FILE of type int
ERR_FILE_EXISTS	Constant ERR_FILE_EXISTS of type int
ERR_FILE_IN_USE	Constant ERR_FILE_IN_USE of type int
ERR_NO_SPACE	Constant ERR_NO_SPACE of type int
ERR_NO_SUCH_FILE	Constant ERR_NO_SUCH_FILE of type int
ERR_IO	Constant ERR_IO of type int
ERR_READ_ONLY	Constant ERR_READ_ONLY of type int
ERR_CONVERSION	Constant ERR_CONVERSION of type int
ERR_DUP_DATAREP	Constant ERR_DUP_DATAREP of type int
ERR_UNSUPPORTED_DATAREP	Constant ERR_UNSUPPORTED_DATAREP of type int
ERR_UNSUPPORTED_OPERATION	Constant ERR_UNSUPPORTED_OPERATION of type int
ERR_NAME	Constant ERR_NAME of type int
ERR_NO_MEM	Constant ERR_NO_MEM of type int
ERR_NOT_SAME	Constant ERR_NOT_SAME of type int
ERR_PORT	Constant ERR_PORT of type int
ERR_QUOTA	Constant ERR_QUOTA of type int
ERR_SERVICE	Constant ERR_SERVICE of type int
ERR_SPAWN	Constant ERR_SPAWN of type int
ERR_BASE	Constant ERR_BASE of type int
ERR_SIZE	Constant ERR_SIZE of type int
ERR_DISP	Constant ERR_DISP of type int
ERR_ASSERT	Constant ERR_ASSERT of type int
	Constant ERR_LOCKTYPE of type int
ERR_LOCKTYPE EDD_DMA_CONFLICT	• •
ERR_RMA_CONFLICT	Constant ERR_RMA_CONFLICT of type int
ERR_RMA_SYNC	Constant ERR_RMA_SYNC of type int
ERR_RMA_RANGE	Constant ERR_RMA_RANGE of type int
ERR_RMA_ATTACH	Constant ERR_RMA_ATTACH of type int
	continues on next page

Table 1 – continued from previous page

	ontinued from previous page
ERR_RMA_SHARED	Constant ERR_RMA_SHARED of type int
ERR_RMA_FLAVOR	Constant ERR_RMA_FLAVOR of type int
ORDER_C	Constant ORDER_C of type int
ORDER_F	Constant ORDER_F of type int
ORDER_FORTRAN	Constant ORDER_FORTRAN of type int
TYPECLASS_INTEGER	Constant TYPECLASS_INTEGER of type int
TYPECLASS_REAL	Constant TYPECLASS_REAL of type int
TYPECLASS_COMPLEX	Constant TYPECLASS_COMPLEX of type int
DISTRIBUTE_NONE	Constant DISTRIBUTE_NONE of type int
DISTRIBUTE_BLOCK	Constant DISTRIBUTE_BLOCK of type int
DISTRIBUTE_CYCLIC	Constant DISTRIBUTE_CYCLIC of type int
DISTRIBUTE_DFLT_DARG	Constant DISTRIBUTE_DFLT_DARG of type int
COMBINER_NAMED	Constant COMBINER_NAMED of type int
COMBINER_DUP	Constant COMBINER_DUP of type int
COMBINER_CONTIGUOUS	Constant COMBINER_CONTIGUOUS of type int
COMBINER_VECTOR	Constant COMBINER_VECTOR of type int
COMBINER_HVECTOR	Constant COMBINER_HVECTOR of type int
COMBINER_INDEXED	Constant COMBINER_INDEXED of type int
COMBINER_HINDEXED	Constant COMBINER_HINDEXED of type int
COMBINER_INDEXED_BLOCK	Constant COMBINER_INDEXED_BLOCK of type int
COMBINER_HINDEXED_BLOCK	Constant COMBINER_HINDEXED_BLOCK of type int
COMBINER_STRUCT	Constant COMBINER_STRUCT of type int
COMBINER_SUBARRAY	Constant COMBINER_SUBARRAY of type int
COMBINER_DARRAY	Constant COMBINER_DARRAY of type int
COMBINER_RESIZED	Constant COMBINER_RESIZED of type int
COMBINER_VALUE_INDEX	Constant COMBINER_VALUE_INDEX of type int
COMBINER_F90_REAL	Constant COMBINER_F90_REAL of type int
COMBINER_F90_COMPLEX	Constant COMBINER_F90_COMPLEX of type int
COMBINER_F90_INTEGER	Constant COMBINER_F90_INTEGER of type int
IDENT	Constant IDENT of type int
CONGRUENT	Constant CONGRUENT of type int
SIMILAR	Constant SIMILAR of type int
UNEQUAL	Constant UNEQUAL of type int
CART	Constant CART of type int
GRAPH	Constant GRAPH of type int
DIST_GRAPH	Constant DIST_GRAPH of type int
UNWEIGHTED	Constant UNWEIGHTED of type int
WEIGHTS_EMPTY	Constant WEIGHTS_EMPTY of type int
COMM_TYPE_SHARED	Constant COMM_TYPE_SHARED of type int
BSEND_OVERHEAD	Constant BSEND_OVERHEAD of type int
WIN_FLAVOR_CREATE	Constant WIN_FLAVOR_CREATE of type int
WIN_FLAVOR_ALLOCATE	Constant WIN_FLAVOR_ALLOCATE of type int
WIN_FLAVOR_DYNAMIC	Constant WIN_FLAVOR_DYNAMIC of type int
WIN_FLAVOR_SHARED	Constant WIN_FLAVOR_SHARED of type int
WIN_SEPARATE	Constant WIN_SEPARATE of type int
WIN_UNIFIED	Constant WIN_UNIFIED of type int
MODE_NOCHECK	Constant MODE_NOCHECK of type int
MODE_NOSTORE	Constant MODE_NOSTORE of type int
MODE_NOPUT	Constant MODE_NOPUT of type int
MODE_NOPRECEDE	Constant MODE_NOPRECEDE of type int
MODE_NOSUCCEED	Constant MODE_NOSUCCEED of type int
LOCK_EXCLUSIVE	Constant LOCK_EXCLUSIVE of type int
	continues on next nage

Table 1 – continued from previous page

Table 1 – conf	tinued from previous page
LOCK_SHARED	Constant LOCK_SHARED of type int
MODE_RDONLY	Constant MODE_RDONLY of type int
MODE_WRONLY	Constant MODE_WRONLY of type int
MODE_RDWR	Constant MODE_RDWR of type int
MODE_CREATE	Constant MODE_CREATE of type int
MODE_EXCL	Constant MODE_EXCL of type int
MODE_DELETE_ON_CLOSE	Constant MODE_DELETE_ON_CLOSE of type int
MODE_UNIQUE_OPEN	Constant MODE_UNIQUE_OPEN of type int
MODE_SEQUENTIAL	Constant MODE_SEQUENTIAL of type int
MODE_APPEND	Constant MODE_APPEND of type int
SEEK_SET	Constant SEEK_SET of type int
SEEK_CUR	Constant SEEK_CUR of type int
SEEK_END	Constant SEEK_END of type int
DISPLACEMENT_CURRENT	Constant DISPLACEMENT_CURRENT of type int
DISP_CUR	Constant DISP_CUR of type int
THREAD_SINGLE	Constant THREAD_SINGLE of type int
THREAD_FUNNELED	Constant THREAD_FUNNELED of type int
THREAD_SERIALIZED	Constant THREAD_SERIALIZED of type int
THREAD_MULTIPLE	Constant THREAD_MULTIPLE of type int
VERSION	Constant VERSION of type int
SUBVERSION	Constant SUBVERSION of type int
MAX_PROCESSOR_NAME	Constant MAX_PROCESSOR_NAME of type int
MAX_ERROR_STRING	Constant MAX_ERROR_STRING of type int
MAX_PORT_NAME	Constant MAX_PORT_NAME of type int
MAX_INFO_KEY	Constant MAX_INFO_KEY of type int
MAX_INFO_VAL	Constant MAX_INFO_VAL of type int
MAX_OBJECT_NAME	Constant MAX_OBJECT_NAME of type int
MAX_DATAREP_STRING	Constant MAX_DATAREP_STRING of type int
MAX_LIBRARY_VERSION_STRING	Constant MAX_LIBRARY_VERSION_STRING of type int
DATATYPE_NULL	Object DATATYPE_NULL of type Datatype
PACKED	Object PACKED of type Datatype
BYTE	Object BYTE of type Datatype
AINT	Object AINT of type Datatype
OFFSET	Object OFFSET of type Datatype
COUNT	Object COUNT of type Datatype
CHAR	Object CHAR of type Datatype
WCHAR	Object WCHAR of type Datatype
SIGNED_CHAR	Object SIGNED_CHAR of type Datatype
SHORT	Object SHORT of type Datatype
INT	Object INT of type Datatype
LONG	Object LONG of type Datatype
LONG_LONG	Object LONG_LONG of type Datatype
UNSIGNED_CHAR	Object UNSIGNED_CHAR of type Datatype
UNSIGNED_SHORT	Object UNSIGNED_SHORT of type Datatype
UNSIGNED	Object UNSIGNED of type Datatype
UNSIGNED_LONG	Object UNSIGNED_LONG of type Datatype
UNSIGNED_LONG_LONG	Object UNSIGNED_LONG_LONG of type Datatype
FLOAT	Object FLOAT of type Datatype
DOUBLE	Object DOUBLE of type Datatype
LONG_DOUBLE	Object LONG_DOUBLE of type Datatype
C_BOOL	Object C_BOOL of type Datatype
INT8_T	Object INT8_T of type Datatype
	continues on next page

Table 1 – continued from previous page

	Table 1 – continued from previous page
INT16_T	Object INT16_T of type Datatype
INT32_T	Object INT32_T of type Datatype
INT64_T	Object INT64_T of type Datatype
UINT8_T	Object UINT8_T of type Datatype
UINT16_T	Object UINT16_T of type Datatype
UINT32_T	Object UINT32_T of type Datatype
UINT64_T	Object UINT64_T of type Datatype
C_COMPLEX	Object C_COMPLEX of type Datatype
C_FLOAT_COMPLEX	Object C_FLOAT_COMPLEX of type Datatype
C_DOUBLE_COMPLEX	Object C_DOUBLE_COMPLEX of type Datatype
C_LONG_DOUBLE_COMPLEX	Object C_LONG_DOUBLE_COMPLEX of type Datatype
CXX_BOOL	Object CXX_B00L of type Datatype
CXX_FLOAT_COMPLEX	Object CXX_FLOAT_COMPLEX of type Datatype
CXX_DOUBLE_COMPLEX	Object CXX_DOUBLE_COMPLEX of type Datatype
CXX_LONG_DOUBLE_COMPLEX	Object CXX_LONG_DOUBLE_COMPLEX of type Datatype
SHORT_INT	Object SHORT_INT of type Datatype
INT_INT	Object INT_INT of type Datatype
TWOINT	Object TWOINT of type Datatype
LONG_INT	Object LONG_INT of type Datatype
FLOAT_INT	Object FLOAT_INT of type Datatype
DOUBLE_INT	Object DOUBLE_INT of type Datatype
LONG_DOUBLE_INT	Object LONG_DOUBLE_INT of type Datatype
CHARACTER	Object CHARACTER of type Datatype
LOGICAL	Object LOGICAL of type Datatype
INTEGER	Object INTEGER of type Datatype
REAL	Object REAL of type Datatype
DOUBLE_PRECISION	Object DOUBLE_PRECISION of type Datatype
COMPLEX	Object COMPLEX of type Datatype
DOUBLE_COMPLEX	Object DOUBLE_COMPLEX of type Datatype
LOGICAL1	Object LOGICAL1 of type Datatype
LOGICAL2	Object LOGICAL2 of type Datatype
LOGICAL4	Object LOGICAL4 of type Datatype
LOGICAL8	Object LOGICAL8 of type Datatype
INTEGER1	Object INTEGER1 of type Datatype
INTEGER2	Object INTEGER2 of type Datatype
INTEGER4	Object INTEGER4 of type Datatype
INTEGER8	Object INTEGERS of type Datatype Object INTEGERS of type Datatype
INTEGER16	Object INTEGER16 of type Datatype
REAL2	Object REAL2 of type Datatype
REAL4	Object REAL4 of type Datatype
REAL8	Object REAL8 of type Datatype Object REAL8 of type Datatype
REAL16	Object REAL16 of type Datatype Object REAL16 of type Datatype
COMPLEX4	Object REALTO of type Datatype Object COMPLEX4 of type Datatype
COMPLEX8	Object COMPLEX8 of type Datatype Object COMPLEX8 of type Datatype
COMPLEX16	Object COMPLEX16 of type Datatype Object COMPLEX16 of type Datatype
COMPLEX32	Object COMPLEX32 of type Datatype
UNSIGNED_INT	Object Confidence of type Datatype Object UNSIGNED_INT of type Datatype
SIGNED_SHORT	Object UNSIGNED_INT of type Datatype Object SIGNED_SHORT of type Datatype
SIGNED_INT	Object SIGNED_SHORT of type Datatype Object SIGNED_INT of type Datatype
SIGNED_LONG	Object SIGNED_INT of type Datatype Object SIGNED_LONG of type Datatype
SIGNED_LONG_LONG	Object SIGNED_LONG of type Datatype Object SIGNED_LONG_LONG of type Datatype
BOOL	Object BOOL of type Datatype Object BOOL of type Datatype
DOOL	continues on next page

Table 1 – continued from previous page

SINT8.T Object SINT8.T of type Datatype SINT16.T Object SINT16.T of type Datatype SINT32.T Object SINT32.T of type Datatype SINT64.T Object SINT64.T of type Datatype F_BOOL Object F_BOOL of type Datatype F_BOOL Object F_BOOL of type Datatype F_LNT Object F_LNT of type Datatype F_LNT Object F_LNT of type Datatype F_LOW_BEACH Object F_LOW_BEACH Ob		able 1 – continued from previous page
SINT32_T Object SINT32_T of type Datatype SINT64_T Object F_BOOL Object F_BOOL of type Datatype F_BOOL Object F_ENOL of type Datatype F_INT Object F_ENOL of type Datatype F_FLOAT Object F_LNT of type Datatype F_FLOAT Object F_DOUBLE of type Datatype F_COWPLEX Object F_DOUBLE of type Datatype F_COWPLEX Object F_DOUBLE of type Datatype F_COWPLEX Object F_DOUBLE of type Datatype F_FLOAT_COMPLEX Object F_DOUBLE COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_DOUBLE COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_DOUBLE COMPLEX of type Datatype REQUEST_NULL Object F_DOUBLE COMPLEX of type Datatype REQUEST_NULL Object MESSAGE_NOLL of type Message MESSAGE_NOLL Object MESSAGE_NOLL of type Message OP_NULL Object MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object MIN of type Op MAX Object MIN of type Op NOM Object LAND of type Op LAND Object LAND of type Op LAND Object LAND of type Op LOR Object LAND of type Op DOBJECT LAND of type Op LXOR Object LAND of type Op MAXLOC Object BAND of type Op MAXLOC Object BAND of type Op MAXLOC Object MAXLOC of type Op MAXLOC Object MINLOC Object MINLOC of type Op NO_OP Object NO_OP of type Op NO_OP Object NO_OP of type Op NO_OP Object NO_OP of type Op NO_OP Object INFO_ENV of type Group GROUP_EMPTY object GROUP_NULL of type Group INFO_NULL Object INFO_ENV of type Info ERRHANDLER_NULL of type Errhandler COMM_SELF Object COMM_SELF of type Omm Object COMM_SELF of type Omm Object COMM_NULL of type Errhandler Object COMM_NULL of type Errhandler Object COMM_NULL of type Inracomm Object TITE_NULL of type File	SINT8_T	Object SINT8_T of type Datatype
SINT64_T Object SINT64_T of type Datatype F_BOOL Object F_BOOL of type Datatype F_LINT Object F_INT of type Datatype F_FLOAT Object F_INT of type Datatype F_FLOAT Object F_INT of type Datatype F_DOUBLE Object F_OUDBLE of type Datatype F_DOUBLE Object F_OUDBLE of type Datatype F_COMPLEX Object F_COMPLEX of type Datatype F_COMPLEX Object F_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_DOUBLE_COMPLEX of type Datatype F_DOUBLE_COMPLEX Object MESSAGE_NULL of type Datatype F_DOUBLE_COMPLEX Object MAX of type Dp DOUBLE_COMPLEX Object MAX of type Op DOJECT MAX Object LAND of type Op DOJECT LAND Object LAND of type Op DOJECT LAND Object BOR of type Op DOJECT LOR Of type Op DOJECT MAXLOC Of type Op DOJECT MAXLOC OD Type Op DOJECT MINLOC OF Type Op DOJECT MINLOC OF Type Op DOJECT MODULL OF Type Comp DOJECT MODULL OF Type Comm DOJECT COMM_NOLL Object COMM_NOLL OF Type Comm DOJECT COMM_NOLL Object COM	SINT16_T	Object SINT16_T of type Datatype
F_BOOL Object F_BOOL of type Datatype F_INT Object F_INT of type Datatype F_FFLOAT Object F_IDAT of type Datatype F_FOOUBLE Object F_FLOAT of type Datatype F_COMPLEX Object F_COMPLEX of type Datatype F_COMPLEX Object F_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_DOUBLE_COMPLEX object F_FLOAT_COMPLEX of type Datatype Object F_FLOAT_COMPLEX object F_FLOAT_COMPLEX of type Datatype REQUEST_NULL Object RESSAGE_NULL of type Reguest MESSAGE_NOLPROC Object MESSAGE_NOLPROC Object MESSAGE_NOLPROC of type Message OP_NULL of type Op MAX Object MAX of type Op MAX Object MAX of type Op SUM Object SUM of type Op SUM Object SUM of type Op DOBOD Object PROD of type Op LAND Object LAND of type Op BAND Object BAND of type Op LOR Object LOR of type Op BOR Object LOR of type Op BOR Object LOR of type Op MAXLOC Object LOR of type Op MAXLOC Object MAXLOC of type Op OD REPLACE Object REPLACE of type Op NO_OP Object ROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object GROUP_MULL of type Group RERRANDLER_NULL of type Group RERRANDLER_NULL of type Group RERRANDLER_NULL of type Errhandler RERRORS_RETURN Object ERRORS_RETURN of type Errhandler RERRORS_RETURN Object ERRORS_RETURN of type Errhandler COMM_NORLD Object COMM_NORLD of type Intracomm COMM_NORLD Object COMM_NORLD of type Intracomm TINN_NULL of type Comm FILE_NULL of type Comm	SINT32_T	Object SINT32_T of type Datatype
F_INT P_INT Object F_INT of type Datatype F_FLOAT Object F_IOAT of type Datatype F_DOUBLE Object F_COMPLEX Object F_COMPLEX of type Datatype F_COMPLEX Object F_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_LOAT_COMPLEX of type Datatype REQUEST_NULL Object REQUEST_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Message OP_NULL Object MESSAGE_NULL of type Op MIN MAX Object MAX Object MAX of type Op MIN Object MIN of type Op SUM Object SUM of type Op Company Divided Data of type Op Company Divided Datatype Double D	SINT64_T	Object SINT64_T of type Datatype
F_FLOAT P_DOUBLE Object F_LOUBLE of type Datatype F_DOUBLE Object F_COMPLEX of type Datatype F_COMPLEX Object F_LOAT_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_LOAT_COMPLEX of type Datatype F_DOUBLE_COMPLEX Object F_LOAT_COMPLEX of type Datatype P_DOUBLE_COMPLEX Object RESOURT_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Message MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object MESSAGE_NO_PROC of type Message OP_NULL Object MIN of type Op MAX Object MIN of type Op DOJECT MEND of type Op LAND Object PROD of type Op LAND Object LAND of type Op LOR Object LAND of type Op LOR Object LAND of type Op LOR Object LAND of type Op DOJECT MEND of type Op LOR Object LAND of type Op MINLOC Object BAND of type Op DOJECT MEND OF type Op MINLOC Object MESSAGE_NO_PROC Object MESSAGE_NO_PROC ODJECT	F_BOOL	Object F_BOOL of type Datatype
F_DOUBLE F_COMPLEX Object F_LOUBLE of type Datatype F_COMPLEX Object F_FLOAT_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_DOUBLE_COMPLEX Object F_DOUBLE_COMPLEX of type Datatype REQUEST_NULL Object MESSAGE_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Message MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object OP_NULL of type Op MAX Object MAX of type Op MIN Object MIN of type Op SUM Object MIN of type Op PROD Object SUM of type Op LAND Object LAND of type Op LAND Object BAND of type Op LOR Object BAND of type Op LOR Object BOR of type Op BOR LXOR Object BOR of type Op MAXLOC Object BOR of type Op MAXLOC Object BOR of type Op MAXLOC Object MINLOC Object MAXLOC of type Op REPLACE Object MAXLOC of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_NULL Object GROUP_NULL of type Group GROUP_MOLD GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info Diject INFO_NULL of type Info ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_RETAL Object COMM_NULL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm Object WIN_NULL of type File	F_INT	Object F_INT of type Datatype
F_COMPLEX Object F_COMPLEX of type Datatype F_FLOAT_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_DOUBLE_COMPLEX of type Datatype REQUEST_NULL Object REQUEST_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Message MESSAGE_NO_PROC Object MESSAGE_NULL of type Message OP_NULL Object OP_NULL of type Op MAX Object MAX of type Op MAX Object MIN of type Op NIN Object SUM of type Op PROD Object SUM of type Op LAND Object LAND of type Op LAND Object LAND of type Op BAND Object LAND of type Op LOR Object BAND of type Op BOR Object LOR of type Op LXOR Object LXOR of type Op MAXLOC Object BAND of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MAXLOC of type Op GROUP_NULL Object GROUP_NULL of type Group Object REPLACE Object GROUP_NULL of type Group INFO_NULL Object GROUP_EMPTY of type Group INFO_NULL Object GROUP_EMPTY of type Group ERRHANDLER_NULL Object ERROS_RETURN of type Errhandler ERRORS_RETURN Object ERROS_ARE_FATAL of type Errhandler ERRORS_ARE_FATAL Object COMM_NULL of type Intracomm MIN_NULL Object COMM_NULL of type Intracomm WIN_NULL Object COMM_NULL of type Intracomm	F_FLOAT	Object F_FLOAT of type Datatype
F_FLOAT_COMPLEX F_DOUBLE_COMPLEX Object F_FLOAT_COMPLEX of type Datatype F_DOUBLE_COMPLEX Object F_DOUBLE_COMPLEX of type Patatype REQUEST_NULL Object REQUEST_NULL of type Patatype MESSAGE_NULL Object RESSAGE_NULL of type Message MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object MIN of type OP MAX Object MIN of type OP NOBJECT SUM of type OP SUM Object SUM of type OP PROD Object SUM of type OP BAND Object LAND of type OP LAND Object LAND of type OP BOR Object LOR of type OP BOR Object LOR of type OP BOR Object LOR of type OP MAXLOC Object LOR of type OP MAXLOC Object LOR of type OP MINLOC Object MAXLOC of type OP MINLOC Object MAXLOC of type OP MINLOC Object MINLOC of type OP NO_OP Object RPLACE of type OP NO_OP Object RPLACE of type OP NO_OP Object ROD_OP Object ROD_OP Object ROD_O	F_DOUBLE	Object F_DOUBLE of type Datatype
F_DOUBLE_COMPLEX Object F_DOUBLE_COMPLEX of type Datatype	F_COMPLEX	Object F_COMPLEX of type Datatype
REQUEST_NULL Object REQUEST_NULL of type Request MESSAGE_NULL Object MESSAGE_NULL of type Message MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object OP_NULL of type Op MAX Object MIN of type Op MIN Object MIN of type Op SUM Object SUM of type Op LAND Object EROD of type Op LAND Object BAND of type Op LAND Object BAND of type Op LOR Object BAND of type Op LOR Object BOR of type Op LOR Object LOR of type Op MAXLOC Object BOR of type Op MAXLOC Object MINLOC of type Op MAXLOC Object MINLOC of type Op REPLACE Object MINLOC of type Op REPLACE Object MINLOC of type Op REPLACE Object MINLOC of type Op ROO_P ROO	F_FLOAT_COMPLEX	Object F_FLOAT_COMPLEX of type Datatype
MESSAGE_NULL Object MESSAGE_NULL of type Message MESSAGE NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object OP_NULL of type OP MAX Object MIN of type OP MIN Object MIN of type OP SUM Object SUM of type OP PROD Object SUM of type OP LAND Object LAND of type OP LAND Object LAND of type OP LOR Object BAND of type OP BOR Object BOR of type OP LXOR Object LOR of type OP BXOR Object BXOR of type OP MAXLOC Object MAXLOC of type OP MINLOC Object MINLOC of type OP REPLACE Object REPLACE of type OP NO_OP Object ROUP_BULL of type Group GROUP_MULL Object GROUP_MULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_ENV of type Info LINFO_ENV Object ERRORS_RETURN of type Errhandler ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Int	F_DOUBLE_COMPLEX	Object F_DOUBLE_COMPLEX of type Datatype
MESSAGE_NO_PROC Object MESSAGE_NO_PROC of type Message OP_NULL Object OP_NULL of type Op MAX Object MAX of type Op MIN Object MIN of type Op SUM Object SUM of type Op PROD Object SUM of type Op LAND Object LAND of type Op LAND Object LAND of type Op LOR Object BOR of type Op BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object BXOR of type Op MINLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object NO_OP of type Op NO_OP Object ROUP_DULL of type Group GROUP_NULL Object GROUP_EMPTY of type Group INFO_NULL Object GROUP_EMPTY of type Info INFO_NULL Object TNFO_ENV of type Info ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_BET of type Intracomm COMM_NULL Object COMM_NULL of type Intracomm OWN_WORLD Object COMM_WORLD of type Intracomm<	REQUEST_NULL	Object REQUEST_NULL of type Request
Object OP_NULL of type Op MAX Object MAX of type Op MIN Object MIN of type Op MIN Object MIN of type Op PROD Object SUM of type Op PROD Object PROD of type Op LAND Object LAND of type Op BAND Object LAND of type Op LOR Object LOR of type Op BOR Object LOR of type Op LXOR Object LOR of type Op BXOR Object LOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MAXLOC of type Op REPLACE Object REPLACE of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object COMM_NULL of type Intracomm COMM_SELF Object COMM_SELF of type Intracomm WIN_NULL Object Win_NULL of type Intracomm Object COMM_WORLD Object Win_NULL of type Intracomm Object Win_NULL of type File	MESSAGE_NULL	Object MESSAGE_NULL of type Message
MAX Object MAX of type Op MIN Object MIN of type Op SUM Object SUM of type Op PROD Object SUM of type Op PROD Object PROD of type Op LAND Object LAND of type Op BAND Object BAND of type Op LOR Object LOR of type Op LOR Object BOR of type Op LXOR Object BOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MAXLOC of type Op REPLACE Object MINLOC of type Op REPLACE Object REPLACE of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object COMM_NULL Object COMM_NULL Object COMM_NULL Object COMM_NULL of type Intracomm COMM_WORLD Object WIN_NULL of type Win FILE_NULL of type File	MESSAGE_NO_PROC	Object MESSAGE_NO_PROC of type Message
MIN Object MIN of type Op SUM Object SUM of type Op PROD Object SUM of type Op LAND Object LAND of type Op LAND Object LAND of type Op LOR Object LOR of type Op LOR Object LOR of type Op BOR Object BOR of type Op LXOR Object LXOR of type Op LXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MAXLOC Object MAXLOC of type Op REPLACE Object MINLOC of type Op REPLACE Object MINLOC of type Op GROUP_NULL Object REPLACE of type Op GROUP_NULL Object GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info ERRHANDLER_NULL Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object COMM_NULL of type Intracomm COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_SULL of type Intracomm WIN_NULL Object COMM_NULL of type Intracomm WIN_NULL Object COMM_NULL of type Intracomm Object COMM_NULL of type Intracomm Object COMM_NULL of type Intracomm Object COMM_SULL of type Intracomm	OP_NULL	Object OP_NULL of type Op
SUM Object SUM of type Op PROD Object PROD of type Op LAND Object LAND of type Op BAND Object BAND of type Op LOR Object LOR of type Op LOR Object BOR of type Op LXOR Object BOR of type Op EXOR Object BOR of type Op MAXLOC Object BOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op ROP Object NO_OP of type Op GROUP_NULL Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_REFLACE Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL Object Intracomm COMM_SELF Object COMM_NULL of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm Object COMM_NULL of type Intracomm Object COMM_NULL of type Intracomm Object COMM_WORLD of type Intracomm Object COMM_NULL of type Intracomm	MAX	Object MAX of type Op
PROD Object PROD of type Op LAND Object LAND of type Op BAND Object BAND of type Op LOR Object BOR of type Op BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object LXOR of type Op BXOR Object BXDR of type Op MAXLOC Object BXDR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op MINLOC Object REPLACE of type Op REPLACE Object REPLACE of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object COMM_NULL Object COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type File	MIN	Object MIN of type Op
LAND Object LAND of type Op BAND Object BAND of type Op LOR Object LOR of type Op BOR Object BOR of type Op BOR Object BOR of type Op BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object BXOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MAXLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_NULL of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm Object FILE_NULL of type Win FILE_NULL of type File	SUM	Object SUM of type Op
BAND Object BAND of type Op LOR Object LOR of type Op BOR Object EOR of type Op LXOR Object EXOR of type Op BXOR Object EXOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op REPLACE Object REPLACE of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_MULL of type Group INFO_NULL Object INFO_NULL of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_WORLD of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm WIN_NULL Object FILE_NULL of type Win FILE_NULL of type Win	PROD	Object PROD of type <i>Op</i>
LOR Object LOR of type Op BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object BXOR of type Op MAXLOC Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Of type Group GROUP_EMPTY Object GROUP_NULL of type Group INFO_NULL Object INFO_NULL of type Info ERRHANDLER_NULL Object INFO_ENV Object INFO_ENV Of type Info ERRHANDLER_NULL Object ERRORS_RETURN Of type Errhandler ERRORS_RETURN Object ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL Of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_WORLD Of type Intracomm WIN_NULL Object COMM_WORLD of type Intracomm WIN_NULL Object FILE_NULL of type Win FILE_NULL Object FILE_NULL of type File	LAND	***
BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object TILE_NULL of type Win FILE_NULL Object FILE_NULL of type File	BAND	Object BAND of type Op
BOR Object BOR of type Op LXOR Object LXOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object TILE_NULL of type Win FILE_NULL Object FILE_NULL of type File	LOR	• • • • • • • • • • • • • • • • • • • •
LXOR Object LXOR of type Op BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRORS_RETURN of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		· · · · · · · · · · · · · · · · · · ·
BXOR Object BXOR of type Op MAXLOC Object MAXLOC of type Op MINLOC Object MINLOC of type Op REPLACE Object REPLACE of type Op NO_OP Object NO_OP of type Op GROUP_NULL Object GROUP_NULL of type Group GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm Object COMM_WORLD Object FILE_NULL of type Win FILE_NULL Object FILE_NULL of type File		Y
MAXLOCObject MAXLOC of type OpMINLOCObject MINLOC of type OpREPLACEObject REPLACE of type OpNO_OPObject NO_OP of type OpGROUP_NULLObject GROUP_NULL of type GroupGROUP_EMPTYObject GROUP_EMPTY of type GroupINFO_NULLObject INFO_NULL of type InfoINFO_ENVObject INFO_ENV of type InfoERRHANDLER_NULLObject ERRHANDLER_NULL of type ErrhandlerERRORS_RETURNObject ERRORS_RETURN of type ErrhandlerERRORS_ARE_FATALObject ERRORS_ARE_FATAL of type ErrhandlerCOMM_NULLObject COMM_NULL of type CommCOMM_SELFObject COMM_SELF of type IntracommCOMM_WORLDObject COMM_WORLD of type IntracommWIN_NULLObject WIN_NULL of type WinFILE_NULLObject FILE_NULL of type File		Y
MINLOCObject MINLOC of type OpREPLACEObject REPLACE of type OpNO_OPObject NO_OP of type OpGROUP_NULLObject GROUP_NULL of type GroupGROUP_EMPTYObject GROUP_EMPTY of type GroupINFO_NULLObject INFO_NULL of type InfoINFO_ENVObject INFO_ENV of type InfoERRHANDLER_NULLObject ERRHANDLER_NULL of type ErrhandlerERRORS_RETURNObject ERRORS_RETURN of type ErrhandlerCOMM_SELFObject COMM_NULL of type CommCOMM_SELFObject COMM_SELF of type IntracommCOMM_WORLDObject COMM_WORLD of type IntracommWIN_NULLObject WIN_NULL of type WinFILE_NULLObject FILE_NULL of type File	MAXLOC	***
REPLACEObject REPLACE of type OpNO_OPObject NO_OP of type OpGROUP_NULLObject GROUP_NULL of type GroupGROUP_EMPTYObject GROUP_EMPTY of type GroupINFO_NULLObject INFO_NULL of type InfoINFO_ENVObject INFO_ENV of type InfoERRHANDLER_NULLObject ERRHANDLER_NULL of type ErrhandlerERRORS_RETURNObject ERRORS_RETURN of type ErrhandlerERRORS_ARE_FATALObject ERRORS_ARE_FATAL of type ErrhandlerCOMM_NULLObject COMM_NULL of type CommCOMM_SELFObject COMM_SELF of type IntracommCOMM_WORLDObject COMM_WORLD of type IntracommWIN_NULLObject WIN_NULL of type WinFILE_NULLObject FILE_NULL of type File		• • • •
NO_OPObject NO_OP of type OpGROUP_NULLObject GROUP_NULL of type GroupGROUP_EMPTYObject GROUP_EMPTY of type GroupINFO_NULLObject INFO_NULL of type InfoINFO_ENVObject INFO_ENV of type InfoERRHANDLER_NULLObject ERRHANDLER_NULL of type ErrhandlerERRORS_RETURNObject ERRORS_RETURN of type ErrhandlerERRORS_ARE_FATALObject ERRORS_ARE_FATAL of type ErrhandlerCOMM_NULLObject COMM_NULL of type CommCOMM_SELFObject COMM_SELF of type IntracommCOMM_WORLDObject COMM_WORLD of type IntracommWIN_NULLObject WIN_NULL of type WinFILE_NULLObject FILE_NULL of type File		V VI -
GROUP_NULL GROUP_EMPTY Object GROUP_EMPTY of type Group Object INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Intracomm COMM_SELF Object COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		V
GROUP_EMPTY Object GROUP_EMPTY of type Group INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object COMM_NULL of type Errhandler COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File	GROUP_NULL	
INFO_NULL Object INFO_NULL of type Info INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		
INFO_ENV Object INFO_ENV of type Info ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		* * * * * * * * * * * * * * * * * * * *
ERRHANDLER_NULL Object ERRHANDLER_NULL of type Errhandler ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		* **
ERRORS_RETURN Object ERRORS_RETURN of type Errhandler ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		* **
ERRORS_ARE_FATAL Object ERRORS_ARE_FATAL of type Errhandler COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		**
COMM_NULL Object COMM_NULL of type Comm COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		· · · · · · · · · · · · · · · · · · ·
COMM_SELF Object COMM_SELF of type Intracomm COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		
COMM_WORLD Object COMM_WORLD of type Intracomm WIN_NULL Object WIN_NULL of type Win FILE_NULL Object FILE_NULL of type File		
WIN_NULL Of type Win FILE_NULL Of type File		
FILE_NULL of type File		
· · · · · · · · · · · · · · · · · · ·		
	•	J . JI

6 mpi4py.typing

Added in version 4.0.0.

This module provides type aliases used to add type hints to the various functions and methods within the MPI module.

See also

Module typing

Documentation of the typing standard module.

Types Summary

SupportsBuffer	Python buffer protocol.
SupportsDLPack	DLPack data interchange protocol.
SupportsCAI	CUDA Array Interface (CAI) protocol.
Buffer	Buffer-like object.
Bottom	Start of the address range.
InPlace	In-place buffer argument.
Aint	Address-sized integral type.
Count	Integral type for counts.
Displ	Integral type for displacements.
Offset	Integral type for offsets.
TypeSpec	Datatype specification.
BufSpec	Buffer specification.
BufSpecB	Buffer specification (block).
BufSpecV	Buffer specification (vector).
BufSpecW	Buffer specification (generalized).
TargetSpec	Target specification.

Types Documentation

See also

Buffer Protocol

mpi4py.typing.SupportsDLPack = <class 'mpi4py.typing.SupportsDLPack'>
 DLPack data interchange protocol.

See also

Python Specification for DLPack

See also

CUDA Array Interface (Version 3)

```
mpi4py.typing.Buffer
     Buffer-like object.
     alias of SupportsBuffer | SupportsDLPack | SupportsCAI
mpi4py.typing.Bottom
     Start of the address range.
     alias of BottomType | None
mpi4py.typing.InPlace
     In-place buffer argument.
     alias of InPlaceType | None
mpi4py.typing.Aint = <class 'numbers.Integral'>
     Address-sized integral type.
     alias of numbers. Integral
mpi4py.typing.Count = <class 'numbers.Integral'>
     Integral type for counts.
     alias of numbers. Integral
mpi4py.typing.Displ = <class 'numbers.Integral'>
     Integral type for displacements.
     alias of numbers. Integral
mpi4py.typing.Offset = <class 'numbers.Integral'>
     Integral type for offsets.
     alias of numbers. Integral
mpi4py.typing.TypeSpec
     Datatype specification.
     alias of Datatype | str
mpi4py.typing.BufSpec
     Buffer specification.
        • Buffer
        • Tuple[Buffer, Count]
        • Tuple[Buffer, TypeSpec]
        • Tuple[Buffer, Count, TypeSpec]
        • Tuple[Bottom, Count, Datatype]
```

alias of SupportsBuffer | SupportsDLPack | SupportsCAI | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Integral] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Datatype | str] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Integral, Datatype | str] | Tuple[BottomType | None, Integral, Datatype] | List[Any]

mpi4py.typing.BufSpecB

Buffer specification (block).

- Buffer
- Tuple[Buffer, Count]
- Tuple[Buffer, TypeSpec]
- Tuple[Buffer, Count, TypeSpec]

 $a lias \ of \ SupportsBuffer \ | \ SupportsDLPack \ | \ SupportsCAI \ | \ Tuple [SupportsBuffer \ | \ SupportsDLPack \ | \ SupportsCAI, \ Integral] \ | \ Tuple [SupportsBuffer \ | \ SupportsDLPack \ | \ SupportsDLPack \ | \ SupportsCAI, \ Integral, \ Datatype \ | \ str] \ | \ List[Any]$

mpi4py.typing.BufSpecV

Buffer specification (vector).

- Buffer
- Tuple[Buffer, Sequence[Count]]
- Tuple[Buffer, Tuple[Sequence[Count], Sequence[Disp1]]]
- Tuple[Buffer, TypeSpec]
- Tuple[Buffer, Sequence[Count], TypeSpec]
- Tuple[Buffer, Tuple[Sequence[Count], Sequence[Disp1]], TypeSpec]
- Tuple[Buffer, Sequence[Count], Sequence[Disp1], TypeSpec]
- $\bullet \ \ \mathsf{Tuple}[\mathit{Bottom}, \mathsf{Tuple}[\mathsf{Sequence}[\mathit{Count}], \mathsf{Sequence}[\mathit{Disp1}]], \mathit{Datatype}]$
- Tuple[Bottom, Sequence[Count], Sequence[Disp1], Datatype]

alias of SupportsBuffer | SupportsDLPack | SupportsCAI | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Sequence[Integral]] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Tuple[Sequence[Integral], Sequence[Integral]]] | Tuple[SupportsBuffer | SupportsDLPack | SupportsDLPack | SupportsCAI, Datatype | str] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Sequence[Integral], Datatype | str] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Tuple[Sequence[Integral], Sequence[Integral], Datatype | str] | Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Sequence[Integral], Sequence[Integral], Datatype | str] | Tuple[BottomType | None, Tuple[Sequence[Integral], Sequence[Integral], Datatype] | Tuple[BottomType | None, Sequence[Integral], Sequence[Integral], Datatype] | List[Any]

mpi4py.typing.BufSpecW

Buffer specification (generalized).

- Tuple[Buffer, Sequence[Datatype]]
- Tuple[Buffer, Tuple[Sequence[Count], Sequence[Disp1]], Sequence[Datatype]]
- Tuple[Buffer, Sequence[Count], Sequence[Disp1], Sequence[Datatype]]
- Tuple[Bottom, Tuple[Sequence[Count], Sequence[Disp1]], Sequence[Datatype]]
- Tuple[Bottom, Sequence[Count], Sequence[Displ], Sequence[Datatype]]

alias of Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Sequence[Datatype]]
| Tuple[SupportsBuffer | SupportsDLPack | SupportsCAI, Tuple[Sequence[Integral],
Sequence[Integral]], Sequence[Datatype]] | Tuple[SupportsBuffer | SupportsDLPack |
SupportsCAI, Sequence[Integral], Sequence[Integral], Sequence[Datatype]] | Tuple[BottomType |
None, Tuple[Sequence[Integral], Sequence[Integral]], Sequence[Datatype]] | Tuple[BottomType |
None, Sequence[Integral], Sequence[Integral], Sequence[Datatype]] | List[Any]

mpi4py.typing.TargetSpec

Target specification.

- Displ
- Tuple[()]
- Tuple[Disp1]
- Tuple[Displ, Count]
- Tuple[Displ, Count, Datatype]

alias of Integral | Tuple | Tuple[Integral] | Tuple[Integral, Integral] | Tuple[Integral, Integral,
Datatype | str] | List[Any]

7 mpi4py.futures

Added in version 3.0.0.

This package provides a high-level interface for asynchronously executing callables on a pool of worker processes using MPI for inter-process communication.

The <code>mpi4py.futures</code> package is based on <code>concurrent.futures</code> from the Python standard library. More precisely, <code>mpi4py.futures</code> provides the <code>MPIPoolExecutor</code> class as a concrete implementation of the abstract class <code>Executor</code>. The <code>submit()</code> interface schedules a callable to be executed asynchronously and returns a <code>Future</code> object representing the execution of the callable. <code>Future</code> instances can be queried for the call result or exception. Sets of <code>Future</code> instances can be passed to the <code>wait()</code> and <code>as_completed()</code> functions.

See also

Module concurrent.futures

Documentation of the concurrent, futures standard module.

7.1 MPIPoolExecutor

The MPIPoolExecutor class uses a pool of MPI processes to execute calls asynchronously. By performing computations in separate processes, it allows to side-step the global interpreter lock but also means that only picklable objects can be executed and returned. The __main__ module must be importable by worker processes, thus MPIPoolExecutor instances may not work in the interactive interpreter.

MPIPoolExecutor takes advantage of the dynamic process management features introduced in the MPI-2 standard. In particular, the MPI.Intracomm.Spawn method of MPI.COMM_SELF is used in the master (or parent) process to spawn new worker (or child) processes running a Python interpreter. The master process uses a separate thread (one for each MPIPoolExecutor instance) to communicate back and forth with the workers. The worker processes serve the execution of tasks in the main (and only) thread until they are signaled for completion.

Note

The worker processes must import the main script in order to *unpickle* any callable defined in the __main__ module and submitted from the master process. Furthermore, the callables may need access to other global variables. At the worker processes, *mpi4py.futures* executes the main script code (using the runpy module) under the __worker__ namespace to define the __main__ module. The __main__ and __worker__ modules are added to sys.modules (both at the master and worker processes) to ensure proper *pickling* and *unpickling*.

Warning

During the initial import phase at the workers, the main script cannot create and use new *MPIPoo1Executor* instances. Otherwise, each worker would attempt to spawn a new pool of workers, leading to infinite recursion. *mpi4py.futures* detects such recursive attempts to spawn new workers and aborts the MPI execution environment. As the main script code is run under the __worker__ namespace, the easiest way to avoid spawn recursion is using the idiom if __name__ == '__main__': ... in the main script.

class mpi4py.futures.MPIPoolExecutor(max_workers=None, initializer=None, initializer=None, initializer=None, initializer=None, initializer=None

An Executor subclass that executes calls asynchronously using a pool of at most *max_workers* processes. If *max_workers* is None or not given, its value is determined from the *MPI4PY_FUTURES_MAX_WORKERS* environment variable if set, or the MPI universe size if set, otherwise a single worker process is spawned. If *max_workers* is lower than or equal to 0, then a ValueError will be raised.

initializer is an optional callable that is called at the start of each worker process before executing any tasks; *initargs* is a tuple of arguments passed to the initializer. If *initializer* raises an exception, all pending tasks and any attempt to submit new tasks to the pool will raise a BrokenExecutor exception.

Other parameters:

- python_exe: Path to the Python interpreter executable used to spawn worker processes, otherwise sys. executable is used.
- python_args: list or iterable with additional command line flags to pass to the Python executable. Command line flags determined from inspection of sys.flags, sys.warnoptions and sys._xoptions in are passed unconditionally.
- mpi_info: dict or iterable yielding (key, value) pairs. These (key, value) pairs are passed (through an MPI.Info object) to the MPI.Intracomm. Spawn call used to spawn worker processes. This mechanism allows telling the MPI runtime system where and how to start the processes. Check the documentation of the backend MPI implementation about the set of keys it interprets and the corresponding format for values.
- globals: dict or iterable yielding (name, value) pairs to initialize the main module namespace in worker processes.

- *main*: If set to False, do not import the __main__ module in worker processes. Setting *main* to False prevents worker processes from accessing definitions in the parent __main__ namespace.
- path: list or iterable with paths to append to sys.path in worker processes to extend the module search path.
- *wdir*: Path to set the current working directory in worker processes using os.chdir(). The initial working directory is set by the MPI implementation. Quality MPI implementations should honor a wdir info key passed through *mpi info*, although such feature is not mandatory.
- env: dict or iterable yielding (name, value) pairs with environment variables to update os.environ in worker processes. The initial environment is set by the MPI implementation. MPI implementations may allow setting the initial environment through mpi_info, however such feature is not required nor recommended by the MPI standard.
- *use_pkl5*: If set to True, use pickle5 with out-of-band buffers for interprocess communication. If *use_pkl5* is set to None or not given, its value is determined from the *MPI4PY_FUTURES_USE_PKL5* environment variable. Using pickle5 with out-of-band buffers may benefit applications dealing with large buffer-like objects like NumPy arrays. See *mpi4py.util.pkl5* for additional information.
- backoff: float value specifying the maximum number of seconds a worker thread or process suspends execution with time.sleep() while idle-waiting. If not set, its value is determined from the MPI4PY_FUTURES_BACKOFF environment variable if set, otherwise the default value of 0.001 seconds is used. Lower values will reduce latency and increase execution throughput for very short-lived tasks, albeit at the expense of spinning CPU cores and increased energy consumption.

```
submit(func, *args, **kwargs)
```

Schedule the callable, *func*, to be executed as func(*args, **kwargs) and returns a Future object representing the execution of the callable.

```
executor = MPIPoolExecutor(max_workers=1)
future = executor.submit(pow, 321, 1234)
print(future.result())
```

map(func, *iterables, timeout=None, chunksize=1, **kwargs)

Equivalent to map(func, *iterables) except func is executed asynchronously and several calls to func may be made concurrently, out-of-order, in separate processes. The returned iterator raises a TimeoutError if __next__() is called and the result isn't available after timeout seconds from the original call to map(). timeout can be an int or a float. If timeout is not specified or None, there is no limit to the wait time. If a call raises an exception, then that exception will be raised when its value is retrieved from the iterator. This method chops iterables into a number of chunks which it submits to the pool as separate tasks. The (approximate) size of these chunks can be specified by setting chunksize to a positive integer. For very long iterables, using a large value for chunksize can significantly improve performance compared to the default size of one. By default, the returned iterator yields results in-order, waiting for successive tasks to complete. This behavior can be changed by passing the keyword argument unordered as True, then the result iterator will yield a result as soon as any of the tasks complete.

```
executor = MPIPoolExecutor(max_workers=3)
for result in executor.map(pow, [2]*32, range(32)):
    print(result)
```

starmap(func, iterable, timeout=None, chunksize=1, **kwargs)

Equivalent to itertools.starmap(func, iterable). Used instead of map() when argument parameters are already grouped in tuples from a single iterable (the data has been "pre-zipped"). map(func, *iterable) is equivalent to starmap(func, zip(*iterable)).

```
executor = MPIPoolExecutor(max_workers=3)
iterable = ((2, n) for n in range(32))
for result in executor.starmap(pow, iterable):
    print(result)
```

shutdown(*wait=True*, *cancel_futures=False*)

Signal the executor that it should free any resources that it is using when the currently pending futures are done executing. Calls to *submit()* and *map()* made after *shutdown()* will raise RuntimeError.

If *wait* is True then this method will not return until all the pending futures are done executing and the resources associated with the executor have been freed. If *wait* is False then this method will return immediately and the resources associated with the executor will be freed when all pending futures are done executing. Regardless of the value of *wait*, the entire Python program will not exit until all pending futures are done executing.

If *cancel_futures* is True, this method will cancel all pending futures that the executor has not started running. Any futures that are completed or running won't be cancelled, regardless of the value of *cancel_futures*.

You can avoid having to call this method explicitly if you use the with statement, which will shutdown the executor instance (waiting as if *shutdown()* were called with *wait* set to True).

```
import time
with MPIPoolExecutor(max_workers=1) as executor:
    future = executor.submit(time.sleep, 2)
assert future.done()
```

bootup(wait=True)

Signal the executor that it should allocate eagerly any required resources (in particular, MPI worker processes). If wait is True, then bootup() will not return until the executor resources are ready to process submissions. Resources are automatically allocated in the first call to submit(), thus calling bootup() explicitly is seldom needed.

num workers

Number or worker processes in the pool.

MPI4PY_FUTURES_MAX_WORKERS

If the *max_workers* parameter to *MPIPoolExecutor* is None or not given, the *MPI4PY_FUTURES_MAX_WORKERS* environment variable provides a fallback value for the maximum number of MPI worker processes to spawn.

Added in version 3.1.0.

MPI4PY_FUTURES_USE_PKL5

If the *use_pkl5* keyword argument to *MPIPoolExecutor* is None or not given, the *MPI4PY_FUTURES_USE_PKL5* environment variable provides a fallback value for whether the executor should use pickle5 with out-of-band buffers for interprocess communication. Accepted values are 0 and 1 (interpreted as False and True, respectively), and strings specifying a YAML boolean value (case-insensitive). Using pickle5 with out-of-band buffers may benefit applications dealing with large buffer-like objects like NumPy arrays. See *mpi4py.util.pkl5* for additional information.

Added in version 4.0.0.

MPI4PY_FUTURES_BACKOFF

If the *backoff* keyword argument to *MPIPoolExecutor* is not given, the *MPI4PY_FUTURES_BACKOFF* environment variable can be set to a float value specifying the maximum number of seconds a worker thread or process

suspends execution with time.sleep() while idle-waiting. If not set, the default backoff value is 0.001 seconds. Lower values will reduce latency and increase execution throughput for very short-lived tasks, albeit at the expense of spinning CPU cores and increased energy consumption.

Added in version 4.0.0.

Note

As the master process uses a separate thread to perform MPI communication with the workers, the backend MPI implementation should provide support for MPI. THREAD_MULTIPLE. However, some popular MPI implementations do not support yet concurrent MPI calls from multiple threads. Additionally, users may decide to initialize MPI with a lower level of thread support. If the level of thread support in the backend MPI is less than MPI. THREAD_MULTIPLE, mpi4py.futures will use a global lock to serialize MPI calls. If the level of thread support is less than MPI.THREAD_SERIALIZED, mpi4py.futures will emit a RuntimeWarning.

Warning

If the level of thread support in the backend MPI is less than MPI. THREAD_SERIALIZED (i.e, it is either MPI. THREAD_SINGLE or MPI. THREAD_FUNNELED), in theory mpi4py.futures cannot be used. Rather than raising an exception, mpi4py.futures emits a warning and takes a "cross-fingers" attitude to continue execution in the hope that serializing MPI calls with a global lock will actually work.

7.2 MPICommExecutor

Legacy MPI-1 implementations (as well as some vendor MPI-2 implementations) do not support the dynamic process management features introduced in the MPI-2 standard. Additionally, job schedulers and batch systems in supercomputing facilities may pose additional complications to applications using the MPI_Comm_spawn() routine.

With these issues in mind, <code>mpi4py.futures</code> supports an additional, more traditional, SPMD-like usage pattern requiring MPI-1 calls only. Python applications are started the usual way, e.g., using the <code>mpiexec</code> command. Python code should make a collective call to the <code>MPICommExecutor</code> context manager to partition the set of MPI processes within a MPI communicator in one master processes and many workers processes. The master process gets access to an <code>MPIPoolExecutor</code> instance to submit tasks. Meanwhile, the worker process follow a different execution path and team-up to execute the tasks submitted from the master.

Besides alleviating the lack of dynamic process management features in legacy MPI-1 or partial MPI-2 implementations, the <code>MPICommExecutor</code> context manager may be useful in classic MPI-based Python applications willing to take advantage of the simple, task-based, master/worker approach available in the <code>mpi4py.futures</code> package.

```
class mpi4py.futures.MPICommExecutor(comm=None, root=0)
```

Context manager for MPIPoolExecutor. This context manager splits a MPI (intra)communicator comm (defaults to MPI.COMM_WORLD if not provided or None) in two disjoint sets: a single master process (with rank root in comm) and the remaining worker processes. These sets are then connected through an intercommunicator. The target of the with statement is assigned either an MPIPoolExecutor instance (at the master) or None (at the workers).

```
from mpi4py import MPI
from mpi4py.futures import MPICommExecutor

with MPICommExecutor(MPI.COMM_WORLD, root=0) as executor:
    if executor is not None:
        future = executor.submit(abs, -42)
```

(continues on next page)

(continued from previous page)

```
assert future.result() == 42
answer = set(executor.map(abs, [-42, 42]))
assert answer == {42}
```

Warning

If <code>MPICommExecutor</code> is passed a communicator of size one (e.g., <code>MPI.COMM_SELF</code>), then the executor instance assigned to the target of the <code>with</code> statement will execute all submitted tasks in a single worker thread, thus ensuring that task execution still progress asynchronously. However, the GIL will prevent the main and worker threads from running concurrently in multicore processors. Moreover, the thread context switching may harm noticeably the performance of CPU-bound tasks. In case of I/O-bound tasks, the GIL is not usually an issue, however, as a single worker thread is used, it progress one task at a time. We advice against using <code>MPICommExecutor</code> with communicators of size one and suggest refactoring your code to use instead a <code>ThreadPoolExecutor</code>.

7.3 Command line

Recalling the issues related to the lack of support for dynamic process management features in MPI implementations, <code>mpi4py.futures</code> supports an alternative usage pattern where Python code (either from scripts, modules, or zip files) is run under command line control of the <code>mpi4py.futures</code> package by passing <code>-m mpi4py.futures</code> to the <code>python</code> executable. The <code>mpi4py.futures</code> invocation should be passed a <code>pyfile</code> path to a script (or a zipfile/directory containing a <code>__main__.py</code> file). Additionally, <code>mpi4py.futures</code> accepts <code>-m mod</code> to execute a module named <code>mod</code>, <code>-c cmd</code> to execute a command string <code>cmd</code>, or even <code>-</code> to read commands from standard input (<code>sys.stdin</code>). Summarizing, <code>mpi4py.futures</code> can be invoked in the following ways:

```
$ mpiexec -n numprocs python -m mpi4py.futures pyfile [arg] ...
$ mpiexec -n numprocs python -m mpi4py.futures -m mod [arg] ...
$ mpiexec -n numprocs python -m mpi4py.futures -c cmd [arg] ...
$ mpiexec -n numprocs python -m mpi4py.futures - [arg] ...
```

Before starting the main script execution, <code>mpi4py.futures</code> splits <code>MPI.COMM_WORLD</code> in one master (the process with rank 0 in <code>MPI.COMM_WORLD</code>) and <code>numprocs - 1</code> workers and connects them through an MPI intercommunicator. Afterwards, the master process proceeds with the execution of the user script code, which eventually creates <code>MPIPoolExecutor</code> instances to submit tasks. Meanwhile, the worker processes follow a different execution path to serve the master. Upon successful termination of the main script at the master, the entire MPI execution environment exists gracefully. In case of any unhandled exception in the main script, the master process calls <code>MPI.COMM_WORLD</code>. Abort(1) to prevent deadlocks and force termination of entire MPI execution environment.

Warning

Running scripts under command line control of *mpi4py.futures* is quite similar to executing a single-process application that spawn additional workers as required. However, there is a very important difference users should be aware of. All *MPIPoolExecutor* instances created at the master will share the pool of workers. Tasks submitted at the master from many different executors will be scheduled for execution in random order as soon as a worker is idle. Any executor can easily starve all the workers (e.g., by calling *MPIPoolExecutor.map()* with long iterables). If that ever happens, submissions from other executors will not be serviced until free workers are available.

See also

Command line

Documentation on Python command line interface.

7.4 Parallel tasks

The *mpi4py.futures* package favors an embarrassingly parallel execution model involving a series of sequential tasks independent of each other and executed asynchronously. Albeit unnatural, *MPIPoolExecutor* can still be used for handling workloads involving parallel tasks, where worker processes communicate and coordinate each other via MPI

```
mpi4py.futures.get_comm_workers()
```

Access an intracommunicator grouping MPI worker processes.

Executing parallel tasks with mpi4py. futures requires following some rules, cf. highlighted lines in example cpi.py:

- Use MPIPoolExecutor.num_workers to determine the number of worker processes in the executor and submit exactly one callable per worker process using the MPIPoolExecutor.submit() method.
- The submitted callable must use get_comm_workers() to access an intracommunicator grouping MPI worker processes. Afterwards, it is highly recommended calling the Barrier() method on the communicator. The barrier synchronization ensures that every worker process is executing the submitted callable exactly once. Afterwards, the parallel task can safely perform any kind of point-to-point or collective operation using the returned communicator.
- The Future instances returned by MPIPoolExecutor.submit() should be collected in a sequence. Use wait() with the sequence of Future instances to ensure logical completion of the parallel task.

7.5 Utilities

The *mpi4py*. *futures* package provides additional utilities for handling Future instances.

```
mpi4py.futures.collect(fs)
```

Gather a collection of futures in a new future.

Parameters

fs – Collection of futures.

Returns

New future producing as result a list with results from fs.

mpi4py.futures.compose(future, resulthook=None, excepthook=None)

Compose the completion of a future with result and exception handlers.

Parameters

- **future** Input future instance.
- **resulthook** Function to be called once the input future completes with success. Once the input future finish running with success, its result value is the input argument for *resulthook*. The result of *resulthook* is set as the result of the output future. If *resulthook* is None, the output future is completed directly with the result of the input future.

• **excepthook** – Function to be called once the input future completes with failure. Once the input future finish running with failure, its exception value is the input argument for *excepthook*. If *excepthook* returns an Exception instance, it is set as the exception of the output future. Otherwise, the result of *excepthook* is set as the result of the output future. If *excepthook* is None, the output future is set as failed with the exception from the input future.

Returns

Output future instance to be completed once the input future is completed and either *resulthook* or *excepthook* finish executing.

7.6 Examples

Computing the Julia set

The following *julia.py* script computes the Julia set and dumps an image to disk in binary PGM format. The code starts by importing *MPIPoolExecutor* from the *mpi4py.futures* package. Next, some global constants and functions implement the computation of the Julia set. The computations are protected with the standard if __name__ == '__main__': ... idiom. The image is computed by whole scanlines submitting all these tasks at once using the *map* method. The result iterator yields scanlines in-order as the tasks complete. Finally, each scanline is dumped to disk.

Listing 1: julia.py

```
from mpi4py.futures import MPIPoolExecutor
2
   x0, x1, w = -2.0, +2.0, 640*2
   y0, y1, h = -1.5, +1.5, 480*2
   dx = (x1 - x0) / w
   dy = (y1 - y0) / h
   c = complex(0, 0.65)
   def julia(x, y):
10
       z = complex(x, y)
11
       n = 255
12
       while abs(z) < 3 and n > 1:
            z = z^{**}2 + c
14
           n -= 1
15
       return n
16
17
   def julia_line(k):
18
       line = bytearray(w)
19
       y = y1 - k * dy
20
       for j in range(w):
21
            x = x0 + j * dx
22
            line[j] = julia(x, y)
23
       return line
24
25
      __name__ == '__main__':
   if
26
27
       with MPIPoolExecutor() as executor:
28
            image = executor.map(julia_line, range(h))
29
            with open('julia.pgm', 'wb') as f:
```

(continues on next page)

```
f.write(b'P5 %d %d %d\n' % (w, h, 255))

for line in image:
f.write(line)
```

The recommended way to execute the script is by using the **mpiexec** command specifying one MPI process (master) and (optional but recommended) the desired MPI universe size, which determines the number of additional dynamically spawned processes (workers). The MPI universe size is provided either by a batch system or set by the user via command-line arguments to **mpiexec** or environment variables. Below we provide examples for MPICH and Open MPI implementations¹. In all of these examples, the **mpiexec** command launches a single master process running the Python interpreter and executing the main script. When required, **mpi4py.futures** spawns the pool of 16 worker processes. The master submits tasks to the workers and waits for the results. The workers receive incoming tasks, execute them, and send back the results to the master.

When using MPICH implementation or its derivatives based on the Hydra process manager, users can set the MPI universe size via the -usize argument to **mpiexec**:

```
$ mpiexec -n 1 -usize 17 python julia.py
```

or, alternatively, by setting the MPIEXEC_UNIVERSE_SIZE environment variable:

```
$ env MPIEXEC_UNIVERSE_SIZE=17 mpiexec -n 1 python julia.py
```

In the Open MPI implementation, the MPI universe size can be set via the -host argument to mpiexec:

```
$ mpiexec -n 1 -host localhost:17 python julia.py
```

Another way to specify the number of workers is to use the <code>mpi4py.futures</code>-specific environment variable <code>MPI4PY_FUTURES_MAX_WORKERS</code>:

```
$ env MPI4PY_FUTURES_MAX_WORKERS=16 mpiexec -n 1 python julia.py
```

Note that in this case, the MPI universe size is ignored.

Alternatively, users may decide to execute the script in a more traditional way, that is, all the MPI processes are started at once. The user script is run under command-line control of *mpi4py.futures* passing the -m flag to the **python** executable:

```
$ mpiexec -n 17 python -m mpi4py.futures julia.py
```

As explained previously, the 17 processes are partitioned in one master and 16 workers. The master process executes the main script while the workers execute the tasks submitted by the master.

Computing Pi (parallel task)

The number π can be approximated via numerical integration with the simple midpoint rule, that is:

$$\pi = \int_0^1 \frac{4}{1+x^2} \, dx \approx \frac{1}{n} \sum_{i=1}^n \frac{4}{1+\left[\frac{1}{n}\left(i-\frac{1}{2}\right)\right]^2}.$$

The following *cpi.py* script computes such approximations using *mpi4py.futures* with a parallel task involving a collective reduction operation. Highlighted lines correspond to the rules discussed in *Parallel tasks*.

¹ When using an MPI implementation other than MPICH or Open MPI, please check the documentation of the implementation and/or batch system for the ways to specify the desired MPI universe size.

Listing 2: cpi.py

```
import math
   import sys
   from mpi4py.futures import MPIPoolExecutor, wait
   from mpi4py.futures import get_comm_workers
6
   def compute_pi(n):
        # Access intracommunicator and synchronize
       comm = get_comm_workers()
       comm.Barrier()
10
11
       rank = comm.Get_rank()
12
       size = comm.Get_size()
13
14
        # Local computation
15
       h = 1.0 / n
16
       s = 0.0
17
       for i in range(rank + 1, n + 1, size):
18
            x = h * (i - 0.5)
19
            s += 4.0 / (1.0 + x**2)
20
       pi_partial = s * h
21
22
        # Parallel reduce-to-all
23
       pi = comm.allreduce(pi_partial)
24
25
       # All workers return the same value
26
       return pi
27
29
   if __name__ == '__main__':
       n = int(sys.argv[1]) if len(sys.argv) > 1 else 256
31
32
       with MPIPoolExecutor() as executor:
33
            # Submit exactly one callable per worker
            P = executor.num_workers
35
            fs = [executor.submit(compute_pi, n) for _ in range(P)]
36
37
            # Wait for all workers to finish
38
           wait(fs)
40
            # Get result from the first future object.
41
            # In this particular example, due to using reduce-to-all,
42
            # all the other future objects hold the same result value.
           pi = fs[0].result()
44
           print(
                f"pi: {pi:.16f}, error: {abs(pi - math.pi):.3e}",
46
                f"({n:d} intervals, {P:d} workers)",
47
            )
48
```

To run in modern MPI-2 mode:

```
$ env MPI4PY_FUTURES_MAX_WORKERS=4 mpiexec -n 1 python cpi.py 128
pi: 3.1415977398528137, error: 5.086e-06 (128 intervals, 4 workers)
$ env MPI4PY_FUTURES_MAX_WORKERS=8 mpiexec -n 1 python cpi.py 512
pi: 3.1415929714812316, error: 3.179e-07 (512 intervals, 8 workers)
```

To run in legacy MPI-1 mode:

```
$ mpiexec -n 5 python -m mpi4py.futures cpi.py 128
pi: 3.1415977398528137, error: 5.086e-06 (128 intervals, 4 workers)

$ mpiexec -n 9 python -m mpi4py.futures cpi.py 512
pi: 3.1415929714812316, error: 3.179e-07 (512 intervals, 8 workers)
```

7.7 Citation

If *mpi4py.futures* been significant to a project that leads to an academic publication, please acknowledge our work by citing the following article [mpi4py-futures]:

8 mpi4py.util

Added in version 3.1.0.

The mpi4py.util package collects miscellaneous utilities within the intersection of Python and MPI.

8.1 mpi4py.util.dtlib

```
Added in version 3.1.0.
```

The mpi4py.util.dtlib module provides converter routines between NumPy and MPI datatypes.

```
mpi4py.util.dtlib.from_numpy_dtype(dtype)
```

Convert NumPy datatype to MPI datatype.

```
Parameters
```

dtype (*DTypeLike*) – NumPy dtype-like object.

Return type

Datatype

mpi4py.util.dtlib.to_numpy_dtype(datatype)

Convert MPI datatype to NumPy datatype.

Parameters

datatype (Datatype) – MPI datatype.

Return type

dtype[Any]

8.2 mpi4py.util.pkl5

Added in version 3.1.0.

pickle protocol 5 (see PEP 574) introduced support for out-of-band buffers, allowing for more efficient handling of certain object types with large memory footprints.

MPI for Python uses the traditional in-band handling of buffers. This approach is appropriate for communicating non-buffer Python objects, or buffer-like objects with small memory footprints. For point-to-point communication, in-band buffer handling allows for the communication of a pickled stream with a single MPI message, at the expense of additional CPU and memory overhead in the pickling and unpickling steps.

The mpi4py.util.pkl5 module provides communicator wrapper classes reimplementing pickle-based point-to-point and collective communication methods using pickle protocol 5. Handling out-of-band buffers necessarily involves multiple MPI messages, thus increasing latency and hurting performance in case of small size data. However, in case of large size data, the zero-copy savings of out-of-band buffer handling more than offset the extra latency costs. Additionally, these wrapper methods overcome the infamous 2 GiB message count limit (MPI-1 to MPI-3).

Note

Support for pickle protocol 5 is available in the pickle module within the Python standard library since Python 3.8. Previous Python 3 releases can use the pickle5 backport, which is available on PyPI and can be installed with:

python -m pip install pickle5

class mpi4py.util.pkl5.Request

Request.

Custom request class for nonblocking communications.

Note

Request is not a subclass of mpi4py.MPI.Request

Free()

Free a communication request.

Return type

None

free()

Free a communication request.

Return type

None

cancel()

Cancel a communication request.

Return type

None

get_status(status=None)

Non-destructive test for the completion of a request.

```
Parameters
                  status (Status | None)
              Return type
                  bool
     test(status=None)
          Test for the completion of a request.
              Parameters
                  status (Status | None)
              Return type
                  tuple[bool, Any | None]
     wait(status=None)
          Wait for a request to complete.
              Parameters
                  status (Status | None)
              Return type
                  Any
     classmethod get_status_all(requests, statuses=None)
          Non-destructive test for the completion of all requests.
              Classmethod
     classmethod testall(requests, statuses=None)
          Test for the completion of all requests.
              Classmethod
     classmethod waitall(requests, statuses=None)
          Wait for all requests to complete.
              Classmethod
class mpi4py.util.pkl5.Message
     Message.
     Custom message class for matching probes.
       Note
       Message is not a subclass of mpi4py.MPI.Message
     free()
          Do nothing.
              Return type
                  None
     recv(status=None)
          Blocking receive of matched message.
              Parameters
                  status (Status | None)
```

```
Return type
```

Any

irecv()

Nonblocking receive of matched message.

Return type

Request

classmethod probe(*comm*, *source=ANY_SOURCE*, *tag=ANY_TAG*, *status=None*) Blocking test for a matched message.

Classmethod

classmethod iprobe(*comm*, *source=ANY_SOURCE*, *tag=ANY_TAG*, *status=None*)

Nonblocking test for a matched message.

Classmethod

class mpi4py.util.pkl5.Comm

Communicator.

Base communicator wrapper class.

send(obj, dest, tag=0)

Blocking send in standard mode.

Parameters

- **obj** (*Any*)
- dest(int)
- **tag** (*int*)

Return type

None

bsend(*obj*, *dest*, *tag*=0)

Blocking send in buffered mode.

Parameters

- **obj** (*Any*)
- dest (int)
- tag(int)

Return type

None

ssend(obj, dest, tag=0)

Blocking send in synchronous mode.

Parameters

- **obj** (*Any*)
- dest(int)
- **tag** (*int*)

Return type

```
isend(obj, dest, tag=0)
```

Nonblocking send in standard mode.

Parameters

- **obj** (*Any*)
- dest(int)
- tag(int)

Return type

Request

ibsend(obj, dest, tag=0)

Nonblocking send in buffered mode.

Parameters

- **obj** (*Any*)
- dest (int)
- **tag** (*int*)

Return type

Request

issend(obj, dest, tag=0)

Nonblocking send in synchronous mode.

Parameters

- obj (Any)
- dest (int)
- **tag** (*int*)

Return type

Request

recv(buf=None, source=ANY_SOURCE, tag=ANY_TAG, status=None) Blocking receive.

Parameters

- buf (Buffer / None)
- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

Any

irecv(buf=None, source=ANY_SOURCE, tag=ANY_TAG)

Nonblocking receive.

Warning

This method cannot be supported reliably and raises RuntimeError.

```
Parameters
```

- **buf** (Buffer / None)
- source (int)
- **tag** (*int*)

Return type

Request

sendrecv(sendobj, dest, sendtag=0, recvbuf=None, source=ANY_SOURCE, recvtag=ANY_TAG, status=None)

Send and receive.

Parameters

- sendobj (Any)
- dest (int)
- sendtag (int)
- recvbuf (Buffer / None)
- source (int)
- recvtag(int)
- status (Status | None)

Return type

Any

mprobe(source=ANY_SOURCE, tag=ANY_TAG, status=None)

Blocking test for a matched message.

Parameters

- source (int)
- tag(int)
- status (Status | None)

Return type

Message

improbe(source=ANY_SOURCE, tag=ANY_TAG, status=None)

Nonblocking test for a matched message.

Parameters

- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

Message | None

bcast(obj, root=0)

Broadcast.

Added in version 3.1.0.

```
Parameters
```

- **obj** (*Any*)
- root (int)

Return type

Any

gather(sendobj, root=0)

Gather.

Added in version 4.0.0.

Parameters

- sendobj (Any)
- root (int)

Return type

list[Any] | None

scatter(sendobj, root=0)

Scatter.

Added in version 4.0.0.

Parameters

- sendobj (Sequence[Any] | None)
- root (int)

Return type

Any

allgather(sendobj)

Gather to All.

Added in version 4.0.0.

Parameters

sendobj (Any)

Return type

list[*Any*]

alltoall(sendobj)

All to All Scatter/Gather.

Added in version 4.0.0.

Parameters

sendobj (Sequence[Any])

Return type

list[Any]

class mpi4py.util.pkl5.Intracomm

Intracommunicator.

Intracommunicator wrapper class.

class mpi4py.util.pkl5.Intercomm

Intercommunicator.

Intercommunicator wrapper class.

Examples

Listing 3: test-pkl5-1.py

```
import numpy as np
   from mpi4py import MPI
   from mpi4py.util import pkl5
   comm = pkl5.Intracomm(MPI.COMM_WORLD) # comm wrapper
   size = comm.Get_size()
   rank = comm.Get_rank()
   dst = (rank + 1) \% size
   src = (rank - 1) \% size
9
   sobj = np.full(1024**3, rank, dtype='i4') # > 4 GiB
11
   sreq = comm.isend(sobj, dst, tag=42)
   robj = comm.recv (None, src, tag=42)
13
   sreq.Free()
14
15
   assert np.min(robj) == src
16
   assert np.max(robj) == src
```

Listing 4: test-pkl5-2.py

```
import numpy as np
   from mpi4py import MPI
   from mpi4py.util import pkl5
   comm = pkl5.Intracomm(MPI.COMM_WORLD) # comm wrapper
   size = comm.Get_size()
   rank = comm.Get_rank()
   dst = (rank + 1) \% size
   src = (rank - 1) \% size
   sobj = np.full(1024**3, rank, dtype='i4') # > 4 GiB
11
   sreq = comm.isend(sobj, dst, tag=42)
12
13
   status = MPI.Status()
  rmsg = comm.mprobe(status=status)
15
   assert status.Get_source() == src
16
   assert status.Get_tag() == 42
   rreq = rmsg.irecv()
18
   robj = rreq.wait()
19
20
   sreq.Free()
21
   assert np.max(robj) == src
22
   assert np.min(robj) == src
```

8.3 mpi4py.util.pool

Added in version 4.0.0.

See also

This module intends to be a drop-in replacement for the multiprocessing.pool interface from the Python standard library. The *Pool* class exposed here is implemented as a thin wrapper around *MPIPoolExecutor*.

Note

The *mpi4py.futures* package offers a higher level interface for asynchronously pushing tasks to MPI worker process, allowing for a clear separation between submitting tasks and waiting for the results.

class mpi4py.util.pool.Pool

Pool using MPI processes as workers.

```
__init__(processes=None, initializer=None, initargs=(), **kwargs)
```

Initialize a new Pool instance.

Parameters

- processes (int / None) Number of worker processes.
- initializer (Callable[[...], None] | None) An callable used to initialize workers processes.
- initargs (Iterable [Any]) A tuple of arguments to pass to the initializer.
- kwargs (Any)

Return type

None

Note

Additional keyword arguments are passed down to the MPIPoolExecutor constructor.

Warning

The *maxtasksperchild* and *context* arguments of multiprocessing.pool.Pool are not supported. Specifying *maxtasksperchild* or *context* with a value other than None will issue a warning of category UserWarning.

```
apply(func, args=(), kwds={})
```

Call func with arguments args and keyword arguments kwds.

Equivalent to func(*args, **kwds).

Parameters

- **func** (Callable[[...], T])
- args (Iterable[Any])

```
• kwds (Mapping[str, Any])
```

Return type

7

apply_async(func, args=(), kwds={}, callback=None, error_callback=None)

Asynchronous version of apply() returning ApplyResult.

Parameters

- **func** (Callable[..., T])
- args (Iterable[Any])
- kwds (Mapping[str, Any])
- callback (Callable[[T], object] | None)
- error_callback (Callable[[BaseException], object] | None)

Return type

AsyncResult[T]

map(func, iterable, chunksize=None)

Apply func to each element in iterable.

Equivalent to list(map(func, iterable)).

Block until all results are ready and return them in a list.

The *iterable* is choped into a number of chunks which are submitted as separate tasks. The (approximate) size of these chunks can be specified by setting *chunksize* to a positive integer.

Consider using *imap()* or *imap_unordered()* with explicit *chunksize* for better efficiency.

Parameters

- func (Callable[[S], T])
- iterable (Iterable[S])
- chunksize (int | None)

Return type

list[T]

map_async(func, iterable, chunksize=None, callback=None, error_callback=None)

Asynchronous version of map() returning MapResult.

Parameters

- func (Callable[[S], T])
- iterable (Iterable[S])
- chunksize (int | None)
- callback (Callable[[T], None] | None)
- error_callback (Callable[[BaseException], None] | None)

Return type

MapResult[T]

```
imap(func, iterable, chunksize=1)
     Like map() but return an iterator.
     Equivalent to map(func, iterable).
         Parameters
             • func (Callable[[S], T])
             • iterable (Iterable[S])
             • chunksize (int)
         Return type
             Iterator[T]
imap_unordered(func, iterable, chunksize=1)
     Like imap() but ordering of results is arbitrary.
         Parameters
             • func (Callable [[S], T])
             • iterable (Iterable [S])
             • chunksize (int)
         Return type
             Iterator[T]
starmap(func, iterable, chunksize=None)
     Apply func to each argument tuple in iterable.
     Equivalent to list(itertools.starmap(func, iterable)).
     Block until all results are ready and return them in a list.
     The iterable is choped into a number of chunks which are submitted as separate tasks. The (approximate)
     size of these chunks can be specified by setting chunksize to a positive integer.
     Consider using istarmap() or istarmap_unordered() with explicit chunksize for better efficiency.
         Parameters
             • func (Callable[[...], T])
             • iterable (Iterable [Iterable [Any]])
             • chunksize (int | None)
         Return type
             list[T]
starmap_async(func, iterable, chunksize=None, callback=None, error_callback=None)
     Asynchronous version of starmap() returning MapResult.
         Parameters
             • func (Callable[..., T])
             • iterable (Iterable [Iterable [Any]])
             • chunksize (int | None)
             • callback (Callable[[T], None] | None)
```

• error_callback (Callable[[BaseException], None] | None)

```
Return type
                  MapResult[T]
     istarmap(func, iterable, chunksize=1)
          Like starmap() but return an iterator.
          Equivalent to itertools.starmap(func, iterable).
              Parameters
                  • func (Callable[[...], T])
                  • iterable (Iterable [Iterable [Any]])
                  • chunksize (int)
              Return type
                  Iterator[T]
     istarmap_unordered(func, iterable, chunksize=1)
          Like istarmap() but ordering of results is arbitrary.
              Parameters
                  • func (Callable[[...], T])
                  • iterable (Iterable [Iterable [Any]])
                  • chunksize (int)
              Return type
                  Iterator[T]
     close()
          Prevent any more tasks from being submitted to the pool.
              Return type
                  None
     terminate()
          Stop the worker processes without completing pending tasks.
              Return type
                  None
     join()
          Wait for the worker processes to exit.
              Return type
                  None
class mpi4py.util.pool.ThreadPool
     Bases: Pool
     Pool using threads as workers.
class mpi4py.util.pool.AsyncResult
```

Asynchronous result.

get(timeout=None)

Return the result when it arrives.

If timeout is not None and the result does not arrive within timeout seconds then raise TimeoutError.

If the remote call raised an exception then that exception will be reraised.

```
Parameters
                  timeout (float | None)
              Return type
     wait(timeout=None)
          Wait until the result is available or timeout seconds pass.
              Parameters
                  timeout(float | None)
              Return type
                  None
     ready()
          Return whether the call has completed.
              Return type
                  bool
     successful()
          Return whether the call completed without raising an exception.
          If the result is not ready then raise ValueError.
              Return type
                  bool
class mpi4py.util.pool.ApplyResult
     Bases: AsyncResult
     Result type of apply_async().
class mpi4py.util.pool.MapResult
     Bases: AsyncResult
     Result type of map_async() and starmap_async().
8.4 mpi4py.util.sync
```

Added in version 4.0.0.

The mpi4py.util.sync module provides parallel synchronization utilities.

Sequential execution

```
class mpi4py.util.sync.Sequential
```

Sequential execution.

Context manager for sequential execution within a group of MPI processes.

The implementation is based in MPI-1 point-to-point communication. A process with rank i waits in a blocking receive until the previous process rank i-1 finish executing and signals the next rank i with a send.

```
__init__(comm, tag=0)
```

Initialize sequential execution.

Parameters

```
• comm (Intracomm) – Intracommunicator context.
```

• tag (int) – Tag for point-to-point communication.

Return type

None

__enter__()

Enter sequential execution.

Return type

Self

__exit__(*exc)

Exit sequential execution.

Parameters

exc (object)

Return type

None

begin()

Begin sequential execution.

Return type

None

end()

End sequential execution.

Return type

None

Global counter

class mpi4py.util.sync.Counter

Global counter.

Produce consecutive values within a group of MPI processes. The counter interface is close to that of itertools.count.

The implementation is based in MPI-3 one-sided operations. A root process (typically rank 0) holds the counter, and its value is queried and incremented with an atomic RMA *fetch-and-add* operation.

__init__(start=0, step=1, *, typecode='i', comm=COMM_SELF, info=INFO_NULL, root=0)
Initialize global counter.

Parameters

- start (int) Start value.
- **step** (*int*) Increment value.
- **typecode** (*str*) Type code as defined in the array module.
- **comm** (Intracomm) Intracommunicator context.
- **info** (Info) Info object for RMA context creation.
- **root** (*int*) Process rank holding the counter memory.

```
Return type
             None
__iter__()
     Implement iter(self).
         Return type
             Self
__next__()
     Implement next(self).
         Return type
             int
next(incr=None)
     Return current value and increment.
         Parameters
             incr (int | None) - Increment value.
         Returns
             The counter value before incrementing.
         Return type
             int
free()
     Free counter resources.
         Return type
             None
```

Mutual exclusion

```
class mpi4py.util.sync.Mutex
```

Parameters

Mutual exclusion.

Establish a critical section or mutual exclusion among MPI processes.

The mutex interface is close to that of threading.Lock and threading.RLock, allowing the use of either recursive or non-recursive mutual exclusion. However, a mutex should be used within a group of MPI processes, not threads.

In non-recursive mode, the semantics of *Mutex* are somewhat different than these of threading.Lock:

- Once acquired, a mutex is held and owned by a process until released.
- Trying to acquire a mutex already held raises RuntimeError.
- Trying to release a mutex not yet held raises RuntimeError.

This mutex implementation uses the scalable and fair spinlock algorithm from [mcs-paper] and took inspiration from the MPI-3 RMA implementation of [uam-book].

```
__init__(*, recursive=False, comm=COMM_SELF, info=INFO_NULL)
Initialize mutex object.
```

• comm (Intracomm) – Intracommunicator context.

- $\mathbf{recursive}\ (bool)$ Whether to allow recursive acquisition.
- info (Info) Info object for RMA context creation.

Return type

None

__enter__()

Acquire mutex.

Return type

Self

__exit__(*exc)

Release mutex.

Parameters

exc (object)

Return type

None

acquire(blocking=True)

Acquire mutex, blocking or non-blocking.

Parameters

blocking (*bool*) – If True, block until the mutex is held.

Returns

True if the mutex is held, False otherwise.

Return type

bool

release()

Release mutex.

Return type

None

locked()

Return whether the mutex is held.

Return type

bool

count()

Return the recursion count.

Return type

int

free()

Free mutex resources.

Return type

Condition variable

```
class mpi4py.util.sync.Condition
```

Condition variable.

A condition variable allows one or more MPI processes to wait until they are notified by another processes.

The condition variable interface is close to that of threading. Condition, allowing the use of either recursive or non-recursive mutual exclusion. However, the condition variable should be used within a group of MPI processes, not threads.

This condition variable implementation uses a MPI-3 RMA-based scalable and fair circular queue algorithm to track the set of waiting processes.

```
__init__(mutex=None, *, recursive=True, comm=COMM_SELF, info=INFO_NULL)
Initialize condition variable.
```

Parameters

- mutex (Mutex / None) Mutual exclusion object.
- **recursive** (*bool*) Whether to allow recursive acquisition.
- comm (Intracomm) Intracommunicator context.
- info (Info) Info object for RMA context creation.

Return type

None

```
__enter__()
```

Acquire the underlying mutex.

Return type

Self

```
__exit__(*exc)
```

Release the underlying mutex.

Parameters

exc (object)

Return type

None

acquire(blocking=True)

Acquire the underlying mutex.

Parameters

blocking (bool)

Return type

bool

release()

Release the underlying mutex.

Return type

```
locked()
```

Return whether the underlying mutex is held.

Return type

bool

wait()

Wait until notified by another process.

Returns

Always True.

Return type

Literal[True]

wait_for(predicate)

Wait until a predicate evaluates to True.

Parameters

predicate (Callable[[], T]) - callable returning a boolean.

Returns

The result of predicate once it evaluates to True.

Return type

T

notify(n=1)

Wake up one or more processes waiting on this condition.

Parameters

n (*int*) – Maximum number of processes to wake up.

Returns

The actual number of processes woken up.

Return type

int

notify_all()

Wake up all processes waiting on this condition.

Returns

The actual number of processes woken up.

Return type

int

free()

Free condition resources.

Return type

Semaphore object

```
class mpi4py.util.sync.Semaphore
```

Semaphore object.

A semaphore object manages an internal counter which is decremented by each acquire() call and incremented by each release() call. The internal counter never reaches a value below zero; when acquire() finds that it is zero, it blocks and waits until some other process calls release().

The semaphore interface is close to that of threading. Semaphore and threading. BoundedSemaphore, allowing the use of either bounded (default) or unbounded semaphores. With a bounded semaphore, the internal counter never exceeds its initial value; otherwise *release()* raises ValueError.

This semaphore implementation uses a global *Counter* and a *Condition* variable to handle waiting and and notification.

```
__init__(value=1, *, bounded=True, comm=COMM_SELF, info=INFO_NULL)
Initialize semaphore object.
```

Parameters

- value (int) Initial value for internal counter.
- **bounded** (*boo1*) Bound internal counter to initial value.
- comm (Intracomm) Intracommunicator context.
- **info** (Info) Info object for RMA context creation.

Return type

None

```
__enter__()
```

Acquire semaphore.

Return type

Self

__exit__(*exc)

Release semaphore.

Parameters

exc (object)

Return type

None

acquire(blocking=True)

Acquire semaphore, decrementing the internal counter by one.

Parameters

blocking (*bool*) – If True, block until the semaphore is acquired.

Returns

True if the semaphore is acquired, False otherwise.

Return type

bool

release(n=1)

Release semaphore, incrementing the internal counter by one or more.

Parameters

n (*int*) – Increment for the internal counter.

Return type

None

free()

Free semaphore resources.

Return type

None

Examples

Listing 5: test-sync-1.py

```
from mpi4py import MPI
from mpi4py.util.sync import Counter, Sequential

comm = MPI.COMM_WORLD

counter = Counter(comm)
with Sequential(comm):
   value = next(counter)
counter.free()

assert comm.rank == value
```

Listing 6: test-sync-2.py

```
from mpi4py import MPI
   from mpi4py.util.sync import Counter, Mutex
   comm = MPI.COMM_WORLD
   mutex = Mutex(comm)
   counter = Counter(comm)
   with mutex:
      value = next(counter)
   counter.free()
   mutex.free()
11
   assert (
13
      list(range(comm.size)) ==
      sorted(comm.allgather(value))
15
   )
16
```

9 mpi4py.run

Added in version 3.0.0.

At import time, <code>mpi4py</code> initializes the MPI execution environment calling <code>MPI_Init_thread()</code> and installs an exit hook to automatically call <code>MPI_Finalize()</code> just before the Python process terminates. Additionally, <code>mpi4py</code> overrides the default <code>ERRORS_ARE_FATAL</code> error handler in favor of <code>ERRORS_RETURN</code>, which allows translating MPI errors in Python exceptions. These departures from standard MPI behavior may be controversial, but are quite convenient within the highly dynamic Python programming environment. Third-party code using <code>mpi4py</code> can just <code>from mpi4py</code> import <code>MPI</code> and perform MPI calls without the tedious initialization/finalization handling. MPI errors, once translated automatically to Python exceptions, can be dealt with the common <code>try...except...finally</code> clauses; unhandled MPI exceptions will print a traceback which helps in locating problems in source code.

Unfortunately, the interplay of automatic MPI finalization and unhandled exceptions may lead to deadlocks. In unattended runs, these deadlocks will drain the battery of your laptop, or burn precious allocation hours in your supercomputing facility.

9.1 Exceptions and deadlocks

Consider the following snippet of Python code. Assume this code is stored in a standard Python script file and run with **mpiexec** in two or more processes.

Listing 7: deadlock.py

Process 0 raises ZeroDivisionError exception before performing a send call to process 1. As the exception is not handled, the Python interpreter running in process 0 will proceed to exit with non-zero status. However, as *mpi4py* installed a finalize hook to call MPI_Finalize() before exit, process 0 will block waiting for other processes to also enter the MPI_Finalize() call. Meanwhile, process 1 will block waiting for a message to arrive from process 0, thus never reaching to MPI_Finalize(). The whole MPI execution environment is irremediably in a deadlock state.

To alleviate this issue, *mpi4py* offers a simple, alternative command line execution mechanism based on using the -m flag and implemented with the runpy module. To use this features, Python code should be run passing -m mpi4py in the command line invoking the Python interpreter. In case of unhandled exceptions, the finalizer hook will call MPI_Abort() on the MPI_COMM_WORLD communicator, thus effectively aborting the MPI execution environment.

Warning

When a process is forced to abort, resources (e.g. open files) are not cleaned-up and any registered finalizers (either with the atexit module, the Python C/API function Py_AtExit(), or even the C standard library function atexit()) will not be executed. Thus, aborting execution is an extremely impolite way of ensuring process termination. However, MPI provides no other mechanism to recover from a deadlock state.

9.2 Command line

The use of -m mpi4py to execute Python code on the command line resembles that of the Python interpreter.

- mpiexec -n numprocs python -m mpi4py pyfile [arg] ...
- mpiexec -n numprocs python -m mpi4py -m mod [arg] ...
- mpiexec -n numprocs python -m mpi4py -c cmd [arg] ...
- mpiexec -n numprocs python -m mpi4py [arg] ...

<pyfile>

Execute the Python code contained in *pyfile*, which must be a filesystem path referring to either a Python file, a directory containing a __main__.py file, or a zipfile containing a __main__.py file.

-m < mod >

Search sys.path for the named module *mod* and execute its contents.

-c <cmd>

Execute the Python code in the *cmd* string command.

Read commands from standard input (sys.stdin).

See also

Command line

Documentation on Python command line interface.

10 mpi4py.bench

Added in version 3.0.0.

11 Reference

mpi4py.MPI

Message Passing Interface.

11.1 mpi4py.MPI

Message Passing Interface.

Classes

BottomType	Type of BOTTOM.
BufferAutomaticType	Type of BUFFER_AUTOMATIC.
Cartcomm	Cartesian topology intracommunicator.
Comm	Communication context.
Datatype	Datatype object.
Distgraphcomm	Distributed graph topology intracommunicator.
Errhandler	Error handler.
File	File I/O context.
Graphcomm	General graph topology intracommunicator.
Grequest	Generalized request handler.
Group	Group of processes.
InPlaceType	Type of IN_PLACE.
Info	Info object.
Intercomm	Intercommunicator.
Intracomm	Intracommunicator.
Message	Matched message.
Ор	Reduction operation.
Pickle	Pickle/unpickle Python objects.
Prequest	Persistent request handler.
Request	Request handler.
Session	Session context.
Status	Status object.
Topocomm	Topology intracommunicator.
Win	Remote memory access context.
buffer	Buffer.
memory	alias of buffer

mpi4py.MPI.BottomType

mpi4py.MPI.BufferAutomaticType

```
class mpi4py.MPI.BufferAutomaticType
    Bases: int
    Type of BUFFER_AUTOMATIC.
    static __new__(cls)
    Return type
    Self
```

mpi4py.MPI.Cartcomm

class mpi4py.MPI.Cartcomm

Bases: Topocomm

Cartesian topology intracommunicator.

static __new__(cls, comm=None)

Parameters

comm (Cartcomm / None)

Return type

Self

Methods Summary

Get_cart_rank(coords)	Translate logical coordinates to ranks.
<pre>Get_coords(rank)</pre>	Translate ranks to logical coordinates.
<pre>Get_dim()</pre>	Return number of dimensions.
<pre>Get_topo()</pre>	Return information on the cartesian topology.
Shift(direction, disp)	Return a process ranks for data shifting with Sendrecv.
Sub(remain_dims)	Return a lower-dimensional Cartesian topology.

Attributes Summary

coords	Coordinates.
dim	Number of dimensions.
dims	Dimensions.
ndim	Number of dimensions.
periods	Periodicity.
topo	Topology information.

Methods Documentation

Get_cart_rank(coords)

Translate logical coordinates to ranks.

Parameters

coords (Sequence[int])

Return type

int

Get_coords(rank)

Translate ranks to logical coordinates.

Parameters

rank (int)

```
Return type
```

list[int]

Get_dim()

Return number of dimensions.

Return type

int

Get_topo()

Return information on the cartesian topology.

Return type

tuple[list[int], list[int], list[int]]

Shift(direction, disp)

Return a process ranks for data shifting with Sendrecv.

Parameters

- direction (int)
- disp(int)

Return type

tuple[int, int]

Sub(remain_dims)

Return a lower-dimensional Cartesian topology.

Parameters

remain_dims (Sequence[bool])

Return type

Cartcomm

Attributes Documentation

coords

Coordinates.

dim

Number of dimensions.

dims

Dimensions.

ndim

Number of dimensions.

periods

Periodicity.

topo

Topology information.

mpi4py.MPI.Comm

Methods Summary

Abort([errorcode])	Terminate the MPI execution environment.
Ack_failed([num_to_ack])	Acknowledge failures on a communicator.
Agree(flag)	Blocking agreement.
Allgather(sendbuf, recvbuf)	Gather to All.
<pre>Allgather_init(sendbuf, recvbuf[, info])</pre>	Persistent Gather to All.
Allgatherv(sendbuf, recvbuf)	Gather to All Vector.
<pre>Allgatherv_init(sendbuf, recvbuf[, info])</pre>	Persistent Gather to All Vector.
Allreduce(sendbuf, recvbuf[, op])	Reduce to All.
<pre>Allreduce_init(sendbuf, recvbuf[, op, info])</pre>	Persistent Reduce to All.
Alltoall(sendbuf, recvbuf)	All to All Scatter/Gather.
<pre>Alltoall_init(sendbuf, recvbuf[, info])</pre>	Persistent All to All Scatter/Gather.
Alltoallv(sendbuf, recvbuf)	All to All Scatter/Gather Vector.
<pre>Alltoallv_init(sendbuf, recvbuf[, info])</pre>	Persistent All to All Scatter/Gather Vector.
Alltoallw(sendbuf, recvbuf)	All to All Scatter/Gather General.
<pre>Alltoallw_init(sendbuf, recvbuf[, info])</pre>	Persistent All to All Scatter/Gather General.
Attach_buffer(buf)	Attach a user-provided buffer for sending in buffered
	mode.
Barrier()	Barrier synchronization.
<pre>Barrier_init([info])</pre>	Persistent Barrier.
<pre>Bcast(buf[, root])</pre>	Broadcast data from one process to all other pro-
	cesses.
<pre>Bcast_init(buf[, root, info])</pre>	Persistent Broadcast.
Bsend(buf, dest[, tag])	Blocking send in buffered mode.
<pre>Bsend_init(buf, dest[, tag])</pre>	Persistent request for a send in buffered mode.
Call_errhandler(errorcode)	Call the error handler installed on a communicator.
Clone()	Clone an existing communicator.
Compare(comm)	Compare two communicators.
Create(group)	Create communicator from group.
<pre>Create_errhandler(errhandler_fn)</pre>	Create a new error handler for communicators.
<pre>Create_keyval([copy_fn, delete_fn, nopython])</pre>	Create a new attribute key for communicators.
Delete_attr(keyval)	Delete attribute value associated with a key.
Detach_buffer()	Remove an existing attached buffer.
Disconnect()	Disconnect from a communicator.
Dup([info])	Duplicate a communicator.
Dup_with_info(info)	Duplicate a communicator with hints.

Table 2 – continued from previous page

lable 2 – continued	from previous page
Flush_buffer()	Block until all buffered messages have been transmit-
	ted.
Free()	Free a communicator.
Free_keyval(keyval)	Free an attribute key for communicators.
<pre>Gather(sendbuf, recvbuf[, root])</pre>	Gather data to one process from all other processes.
<pre>Gather_init(sendbuf, recvbuf[, root, info])</pre>	Persistent Gather.
Gatherv(sendbuf, recvbuf[, root])	Gather Vector.
<pre>Gatherv_init(sendbuf, recvbuf[, root, info])</pre>	Persistent Gather Vector.
Get_attr(keyval)	Retrieve attribute value by key.
Get_errhandler()	Get the error handler for a communicator.
Get_failed()	Extract the group of failed processes.
Get_group()	Access the group associated with a communicator.
Get_info()	Return the current hints for a communicator.
Get_name()	Get the print name for this communicator.
Get_parent()	Return the parent intercommunicator for this process.
Get_rank()	Return the parent intercommunicator for this process. Return the rank of this process in a communicator.
Get_size()	Return the number of processes in a communicator.
<pre>Get_size() Get_topology()</pre>	Return the number of processes in a communicator. Return the type of topology (if any) associated with a
Get_topology()	
Tagman(flag)	communicator.
Iagree(flag)	Nonblocking agreement.
Iallgather(sendbuf, recybuf)	Nonblocking Gather to All Vector
Iallgatherv(sendbuf, recvbuf)	Nonblocking Gather to All Vector.
Iallreduce(sendbuf, recvbuf[, op])	Nonblocking Reduce to All.
Ialltoall(sendbuf, recvbuf)	Nonblocking All to All Scatter/Gather.
Ialltoallv(sendbuf, recvbuf)	Nonblocking All to All Scatter/Gather Vector.
Ialltoallw(sendbuf, recvbuf)	Nonblocking All to All Scatter/Gather General.
Ibarrier()	Nonblocking Barrier.
Ibcast(buf[, root])	Nonblocking Broadcast.
Ibsend(buf, dest[, tag])	Nonblocking send in buffered mode.
Idup([info])	Nonblocking duplicate a communicator.
Idup_with_info(info)	Nonblocking duplicate a communicator with hints.
Iflush_buffer()	Nonblocking flush for buffered messages.
<pre>Igather(sendbuf, recvbuf[, root])</pre>	Nonblocking Gather.
<pre>Igatherv(sendbuf, recvbuf[, root])</pre>	Nonblocking Gather Vector.
<pre>Improbe([source, tag, status])</pre>	Nonblocking test for a matched message.
Iprobe([source, tag, status])	Nonblocking test for a message.
<pre>Irecv(buf[, source, tag])</pre>	Nonblocking receive.
<pre>Ireduce(sendbuf, recvbuf[, op, root])</pre>	Nonblocking Reduce to Root.
<pre>Ireduce_scatter(sendbuf, recvbuf[,])</pre>	Nonblocking Reduce-Scatter (vector version).
<pre>Ireduce_scatter_block(sendbuf, recvbuf[, op])</pre>	Nonblocking Reduce-Scatter Block (regular, non-
	vector version).
<pre>Irsend(buf, dest[, tag])</pre>	Nonblocking send in ready mode.
<pre>Is_inter()</pre>	Return whether the communicator is an intercommu-
v	nicator.
Is_intra()	Return whether the communicator is an intracommu-
_	nicator.
Is_revoked()	Indicate whether the communicator has been re-
	voked.
<pre>Iscatter(sendbuf, recvbuf[, root])</pre>	Nonblocking Scatter.
Iscatterv(sendbuf, recvbuf[, root])	Nonblocking Scatter Vector.
Isend(buf, dest[, tag])	Nonblocking seatter vector. Nonblocking send.
Isendrecv(sendbuf, dest[, sendtag, recvbuf,])	Nonblocking send and receive.
Total et (solidour, desil, solidiug, recybur,])	continues on next page

Table 2 – continued from previous page

Table 2 – Continued	from previous page
<pre>Isendrecv_replace(buf, dest[, sendtag,])</pre>	Send and receive a message.
Ishrink()	Nonblocking shrink a communicator to remove all
	failed processes.
<pre>Issend(buf, dest[, tag])</pre>	Nonblocking send in synchronous mode.
Join(fd)	Interconnect two processes connected by a socket.
<pre>Mprobe([source, tag, status])</pre>	Blocking test for a matched message.
<pre>Precv_init(buf, partitions[, source, tag, info])</pre>	Create request for a partitioned recv operation.
Probe([source, tag, status])	Blocking test for a message.
Psend_init(buf, partitions, dest[, tag, info])	Create request for a partitioned send operation.
Recv(buf[, source, tag, status])	Blocking receive.
Recv_init(buf[, source, tag])	Create a persistent request for a receive.
Reduce(sendbuf, recvbuf[, op, root])	Reduce to Root.
Reduce_init(sendbuf, recvbuf[, op, root, info])	Persistent Reduce to Root.
Reduce_scatter(sendbuf, recvbuf[,])	Reduce-Scatter (vector version).
Reduce_scatter_block(sendbuf, recvbuf[, op])	Reduce-Scatter Block (regular, non-vector version).
Reduce_scatter_block_init(sendbuf, recvbuf)	Persistent Reduce-Scatter Block (regular, non-vector
neadec_beacet_block_inite(behabai, iee voai)	version).
<pre>Reduce_scatter_init(sendbuf, recvbuf[,])</pre>	Persistent Reduce-Scatter (vector version).
Revoke()	Revoke a communicator.
Rsend(buf, dest[, tag])	Blocking send in ready mode.
Rsend_init(buf, dest[, tag])	Persistent request for a send in ready mode.
Scatter(sendbuf, recvbuf[, root])	Scatter data from one process to all other processes.
<pre>Scatter_init(sendbuf, recvbuf[, root, info])</pre>	Persistent Scatter.
Scatterv(sendbuf, recvbuf[, root])	Scatter Vector.
<pre>Scatterv_init(sendbuf, recvbuf[, root, info])</pre>	Persistent Scatter Vector.
Send(buf, dest[, tag])	Blocking send.
Send_init(buf, dest[, tag])	Create a persistent request for a standard send.
Sendrecv(sendbuf, dest[, sendtag, recvbuf,])	Send and receive a message.
Sendrecv_replace(buf, dest[, sendtag,])	Send and receive a message.
Set_attr(keyval, attrval)	Store attribute value associated with a key.
Set_errhandler(errhandler)	Set the error handler for a communicator.
Set_info(info)	Set new values for the hints associated with a com-
	municator.
<pre>Set_name(name)</pre>	Set the print name for this communicator.
Shrink()	Shrink a communicator to remove all failed processes.
Split([color, key])	Split communicator by color and key.
Split_type(split_type[, key, info])	Split communicator by split type.
Ssend(buf, dest[, tag])	Blocking send in synchronous mode.
Ssend_init(buf, dest[, tag])	Persistent request for a send in synchronous mode.
allgather(sendobj)	Gather to All.
allreduce(sendobj[, op])	Reduce to All.
alltoall(sendobj)	All to All Scatter/Gather.
barrier()	Barrier synchronization.
bcast(obj[, root])	Broadcast.
bsend(obj, dest[, tag])	Send in buffered mode.
f2py(arg)	
free()	Call Free if not null or predefined.
fromhandle(handle)	Create object from MPI handle.
<pre>gather(sendobj[, root])</pre>	Gather.
ibsend(obj, dest[, tag])	Nonblocking send in buffered mode.
, 0. 2. 32.	continues on nevt nage

Table 2 – continued from previous page

<pre>improbe([source, tag, status])</pre>	Nonblocking test for a matched message.
<pre>iprobe([source, tag, status])</pre>	Nonblocking test for a message.
<pre>irecv([buf, source, tag])</pre>	Nonblocking receive.
isend(obj, dest[, tag])	Nonblocking send.
issend(obj, dest[, tag])	Nonblocking send in synchronous mode.
<pre>mprobe([source, tag, status])</pre>	Blocking test for a matched message.
<pre>probe([source, tag, status])</pre>	Blocking test for a message.
py2f()	
recv([buf, source, tag, status])	Receive.
<pre>reduce(sendobj[, op, root])</pre>	Reduce to Root.
scatter(sendobj[, root])	Scatter.
send(obj, dest[, tag])	Send in standard mode.
<pre>sendrecv(sendobj, dest[, sendtag, recvbuf,])</pre>	Send and Receive.
ssend(obj, dest[, tag])	Send in synchronous mode.
<pre>issend(obj, dest[, tag]) mprobe([source, tag, status]) probe([source, tag, status]) py2f() recv([buf, source, tag, status]) reduce(sendobj[, op, root]) scatter(sendobj[, root]) send(obj, dest[, tag]) sendrecv(sendobj, dest[, sendtag, recvbuf,])</pre>	Nonblocking send in synchronous mode. Blocking test for a matched message. Blocking test for a message. Receive. Reduce to Root. Scatter. Send in standard mode. Send and Receive.

Attributes Summary

group	Group.
handle	MPI handle.
info	Info hints.
is_inter	Is intercommunicator.
is_intra	Is intracommunicator.
is_topo	Is a topology.
name	Print name.
rank	Rank of this process.
size	Number of processes.
topology	Topology type.

Methods Documentation

Abort(errorcode=0)

Terminate the MPI execution environment.

Warning

The invocation of this method prevents the execution of various Python exit and cleanup mechanisms. Use this method as a last resort to prevent parallel deadlocks in case of unrecoverable errors.

 $\begin{array}{c} \textbf{Parameters} \\ \textbf{errorcode} \ (int) \end{array}$

Return type NoReturn

Ack_failed(num_to_ack=None)

Acknowledge failures on a communicator.

```
Parameters
            num_to_ack(int | None)
         Return type
            int
Agree(flag)
     Blocking agreement.
         Parameters
             flag(int)
         Return type
             int
Allgather(sendbuf, recvbuf)
     Gather to All.
     Gather data from all processes and broadcast the combined data to all other processes.
         Parameters
             • sendbuf (BufSpec / InPlace)
             • recvbuf (BufSpecB)
         Return type
            None
Allgather_init(sendbuf, recvbuf, info=INFO_NULL)
     Persistent Gather to All.
         Parameters
             • sendbuf (BufSpec / InPlace)
             • recvbuf (BufSpecB)
             • info (Info)
         Return type
             Prequest
Allgatherv(sendbuf, recvbuf)
     Gather to All Vector.
     Gather data from all processes and send it to all other processes providing different amounts of data and
     displacements.
         Parameters
             • sendbuf (BufSpec / InPlace)
             • recvbuf (BufSpecV)
         Return type
            None
Allgatherv_init(sendbuf, recvbuf, info=INFO_NULL)
     Persistent Gather to All Vector.
         Parameters
             • sendbuf (BufSpec / InPlace)
```

• recvbuf (BufSpecV)

```
• info (Info)
```

Return type

Prequest

Allreduce(sendbuf, recvbuf, op=SUM)

Reduce to All.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- **op** (0p)

Return type

None

Allreduce_init(sendbuf, recvbuf, op=SUM, info=INFO_NULL)

Persistent Reduce to All.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- op (0p)
- info (Info)

Return type

Prequest

Alltoall(sendbuf, recvbuf)

All to All Scatter/Gather.

Send data to all processes and recy data from all processes.

Parameters

- **sendbuf** (BufSpecB / InPlace)
- recvbuf (BufSpecB)

Return type

None

 ${\tt Alltoall_init} (\mathit{sendbuf}, \mathit{recvbuf}, \mathit{info=INFO_NULL})$

Persistent All to All Scatter/Gather.

Parameters

- **sendbuf** (BufSpecB / InPlace)
- recvbuf (BufSpecB)
- info (Info)

Return type

Prequest

```
Alltoallv(sendbuf, recvbuf)
```

All to All Scatter/Gather Vector.

Send data to all processes and recv data from all processes providing different amounts of data and displacements.

Parameters

- sendbuf (BufSpecV / InPlace)
- recvbuf (BufSpecV)

Return type

None

Alltoallv_init(sendbuf, recvbuf, info=INFO_NULL)

Persistent All to All Scatter/Gather Vector.

Parameters

- **sendbuf** (BufSpecV / InPlace)
- recvbuf (BufSpecV)
- info (Info)

Return type

Prequest

Alltoallw(sendbuf, recvbuf)

All to All Scatter/Gather General.

Send/recv data to/from all processes allowing the specification of different counts, displacements, and datatypes for each dest/source.

Parameters

- **sendbuf** (BufSpecW / InPlace)
- recvbuf (BufSpecW)

Return type

None

Alltoallw_init(sendbuf, recvbuf, info=INFO_NULL)

Persistent All to All Scatter/Gather General.

Parameters

- **sendbuf** (BufSpecW / InPlace)
- recvbuf (BufSpecW)
- info (Info)

Return type

Prequest

Attach_buffer(buf)

Attach a user-provided buffer for sending in buffered mode.

Parameters

buf (Buffer | None)

Return type

None

Barrier()

Barrier synchronization.

Return type

None

Barrier_init(info=INFO_NULL)

Persistent Barrier.

Parameters

info (Info)

Return type

Prequest

Bcast(buf, root=0)

Broadcast data from one process to all other processes.

Parameters

- buf (BufSpec)
- root (int)

Return type

None

Bcast_init(buf, root=0, info=INFO_NULL)

Persistent Broadcast.

Parameters

- **buf** (BufSpec)
- root (int)
- info (Info)

Return type

Prequest

Bsend(buf, dest, tag=0)

Blocking send in buffered mode.

Parameters

- **buf** (BufSpec)
- dest (int)
- **tag** (*int*)

Return type

None

Bsend_init(buf, dest, tag=0)

Persistent request for a send in buffered mode.

- **buf** (BufSpec)
- dest (int)
- **tag** (*int*)

```
Return type
            Request
Call_errhandler(errorcode)
     Call the error handler installed on a communicator.
        Parameters
            errorcode (int)
        Return type
            None
Clone()
     Clone an existing communicator.
        Return type
            Self
Compare(comm)
     Compare two communicators.
        Parameters
            comm (Comm)
        Return type
            int
Create(group)
     Create communicator from group.
        Parameters
            group (Group)
        Return type
            Comm
classmethod Create_errhandler(errhandler_fn)
     Create a new error handler for communicators.
        Parameters
            errhandler_fn (Callable[[Comm, int], None])
        Return type
            Errhandler
classmethod Create_keyval(copy_fn=None, delete_fn=None, nopython=False)
     Create a new attribute key for communicators.
        Parameters
             • copy_fn (Callable[[Comm, int, Any], Any] | None)
             • delete_fn(Callable[[Comm, int, Any], None] | None)
             • nopython (bool)
        Return type
            int
Delete_attr(keyval)
```

Delete attribute value associated with a key.

```
Parameters
             keyval (int)
         Return type
             None
Detach_buffer()
     Remove an existing attached buffer.
         Return type
             Buffer | None
Disconnect()
     Disconnect from a communicator.
         Return type
             None
Dup(info=None)
     Duplicate a communicator.
         Parameters
             info (Info | None)
         Return type
             Self
Dup_with_info(info)
     Duplicate a communicator with hints.
         Parameters
             info (Info)
         Return type
             Self
Flush_buffer()
     Block until all buffered messages have been transmitted.
         Return type
             None
Free()
     Free a communicator.
         Return type
             None
classmethod Free_keyval(keyval)
     Free an attribute key for communicators.
         Parameters
             keyval (int)
         Return type
             int
Gather(sendbuf, recvbuf, root=0)
     Gather data to one process from all other processes.
         Parameters
```

• sendbuf (BufSpec / InPlace)

```
• recvbuf (BufSpecB / None)
```

• root (int)

Return type

None

Gather_init(sendbuf, recvbuf, root=0, info=INFO_NULL)

Persistent Gather.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpecB | None)
- root (int)
- info (Info)

Return type

Prequest

Gatherv(sendbuf, recvbuf, root=0)

Gather Vector.

Gather data to one process from all other processes providing different amounts of data and displacements.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpecV / None)
- root (int)

Return type

None

Gatherv_init(sendbuf, recvbuf, root=0, info=INFO_NULL)

Persistent Gather Vector.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpecV / None)
- root (int)
- info (Info)

Return type

Prequest

Get_attr(keyval)

Retrieve attribute value by key.

Parameters

keyval (int)

Return type

int | Any | None

```
Get_errhandler()
     Get the error handler for a communicator.
         Return type
             Errhandler
Get_failed()
     Extract the group of failed processes.
         Return type
             Group
Get_group()
     Access the group associated with a communicator.
         Return type
             Group
Get_info()
     Return the current hints for a communicator.
         Return type
             Info
Get_name()
     Get the print name for this communicator.
         Return type
             str
classmethod Get_parent()
     Return the parent intercommunicator for this process.
         Return type
             Intercomm
Get_rank()
     Return the rank of this process in a communicator.
         Return type
             int
Get_size()
     Return the number of processes in a communicator.
         Return type
             int
Get_topology()
     Return the type of topology (if any) associated with a communicator.
         Return type
             int
```

Iagree(flag)

Nonblocking agreement.

Parameters

Return type Request

flag (Buffer)

Iallgather(sendbuf, recvbuf)

Nonblocking Gather to All.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpecB)

Return type

Request

Iallgatherv(sendbuf, recvbuf)

Nonblocking Gather to All Vector.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpecV)

Return type

Request

Iallreduce(sendbuf, recvbuf, op=SUM)

Nonblocking Reduce to All.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- op (0p)

Return type

Request

Ialltoall(sendbuf, recvbuf)

Nonblocking All to All Scatter/Gather.

Parameters

- **sendbuf** (BufSpecB / InPlace)
- recvbuf (BufSpecB)

Return type

Request

Ialltoallv(sendbuf, recvbuf)

Nonblocking All to All Scatter/Gather Vector.

Parameters

- **sendbuf** (BufSpecV / InPlace)
- recvbuf (BufSpecV)

Return type

Request

Ialltoallw(sendbuf, recvbuf)

Nonblocking All to All Scatter/Gather General.

- sendbuf (BufSpecW / InPlace)
- recvbuf (BufSpecW)

Return type

Request

Ibarrier()

Nonblocking Barrier.

Return type

Request

Ibcast(buf, root=0)

Nonblocking Broadcast.

Parameters

- **buf** (BufSpec)
- root (int)

Return type

Request

Ibsend(buf, dest, tag=0)

Nonblocking send in buffered mode.

Parameters

- **buf** (BufSpec)
- dest(int)
- **tag** (*int*)

Return type

Request

Idup(info=None)

Nonblocking duplicate a communicator.

Parameters

info (Info | None)

Return type

tuple[Self, Request]

Idup_with_info(info)

Nonblocking duplicate a communicator with hints.

Parameters

info (Info)

Return type

tuple[Self, Request]

Iflush_buffer()

Nonblocking flush for buffered messages.

Return type

Request

Igather(sendbuf, recvbuf, root=0)

Nonblocking Gather.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpecB / None)
- root (int)

Return type

Request

Igatherv(sendbuf, recvbuf, root=0)

Nonblocking Gather Vector.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpecV | None)
- root (int)

Return type

Request

Improbe(source=ANY_SOURCE, tag=ANY_TAG, status=None)

Nonblocking test for a matched message.

Parameters

- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

Message | None

Iprobe(*source=ANY_SOURCE*, *tag=ANY_TAG*, *status=None*)

Nonblocking test for a message.

Parameters

- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

bool

Irecv(buf, source=ANY_SOURCE, tag=ANY_TAG)

Nonblocking receive.

- buf (BufSpec)
- source (int)
- **tag** (*int*)

Return type

Request

Ireduce(sendbuf, recvbuf, op=SUM, root=0)

Nonblocking Reduce to Root.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec | None)
- op (0p)
- root (int)

Return type

Request

Ireduce_scatter(sendbuf, recvbuf, recvcounts=None, op=SUM)

Nonblocking Reduce-Scatter (vector version).

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- recvcounts (Sequence[int] | None)
- op (0p)

Return type

Request

Ireduce_scatter_block(sendbuf, recvbuf, op=SUM)

Nonblocking Reduce-Scatter Block (regular, non-vector version).

Parameters

- sendbuf (BufSpecB / InPlace)
- recvbuf (BufSpec / BufSpecB)
- op (0p)

Return type

Request

Irsend(buf, dest, tag=0)

Nonblocking send in ready mode.

Parameters

- **buf** (BufSpec)
- dest (int)
- **tag** (*int*)

Return type

Request

```
Is_inter()
```

Return whether the communicator is an intercommunicator.

Return type

bool

Is_intra()

Return whether the communicator is an intracommunicator.

Return type

bool

Is_revoked()

Indicate whether the communicator has been revoked.

Return type

bool

Iscatter(sendbuf, recvbuf, root=0)

Nonblocking Scatter.

Parameters

- sendbuf (BufSpecB / None)
- recvbuf (BufSpec / InPlace)
- root (int)

Return type

Request

Iscatterv(sendbuf, recvbuf, root=0)

Nonblocking Scatter Vector.

Parameters

- sendbuf (BufSpecV / None)
- recvbuf (BufSpec / InPlace)
- root (int)

Return type

Request

Isend(buf, dest, tag=0)

Nonblocking send.

Parameters

- **buf** (BufSpec)
- dest(int)
- tag(int)

Return type

Request

Isendrecv(*sendbuf*, *dest*, *sendtag*=0, *recvbuf*=None, *source*=ANY_SOURCE, *recvtag*=ANY_TAG) Nonblocking send and receive.

- sendbuf (BufSpec)
- dest (int)
- sendtag (int)
- recvbuf (BufSpec / None)
- source (int)
- recvtag(int)

Return type

Request

Isendrecv_replace(buf, dest, sendtag=0, source=ANY_SOURCE, recvtag=ANY_TAG)

Send and receive a message.

Note

This function is guaranteed not to deadlock in situations where pairs of blocking sends and receives may deadlock.

Caution

A common mistake when using this function is to mismatch the tags with the source and destination ranks, which can result in deadlock.

Parameters

- **buf** (BufSpec)
- dest(int)
- sendtag(int)
- source (int)
- recvtag(int)

Return type

Request

Ishrink()

Nonblocking shrink a communicator to remove all failed processes.

Return type

tuple[Comm, Request]

Issend(buf, dest, tag=0)

Nonblocking send in synchronous mode.

- buf (BufSpec)
- dest (int)
- **tag** (*int*)

```
Return type
```

Request

classmethod Join(fd)

Interconnect two processes connected by a socket.

Parameters

fd(int)

Return type

Intercomm

Mprobe(source=ANY_SOURCE, tag=ANY_TAG, status=None)

Blocking test for a matched message.

Parameters

- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

Message

Precv_init(buf, partitions, source=ANY_SOURCE, tag=ANY_TAG, info=INFO_NULL)

Create request for a partitioned recv operation.

Parameters

- **buf** (BufSpec)
- partitions (int)
- source (int)
- tag (int)
- info (Info)

Return type

Prequest

Probe(source=ANY_SOURCE, tag=ANY_TAG, status=None)

Blocking test for a message.

Note

This function blocks until the message arrives.

Parameters

- source (int)
- **tag**(*int*)
- status (Status / None)

Return type

Literal[True]

```
Psend_init(buf, partitions, dest, tag=0, info=INFO_NULL)
```

Create request for a partitioned send operation.

Parameters

- **buf** (BufSpec)
- partitions (int)
- dest (int)
- **tag** (*int*)
- info (Info)

Return type

Prequest

Recv(buf, source=ANY_SOURCE, tag=ANY_TAG, status=None)

Blocking receive.

Note

This function blocks until the message is received.

Parameters

- **buf** (BufSpec)
- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

None

Recv_init(buf, source=ANY_SOURCE, tag=ANY_TAG)

Create a persistent request for a receive.

Parameters

- buf (BufSpec)
- source (int)
- tag(int)

Return type

Prequest

Reduce(sendbuf, recvbuf, op=SUM, root=0)

Reduce to Root.

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpec | None)
- **op** (0p)
- root (int)

```
Return type
```

None

Reduce_init(sendbuf, recvbuf, op=SUM, root=0, info=INFO_NULL)

Persistent Reduce to Root.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec | None)
- op (0p)
- root (int)
- info (Info)

Return type

Prequest

Reduce_scatter(*sendbuf*, *recvbuf*, *recvcounts=None*, *op=SUM*)

Reduce-Scatter (vector version).

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- recvcounts (Sequence[int] | None)
- op (0p)

Return type

None

Reduce_scatter_block(sendbuf, recvbuf, op=SUM)

Reduce-Scatter Block (regular, non-vector version).

Parameters

- sendbuf (BufSpecB / InPlace)
- recvbuf (BufSpec / BufSpecB)
- **op** (0p)

Return type

None

Reduce_scatter_block_init(sendbuf, recvbuf, op=SUM, info=INFO_NULL)

Persistent Reduce-Scatter Block (regular, non-vector version).

Parameters

- sendbuf (BufSpecB / InPlace)
- recvbuf (BufSpec / BufSpecB)
- op (0p)
- info (Info)

Return type

Prequest

```
Reduce_scatter_init(sendbuf, recvbuf, recvcounts=None, op=SUM, info=INFO_NULL)
     Persistent Reduce-Scatter (vector version).
         Parameters
             • sendbuf (BufSpec / InPlace)
             • recvbuf (BufSpec)
             • recvcounts (Sequence[int] | None)
             • op (0p)
             • info (Info)
         Return type
             Prequest
Revoke()
     Revoke a communicator.
         Return type
            None
Rsend(buf, dest, tag=0)
     Blocking send in ready mode.
         Parameters
             • buf (BufSpec)
             • dest(int)
             • tag(int)
         Return type
            None
Rsend_init(buf, dest, tag=0)
     Persistent request for a send in ready mode.
         Parameters
             • buf (BufSpec)
             • dest (int)
             • tag (int)
         Return type
             Request
Scatter(sendbuf, recvbuf, root=0)
     Scatter data from one process to all other processes.
         Parameters
             • sendbuf (BufSpecB / None)
```

- recvbuf (BufSpec / InPlace)
- root (int)

Return type

None

```
Scatter_init(sendbuf, recvbuf, root=0, info=INFO_NULL)
```

Persistent Scatter.

Parameters

- sendbuf (BufSpecB / None)
- recvbuf (BufSpec / InPlace)
- root (int)
- info (Info)

Return type

Prequest

Scatterv(sendbuf, recvbuf, root=0)

Scatter Vector.

Scatter data from one process to all other processes providing different amounts of data and displacements.

Parameters

- sendbuf (BufSpecV / None)
- recvbuf (BufSpec / InPlace)
- root (int)

Return type

None

Scatterv_init(sendbuf, recvbuf, root=0, info=INFO_NULL)

Persistent Scatter Vector.

Parameters

- sendbuf (BufSpecV / None)
- recvbuf (BufSpec / InPlace)
- root (int)
- info (Info)

Return type

Prequest

Send(buf, dest, tag=0)

Blocking send.

Note

This function may block until the message is received. Whether *Send* blocks or not depends on several factors and is implementation dependent.

- buf (BufSpec)
- dest(int)
- **tag** (*int*)

Return type

None

```
Send_init(buf, dest, tag=0)
```

Create a persistent request for a standard send.

Parameters

- **buf** (BufSpec)
- dest (int)
- tag (int)

Return type

Prequest

Sendrecv(sendbuf, dest, sendtag=0, recvbuf=None, source=ANY_SOURCE, recvtag=ANY_TAG, status=None)

Send and receive a message.

Note

This function is guaranteed not to deadlock in situations where pairs of blocking sends and receives may deadlock.

Caution

A common mistake when using this function is to mismatch the tags with the source and destination ranks, which can result in deadlock.

Parameters

- sendbuf (BufSpec)
- dest (int)
- sendtag (int)
- recvbuf (BufSpec / None)
- source (int)
- recvtag(int)
- status (Status / None)

Return type

None

Sendrecv_replace(buf, dest, sendtag=0, source=ANY_SOURCE, recvtag=ANY_TAG, status=None) Send and receive a message.

Note

This function is guaranteed not to deadlock in situations where pairs of blocking sends and receives may deadlock.

Caution

A common mistake when using this function is to mismatch the tags with the source and destination ranks, which can result in deadlock.

```
Parameters
```

- **buf** (BufSpec)
- dest(int)
- sendtag(int)
- source (int)
- recvtag(int)
- status (Status / None)

Return type

None

Set_attr(keyval, attrval)

Store attribute value associated with a key.

Parameters

- keyval (int)
- attrval (Any)

Return type

None

Set_errhandler(errhandler)

Set the error handler for a communicator.

```
Parameters
```

errhandler (Errhandler)

Return type

None

Set_info(info)

Set new values for the hints associated with a communicator.

Parameters

info (Info)

Return type

None

Set_name(name)

Set the print name for this communicator.

Parameters

name (str)

Return type

None

Shrink()

Shrink a communicator to remove all failed processes.

Return type

Comm

Split(color=0, key=0)

Split communicator by color and key.

Parameters

- color (int)
- **key** (*int*)

Return type

Comm

Split_type(split_type, key=0, info=INFO_NULL)

Split communicator by split type.

Parameters

- split_type (int)
- **key** (*int*)
- info (Info)

Return type

Comm

Ssend(buf, dest, tag=0)

Blocking send in synchronous mode.

Parameters

- buf (BufSpec)
- dest(int)
- **tag** (*int*)

Return type

None

Ssend_init(buf, dest, tag=0)

Persistent request for a send in synchronous mode.

Parameters

- **buf** (BufSpec)
- dest (int)
- tag(int)

Return type

Request

allgather(sendobj)

Gather to All.

Parameters

 ${\tt sendobj}\;({\tt Any})$

```
Return type
            list[Any]
allreduce(sendobj, op=SUM)
     Reduce to All.
         Parameters
             • sendobj (Any)
             • op (Op / Callable[[Any, Any], Any])
         Return type
            Any
{\tt alltoall}(sendobj)
     All to All Scatter/Gather.
         Parameters
             sendobj (Sequence[Any])
         Return type
            list[Any]
barrier()
     Barrier synchronization.
```

Note

This method is equivalent to Barrier.

Return type

None

bcast(obj, root=0)

Broadcast.

Parameters

- **obj** (*Any*)
- root (int)

Return type

Any

bsend(*obj*, *dest*, *tag*=0)

Send in buffered mode.

Parameters

- obj (Any)
- dest(int)
- **tag** (*int*)

Return type

None

```
classmethod f2py(arg)
        Parameters
            arg(int)
        Return type
            Comm
free()
    Call Free if not null or predefined.
        Return type
            None
classmethod fromhandle(handle)
    Create object from MPI handle.
        Parameters
            handle (int)
        Return type
            Comm
gather(sendobj, root=0)
    Gather.
        Parameters
            • sendobj (Any)
            • root (int)
        Return type
            list[Any] | None
ibsend(obj, dest, tag=0)
    Nonblocking send in buffered mode.
        Parameters
            • obj (Any)
            • dest (int)
            • tag(int)
        Return type
            Request
improbe(source=ANY_SOURCE, tag=ANY_TAG, status=None)
    Nonblocking test for a matched message.
        Parameters
            • source (int)
            • tag (int)
            • status (Status / None)
        Return type
```

Message | None

```
iprobe(source=ANY_SOURCE, tag=ANY_TAG, status=None)
```

Nonblocking test for a message.

Parameters

- source (int)
- tag (int)
- status (Status / None)

Return type

bool

irecv(buf=None, source=ANY_SOURCE, tag=ANY_TAG)

Nonblocking receive.

Parameters

- buf (Buffer / None)
- source (int)
- **tag** (*int*)

Return type

Request

isend(obj, dest, tag=0)

Nonblocking send.

Parameters

- **obj** (*Any*)
- dest(int)
- **tag** (*int*)

Return type

Request

issend(obj, dest, tag=0)

Nonblocking send in synchronous mode.

Parameters

- **obj** (*Any*)
- dest(int)
- **tag** (*int*)

Return type

Request

 $\label{eq:mprobe} \textbf{mprobe}(\textit{source=ANY_SOURCE}, \textit{tag=ANY_TAG}, \textit{status=None})$

Blocking test for a matched message.

- source (int)
- **tag** (*int*)
- status (Status / None)

```
Return type
            Message
probe(source=ANY_SOURCE, tag=ANY_TAG, status=None)
    Blocking test for a message.
        Parameters
            • source (int)
            • tag (int)
            • status (Status / None)
        Return type
            Literal[True]
py2f()
        Return type
            int
recv(buf=None, source=ANY_SOURCE, tag=ANY_TAG, status=None)
    Receive.
        Parameters
            • buf (Buffer / None)
            • source (int)
            • tag (int)
            • status (Status | None)
        Return type
            Any
reduce(sendobj, op=SUM, root=0)
    Reduce to Root.
        Parameters
            • sendobj (Any)
            • op (Op | Callable[[Any, Any], Any])
            • root (int)
        Return type
            Any | None
scatter(sendobj, root=0)
    Scatter.
        Parameters
            • sendobj (Sequence[Any] | None)
            • root (int)
```

Return type

Any

```
send(obj, dest, tag=0)
    Send in standard mode.
        Parameters
            • obj (Any)
            • dest (int)
            • tag (int)
        Return type
            None
sendrecv(sendobj, dest, sendtag=0, recvbuf=None, source=ANY_SOURCE, recvtag=ANY_TAG,
          status=None)
    Send and Receive.
        Parameters
            • sendobj (Any)
            • dest (int)
            • sendtag (int)
            • recvbuf (Buffer | None)
            • source (int)
            • recvtag (int)
            • status (Status / None)
        Return type
            Any
ssend(obj, dest, tag=0)
    Send in synchronous mode.
        Parameters
            • obj (Any)
            • dest(int)
            • tag (int)
        Return type
            None
Attributes Documentation
group
    Group.
handle
    MPI handle.
info
```

Info hints.

is_inter

Is intercommunicator.

is_intra

Is intracommunicator.

is_topo

Is a topology.

name

Print name.

rank

Rank of this process.

size

Number of processes.

topology

Topology type.

mpi4py.MPI.Datatype

```
class mpi4py.MPI.Datatype
```

Bases: object

Datatype object.

static __new__(cls, datatype=None)

Parameters

datatype (Datatype / None)

Return type

Self

Methods Summary

Commit()	Commit the datatype.
Create_contiguous(count)	Create a contiguous datatype.
Create_darray(size, rank, gsizes, distribs,)	Create a datatype for a distributed array on Cartesian process grids.
<pre>Create_f90_complex(p, r)</pre>	Return a bounded complex datatype.
Create_f90_integer(r)	Return a bounded integer datatype.
Create_f90_real(p,r)	Return a bounded real datatype.
<pre>Create_hindexed(blocklengths, displacements)</pre>	Create an indexed datatype.
<pre>Create_hindexed_block(blocklength, displace- ments)</pre>	Create an indexed datatype with constant-sized blocks.
<pre>Create_hvector(count, blocklength, stride)</pre>	Create a vector (strided) datatype with stride in bytes.
<pre>Create_indexed(blocklengths, displacements)</pre>	Create an indexed datatype.
<pre>Create_indexed_block(blocklength, displace- ments)</pre>	Create an indexed datatype with constant-sized blocks.
<pre>Create_keyval([copy_fn, delete_fn, nopython])</pre>	Create a new attribute key for datatypes.

Table 3 – continued from previous page

	nom previous page
Create_resized(lb, extent)	Create a datatype with a new lower bound and extent.
<pre>Create_struct(blocklengths, displacements,)</pre>	Create a general composite (struct) datatype.
<pre>Create_subarray(sizes, subsizes, starts[, order])</pre>	Create a datatype for a subarray of a multidimensional array.
<pre>Create_vector(count, blocklength, stride)</pre>	Create a vector (strided) datatype.
Delete_attr(keyval)	Delete attribute value associated with a key.
Dup()	Duplicate a datatype.
Free()	Free the datatype.
Free_keyval(keyval)	Free an attribute key for datatypes.
<pre>Get_attr(keyval)</pre>	Retrieve attribute value by key.
<pre>Get_contents()</pre>	Return the input arguments used to create a datatype.
<pre>Get_envelope()</pre>	Return the number of input arguments used to create a datatype.
<pre>Get_extent()</pre>	Return lower bound and extent of datatype.
<pre>Get_name()</pre>	Get the print name for this datatype.
<pre>Get_size()</pre>	Return the number of bytes occupied by entries in the datatype.
<pre>Get_true_extent()</pre>	Return the true lower bound and extent of a datatype.
<pre>Get_value_index(value, index)</pre>	Return a predefined pair datatype.
<pre>Match_size(typeclass, size)</pre>	Find a datatype matching a specified size in bytes.
<pre>Pack(inbuf, outbuf, position, comm)</pre>	Pack into contiguous memory according to datatype.
<pre>Pack_external(datarep, inbuf, outbuf, position)</pre>	Pack into contiguous memory according to datatype.
Pack_external_size(datarep, count)	Determine the amount of space needed to pack a message.
Pack_size(count, comm)	Determine the amount of space needed to pack a message.
Set_attr(keyval, attrval)	Store attribute value associated with a key.
Set_name(name)	Set the print name for this datatype.
<pre>Unpack(inbuf, position, outbuf, comm)</pre>	Unpack from contiguous memory according to datatype.
<pre>Unpack_external(datarep, inbuf, position, outbuf)</pre>	Unpack from contiguous memory according to datatype.
decode()	Convenience method for decoding a datatype.
f2py(arg)	ζ ,,
free()	Call <i>Free</i> if not null or predefined.
fromcode(code)	Get predefined MPI datatype from character code or type string.
fromhandle(handle)	Create object from MPI handle.
py2f()	Create object from Mi I nandie.
tocode()	Get character code or type string from predefined MPI datatype.

Attributes Summary

combiner	Combiner.
contents	Contents.
envelope	Envelope.
extent	Extent.
handle	MPI handle.
is_named	Is a named datatype.
is_predefined	Is a predefined datatype.
1b	Lower bound.
name	Print name.
size	Size (in bytes).
true_extent	True extent.
true_lb	True lower bound.
true_ub	True upper bound.
typechar	Character code.
typestr	Type string.
ub	Upper bound.

Methods Documentation

Commit()

Commit the datatype.

Return type

Self

Create_contiguous(count)

Create a contiguous datatype.

Parameters

count (int)

Return type

Self

Create_darray(size, rank, gsizes, distribs, dargs, psizes, order=ORDER_C)

Create a datatype for a distributed array on Cartesian process grids.

Parameters

- size (int)
- rank (int)
- gsizes (Sequence[int])
- distribs (Sequence[int])
- dargs (Sequence[int])
- psizes (Sequence[int])
- order (int)

Return type

Self

classmethod Create_f90_complex(p, r)

Return a bounded complex datatype.

Parameters

- **p** (int)
- **r** (int)

Return type

Self

classmethod Create_f90_integer(r)

Return a bounded integer datatype.

Parameters

r (int)

Return type

Self

classmethod Create_f90_real(p, r)

Return a bounded real datatype.

Parameters

- **p**(int)
- **r** (int)

Return type

Self

Create_hindexed(blocklengths, displacements)

Create an indexed datatype.

Note

Displacements are measured in bytes.

Parameters

- blocklengths (Sequence[int])
- displacements (Sequence[int])

Return type

Self

Create_hindexed_block(blocklength, displacements)

Create an indexed datatype with constant-sized blocks.

Note

Displacements are measured in bytes.

Parameters

• blocklength (int)

```
• displacements (Sequence[int])
        Return type
            Self
Create_hvector(count, blocklength, stride)
    Create a vector (strided) datatype with stride in bytes.
        Parameters
             • count (int)
             • blocklength (int)
            • stride (int)
        Return type
            Self
Create_indexed(blocklengths, displacements)
    Create an indexed datatype.
        Parameters
             • blocklengths (Sequence[int])
             • displacements (Sequence[int])
        Return type
            Self
Create_indexed_block(blocklength, displacements)
    Create an indexed datatype with constant-sized blocks.
        Parameters
            • blocklength (int)
             • displacements (Sequence[int])
        Return type
            Self
classmethod Create_keyval(copy_fn=None, delete_fn=None, nopython=False)
    Create a new attribute key for datatypes.
        Parameters
             • copy_fn (Callable[[Datatype, int, Any], Any] | None)
             • delete_fn(Callable[[Datatype, int, Any], None] | None)
             • nopython (bool)
        Return type
            int
Create_resized(lb, extent)
    Create a datatype with a new lower bound and extent.
        Parameters
```

- **lb** (*int*)
- extent (int)

```
Return type
```

Self

 ${\bf classmethod} \ \ {\bf Create_struct} ({\it blocklengths}, {\it displacements}, {\it datatypes})$

Create a general composite (struct) datatype.

Note

Displacements are measured in bytes.

Parameters

- blocklengths (Sequence[int])
- displacements (Sequence[int])
- datatypes (Sequence[Datatype])

Return type

Self

Create_subarray(sizes, subsizes, starts, order=ORDER_C)

Create a datatype for a subarray of a multidimensional array.

Parameters

- **sizes** (Sequence[int])
- subsizes (Sequence[int])
- starts (Sequence[int])
- order (int)

Return type

Self

 ${\bf Create_vector}(count, blocklength, stride)$

Create a vector (strided) datatype.

Parameters

- count (int)
- blocklength (int)
- stride (int)

Return type

Self

Delete_attr(keyval)

Delete attribute value associated with a key.

Parameters

keyval (int)

Return type

```
Dup()
     Duplicate a datatype.
         Return type
             Self
Free()
     Free the datatype.
         Return type
             None
classmethod Free_keyval(keyval)
     Free an attribute key for datatypes.
         Parameters
             keyval (int)
         Return type
             int
Get_attr(keyval)
     Retrieve attribute value by key.
         Parameters
             keyval (int)
         Return type
             int | Any | None
Get_contents()
     Return the input arguments used to create a datatype.
         Return type
             tuple[list[int], list[int], list[int], list[Datatype]]
Get_envelope()
     Return the number of input arguments used to create a datatype.
         Return type
             tuple[int, int, int, int, int]
Get_extent()
     Return lower bound and extent of datatype.
         Return type
             tuple[int, int]
Get_name()
     Get the print name for this datatype.
         Return type
             str
Get_size()
     Return the number of bytes occupied by entries in the datatype.
         Return type
```

int

```
Get_true_extent()
```

Return the true lower bound and extent of a datatype.

Return type

tuple[int, int]

classmethod Get_value_index(value, index)

Return a predefined pair datatype.

Parameters

- value (Datatype)
- index (Datatype)

Return type

Self

classmethod Match_size(typeclass, size)

Find a datatype matching a specified size in bytes.

Parameters

- typeclass (int)
- size (int)

Return type

Self

Pack(inbuf, outbuf, position, comm)

Pack into contiguous memory according to datatype.

Parameters

- inbuf (BufSpec)
- **outbuf** (BufSpec)
- position (int)
- comm (Comm)

Return type

int

Pack_external(datarep, inbuf, outbuf, position)

Pack into contiguous memory according to datatype.

Uses the portable data representation external32.

Parameters

- datarep (str)
- inbuf (BufSpec)
- outbuf (BufSpec)
- position (int)

Return type

int

Pack_external_size(datarep, count)

Determine the amount of space needed to pack a message.

Uses the portable data representation external32.

Note

Returns an upper bound measured in bytes.

Parameters

- datarep (str)
- count (int)

Return type

int

Pack_size(count, comm)

Determine the amount of space needed to pack a message.

Note

Returns an upper bound measured in bytes.

Parameters

- count (int)
- comm (Comm)

Return type

int

Set_attr(keyval, attrval)

Store attribute value associated with a key.

Parameters

- keyval (int)
- attrval (Any)

Return type

None

Set_name(name)

Set the print name for this datatype.

Parameters

name (str)

Return type

None

Unpack(inbuf, position, outbuf, comm)

Unpack from contiguous memory according to datatype.

Parameters

```
• inbuf (BufSpec)
             • position (int)
             • outbuf (BufSpec)
             • comm (Comm)
         Return type
             int
Unpack_external(datarep, inbuf, position, outbuf)
     Unpack from contiguous memory according to datatype.
     Uses the portable data representation external32.
         Parameters
             • datarep (str)
             • inbuf (BufSpec)
             • position (int)
             • outbuf (BufSpec)
         Return type
            int
decode()
    Convenience method for decoding a datatype.
         Return type
             tuple[Datatype, str, dict[str, Any]]
classmethod f2py(arg)
         Parameters
             arg(int)
         Return type
            Datatype
free()
    Call Free if not null or predefined.
         Return type
            None
classmethod fromcode(code)
     Get predefined MPI datatype from character code or type string.
         Parameters
            code (str)
         Return type
             Datatype
classmethod fromhandle(handle)
    Create object from MPI handle.
         Parameters
            handle (int)
```

Return type

Datatype

py2f()

Return type

int

tocode()

Get character code or type string from predefined MPI datatype.

Return type

str

Attributes Documentation

combiner

Combiner.

contents

Contents.

envelope

Envelope.

extent

Extent.

handle

MPI handle.

is_named

Is a named datatype.

is_predefined

Is a predefined datatype.

1b

Lower bound.

name

Print name.

size

Size (in bytes).

true_extent

True extent.

true_lb

True lower bound.

true_ub

True upper bound.

typechar

Character code.

```
typestr
```

Type string.

ub

Upper bound.

mpi4py.MPI.Distgraphcomm

class mpi4py.MPI.Distgraphcomm

Bases: Topocomm

Distributed graph topology intracommunicator.

static __new__(cls, comm=None)

Parameters

comm (Distgraphcomm | None)

Return type

Self

Methods Summary

<pre>Get_dist_neighbors()</pre>	Return adjacency information for a distributed graph topology.
<pre>Get_dist_neighbors_count()</pre>	Return adjacency information for a distributed graph topology.

Methods Documentation

Get_dist_neighbors()

Return adjacency information for a distributed graph topology.

Return type

tuple[list[int], list[int], tuple[list[int], list[int]] | None]

Get_dist_neighbors_count()

Return adjacency information for a distributed graph topology.

Return type

int

mpi4py.MPI.Errhandler

class mpi4py.MPI.Errhandler

Bases: object

Error handler.

static __new__(cls, errhandler=None)

Parameters

errhandler (Errhandler / None)

Return type

Self

Methods Summary

Free()	Free an error handler.
f2py(arg)	
free()	Call Free if not null.
fromhandle(handle)	Create object from MPI handle.
py2f()	

Attributes Summary

handle MPI handle.

Methods Documentation

Free()

Free an error handler.

Return type

None

classmethod f2py(arg)

Parameters

arg (int)

Return type

Errhandler

free()

Call Free if not null.

Return type

None

classmethod fromhandle(handle)

Create object from MPI handle.

Parameters

handle(int)

Return type

Errhandler

py2f()

Return type

int

Attributes Documentation

handle

MPI handle.

mpi4py.MPI.File

```
class mpi4py.MPI.File
    Bases: object
    File I/O context.
    static __new__(cls, file=None)
        Parameters
            file (File / None)
        Return type
            Self
```

Methods Summary

Call the error handler installed on a file.
Close a file.
Create a new error handler for files.
Delete a file.
Return the file access mode.
Return the atomicity mode.
Return the absolute byte position in the file.
Get the error handler for a file.
Access the group of processes that opened the file.
Return the current hints for a file.
Return the current position of the individual file pointer.
Return the current position of the shared file pointer.
Return the file size.
Return the extent of datatype in the file.
Return the file view.
Nonblocking read using individual file pointer.
Nonblocking collective read using individual file pointer.
Nonblocking read using explicit offset.
Nonblocking collective read using explicit offset.
Nonblocking read using shared file pointer.
Nonblocking write using individual file pointer.
Nonblocking collective write using individual file pointer.
Nonblocking write using explicit offset.
Nonblocking collective write using explicit offset.
Nonblocking write using shared file pointer.
Open a file.
Preallocate storage space for a file.

continues on next page

Table 4 – continued from previous page

	eu nom previous page
Read(buf[, status])	Read using individual file pointer.
Read_all(buf[, status])	Collective read using individual file pointer.
Read_all_begin(buf)	Start a split collective read using individual file
	pointer.
<pre>Read_all_end(buf[, status])</pre>	Complete a split collective read using individual file
	pointer.
<pre>Read_at(offset, buf[, status])</pre>	Read using explicit offset.
<pre>Read_at_all(offset, buf[, status])</pre>	Collective read using explicit offset.
<pre>Read_at_all_begin(offset, buf)</pre>	Start a split collective read using explicit offset.
<pre>Read_at_all_end(buf[, status])</pre>	Complete a split collective read using explicit offset.
Read_ordered(buf[, status])	Collective read using shared file pointer.
Read_ordered_begin(buf)	Start a split collective read using shared file pointer.
Read_ordered_end(buf[, status])	Complete a split collective read using shared file
, <u>-</u>	pointer.
Read_shared(buf[, status])	Read using shared file pointer.
Seek(offset[, whence])	Update the individual file pointer.
Seek_shared(offset[, whence])	Update the shared file pointer.
Set_atomicity(flag)	Set the atomicity mode.
Set_errhandler(errhandler)	Set the error handler for a file.
Set_info(info)	Set new values for the hints associated with a file.
Set_size(size)	Set the file size.
Set_view([disp, etype, filetype, datarep, info])	Set the file view.
Sync()	Causes all previous writes to be transferred to the stor-
5)()	age device.
<pre>Write(buf[, status])</pre>	Write using individual file pointer.
Write_all(buf[, status])	Collective write using individual file pointer.
Write_all_begin(buf)	Start a split collective write using individual file
wirec_air_begin(bar)	pointer.
<pre>Write_all_end(buf[, status])</pre>	Complete a split collective write using individual file
wrree_arr_ena(bart, sattasj)	pointer.
<pre>Write_at(offset, buf[, status])</pre>	Write using explicit offset.
Write_at_all(offset, buf[, status])	Collective write using explicit offset.
Write_at_all_begin(offset, buf)	Start a split collective write using explicit offset.
Write_at_all_end(buf[, status])	Complete a split collective write using explicit offset.
Write_ordered(buf[, status]) Write_ordered(buf[, status])	Collective write using shared file pointer.
, =: =:	Start a split collective write using shared file pointer.
Write_ordered_begin(buf) Write_ordered_end(buff_status])	
<pre>Write_ordered_end(buf[, status])</pre>	Complete a split collective write using shared file pointer.
<pre>Write_shared(buf[, status])</pre>	Write using shared file pointer.
f2py(arg)	
free()	Call Close if not null.
fromhandle(handle)	Create object from MPI handle.
py2f()	·

Attributes Summary

amode	Access mode.
atomicity	Atomicity mode.
group	Group.
group_rank	Group rank.
group_size	Group size.
handle	MPI handle.
info	Info hints.
size	Size (in bytes).

```
Methods Documentation
Call_errhandler(errorcode)
    Call the error handler installed on a file.
         Parameters
            errorcode (int)
        Return type
            None
Close()
    Close a file.
        Return type
            None
classmethod Create_errhandler(errhandler_fn)
    Create a new error handler for files.
         Parameters
            errhandler_fn (Callable[[File, int], None])
         Return type
            Errhandler
classmethod Delete(filename, info=INFO_NULL)
    Delete a file.
         Parameters
            • filename (PathLike | str | bytes)
            • info (Info)
         Return type
            None
Get_amode()
    Return the file access mode.
         Return type
Get_atomicity()
```

Return the atomicity mode.

Return type

bool

Get_byte_offset(offset)

Return the absolute byte position in the file.

Note

Input offset is measured in etype units relative to the current file view.

Parameters

offset (int)

Return type

int

Get_errhandler()

Get the error handler for a file.

Return type

Errhandler

Get_group()

Access the group of processes that opened the file.

Return type

Group

Get_info()

Return the current hints for a file.

Return type

Info

Get_position()

Return the current position of the individual file pointer.

Note

Position is measured in etype units relative to the current file view.

Return type

int

Get_position_shared()

Return the current position of the shared file pointer.

Note

Position is measured in etype units relative to the current view.

Return type

int

```
Get_size()
     Return the file size.
         Return type
             int
Get_type_extent(datatype)
     Return the extent of datatype in the file.
         Parameters
             datatype (Datatype)
         Return type
             int
Get_view()
     Return the file view.
         Return type
             tuple[int, Datatype, Datatype, str]
Iread(buf)
     Nonblocking read using individual file pointer.
         Parameters
             buf (BufSpec)
         Return type
             Request
Iread_all(buf)
     Nonblocking collective read using individual file pointer.
         Parameters
             buf (BufSpec)
         Return type
             Request
Iread_at(offset, buf)
     Nonblocking read using explicit offset.
         Parameters
              • offset (int)
             • buf (BufSpec)
         Return type
             Request
Iread_at_all(offset, buf)
     Nonblocking collective read using explicit offset.
         Parameters
              • offset (int)
             • buf (BufSpec)
         Return type
```

Request

```
Iread_shared(buf)
    Nonblocking read using shared file pointer.
         Parameters
             buf (BufSpec)
         Return type
             Request
Iwrite(buf)
    Nonblocking write using individual file pointer.
         Parameters
             buf (BufSpec)
         Return type
             Request
Iwrite_all(buf)
    Nonblocking collective write using individual file pointer.
         Parameters
            buf (BufSpec)
         Return type
             Request
Iwrite_at(offset, buf)
     Nonblocking write using explicit offset.
         Parameters
             • offset (int)
             • buf (BufSpec)
         Return type
             Request
Iwrite_at_all(offset, buf)
     Nonblocking collective write using explicit offset.
         Parameters
             • offset (int)
             • buf (BufSpec)
         Return type
             Request
Iwrite_shared(buf)
    Nonblocking write using shared file pointer.
         Parameters
             buf (BufSpec)
         Return type
             Request
classmethod Open(comm, filename, amode=MODE_RDONLY, info=INFO_NULL)
    Open a file.
```

Parameters

```
• comm (Intracomm)
```

- filename (PathLike | str | bytes)
- amode (int)
- info (Info)

Return type

Self

Preallocate(size)

Preallocate storage space for a file.

Parameters

size(int)

Return type

None

Read(buf, status=None)

Read using individual file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Read_all(buf, status=None)

Collective read using individual file pointer.

Parameters

- buf (BufSpec)
- status (Status / None)

Return type

None

Read_all_begin(buf)

Start a split collective read using individual file pointer.

Parameters

buf (BufSpec)

Return type

None

Read_all_end(buf, status=None)

Complete a split collective read using individual file pointer.

Parameters

- buf (BufSpec)
- status (Status / None)

Return type

Read_at(offset, buf, status=None)

Read using explicit offset.

Parameters

- offset (int)
- **buf** (BufSpec)
- status (Status / None)

Return type

None

Read_at_all(offset, buf, status=None)

Collective read using explicit offset.

Parameters

- offset (int)
- **buf** (BufSpec)
- status (Status / None)

Return type

None

Read_at_all_begin(offset, buf)

Start a split collective read using explicit offset.

Parameters

- offset (int)
- **buf** (BufSpec)

Return type

None

Read_at_all_end(buf, status=None)

Complete a split collective read using explicit offset.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Read_ordered(buf, status=None)

Collective read using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

```
Read_ordered_begin(buf)
```

Start a split collective read using shared file pointer.

Parameters

buf (BufSpec)

Return type

None

Read_ordered_end(buf, status=None)

Complete a split collective read using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Read_shared(buf, status=None)

Read using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Seek(offset, whence=SEEK_SET)

Update the individual file pointer.

Parameters

- offset (int)
- whence (int)

Return type

None

Seek_shared(offset, whence=SEEK_SET)

Update the shared file pointer.

Parameters

- offset (int)
- whence (int)

Return type

None

Set_atomicity(flag)

Set the atomicity mode.

Parameters

flag (bool)

Return type

```
Set_errhandler(errhandler)
     Set the error handler for a file.
         Parameters
             errhandler (Errhandler)
         Return type
             None
Set_info(info)
     Set new values for the hints associated with a file.
         Parameters
             info (Info)
         Return type
             None
Set_size(size)
     Set the file size.
         Parameters
             size(int)
         Return type
             None
Set_view(disp=0, etype=BYTE, filetype=None, datarep='native', info=INFO_NULL)
     Set the file view.
         Parameters
             • disp(int)
             • etype (Datatype)
             • filetype (Datatype / None)
             • datarep (str)
             • info (Info)
         Return type
             None
Sync()
     Causes all previous writes to be transferred to the storage device.
         Return type
             None
Write(buf, status=None)
     Write using individual file pointer.
         Parameters
             • buf (BufSpec)
             • status (Status / None)
         Return type
```

```
Write_all(buf, status=None)
```

Collective write using individual file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_all_begin(buf)

Start a split collective write using individual file pointer.

Parameters

buf (BufSpec)

Return type

None

Write_all_end(buf, status=None)

Complete a split collective write using individual file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_at(offset, buf, status=None)

Write using explicit offset.

Parameters

- offset (int)
- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_at_all(offset, buf, status=None)

Collective write using explicit offset.

Parameters

- offset (int)
- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_at_all_begin(offset, buf)

Start a split collective write using explicit offset.

Parameters

```
• offset (int)
```

• **buf** (BufSpec)

Return type

None

Write_at_all_end(buf, status=None)

Complete a split collective write using explicit offset.

Parameters

- buf (BufSpec)
- status (Status / None)

Return type

None

Write_ordered(buf, status=None)

Collective write using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_ordered_begin(buf)

Start a split collective write using shared file pointer.

Parameters

buf (BufSpec)

Return type

None

Write_ordered_end(buf, status=None)

Complete a split collective write using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

None

Write_shared(buf, status=None)

Write using shared file pointer.

Parameters

- **buf** (BufSpec)
- status (Status / None)

Return type

```
classmethod f2py(arg)
        Parameters
            arg(int)
        Return type
            File
free()
    Call Close if not null.
        Return type
            None
classmethod fromhandle(handle)
    Create object from MPI handle.
        Parameters
            handle (int)
        Return type
            File
py2f()
        Return type
            int
Attributes Documentation
amode
    Access mode.
atomicity
    Atomicity mode.
group
    Group.
group_rank
    Group rank.
group_size
    Group size.
handle
    MPI handle.
info
    Info hints.
size
    Size (in bytes).
```

mpi4py.MPI.Graphcomm

class mpi4py.MPI.Graphcomm

Bases: Topocomm

General graph topology intracommunicator.

static __new__(cls, comm=None)

Parameters

comm (Graphcomm / None)

Return type

Self

Methods Summary

<pre>Get_dims()</pre>	Return the number of nodes and edges.
<pre>Get_neighbors(rank)</pre>	Return list of neighbors of a process.
<pre>Get_neighbors_count(rank)</pre>	Return number of neighbors of a process.
<pre>Get_topo()</pre>	Return index and edges.

Attributes Summary

dims	Number of nodes and edges.
edges	Edges.
index	Index.
nedges	Number of edges.
neighbors	Neighbors.
nneighbors	Number of neighbors.
nnodes	Number of nodes.
topo	Topology information.

Methods Documentation

Get_dims()

Return the number of nodes and edges.

Return type

tuple[int, int]

Get_neighbors(rank)

Return list of neighbors of a process.

Parameters

rank (int)

Return type

list[int]

```
Get_neighbors_count(rank)
          Return number of neighbors of a process.
              Parameters
                  rank (int)
              Return type
                  int
     Get_topo()
          Return index and edges.
              Return type
                  tuple[list[int], list[int]]
     Attributes Documentation
     dims
          Number of nodes and edges.
     edges
          Edges.
     index
          Index.
     nedges
          Number of edges.
     neighbors
          Neighbors.
     nneighbors
          Number of neighbors.
     nnodes
          Number of nodes.
     topo
          Topology information.
mpi4py.MPI.Grequest
class mpi4py.MPI.Grequest
     Bases: Request
     Generalized request handler.
     static __new__(cls, request=None)
              Parameters
                  request (Grequest | None)
              Return type
                  Self
```

Methods Summary

Complete()	Notify that a user-defined request is complete.
<pre>Start([query_fn, free_fn, cancel_fn, args,])</pre>	Create and return a user-defined request.
<pre>complete([obj])</pre>	Notify that a user-defined request is complete.

Methods Documentation

Complete()

Notify that a user-defined request is complete.

Return type

None

classmethod Start(query_fn=None, free_fn=None, cancel_fn=None, args=None, kwargs=None) Create and return a user-defined request.

Parameters

- query_fn (Callable[[...], None] | None)
- free_fn(Callable[[...], None] | None)
- cancel_fn(Callable[[...], None] | None)
- args(tuple[Any] | None)
- kwargs (dict[str, Any] | None)

Return type

Grequest

complete(obj=None)

Notify that a user-defined request is complete.

Parameters

obj (Any)

Return type

None

mpi4py.MPI.Group

```
class mpi4py.MPI.Group
```

Bases: object

Group of processes.

static __new__(cls, group=None)

Parameters

group (Group | None)

Return type

Self

Methods Summary

Compare(group)	Compare two groups.
<pre>Create_from_session_pset(session, pset_name)</pre>	Create a new group from session and process set.
Difference(group1, group2)	Create a new group from the difference of two existing groups.
Dup()	Duplicate a group.
Excl(ranks)	Create a new group by excluding listed members.
Free()	Free a group.
<pre>Get_rank()</pre>	Return the rank of this process in a group.
<pre>Get_size()</pre>	Return the number of processes in a group.
Incl(ranks)	Create a new group by including listed members.
<pre>Intersection(group1, group2)</pre>	Create a new group from the intersection of two existing groups.
Range_excl(ranks)	Create a new group by excluding ranges of members.
Range_incl(ranks)	Create a new group by including ranges of members.
<pre>Translate_ranks([ranks, group])</pre>	Translate ranks in a group to those in another group.
Union(group1, group2)	Create a new group from the union of two existing groups.
f2py(arg)	
free()	Call <i>Free</i> if not null or predefined.
fromhandle(handle)	Create object from MPI handle.
py2f()	

Attributes Summary

handle	MPI handle.
rank	Rank of this process.
size	Number of processes.

Methods Documentation

```
Compare(group)
```

Compare two groups.

Parameters

group (Group)

Return type

int

classmethod Create_from_session_pset(session, pset_name)

Create a new group from session and process set.

Parameters

- session (Session)
- $pset_name(str)$

```
Return type
             Self
classmethod Difference(group1, group2)
     Create a new group from the difference of two existing groups.
         Parameters
             • group1 (Group)
             • group2 (Group)
         Return type
             Self
Dup()
     Duplicate a group.
         Return type
             Self
Excl(ranks)
     Create a new group by excluding listed members.
         Parameters
             ranks (Sequence[int])
         Return type
             Self
Free()
     Free a group.
         Return type
             None
Get_rank()
     Return the rank of this process in a group.
         Return type
             int
Get_size()
     Return the number of processes in a group.
         Return type
             int
Incl(ranks)
     Create a new group by including listed members.
         Parameters
             ranks (Sequence[int])
         Return type
             Self
classmethod Intersection(group1, group2)
     Create a new group from the intersection of two existing groups.
         Parameters
             • group1 (Group)
```

```
• group2 (Group)
        Return type
            Self
Range_excl(ranks)
    Create a new group by excluding ranges of members.
         Parameters
            ranks (Sequence[tuple[int, int, int]])
         Return type
            Self
Range_incl(ranks)
    Create a new group by including ranges of members.
         Parameters
            ranks (Sequence[tuple[int, int, int]])
         Return type
            Self
Translate_ranks(ranks=None, group=None)
     Translate ranks in a group to those in another group.
         Parameters
             • ranks (Sequence[int] | None)
             • group (Group / None)
         Return type
            list[int]
classmethod Union(group1, group2)
     Create a new group from the union of two existing groups.
         Parameters
             • group1 (Group)
             • group2 (Group)
         Return type
            Self
classmethod f2py(arg)
        Parameters
            arg(int)
         Return type
            Group
free()
    Call Free if not null or predefined.
         Return type
            None
```

```
classmethod fromhandle(handle)
          Create object from MPI handle.
              Parameters
                 handle (int)
             Return type
                 Group
     py2f()
             Return type
                 int
     Attributes Documentation
     handle
          MPI handle.
     rank
          Rank of this process.
     size
          Number of processes.
mpi4py.MPI.InPlaceType
class mpi4py.MPI.InPlaceType
     Bases: int
     Type of IN_PLACE.
     static __new__(cls)
             Return type
                 Self
mpi4py.MPI.Info
class mpi4py.MPI.Info
     Bases: object
     Info object.
     static __new__(cls, info=None)
             Parameters
                 info (Info | None)
             Return type
```

Self

Methods Summary

5 (F) 3)	
Create([items])	Create a new info object.
Create_env([args])	Create a new environment info object.
Delete(key)	Remove a (key, value) pair from info.
Dup()	Duplicate an existing info object.
Free()	Free an info object.
Get(key)	Retrieve the value associated with a key.
<pre>Get_nkeys()</pre>	Return the number of currently defined keys in info.
<pre>Get_nthkey(n)</pre>	Return the <i>n</i> -th defined key in info.
Set(key, value)	Store a value associated with a key.
clear()	Clear contents.
copy()	Copy contents.
f2py(arg)	
free()	Call <i>Free</i> if not null or predefined.
<pre>fromhandle(handle)</pre>	Create object from MPI handle.
<pre>get(key[, default])</pre>	Retrieve value by key.
items()	Return list of items.
keys()	Return list of keys.
pop(key, *default)	Pop value by key.
popitem()	Pop first item.
py2f()	
<pre>update([items])</pre>	Update contents.
values()	Return list of values.

Attributes Summary

Methods Documentation

Self

```
classmethod Create(items=None)
    Create a new info object.

Parameters
    items(Info | Mapping[str, str] | Iterable[tuple[str, str]] | None)

Return type
    Self

classmethod Create_env(args=None)
    Create a new environment info object.

Parameters
    args(Sequence[str] | None)

Return type
```

```
Delete(key)
     Remove a (key, value) pair from info.
         Parameters
             key (str)
         Return type
             None
Dup()
     Duplicate an existing info object.
         Return type
             Self
Free()
     Free an info object.
         Return type
             None
Get(key)
     Retrieve the value associated with a key.
         Parameters
             key (str)
         Return type
             str | None
Get_nkeys()
     Return the number of currently defined keys in info.
         Return type
             int
Get_nthkey(n)
     Return the n-th defined key in info.
         Parameters
             n (int)
         Return type
             str
Set(key, value)
     Store a value associated with a key.
         Parameters
             • key (str)
             • value (str)
         Return type
             None
clear()
     Clear contents.
         Return type
```

```
copy()
     Copy contents.
         Return type
             Self
classmethod f2py(arg)
         Parameters
             arg(int)
         Return type
             Info
free()
     Call Free if not null or predefined.
         Return type
             None
classmethod fromhandle(handle)
     Create object from MPI handle.
         Parameters
             handle (int)
         Return type
             Info
get(key, default=None)
     Retrieve value by key.
         Parameters
             • key (str)
             • default(str | None)
         Return type
             str | None
items()
     Return list of items.
         Return type
             list[tuple[str, str]]
keys()
     Return list of keys.
         Return type
             list[str]
pop(key, *default)
     Pop value by key.
         Parameters
             • key (str)
             • default (str)
         Return type
             str
```

```
popitem()
          Pop first item.
              Return type
                 tuple[str, str]
     py2f()
              Return type
                 int
     update(items=(), **kwds)
          Update contents.
              Parameters
                  • items (Info | Mapping[str, str] | Iterable[tuple[str, str]])
                  • kwds (str)
              Return type
                 None
     values()
          Return list of values.
              Return type
                 list[str]
     Attributes Documentation
     handle
          MPI handle.
mpi4py.MPI.Intercomm
class mpi4py.MPI.Intercomm
     Bases: Comm
     Intercommunicator.
     static __new__(cls, comm=None)
              Parameters
                 comm (Intercomm / None)
              Return type
                 Self
```

Methods Summary

<pre>Create_from_groups(local_group,[,])</pre>	Create communicator from group.
<pre>Get_remote_group()</pre>	Access the remote group associated with the inter- communicator.
<pre>Get_remote_size()</pre>	Intercommunicator remote size.
Merge([high])	Merge intercommunicator into an intracommunicator.

Attributes Summary

remote_group	Remote group.
remote_size	Number of remote processes.

Methods Documentation

Create communicator from group.

Parameters

- local_group (Group)
- local_leader(int)
- remote_group (Group)
- remote_leader(int)
- stringtag (str)
- info (Info)
- errhandler (Errhandler / None)

Return type

Intracomm

Get_remote_group()

Access the remote group associated with the inter-communicator.

Return type

Group

Get_remote_size()

Intercommunicator remote size.

Return type

int

Merge(high=False)

Merge intercommunicator into an intracommunicator.

Parameters

 $\mathbf{high} \ (bool)$

Return type

Intracomm

Attributes Documentation

```
remote_group
```

Remote group.

remote_size

Number of remote processes.

mpi4py.MPI.Intracomm

```
class mpi4py.MPI.Intracomm
```

Bases: Comm

Intracommunicator.

static __new__(cls, comm=None)

Parameters

comm (Intracomm / None)

Return type

Self

Methods Summary

<pre>Accept(port_name[, info, root])</pre>	Accept a request to form a new intercommunicator.
<pre>Cart_map(dims[, periods])</pre>	Determine optimal process placement on a Cartesian
	topology.
<pre>Connect(port_name[, info, root])</pre>	Make a request to form a new intercommunicator.
<pre>Create_cart(dims[, periods, reorder])</pre>	Create cartesian communicator.
Create_dist_graph(sources, degrees, destina-	Create distributed graph communicator.
tions)	
Create_dist_graph_adjacent(sources, destina-	Create distributed graph communicator.
tions)	
<pre>Create_from_group(group[, stringtag, info,])</pre>	Create communicator from group.
<pre>Create_graph(index, edges[, reorder])</pre>	Create graph communicator.
<pre>Create_group(group[, tag])</pre>	Create communicator from group.
<pre>Create_intercomm(local_leader, peer_comm,)</pre>	Create intercommunicator.
Exscan(sendbuf, recvbuf[, op])	Exclusive Scan.
<pre>Exscan_init(sendbuf, recvbuf[, op, info])</pre>	Persistent Exclusive Scan.
<pre>Graph_map(index, edges)</pre>	Determine optimal process placement on a graph
	topology.
<pre>Iexscan(sendbuf, recvbuf[, op])</pre>	Inclusive Scan.
Iscan(sendbuf, recvbuf[, op])	Inclusive Scan.
Scan(sendbuf, recvbuf[, op])	Inclusive Scan.
<pre>Scan_init(sendbuf, recvbuf[, op, info])</pre>	Persistent Inclusive Scan.
Spawn(command[, args, maxprocs, info, root,])	Spawn instances of a single MPI application.
<pre>Spawn_multiple(command[, args, maxprocs,])</pre>	Spawn instances of multiple MPI applications.
exscan(sendobj[, op])	Exclusive Scan.
scan(sendobj[, op])	Inclusive Scan.

Methods Documentation

```
Accept(port_name, info=INFO_NULL, root=0)
```

Accept a request to form a new intercommunicator.

Parameters

- port_name (str)
- info (Info)
- root (int)

Return type

Intercomm

Cart_map(dims, periods=None)

Determine optimal process placement on a Cartesian topology.

Parameters

- dims (Sequence[int])
- periods (Sequence[bool] | None)

Return type

int

Connect(port_name, info=INFO_NULL, root=0)

Make a request to form a new intercommunicator.

Parameters

- port_name (str)
- info (Info)
- root (int)

Return type

Intercomm

Create_cart(dims, periods=None, reorder=False)

Create cartesian communicator.

Parameters

- dims (Sequence[int])
- periods (Sequence[bool] | None)
- reorder (bool)

Return type

Cartcomm

Create_dist_graph(sources, degrees, destinations, weights=None, info=INFO_NULL, reorder=False)

Create distributed graph communicator.

- sources (Sequence[int])
- degrees (Sequence[int])
- destinations (Sequence[int])

- weights (Sequence[int] | None)
- info (Info)
- reorder (bool)

Distgraphcomm

Create distributed graph communicator.

Parameters

- sources (Sequence[int])
- destinations (Sequence[int])
- sourceweights (Sequence[int] | None)
- destweights (Sequence[int] | None)
- info (Info)
- reorder (bool)

Return type

Distgraphcomm

classmethod Create_from_group(*group*, *stringtag='org.mpi4py'*, *info=INFO_NULL*, *errhandler=None*)

Create communicator from group.

Parameters

- group (Group)
- stringtag (str)
- info (Info)
- errhandler (Errhandler | None)

Return type

Intracomm

Create_graph(index, edges, reorder=False)

Create graph communicator.

Parameters

- index (Sequence[int])
- edges (Sequence[int])
- reorder (bool)

Return type

Graphcomm

Create_group(group, tag=0)

Create communicator from group.

Parameters

• group (Group)

```
• tag(int)
```

Intracomm

Create_intercomm(local_leader, peer_comm, remote_leader, tag=0)

Create intercommunicator.

Parameters

- local_leader(int)
- peer_comm (Intracomm)
- remote_leader(int)
- **tag** (*int*)

Return type

Intercomm

Exscan(sendbuf, recvbuf, op=SUM)

Exclusive Scan.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- **op** (0p)

Return type

None

Exscan_init(sendbuf, recvbuf, op=SUM, info=INFO_NULL)

Persistent Exclusive Scan.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- **op** (0p)
- info (Info)

Return type

Prequest

Graph_map(index, edges)

Determine optimal process placement on a graph topology.

Parameters

- index (Sequence[int])
- edges (Sequence[int])

Return type

int

lexscan(sendbuf, recvbuf, op=SUM)

Inclusive Scan.

```
• sendbuf (BufSpec / InPlace)
```

- recvbuf (BufSpec)
- **op** (0p)

Request

Iscan(sendbuf, recvbuf, op=SUM)

Inclusive Scan.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpec)
- **op** (0p)

Return type

Request

Scan(sendbuf, recvbuf, op=SUM)

Inclusive Scan.

Parameters

- **sendbuf** (BufSpec / InPlace)
- recvbuf (BufSpec)
- op (0p)

Return type

None

Scan_init(sendbuf, recvbuf, op=SUM, info=INFO_NULL)

Persistent Inclusive Scan.

Parameters

- sendbuf (BufSpec / InPlace)
- recvbuf (BufSpec)
- op (0p)
- info (Info)

Return type

Prequest

Spawn(*command*, *args=None*, *maxprocs=1*, *info=INFO_NULL*, *root=0*, *errcodes=None*)

Spawn instances of a single MPI application.

- command (str)
- args (Sequence[str] | None)
- maxprocs (int)
- info (Info)
- root (int)

```
• errcodes (list[int] | None)
             Return type
                 Intercomm
     Spawn_multiple(command, args=None, maxprocs=None, info=INFO_NULL, root=0, errcodes=None)
          Spawn instances of multiple MPI applications.
             Parameters
                 • command (Sequence[str])
                 • args (Sequence[Sequence[str]] | None)
                 • maxprocs (Sequence[int] | None)
                 • info (Sequence[Info] / Info)
                 • root (int)
                 • errcodes (list[list[int]] | None)
             Return type
                 Intercomm
     exscan(sendobj, op=SUM)
         Exclusive Scan.
             Parameters
                 • sendobj (Any)
                 • op (Op | Callable[[Any, Any], Any])
             Return type
                 Any
     scan(sendobj, op=SUM)
          Inclusive Scan.
             Parameters
                 • sendobj (Any)
                 • op (Op | Callable[[Any, Any], Any])
             Return type
                 Any
mpi4py.MPI.Message
class mpi4py.MPI.Message
     Bases: object
     Matched message.
     static __new__(cls, message=None)
             Parameters
                 message (Message / None)
             Return type
                 Self
```

Iprobe(comm[, source, tag, status])	Nonblocking test for a matched message.
Irecv(buf)	Nonblocking receive of matched message.
<pre>Probe(comm[, source, tag, status])</pre>	Blocking test for a matched message.
Recv(buf[, status])	Blocking receive of matched message.
f2py(arg)	
free()	Do nothing.
<pre>fromhandle(handle)</pre>	Create object from MPI handle.
<pre>iprobe(comm[, source, tag, status])</pre>	Nonblocking test for a matched message.
irecv()	Nonblocking receive of matched message.
<pre>probe(comm[, source, tag, status])</pre>	Blocking test for a matched message.
py2f()	
recv([status])	Blocking receive of matched message.

Attributes Summary

Methods Documentation

 $\textbf{classmethod Iprobe}(\textit{comm}, \textit{source=ANY_SOURCE}, \textit{tag=ANY_TAG}, \textit{status=None})$

Nonblocking test for a matched message.

Parameters

- comm (Comm)
- source (int)
- **tag** (*int*)
- status (Status / None)

Return type

Self | None

Irecv(buf)

Nonblocking receive of matched message.

Parameters

buf (BufSpec)

Return type

Request

classmethod Probe(comm, source=ANY_SOURCE, tag=ANY_TAG, status=None)

Blocking test for a matched message.

Parameters

• comm (Comm)

```
• source (int)
            • tag (int)
             • status (Status / None)
        Return type
            Self
Recv(buf, status=None)
     Blocking receive of matched message.
        Parameters
            • buf (BufSpec)
            • status (Status / None)
        Return type
            None
classmethod f2py(arg)
        Parameters
            arg(int)
        Return type
            Message
free()
    Do nothing.
        Return type
            None
classmethod fromhandle(handle)
    Create object from MPI handle.
        Parameters
            handle (int)
        Return type
            Message
classmethod iprobe(comm, source=ANY_SOURCE, tag=ANY_TAG, status=None)
    Nonblocking test for a matched message.
        Parameters
             • comm (Comm)
             • source (int)
            • tag (int)
            • status (Status | None)
        Return type
            Self | None
irecv()
    Nonblocking receive of matched message.
        Return type
```

Request

```
classmethod probe(comm, source=ANY_SOURCE, tag=ANY_TAG, status=None)
          Blocking test for a matched message.
              Parameters
                  • comm (Comm)
                  • source (int)
                  • tag (int)
                  • status (Status | None)
             Return type
                 Self
     py2f()
             Return type
                 int
     recv(status=None)
          Blocking receive of matched message.
              Parameters
                 status (Status | None)
             Return type
                 Any
     Attributes Documentation
     handle
          MPI handle.
mpi4py.MPI.Op
class mpi4py.MPI.Op
     Bases: object
     Reduction operation.
     static __new__(cls, op=None)
             Parameters
                 op (0p / None)
              Return type
                 Self
```

Create a user-defined reduction operation.
Free a user-defined reduction operation.
Query reduction operations for their commutativity.
Apply a reduction operation to local data.
Call <i>Free</i> if not null or predefined.
Create object from MPI handle.

Attributes Summary

handle	MPI handle.
is_commutative	Is a commutative operation.
is_predefined	Is a predefined operation.

Methods Documentation

classmethod Create(function, commute=False)

Create a user-defined reduction operation.

Parameters

- function (Callable[[Buffer, Buffer, Datatype], None])
- commute (bool)

Return type

Self

Free()

Free a user-defined reduction operation.

Return type

None

Is_commutative()

Query reduction operations for their commutativity.

Return type

bool

Reduce_local(inbuf, inoutbuf)

Apply a reduction operation to local data.

- inbuf (BufSpec)
- inoutbuf (BufSpec)

```
Return type
                 None
     classmethod f2py(arg)
              Parameters
                  arg(int)
              Return type
                 Op
     free()
          Call Free if not null or predefined.
              Return type
                  None
     classmethod fromhandle(handle)
          Create object from MPI handle.
              Parameters
                 handle (int)
              Return type
                  Op
     py2f()
              Return type
                 int
     Attributes Documentation
     handle
          MPI handle.
     is_commutative
          Is a commutative operation.
     is_predefined
          Is a predefined operation.
mpi4py.MPI.Pickle
class mpi4py.MPI.Pickle
     Bases: object
     Pickle/unpickle Python objects.
     static __new__(cls, pickle=None)
              Parameters
                 pickle (Pickle / None)
              Return type
```

Self

dumps(obj)	Serialize object to pickle data stream.
dumps_oob(obj)	Serialize object to pickle data stream and out-of-band buffers.
loads(data)	Deserialize object from pickle data stream.
loads_oob(data, buffers)	Deserialize object from pickle data stream and out- of-band buffers.

Attributes Summary

PROTOCOL	Protocol version.
THRESHOLD	Out-of-band threshold.

Methods Documentation

```
dumps(obj)
```

Serialize object to pickle data stream.

Parameters

obj (Any)

Return type

bytes

 $dumps_oob(obj)$

Serialize object to pickle data stream and out-of-band buffers.

Parameters

obj (Any)

Return type

tuple[bytes, list[buffer]]

loads(data)

Deserialize object from pickle data stream.

Parameters

data (Buffer)

Return type

Any

loads_oob(data, buffers)

Deserialize object from pickle data stream and out-of-band buffers.

Parameters

- data (Buffer)
- buffers (Iterable[Buffer])

Return type

Any

Attributes Documentation

PROTOCOL

Protocol version.

THRESHOLD

Out-of-band threshold.

mpi4py.MPI.Prequest

```
class mpi4py.MPI.Prequest
    Bases: Request

Persistent request handler.

static __new__(cls, request=None)

Parameters
    request (Prequest | None)

Return type

Self
```

Methods Summary

Parrived(partition)	Test partial completion of a partitioned receive operation.
Pready(partition)	Mark a given partition as ready.
<pre>Pready_list(partitions)</pre>	Mark a sequence of partitions as ready.
<pre>Pready_range(partition_low, partition_high)</pre>	Mark a range of partitions as ready.
Start()	Initiate a communication with a persistent request.
Startall(requests)	Start a collection of persistent requests.

Methods Documentation

Parrived(partition)

Test partial completion of a partitioned receive operation.

```
Parameters
partition (int)

Return type
bool
```

Pready(partition)

Mark a given partition as ready.

```
Parameters
partition (int)

Return type
None
```

```
Pready_list(partitions)
          Mark a sequence of partitions as ready.
              Parameters
                  partitions (Sequence[int])
              Return type
                  None
     Pready_range(partition_low, partition_high)
          Mark a range of partitions as ready.
              Parameters
                  • partition_low(int)
                  • partition_high (int)
              Return type
                  None
     Start()
          Initiate a communication with a persistent request.
              Return type
                  None
     classmethod Startall(requests)
          Start a collection of persistent requests.
              Parameters
                  requests (list[Prequest])
              Return type
                  None
mpi4py.MPI.Request
class mpi4py.MPI.Request
     Bases: object
     Request handler.
     static __new__(cls, request=None)
              Parameters
                  request (Request | None)
              Return type
                  Self
```

Cancel a request. Free a communication request.
Non-destructive test for the completion of a request.
Non-destructive test for the completion of all requests.
Non-destructive test for the completion of any requests.
Non-destructive test for completion of some requests.
Test for the completion of a non-blocking operation.
Test for completion of all previously initiated requests.
Test for completion of any previously initiated request.
Test for completion of some previously initiated requests.
Wait for a non-blocking operation to complete.
Wait for all previously initiated requests to complete.
Wait for any previously initiated request to complete.
Wait for some previously initiated requests to complete.
Cancel a request.
Call Free if not null.
Create object from MPI handle.
Non-destructive test for the completion of a request.
Non-destructive test for the completion of all requests.
Non-destructive test for the completion of any requests.
Non-destructive test for completion of some requests.
Test for the completion of a non-blocking operation.
Test for completion of all previously initiated requests.
Test for completion of any previously initiated request.
Test for completion of some previously initiated requests.
Wait for a non-blocking operation to complete.
Wait for all previously initiated requests to complete.
Wait for any previously initiated request to complete.
Wait for some previously initiated requests to complete.

handle MPI handle.

Methods Documentation

Cancel()

Cancel a request.

Return type

None

Free()

Free a communication request.

Return type

None

Get_status(status=None)

Non-destructive test for the completion of a request.

Parameters

status (Status | None)

Return type

bool

classmethod Get_status_all(requests, statuses=None)

Non-destructive test for the completion of all requests.

Parameters

- requests (Sequence [Request])
- statuses (list[Status] | None)

Return type

bool

classmethod Get_status_any(requests, status=None)

Non-destructive test for the completion of any requests.

Parameters

- requests (Sequence [Request])
- status (Status / None)

Return type

tuple[int, bool]

classmethod Get_status_some(requests, statuses=None)

Non-destructive test for completion of some requests.

- requests (Sequence[Request])
- statuses (list[Status] | None)

```
Return type
```

list[int] | None

Test(status=None)

Test for the completion of a non-blocking operation.

Parameters

status (Status | None)

Return type

bool

classmethod Testall(requests, statuses=None)

Test for completion of all previously initiated requests.

Parameters

- requests (Sequence[Request])
- statuses (list[Status] | None)

Return type

bool

classmethod Testany(requests, status=None)

Test for completion of any previously initiated request.

Parameters

- requests (Sequence [Request])
- status (Status / None)

Return type

tuple[int, bool]

classmethod Testsome(requests, statuses=None)

Test for completion of some previously initiated requests.

Parameters

- requests (Sequence [Request])
- statuses (list[Status] | None)

Return type

list[int] | None

Wait(status=None)

Wait for a non-blocking operation to complete.

Parameters

status (Status | None)

Return type

Literal[True]

classmethod Waitall(requests, statuses=None)

Wait for all previously initiated requests to complete.

- requests (Sequence[Request])
- statuses (list[Status] | None)

```
Return type
            Literal[True]
classmethod Waitany(requests, status=None)
     Wait for any previously initiated request to complete.
         Parameters
             • requests (Sequence [Request])
             • status (Status / None)
         Return type
             int
classmethod Waitsome(requests, statuses=None)
     Wait for some previously initiated requests to complete.
         Parameters
             • requests (Sequence[Request])
             • statuses (list[Status] | None)
         Return type
            list[int] | None
cancel()
    Cancel a request.
         Return type
            None
classmethod f2py(arg)
         Parameters
            arg(int)
         Return type
             Request
free()
    Call Free if not null.
         Return type
             None
classmethod fromhandle(handle)
    Create object from MPI handle.
         Parameters
            handle (int)
         Return type
             Request
get_status(status=None)
    Non-destructive test for the completion of a request.
         Parameters
             status (Status | None)
```

Return type bool

```
classmethod get_status_all(requests, statuses=None)
```

Non-destructive test for the completion of all requests.

Parameters

- requests (Sequence [Request])
- statuses (list[Status] | None)

Return type

bool

classmethod get_status_any(requests, status=None)

Non-destructive test for the completion of any requests.

Parameters

- requests (Sequence[Request])
- status (Status / None)

Return type

tuple[int, bool]

classmethod get_status_some(requests, statuses=None)

Non-destructive test for completion of some requests.

Parameters

- requests (Sequence[Request])
- statuses (list[Status] | None)

Return type

list[int] | None

py2f()

Return type

int

test(status=None)

Test for the completion of a non-blocking operation.

Parameters

```
status (Status | None)
```

Return type

tuple[bool, Any | None]

classmethod testall(requests, statuses=None)

Test for completion of all previously initiated requests.

Parameters

- requests (Sequence [Request])
- statuses (list[Status] | None)

Return type

tuple[bool, list[Any] | None]

classmethod testany(requests, status=None)

Test for completion of any previously initiated request.

Parameters

- requests (Sequence [Request])
- status (Status / None)

Return type

tuple[int, bool, Any | None]

classmethod testsome(requests, statuses=None)

Test for completion of some previously initiated requests.

Parameters

- requests (Sequence[Request])
- statuses (list[Status] | None)

Return type

tuple[list[int] | None, list[Any] | None]

wait(status=None)

Wait for a non-blocking operation to complete.

Parameters

status (Status | None)

Return type

Any

classmethod waitall(requests, statuses=None)

Wait for all previously initiated requests to complete.

Parameters

- requests (Sequence [Request])
- statuses (list[Status] | None)

Return type

list[Any]

classmethod waitany(requests, status=None)

Wait for any previously initiated request to complete.

Parameters

- requests (Sequence [Request])
- status (Status / None)

Return type

tuple[int, *Any*]

classmethod waitsome(requests, statuses=None)

Wait for some previously initiated requests to complete.

- requests (Sequence[Request])
- statuses (list[Status] | None)

tuple[list[int] | None, list[Any] | None]

Attributes Documentation

handle

MPI handle.

mpi4py.MPI.Session

```
class mpi4py.MPI.Session
```

Bases: object

Session context.

static __new__(cls, session=None)

Parameters

session (Session | None)

Return type

Self

Methods Summary

Attach_buffer(buf)	Attach a user-provided buffer for sending in buffered mode.
Call_errhandler(errorcode)	Call the error handler installed on a session.
<pre>Create_errhandler(errhandler_fn)</pre>	Create a new error handler for sessions.
Create_group(pset_name)	Create a new group from session and process set.
Detach_buffer()	Remove an existing attached buffer.
Finalize()	Finalize a session.
Flush_buffer()	Block until all buffered messages have been transmitted.
<pre>Get_errhandler()</pre>	Get the error handler for a session.
<pre>Get_info()</pre>	Return the current hints for a session.
<pre>Get_nth_pset(n[, info])</pre>	Name of the <i>n</i> -th process set.
<pre>Get_num_psets([info])</pre>	Number of available process sets.
<pre>Get_pset_info(pset_name)</pre>	Return the current hints for a session and process set.
Iflush_buffer()	Nonblocking flush for buffered messages.
<pre>Init([info, errhandler])</pre>	Create a new session.
Set_errhandler(errhandler)	Set the error handler for a session.
f2py(arg)	
free()	Call Finalize if not null.
<pre>fromhandle(handle)</pre>	Create object from MPI handle.
py2f()	

handle MPI handle.

Methods Documentation

None

```
Attach_buffer(buf)
     Attach a user-provided buffer for sending in buffered mode.
         Parameters
             buf (Buffer | None)
         Return type
             None
Call_errhandler(errorcode)
     Call the error handler installed on a session.
         Parameters
             errorcode (int)
         Return type
             None
classmethod Create_errhandler(errhandler_fn)
     Create a new error handler for sessions.
         Parameters
             errhandler_fn (Callable[[Session, int], None])
         Return type
             Errhandler
Create_group(pset_name)
     Create a new group from session and process set.
         Parameters
             pset_name(str)
         Return type
             Group
Detach_buffer()
     Remove an existing attached buffer.
         Return type
             Buffer | None
Finalize()
     Finalize a session.
         Return type
             None
Flush_buffer()
     Block until all buffered messages have been transmitted.
         Return type
```

```
Get_errhandler()
     Get the error handler for a session.
         Return type
             Errhandler
Get_info()
     Return the current hints for a session.
         Return type
             Info
Get_nth_pset(n, info=INFO_NULL)
     Name of the n-th process set.
         Parameters
             • n (int)
             • info (Info)
         Return type
             str
Get_num_psets(info=INFO_NULL)
     Number of available process sets.
         Parameters
             info (Info)
         Return type
             int
Get_pset_info(pset_name)
     Return the current hints for a session and process set.
         Parameters
             pset_name (str)
         Return type
             Info
Iflush_buffer()
     Nonblocking flush for buffered messages.
         Return type
             Request
classmethod Init(info=INFO_NULL, errhandler=None)
     Create a new session.
         Parameters
             • info (Info)
             • errhandler (Errhandler / None)
         Return type
             Self
```

Set the error handler for a session.

Set_errhandler(errhandler)

```
Parameters
                 errhandler (Errhandler)
             Return type
                 None
     classmethod f2py(arg)
             Parameters
                 arg(int)
             Return type
                 Session
     free()
          Call Finalize if not null.
             Return type
                 None
     classmethod fromhandle(handle)
          Create object from MPI handle.
              Parameters
                 handle (int)
             Return type
                 Session
     py2f()
              Return type
                 int
     Attributes Documentation
     handle
          MPI handle.
mpi4py.MPI.Status
class mpi4py.MPI.Status
     Bases: object
     Status object.
     static __new__(cls, status=None)
             Parameters
                 status (Status | None)
             Return type
                 Self
```

<pre>Get_count([datatype])</pre>	Get the number of <i>top level</i> elements.
<pre>Get_elements(datatype)</pre>	Get the number of basic elements in a datatype.
<pre>Get_error()</pre>	Get message error.
<pre>Get_source()</pre>	Get message source.
<pre>Get_tag()</pre>	Get message tag.
<pre>Is_cancelled()</pre>	Test to see if a request was cancelled.
Set_cancelled(flag)	Set the cancelled state associated with a status.
<pre>Set_elements(datatype, count)</pre>	Set the number of elements in a status.
Set_error(error)	Set message error.
Set_source(source)	Set message source.
Set_tag(tag)	Set message tag.
f2py(arg)	
py2f()	

Attributes Summary

cancelled	Cancelled state.
count	Byte count.
error	Message error.
source	Message source.
tag	Message tag.

Methods Documentation

```
Get_count(datatype=BYTE)
     Get the number of top level elements.
         Parameters
            datatype (Datatype)
         Return type
            int
Get_elements(datatype)
     Get the number of basic elements in a datatype.
         Parameters
            datatype (Datatype)
         Return type
            int
Get_error()
     Get message error.
         Return type
            int
```

```
Get_source()
     Get message source.
         Return type
             int
Get_tag()
     Get message tag.
         Return type
             int
Is_cancelled()
     Test to see if a request was cancelled.
         Return type
             bool
Set_cancelled(flag)
```

Set the cancelled state associated with a status.

Note

This method should be used only when implementing query callback functions for generalized requests.

```
Parameters
   flag (bool)
Return type
   None
```

Set_elements(datatype, count)

Set the number of elements in a status.

Note

This method should be only used when implementing query callback functions for generalized requests.

Parameters

```
• datatype (Datatype)
```

• count (int)

Return type

None

Set_error(error)

Set message error.

Parameters error (int) **Return type**

```
Set_source(source)
          Set message source.
             Parameters
                 source (int)
             Return type
                 None
     Set_tag(tag)
          Set message tag.
             Parameters
                 tag(int)
             Return type
                 None
     classmethod f2py(arg)
             Parameters
                 arg(list[int])
             Return type
                 Self
     py2f()
             Return type
                 list[int]
     Attributes Documentation
     cancelled
          Cancelled state.
     count
          Byte count.
     error
          Message error.
     source
          Message source.
     tag
          Message tag.
mpi4py.MPI.Topocomm
class mpi4py.MPI.Topocomm
     Bases: Intracomm
```

Topology intracommunicator.

<pre>Ineighbor_allgather(sendbuf, recvbuf)</pre>	Nonblocking Neighbor Gather to All.
<pre>Ineighbor_allgatherv(sendbuf, recvbuf)</pre>	Nonblocking Neighbor Gather to All Vector.
<pre>Ineighbor_alltoall(sendbuf, recvbuf)</pre>	Nonblocking Neighbor All to All.
<pre>Ineighbor_alltoallv(sendbuf, recvbuf)</pre>	Nonblocking Neighbor All to All Vector.
<pre>Ineighbor_alltoallw(sendbuf, recvbuf)</pre>	Nonblocking Neighbor All to All General.
<pre>Neighbor_allgather(sendbuf, recvbuf)</pre>	Neighbor Gather to All.
<pre>Neighbor_allgather_init(sendbuf, recvbuf[,</pre>	Persistent Neighbor Gather to All.
info])	
<pre>Neighbor_allgatherv(sendbuf, recvbuf)</pre>	Neighbor Gather to All Vector.
<pre>Neighbor_allgatherv_init(sendbuf, recvbuf[,</pre>	Persistent Neighbor Gather to All Vector.
])	
<pre>Neighbor_alltoall(sendbuf, recvbuf)</pre>	Neighbor All to All.
<pre>Neighbor_alltoall_init(sendbuf, recvbuf[,</pre>	Persistent Neighbor All to All.
info])	
<pre>Neighbor_alltoallv(sendbuf, recvbuf)</pre>	Neighbor All to All Vector.
<pre>Neighbor_alltoallv_init(sendbuf, recvbuf[,</pre>	Persistent Neighbor All to All Vector.
info])	
<pre>Neighbor_alltoallw(sendbuf, recvbuf)</pre>	Neighbor All to All General.
<pre>Neighbor_alltoallw_init(sendbuf, recvbuf[,</pre>	Persistent Neighbor All to All General.
info])	
<pre>neighbor_allgather(sendobj)</pre>	Neighbor Gather to All.
neighbor_alltoall(sendobj)	Neighbor All to All.

Attributes Summary

degrees	Number of incoming and outgoing neighbors.
indegree	Number of incoming neighbors.
inedges	Incoming neighbors.
inoutedges	Incoming and outgoing neighbors.
outdegree	Number of outgoing neighbors.
outedges	Outgoing neighbors.

Methods Documentation

Ineighbor_allgather(sendbuf, recvbuf)

Nonblocking Neighbor Gather to All.

Parameters

- sendbuf (BufSpec)
- recvbuf (BufSpecB)

Return type

Request

Ineighbor_allgatherv(sendbuf, recvbuf)

Nonblocking Neighbor Gather to All Vector.

Parameters

- sendbuf (BufSpec)
- recvbuf (BufSpecV)

Return type

Request

Ineighbor_alltoall(sendbuf, recvbuf)

Nonblocking Neighbor All to All.

Parameters

- sendbuf (BufSpecB)
- recvbuf (BufSpecB)

Return type

Request

Ineighbor_alltoallv(sendbuf, recvbuf)

Nonblocking Neighbor All to All Vector.

Parameters

- sendbuf (BufSpecV)
- recvbuf (BufSpecV)

Return type

Request

Ineighbor_alltoallw(sendbuf, recvbuf)

Nonblocking Neighbor All to All General.

Parameters

- sendbuf (BufSpecW)
- recvbuf (BufSpecW)

Return type

Request

```
Neighbor_allgather(sendbuf, recvbuf)
    Neighbor Gather to All.
        Parameters
             • sendbuf (BufSpec)
             • recvbuf (BufSpecB)
        Return type
            None
Neighbor_allgather_init(sendbuf, recvbuf, info=INFO_NULL)
    Persistent Neighbor Gather to All.
        Parameters
             • sendbuf (BufSpec)
             • recvbuf (BufSpecB)
             • info (Info)
        Return type
            Prequest
Neighbor_allgatherv(sendbuf, recvbuf)
    Neighbor Gather to All Vector.
        Parameters
            • sendbuf (BufSpec)
             • recvbuf (BufSpecV)
        Return type
            None
Neighbor_allgatherv_init(sendbuf, recvbuf, info=INFO_NULL)
    Persistent Neighbor Gather to All Vector.
        Parameters
             • sendbuf (BufSpec)

    recvbuf (BufSpecV)

             • info (Info)
        Return type
            Prequest
Neighbor_alltoall(sendbuf, recvbuf)
    Neighbor All to All.
```

Parameters

- **sendbuf** (BufSpecB)
- recvbuf (BufSpecB)

Return type

None

Neighbor_alltoall_init(sendbuf, recvbuf, info=INFO_NULL)

Persistent Neighbor All to All.

Parameters

- sendbuf (BufSpecB)
- recvbuf (BufSpecB)
- info (Info)

Return type

Prequest

Neighbor_alltoallv(sendbuf, recvbuf)

Neighbor All to All Vector.

Parameters

- sendbuf (BufSpecV)
- recvbuf (BufSpecV)

Return type

None

Neighbor_alltoallv_init(sendbuf, recvbuf, info=INFO_NULL)

Persistent Neighbor All to All Vector.

Parameters

- sendbuf (BufSpecV)
- recvbuf (BufSpecV)
- info (Info)

Return type

Prequest

Neighbor_alltoallw(sendbuf, recvbuf)

Neighbor All to All General.

Parameters

- **sendbuf** (BufSpecW)
- recvbuf (BufSpecW)

Return type

None

Neighbor_alltoallw_init(sendbuf, recvbuf, info=INFO_NULL)

Persistent Neighbor All to All General.

Parameters

- sendbuf (BufSpecW)
- recvbuf (BufSpecW)
- info (Info)

Return type

Prequest

```
neighbor_allgather(sendobj)
          Neighbor Gather to All.
              Parameters
                  sendobj (Any)
              Return type
                  list[Any]
     neighbor_alltoall(sendobj)
          Neighbor All to All.
              Parameters
                  sendobj (list[Any])
              Return type
                  list[Any]
     Attributes Documentation
     degrees
          Number of incoming and outgoing neighbors.
     indegree
          Number of incoming neighbors.
     inedges
          Incoming neighbors.
     inoutedges
          Incoming and outgoing neighbors.
     outdegree
          Number of outgoing neighbors.
     outedges
          Outgoing neighbors.
mpi4py.MPI.Win
class mpi4py.MPI.Win
     Bases: object
     Remote memory access context.
     static __new__(cls, win=None)
              Parameters
                  win (Win / None)
              Return type
                  Self
```

<pre>Accumulate(origin, target_rank[, target, op])</pre>	Accumulate data into the target process.
Allocate(size[, disp_unit, info, comm])	Create an window object for one-sided communication.
Allocate_shared(size[, disp_unit, info, comm])	Create an window object for one-sided communication.
Attach(memory)	Attach a local memory region.
Call_errhandler(errorcode)	Call the error handler installed on a window.
Compare_and_swap(origin, compare, result,)	Perform one-sided atomic compare-and-swap.
Complete()	Complete an RMA operation begun after an Start.
<pre>Create(memory[, disp_unit, info, comm])</pre>	Create an window object for one-sided communication.
<pre>Create_dynamic([info, comm])</pre>	Create an window object for one-sided communication.
<pre>Create_errhandler(errhandler_fn)</pre>	Create a new error handler for windows.
<pre>Create_keyval([copy_fn, delete_fn, nopython])</pre>	Create a new attribute key for windows.
Delete_attr(keyval)	Delete attribute value associated with a key.
Detach(memory)	Detach a local memory region.
Fence([assertion])	Perform an MPI fence synchronization on a window.
<pre>Fetch_and_op(origin, result, target_rank[,])</pre>	Perform one-sided read-modify-write.
Flush(rank)	Complete all outstanding RMA operations at a target.
Flush_all()	Complete all outstanding RMA operations at all targets.
Flush_local(rank)	Complete locally all outstanding RMA operations at a target.
Flush_local_all()	Complete locally all outstanding RMA operations at all targets.
Free()	Free a window.
Free_keyval(keyval)	Free an attribute key for windows.
<pre>Get(origin, target_rank[, target])</pre>	Get data from a memory window on a remote process.
<pre>Get_accumulate(origin, result, target_rank)</pre>	Fetch-and-accumulate data into the target process.
<pre>Get_attr(keyval)</pre>	Retrieve attribute value by key.
<pre>Get_errhandler()</pre>	Get the error handler for a window.
<pre>Get_group()</pre>	Access the group of processes that created the window.
<pre>Get_info()</pre>	Return the current hints for a window.
<pre>Get_name()</pre>	Get the print name for this window.
<pre>Lock(rank[, lock_type, assertion])</pre>	Begin an RMA access epoch at the target process.
Lock_all([assertion])	Begin an RMA access epoch at all processes.
Post(group[, assertion])	Start an RMA exposure epoch.
<pre>Put(origin, target_rank[, target])</pre>	Put data into a memory window on a remote process.
<pre>Raccumulate(origin, target_rank[, target, op])</pre>	Fetch-and-accumulate data into the target process.
<pre>Rget(origin, target_rank[, target])</pre>	Get data from a memory window on a remote process.
Rget_accumulate(origin, result, target_rank)	Accumulate data into the target process using remote memory access.
<pre>Rput(origin, target_rank[, target])</pre>	Put data into a memory window on a remote process.
Set_attr(keyval, attrval)	Store attribute value associated with a key.
Set_errhandler(errhandler)	Set the error handler for a window.
Set_info(info)	Set new values for the hints associated with a window.
<pre>Set_name(name)</pre>	Set the print name for this window.

continues on next page

Table 6 – continued from previous page

Shared_query(rank)	Query the process-local address for remote memory segments.
Start(group[, assertion])	Start an RMA access epoch for MPI.
Sync()	Synchronize public and private copies of the window.
Test()	Test whether an RMA exposure epoch has completed.
Unlock(rank)	Complete an RMA access epoch at the target process.
Unlock_all()	Complete an RMA access epoch at all processes.
Wait()	Complete an RMA exposure epoch begun with <i>Post</i> .
f2py(arg)	
free()	Call Free if not null.
fromhandle(handle)	Create object from MPI handle.
py2f()	
tomemory()	Return window memory buffer.

Attributes Summary

attrs	Attributes.
flavor	Create flavor.
group	Group.
group_rank	Group rank.
group_size	Group size.
handle	MPI handle.
info	Info hints.
model	Memory model.
name	Print name.

Methods Documentation

Accumulate(origin, target_rank, target=None, op=SUM)

Accumulate data into the target process.

Parameters

- origin (BufSpec)
- $target_rank(int)$
- target(TargetSpec / None)
- op (0p)

Return type

None

classmethod Allocate(size, disp_unit=1, info=INFO_NULL, comm=COMM_SELF)

Create an window object for one-sided communication.

- size (int)
- disp_unit (int)

```
• info (Info)
             • comm (Intracomm)
         Return type
            Self
classmethod Allocate_shared(size, disp_unit=1, info=INFO_NULL, comm=COMM_SELF)
    Create an window object for one-sided communication.
         Parameters
             • size (int)
             • disp_unit (int)
             • info (Info)
             • comm (Intracomm)
         Return type
            Self
Attach(memory)
     Attach a local memory region.
         Parameters
            memory (Buffer)
         Return type
            None
Call_errhandler(errorcode)
     Call the error handler installed on a window.
         Parameters
            errorcode(int)
         Return type
            None
Compare_and_swap(origin, compare, result, target_rank, target_disp=0)
    Perform one-sided atomic compare-and-swap.
         Parameters
             • origin (BufSpec)
             • compare (BufSpec)
             • result (BufSpec)
             • target_rank(int)
             • target_disp(int)
         Return type
            None
Complete()
    Complete an RMA operation begun after an Start.
         Return type
            None
```

```
Create an window object for one-sided communication.
        Parameters
            • memory (Buffer / Bottom)
            • disp_unit(int)
            • info (Info)
            • comm (Intracomm)
        Return type
            Self
classmethod Create_dynamic(info=INFO_NULL, comm=COMM_SELF)
    Create an window object for one-sided communication.
        Parameters
            • info (Info)
            • comm (Intracomm)
        Return type
            Self
classmethod Create_errhandler(errhandler fn)
    Create a new error handler for windows.
        Parameters
            errhandler_fn (Callable[[Win, int], None])
        Return type
            Errhandler
classmethod Create_keyval(copy_fn=None, delete_fn=None, nopython=False)
    Create a new attribute key for windows.
        Parameters
            • copy_fn (Callable[[Win, int, Any], Any] | None)
            • delete_fn(Callable[[Win, int, Any], None] | None)
            • nopython (bool)
        Return type
            int
Delete_attr(keyval)
    Delete attribute value associated with a key.
        Parameters
            keyval (int)
        Return type
            None
Detach(memory)
    Detach a local memory region.
        Parameters
            memory (Buffer)
```

classmethod Create(memory, disp_unit=1, info=INFO_NULL, comm=COMM_SELF)

```
Return type
             None
Fence(assertion=0)
     Perform an MPI fence synchronization on a window.
         Parameters
             assertion (int)
         Return type
             None
Fetch_and_op(origin, result, target_rank, target_disp=0, op=SUM)
     Perform one-sided read-modify-write.
         Parameters
             • origin (BufSpec)
             • result (BufSpec)
             • target_rank(int)
             • target_disp(int)
             • op (0p)
         Return type
             None
Flush(rank)
     Complete all outstanding RMA operations at a target.
         Parameters
             rank (int)
         Return type
             None
Flush_all()
     Complete all outstanding RMA operations at all targets.
         Return type
             None
Flush_local(rank)
     Complete locally all outstanding RMA operations at a target.
         Parameters
             rank (int)
         Return type
             None
Flush_local_all()
     Complete locally all outstanding RMA operations at all targets.
         Return type
             None
Free()
```

Free a window.

```
Return type
```

None

classmethod Free_keyval(keyval)

Free an attribute key for windows.

Parameters

keyval (int)

Return type

int

Get(origin, target_rank, target=None)

Get data from a memory window on a remote process.

Parameters

- origin (BufSpec)
- target_rank(int)
- target (TargetSpec / None)

Return type

None

Get_accumulate(origin, result, target_rank, target=None, op=SUM)

Fetch-and-accumulate data into the target process.

Parameters

- origin (BufSpec)
- result (BufSpec)
- target_rank(int)
- target (TargetSpec / None)
- op (0p)

Return type

None

Get_attr(keyval)

Retrieve attribute value by key.

Parameters

keyval (int)

Return type

int | Any | None

Get_errhandler()

Get the error handler for a window.

Return type

Errhandler

Get_group()

Access the group of processes that created the window.

Return type

Group

```
Get_info()
```

Return the current hints for a window.

Return type

Info

Get_name()

Get the print name for this window.

Return type

str

Lock(rank, lock_type=LOCK_EXCLUSIVE, assertion=0)

Begin an RMA access epoch at the target process.

Parameters

- rank (int)
- lock_type (int)
- assertion (int)

Return type

None

Lock_all(assertion=0)

Begin an RMA access epoch at all processes.

Parameters

assertion (int)

Return type

None

Post(group, assertion=0)

Start an RMA exposure epoch.

Parameters

- group (Group)
- assertion (int)

Return type

None

Put(origin, target_rank, target=None)

Put data into a memory window on a remote process.

Parameters

- origin (BufSpec)
- target_rank(int)
- target (TargetSpec / None)

Return type

None

Raccumulate(origin, target_rank, target=None, op=SUM)

Fetch-and-accumulate data into the target process.

Parameters

```
• origin (BufSpec)
```

- target_rank(int)
- target (TargetSpec / None)
- op (0p)

Return type

Request

Rget(origin, target_rank, target=None)

Get data from a memory window on a remote process.

Parameters

- origin (BufSpec)
- target_rank(int)
- target (TargetSpec / None)

Return type

Request

Rget_accumulate(origin, result, target_rank, target=None, op=SUM)

Accumulate data into the target process using remote memory access.

Parameters

- origin (BufSpec)
- result (BufSpec)
- target_rank(int)
- target(TargetSpec / None)
- op (0p)

Return type

Request

Rput(origin, target_rank, target=None)

Put data into a memory window on a remote process.

Parameters

- origin (BufSpec)
- target_rank(int)
- target (TargetSpec / None)

Return type

Request

Set_attr(keyval, attrval)

Store attribute value associated with a key.

Parameters

- keyval (int)
- attrval (Any)

Return type

None

```
Set_errhandler(errhandler)
     Set the error handler for a window.
         Parameters
             errhandler (Errhandler)
         Return type
             None
Set_info(info)
     Set new values for the hints associated with a window.
         Parameters
             info (Info)
         Return type
             None
Set_name(name)
     Set the print name for this window.
         Parameters
            name(str)
         Return type
             None
Shared_query(rank)
     Query the process-local address for remote memory segments.
         Parameters
             rank (int)
         Return type
             tuple[buffer, int]
Start(group, assertion=0)
     Start an RMA access epoch for MPI.
         Parameters
             • group (Group)
             • assertion (int)
         Return type
             None
Sync()
     Synchronize public and private copies of the window.
         Return type
             None
Test()
     Test whether an RMA exposure epoch has completed.
         Return type
```

bool

```
Unlock(rank)
    Complete an RMA access epoch at the target process.
         Parameters
            rank (int)
        Return type
            None
Unlock_all()
    Complete an RMA access epoch at all processes.
         Return type
            None
Wait()
    Complete an RMA exposure epoch begun with Post.
         Return type
            Literal[True]
classmethod f2py(arg)
        Parameters
            arg(int)
        Return type
            Win
free()
    Call Free if not null.
        Return type
            None
classmethod fromhandle(handle)
    Create object from MPI handle.
        Parameters
            handle(int)
        Return type
            Win
py2f()
         Return type
            int
tomemory()
    Return window memory buffer.
         Return type
            buffer
```

Attributes Documentation

```
attrs
```

Attributes.

flavor

Create flavor.

group

Group.

group_rank

Group rank.

group_size

Group size.

handle

MPI handle.

info

Info hints.

model

Memory model.

name

Print name.

mpi4py.MPI.buffer

```
class mpi4py.MPI.buffer
```

Bases: object

Buffer.

static __new__(cls, buf)

Parameters

buf (Buffer)

Return type

Self

Methods Summary

allocate(nbytes[, clear])	Buffer allocation.
<pre>cast(format[, shape])</pre>	Cast to a memoryview with new format or shape.
<pre>fromaddress(address, nbytes[, readonly])</pre>	Buffer from address and size in bytes.
<pre>frombuffer(obj[, readonly])</pre>	Buffer from buffer-like object.
release()	Release the underlying buffer exposed by the buffer object.
tobytes([order])	Return the data in the buffer as a byte string.
toreadonly()	Return a readonly version of the buffer object.

Attributes Summary

address	Buffer address.
format	Format of each element.
itemsize	Size (in bytes) of each element.
nbytes	Buffer size (in bytes).
obj	Object exposing buffer.
readonly	Buffer is read-only.

Methods Documentation

static allocate(nbytes, clear=False)

Buffer allocation.

Parameters

- nbytes (int)
- clear (bool)

Return type

buffer

cast(format, shape=Ellipsis)

Cast to a memoryview with new format or shape.

Parameters

- format (str)
- shape(list[int] | tuple[int, ...])

Return type

memoryview

static fromaddress(address, nbytes, readonly=False)

Buffer from address and size in bytes.

Parameters

- address (int)
- nbytes (int)
- readonly (bool)

Return type

buffer

static frombuffer(obj, readonly=False)

Buffer from buffer-like object.

Parameters

- **obj** (Buffer)
- readonly (bool)

Return type

buffer

```
release()
```

Release the underlying buffer exposed by the buffer object.

Return type

None

tobytes(order=None)

Return the data in the buffer as a byte string.

Parameters

order(str | None)

Return type

bytes

toreadonly()

Return a readonly version of the buffer object.

Return type

buffer

Attributes Documentation

address

Buffer address.

format

Format of each element.

itemsize

Size (in bytes) of each element.

nbytes

Buffer size (in bytes).

obj

Object exposing buffer.

readonly

Buffer is read-only.

mpi4py.MPI.memory

mpi4py.MPI.memory

alias of buffer

Exceptions

mpi4py.MPI.Exception

exception mpi4py.MPI.Exception

Bases: RuntimeError

Exception class.

static __new__(cls, ierr=SUCCESS)

Parameters

ierr (int)

Return type

Self

Methods Summary

<pre>Get_error_class()</pre>	Error class.
<pre>Get_error_code()</pre>	Error code.
<pre>Get_error_string()</pre>	Error string.

Attributes Summary

error_class	Error class.
error_code	Error code.
error_string	Error string.

Methods Documentation

Get_error_class()

Error class.

Return type

int

Get_error_code()

Error code.

Return type

int

Get_error_string()

Error string.

Return type

str

Attributes Documentation

error_class

Error class.

error_code

Error code.

error_string

Error string.

Functions

Add_error_class()	Add an error class to the known error classes.
Add_error_code(errorclass)	Add an error code to an error class.
Add_error_string(errorcode, string)	Associate an <i>error string</i> with an <i>error class</i> or <i>error code</i> .
Aint_add(base, disp)	Return the sum of base address and displacement.
Aint_diff(addr1, addr2)	Return the difference between absolute addresses.
Alloc_mem(size[, info])	Allocate memory for message passing and remote memory access.
Attach_buffer(buf)	Attach a user-provided buffer for sending in buffered mode.
Close_port(port_name)	Close a port.
Compute_dims(nnodes, dims)	Return a balanced distribution of processes per coordinate direction.
<pre>Detach_buffer()</pre>	Remove an existing attached buffer.
Finalize()	Terminate the MPI execution environment.
Flush_buffer()	Block until all buffered messages have been transmitted.
Free_mem(mem)	Free memory allocated with Alloc_mem.
<pre>Get_address(location)</pre>	Get the address of a location in memory.
<pre>Get_error_class(errorcode)</pre>	Convert an error code into an error class.
<pre>Get_error_string(errorcode)</pre>	Return the <i>error string</i> for a given <i>error class</i> or <i>error code</i> .
<pre>Get_hw_resource_info()</pre>	Obtain information about the hardware platform of the calling processor.
<pre>Get_library_version()</pre>	Obtain the version string of the MPI library.
<pre>Get_processor_name()</pre>	Obtain the name of the calling processor.
<pre>Get_version()</pre>	Obtain the version number of the MPI standard.
Iflush_buffer()	Nonblocking flush for buffered messages.
Init()	Initialize the MPI execution environment.
<pre>Init_thread([required])</pre>	Initialize the MPI execution environment.
<pre>Is_finalized()</pre>	Indicate whether Finalize has completed.
<pre>Is_initialized()</pre>	Indicate whether <i>Init</i> has been called.
<pre>Is_thread_main()</pre>	Indicate whether this thread called <i>Init</i> or <i>Init_thread</i> .
Lookup_name(service_name[, info])	Lookup a port name given a service name.
Open_port([info])	Return an address used to connect group of processes.
Pcontrol(level)	Control profiling.
<pre>Publish_name(service_name, port_name[, info])</pre>	Publish a service name.
Query_thread()	Return the level of thread support provided by the MPI library.
	continues on poyt page

Table 7 – continued from previous page

Register_datarep(datarep, read_fn, write_fn,)	Register user-defined data representations.
Remove_error_class(errorclass)	Remove an error class from the known error classes.
Remove_error_code(errorcode)	Remove an error code from the known error codes.
Remove_error_string(errorcode)	Remove <i>error string</i> association from <i>error class</i> or <i>error code</i> .
<pre>Unpublish_name(service_name, port_name[, info])</pre>	Unpublish a service name.
Wtick()	Return the resolution of Wtime.
Wtime()	Return an elapsed time on the calling processor.
<pre>get_vendor()</pre>	Information about the underlying MPI implementation.

mpi4py.MPI.Add_error_class

mpi4py.MPI.Add_error_class()

Add an error class to the known error classes.

Return type

int

mpi4py.MPI.Add_error_code

mpi4py.MPI.Add_error_code(errorclass)

Add an error code to an error class.

Parameters

errorclass(int)

Return type

int

mpi4py.MPI.Add_error_string

mpi4py.MPI.Add_error_string(errorcode, string)

Associate an error string with an error class or error code.

Parameters

- errorcode (int)
- string(str)

Return type

None

```
mpi4py.MPI.Aint_add
```

```
mpi4py.MPI.Aint_add(base, disp)
```

Return the sum of base address and displacement.

Parameters

- base (int)
- disp(int)

Return type

int

mpi4py.MPI.Aint_diff

```
mpi4py.MPI.Aint_diff(addr1, addr2)
```

Return the difference between absolute addresses.

Parameters

- addr1(int)
- addr2 (int)

Return type

int

mpi4py.MPI.Alloc_mem

```
mpi4py.MPI.Alloc_mem(size, info=INFO_NULL)
```

Allocate memory for message passing and remote memory access.

Parameters

- size (int)
- info (Info)

Return type

buffer

mpi4py.MPI.Attach_buffer

```
mpi4py.MPI.Attach_buffer(buf)
```

Attach a user-provided buffer for sending in buffered mode.

Parameters

```
buf (Buffer | None)
```

Return type

None

```
mpi4py.MPI.Close port
mpi4py.MPI.Close_port(port_name)
     Close a port.
          Parameters
              port_name (str)
          Return type
              None
mpi4py.MPI.Compute_dims
mpi4py.MPI.Compute_dims(nnodes, dims)
     Return a balanced distribution of processes per coordinate direction.
          Parameters
                • nnodes (int)
                • dims(int | Sequence[int])
          Return type
              list[int]
mpi4py.MPI.Detach buffer
mpi4py.MPI.Detach_buffer()
     Remove an existing attached buffer.
          Return type
              Buffer | None
mpi4py.MPI.Finalize
mpi4py.MPI.Finalize()
     Terminate the MPI execution environment.
          Return type
              None
mpi4py.MPI.Flush_buffer
mpi4py.MPI.Flush_buffer()
     Block until all buffered messages have been transmitted.
```

Return type None

```
mpi4py.MPI.Free mem
mpi4py.MPI.Free_mem(mem)
     Free memory allocated with Alloc_mem.
          Parameters
              mem (buffer)
          Return type
              None
mpi4py.MPI.Get_address
mpi4py.MPI.Get_address(location)
     Get the address of a location in memory.
          Parameters
              location (Buffer / Bottom)
          Return type
              int
mpi4py.MPI.Get_error_class
mpi4py.MPI.Get_error_class(errorcode)
     Convert an error code into an error class.
          Parameters
              errorcode (int)
          Return type
              int
mpi4py.MPI.Get_error_string
mpi4py.MPI.Get_error_string(errorcode)
     Return the error string for a given error class or error code.
          Parameters
              errorcode (int)
          Return type
              str
mpi4py.MPI.Get_hw_resource_info
mpi4py.MPI.Get_hw_resource_info()
     Obtain information about the hardware platform of the calling processor.
          Return type
              Info
```

```
mpi4py.MPI.Get library version
mpi4py.MPI.Get_library_version()
     Obtain the version string of the MPI library.
          Return type
              str
mpi4py.MPI.Get_processor_name
mpi4py.MPI.Get_processor_name()
     Obtain the name of the calling processor.
          Return type
              str
mpi4py.MPI.Get_version
mpi4py.MPI.Get_version()
     Obtain the version number of the MPI standard.
          Return type
              tuple[int, int]
mpi4py.MPI.Iflush buffer
mpi4py.MPI.Iflush_buffer()
     Nonblocking flush for buffered messages.
          Return type
              Request
mpi4py.MPI.Init
mpi4py.MPI.Init()
     Initialize the MPI execution environment.
          Return type
              None
mpi4py.MPI.Init_thread
mpi4py.MPI.Init_thread(required=THREAD_MULTIPLE)
     Initialize the MPI execution environment.
          Parameters
              required (int)
          Return type
              int
```

```
mpi4py.MPI.Is finalized
mpi4py.MPI.Is_finalized()
     Indicate whether Finalize has completed.
          Return type
              bool
mpi4py.MPI.Is_initialized
mpi4py.MPI.Is_initialized()
     Indicate whether Init has been called.
          Return type
              bool
mpi4py.MPI.Is_thread_main
mpi4py.MPI.Is_thread_main()
     Indicate whether this thread called Init or Init_thread.
          Return type
              bool
mpi4py.MPI.Lookup_name
mpi4py.MPI.Lookup_name(service_name, info=INFO_NULL)
     Lookup a port name given a service name.
          Parameters
                • service_name(str)
                • info (Info)
          Return type
              str
mpi4py.MPI.Open_port
mpi4py.MPI.Open_port(info=INFO_NULL)
     Return an address used to connect group of processes.
          Parameters
              info (Info)
          Return type
              str
```

```
mpi4py.MPI.Pcontrol
mpi4py.MPI.Pcontrol(level)
     Control profiling.
          Parameters
             level(int)
          Return type
             None
mpi4py.MPI.Publish_name
mpi4py.MPI.Publish_name(service_name, port_name, info=INFO_NULL)
     Publish a service name.
          Parameters
               • service_name(str)
               • port_name (str)
               • info (Info)
          Return type
             None
mpi4py.MPI.Query thread
mpi4py.MPI.Query_thread()
     Return the level of thread support provided by the MPI library.
          Return type
             int
mpi4py.MPI.Register_datarep
mpi4py.MPI.Register_datarep(datarep, read_fn, write_fn, extent_fn)
     Register user-defined data representations.
          Parameters
               • datarep(str)
               • read_fn(Callable[[Buffer, Datatype, int, Buffer, int], None])
               • write_fn(Callable[[Buffer, Datatype, int, Buffer, int], None])
               • extent_fn (Callable[[Datatype], int])
```

Return type None

```
mpi4py.MPI.Remove error class
mpi4py.MPI.Remove_error_class(errorclass)
     Remove an error class from the known error classes.
          Parameters
             errorclass(int)
          Return type
             None
mpi4py.MPI.Remove_error_code
mpi4py.MPI.Remove_error_code(errorcode)
     Remove an error code from the known error codes.
          Parameters
             errorcode (int)
          Return type
             None
mpi4py.MPI.Remove_error_string
mpi4py.MPI.Remove_error_string(errorcode)
     Remove error string association from error class or error code.
          Parameters
             errorcode (int)
          Return type
             None
mpi4py.MPI.Unpublish_name
mpi4py.MPI.Unpublish_name(service_name, port_name, info=INFO_NULL)
     Unpublish a service name.
          Parameters
               • service_name (str)
               • port_name (str)
               • info (Info)
          Return type
```

None

mpi4py.MPI.Wtick

```
mpi4py.MPI.Wtick()
```

Return the resolution of Wtime.

Return type

float

mpi4py.MPI.Wtime

```
mpi4py.MPI.Wtime()
```

Return an elapsed time on the calling processor.

Return type

float

mpi4py.MPI.get_vendor

```
mpi4py.MPI.get_vendor()
```

Information about the underlying MPI implementation.

Returns

- string with the name of the MPI implementation.
- integer 3-tuple version number (major, minor, micro).

Return type

tuple[str, tuple[int, int, int]]

Attributes

UNDEFINED	Constant UNDEFINED of type int
ANY_SOURCE	Constant ANY_SOURCE of type int
ANY_TAG	Constant ANY_TAG of type int
PROC_NULL	Constant PROC_NULL of type int
ROOT	Constant ROOT of type int
BOTTOM	Constant BOTTOM of type BottomType
IN_PLACE	Constant IN_PLACE of type InPlaceType
KEYVAL_INVALID	Constant KEYVAL_INVALID of type int
TAG_UB	Constant TAG_UB of type int
IO	Constant IO of type int
WTIME_IS_GLOBAL	Constant WTIME_IS_GLOBAL of type int
UNIVERSE_SIZE	Constant UNIVERSE_SIZE of type int
APPNUM	Constant APPNUM of type int
LASTUSEDCODE	Constant LASTUSEDCODE of type int
WIN_BASE	Constant WIN_BASE of type int
WIN_SIZE	Constant WIN_SIZE of type int
WIN_DISP_UNIT	Constant WIN_DISP_UNIT of type int
WIN_CREATE_FLAVOR	Constant WIN_CREATE_FLAVOR of type int
WIN_FLAVOR	Constant WIN_FLAVOR of type int
WIN_MODEL	Constant WIN_MODEL of type int

Table 8 – continued from previous page

Table 8-	- continued from previous page
SUCCESS	Constant SUCCESS of type int
ERR_LASTCODE	Constant ERR_LASTCODE of type int
ERR_TYPE	Constant ERR_TYPE of type int
ERR_REQUEST	Constant ERR_REQUEST of type int
ERR_OP	Constant ERR_OP of type int
ERR_GROUP	Constant ERR_GROUP of type int
ERR_INFO	Constant ERR_INFO of type int
ERR_ERRHANDLER	Constant ERR_ERRHANDLER of type int
ERR_SESSION	Constant ERR_SESSION of type int
ERR_COMM	Constant ERR_COMM of type int
ERR_WIN	Constant ERR_WIN of type int
ERR_FILE	Constant ERR_FILE of type int
ERR_BUFFER	Constant ERR_BUFFER of type int
ERR_COUNT	Constant ERR_COUNT of type int
ERR_TAG	Constant ERR_TAG of type int
ERR_RANK	Constant ERR_RANK of type int
ERR_ROOT	Constant ERR_ROOT of type int
ERR_TRUNCATE	Constant ERR_TRUNCATE of type int
ERR_IN_STATUS	Constant ERR_IN_STATUS of type int
ERR_PENDING	Constant ERR_PENDING of type int
ERR_TOPOLOGY	Constant ERR_TOPOLOGY of type int
ERR_DIMS	Constant ERR_DIMS of type int
ERR_ARG	Constant ERR_ARG of type int
ERR_OTHER	Constant ERR_OTHER of type int
ERR_UNKNOWN	Constant ERR_UNKNOWN of type int
ERR_INTERN	Constant ERR_INTERN of type int
ERR_KEYVAL	Constant ERR_KEYVAL of type int
ERR_NO_MEM	Constant ERR_NO_MEM of type int
ERR_INFO_KEY	Constant ERR_INFO_KEY of type int
ERR_INFO_VALUE	Constant ERR_INFO_VALUE of type int
ERR_INFO_NOKEY	Constant ERR_INFO_NOKEY of type int
ERR_SPAWN	Constant ERR_SPAWN of type int
ERR_PORT	Constant ERR_PORT of type int
ERR_SERVICE	Constant ERR_SERVICE of type int
ERR_NAME	Constant ERR_NAME of type int
ERR_PROC_ABORTED	Constant ERR_PROC_ABORTED of type int
ERR_BASE	Constant ERR_BASE of type int
ERR_SIZE	Constant ERR_SIZE of type int
ERR_DISP	Constant ERR_DISP of type int
ERR_ASSERT	Constant ERR_ASSERT of type int
ERR_LOCKTYPE	Constant ERR_LOCKTYPE of type int
ERR_RMA_CONFLICT	Constant ERR_RMA_CONFLICT of type int
ERR_RMA_SYNC	Constant ERR_RMA_SYNC of type int
ERR_RMA_RANGE	Constant ERR_RMA_RANGE of type int
ERR_RMA_ATTACH	Constant ERR_RMA_ATTACH of type int
ERR_RMA_SHARED	Constant ERR_RMA_SHARED of type int
ERR_RMA_FLAVOR	Constant ERR_RMA_FLAVOR of type int
ERR_BAD_FILE	Constant ERR_BAD_FILE of type int
ERR_NO_SUCH_FILE	Constant ERR_NO_SUCH_FILE of type int
ERR_FILE_EXISTS	Constant ERR_FILE_EXISTS of type int
ERR_FILE_IN_USE	Constant ERR_FILE_IN_USE of type int
ERR_AMODE	Constant ERR_AMODE of type int
	continues on next nage

Table 8 – continued from previous page

	Table 8 – continued from previous page
ERR_ACCESS	Constant ERR_ACCESS of type int
ERR_READ_ONLY	Constant ERR_READ_ONLY of type int
ERR_NO_SPACE	Constant ERR_NO_SPACE of type int
ERR_QUOTA	Constant ERR_QUOTA of type int
ERR_NOT_SAME	Constant ERR_NOT_SAME of type int
ERR_IO	Constant ERR_IO of type int
ERR_UNSUPPORTED_OPERATION	Constant ERR_UNSUPPORTED_OPERATION of type int
ERR_UNSUPPORTED_DATAREP	Constant ERR_UNSUPPORTED_DATAREP of type int
ERR_CONVERSION	Constant ERR_CONVERSION of type int
ERR_DUP_DATAREP	Constant ERR_DUP_DATAREP of type int
ERR_VALUE_TOO_LARGE	Constant ERR_VALUE_TOO_LARGE of type int
ERR_REVOKED	Constant ERR_REVOKED of type int
ERR_PROC_FAILED	Constant ERR_PROC_FAILED of type int
ERR_PROC_FAILED_PENDING	Constant ERR_PROC_FAILED_PENDING of type int
ORDER_C	Constant ORDER_C of type int
ORDER_FORTRAN	Constant ORDER_FORTRAN of type int
ORDER_F	Constant ORDER_F of type int
TYPECLASS_INTEGER	Constant TYPECLASS_INTEGER of type int
TYPECLASS_REAL	Constant TYPECLASS_REAL of type int
TYPECLASS_COMPLEX	Constant TYPECLASS_COMPLEX of type int
DISTRIBUTE_NONE	Constant DISTRIBUTE_NONE of type int
DISTRIBUTE_BLOCK	Constant DISTRIBUTE_BLOCK of type int
DISTRIBUTE_CYCLIC	Constant DISTRIBUTE_CYCLIC of type int
DISTRIBUTE_DFLT_DARG	Constant DISTRIBUTE_DFLT_DARG of type int
COMBINER_NAMED	Constant COMBINER_NAMED of type int
COMBINER_DUP	Constant COMBINER_DUP of type int
COMBINER_CONTIGUOUS	Constant COMBINER_CONTIGUOUS of type int
COMBINER_VECTOR	Constant COMBINER_VECTOR of type int
COMBINER_HVECTOR	Constant COMBINER_HVECTOR of type int
COMBINER_INDEXED	Constant COMBINER_INDEXED of type int
COMBINER_HINDEXED	Constant COMBINER_HINDEXED of type int
COMBINER_INDEXED_BLOCK	Constant COMBINER_INDEXED_BLOCK of type int
COMBINER_HINDEXED_BLOCK	Constant COMBINER_HINDEXED_BLOCK of type int
COMBINER_STRUCT	Constant COMBINER_STRUCT of type int
COMBINER_SUBARRAY	Constant COMBINER_SUBARRAY of type int
COMBINER_DARRAY	Constant COMBINER_DARRAY of type int
COMBINER_RESIZED	Constant COMBINER_RESIZED of type int
COMBINER_VALUE_INDEX	Constant COMBINER_VALUE_INDEX of type int
COMBINER_F90_INTEGER	Constant COMBINER_F90_INTEGER of type int
COMBINER_F90_REAL	Constant COMBINER_F90_REAL of type int
COMBINER_F90_COMPLEX	Constant COMBINER_F90_COMPLEX of type int
F_SOURCE	Constant F_SOURCE of type int
F_TAG	Constant F_TAG of type int
F_ERROR	Constant F_ERROR of type int
F_STATUS_SIZE	Constant F_STATUS_SIZE of type int
IDENT	Constant IDENT of type int
CONGRUENT	Constant CONGRUENT of type int
SIMILAR	Constant SIMILAR of type int
UNEQUAL	Constant UNEQUAL of type int
CART	Constant CART of type int
GRAPH	Constant GRAPH of type int
DIST_GRAPH	Constant DIST_GRAPH of type int
_	continues on next page

Table 8 – continued from previous page

	Table 8 – continued from previous page
UNWEIGHTED	Constant UNWEIGHTED of type int
WEIGHTS_EMPTY	Constant WEIGHTS_EMPTY of type int
COMM_TYPE_SHARED	Constant COMM_TYPE_SHARED of type int
COMM_TYPE_HW_GUIDED	Constant COMM_TYPE_HW_GUIDED of type int
COMM_TYPE_HW_UNGUIDED	Constant COMM_TYPE_HW_UNGUIDED of type int
COMM_TYPE_RESOURCE_GUIDED	Constant COMM_TYPE_RESOURCE_GUIDED of type int
BSEND_OVERHEAD	Constant BSEND_OVERHEAD of type int
BUFFER_AUTOMATIC	Constant BUFFER_AUTOMATIC of type
	BufferAutomaticType
WIN_FLAVOR_CREATE	Constant WIN_FLAVOR_CREATE of type int
WIN_FLAVOR_ALLOCATE	Constant WIN_FLAVOR_ALLOCATE of type int
WIN_FLAVOR_DYNAMIC	Constant WIN_FLAVOR_DYNAMIC of type int
WIN_FLAVOR_SHARED	Constant WIN_FLAVOR_SHARED of type int
WIN_SEPARATE	Constant WIN_SEPARATE of type int
WIN_UNIFIED	Constant WIN_UNIFIED of type int
MODE_NOCHECK	Constant MODE_NOCHECK of type int
MODE_NOSTORE	Constant MODE_NOSTORE of type int
MODE_NOPUT	Constant MODE_NOPUT of type int
MODE_NOPRECEDE	Constant MODE_NOPRECEDE of type int
MODE_NOSUCCEED	Constant MODE_NOSUCCEED of type int
LOCK_EXCLUSIVE	Constant LOCK_EXCLUSIVE of type int
LOCK_SHARED	Constant LOCK_SHARED of type int
MODE_RDONLY	Constant MODE_RDONLY of type int
MODE_WRONLY	Constant MODE_WRONLY of type int
MODE_RDWR	Constant MODE_RDWR of type int
MODE_CREATE	Constant MODE_CREATE of type int
MODE_EXCL	Constant MODE_EXCL of type int
MODE_DELETE_ON_CLOSE	Constant MODE_DELETE_ON_CLOSE of type int
MODE_UNIQUE_OPEN	Constant MODE_UNIQUE_OPEN of type int
MODE_SEQUENTIAL	Constant MODE_SEQUENTIAL of type int
MODE_APPEND	Constant MODE_APPEND of type int
SEEK_SET	Constant SEEK_SET of type int
SEEK_CUR	Constant SEEK_CUR of type int
SEEK_END	Constant SEEK_END of type int
DISPLACEMENT_CURRENT	Constant DISPLACEMENT_CURRENT of type int
DISP_CUR	Constant DISP_CUR of type int
THREAD_SINGLE	Constant THREAD_SINGLE of type int
THREAD_FUNNELED	Constant THREAD_FUNNELED of type int
THREAD_SERIALIZED	Constant THREAD_SERIALIZED of type int
THREAD_MULTIPLE	Constant THREAD_MULTIPLE of type int
VERSION	Constant VERSION of type int
SUBVERSION	Constant SUBVERSION of type int
MAX_PROCESSOR_NAME	Constant MAX_PROCESSOR_NAME of type int
MAX_ERROR_STRING	Constant MAX_ERROR_STRING of type int
MAX_PORT_NAME	Constant MAX_PORT_NAME of type int
MAX_INFO_KEY	Constant MAX_INFO_KEY of type int
MAX_INFO_VAL	Constant MAX_INFO_VAL of type int
MAX_OBJECT_NAME	Constant MAX_OBJECT_NAME of type int
MAX_DATAREP_STRING	Constant MAX_DATAREP_STRING of type int
MAX_LIBRARY_VERSION_STRING	· •
MAX_PSET_NAME_LEN	
MAX_STRINGTAG_LEN	Constant MAX_PSET_NAME_LEN of type int Constant MAX_STRINGTAG_LEN of type int

Table 8 – continued from previous page

Table 8 – contin	ued from previous page
DATATYPE_NULL	Object DATATYPE_NULL of type Datatype
PACKED	Object PACKED of type Datatype
BYTE	Object BYTE of type Datatype
AINT	Object AINT of type Datatype
OFFSET	Object OFFSET of type Datatype
COUNT	Object COUNT of type Datatype
CHAR	Object CHAR of type Datatype
WCHAR	Object WCHAR of type Datatype
SIGNED_CHAR	Object SIGNED_CHAR of type Datatype
SHORT	Object SHORT of type Datatype
INT	Object INT of type Datatype
LONG	Object LONG of type Datatype
LONG_LONG	Object LONG_LONG of type Datatype
UNSIGNED_CHAR	Object UNSIGNED_CHAR of type Datatype
UNSIGNED_SHORT	Object UNSIGNED_SHORT of type Datatype
UNSIGNED	Object UNSIGNED of type Datatype
UNSIGNED_LONG	Object UNSIGNED_LONG of type Datatype
UNSIGNED_LONG_LONG	Object UNSIGNED_LONG_LONG of type Datatype
FLOAT	Object FLOAT of type Datatype
DOUBLE	Object DOUBLE of type Datatype
LONG_DOUBLE	Object LONG_DOUBLE of type Datatype
C_BOOL	Object C_BOOL of type Datatype
INT8_T	Object INT8_T of type Datatype
INT16_T	Object INT16_T of type Datatype Object INT16_T of type Datatype
INT32_T	Object INT32_T of type Datatype
INT64_T	Object INT64_T of type Datatype Object INT64_T of type Datatype
UINT8_T	Object INTO4_1 of type Datatype Object UINT8_T of type Datatype
UINT16_T	Object UINT16_T of type Datatype Object UINT16_T of type Datatype
UINT32_T	Object UINT10_1 of type Datatype Object UINT32_T of type Datatype
UINT64_T	Object UINT64_T of type Datatype
C_COMPLEX	Object C_COMPLEX of type Datatype
C_FLOAT_COMPLEX	Object C_FLOAT_COMPLEX of type Datatype
C_DOUBLE_COMPLEX	Object C_PLOAT_COMPLEX of type Datatype Object C_DOUBLE_COMPLEX of type Datatype
C_LONG_DOUBLE_COMPLEX	Object C_DOUBLE_COMPLEX of type Datatype Object C_LONG_DOUBLE_COMPLEX of type Datatype
CXX_BOOL	Object CXX_BOOL of type Datatype
CXX_FLOAT_COMPLEX	Object CXX_BOOL of type Datatype Object CXX_FLOAT_COMPLEX of type Datatype
CXX_DOUBLE_COMPLEX	Object CXX_FLOAT_COMPLEX of type Datatype Object CXX_DOUBLE_COMPLEX of type Datatype
CXX_LONG_DOUBLE_COMPLEX	Object CXX_LONG_DOUBLE_COMPLEX of type Datatype
SHORT_INT	Object SHORT_INT of type Datatype
INT_INT	Object INT_INT of type Datatype Object INT_INT of type Datatype
	J
TWOINT	Object TWOINT of type Datatype
LONG_INT	Object LONG_INT of type Datatype
FLOAT_INT	Object FLOAT_INT of type Datatype
DOUBLE_INT	Object LONG POURLE INT of type Datatype
LONG_DOUBLE_INT	Object LONG_DOUBLE_INT of type Datatype
CHARACTER	Object CHARACTER of type Datatype
LOGICAL	Object LOGICAL of type Datatype
INTEGER	Object INTEGER of type Datatype
REAL PROJECTION	Object REAL of type Datatype
DOUBLE_PRECISION	Object DOUBLE_PRECISION of type Datatype
COMPLEX DOUBLE_COMPLEX	Object COMPLEX of type Datatype Object DOUBLE_COMPLEX of type Datatype

Table 8 – continued from previous page

lab	ole 8 – continued from previous page
LOGICAL1	Object LOGICAL1 of type Datatype
LOGICAL2	Object LOGICAL2 of type Datatype
LOGICAL4	Object LOGICAL4 of type Datatype
LOGICAL8	Object LOGICAL8 of type Datatype
INTEGER1	Object INTEGER1 of type Datatype
INTEGER2	Object INTEGER2 of type Datatype
INTEGER4	Object INTEGER4 of type Datatype
INTEGER8	Object INTEGER8 of type Datatype
INTEGER16	Object INTEGER16 of type Datatype
REAL2	Object REAL2 of type Datatype
REAL4	Object REAL4 of type Datatype
REAL8	Object REAL8 of type Datatype
REAL16	Object REAL16 of type Datatype
COMPLEX4	Object COMPLEX4 of type Datatype
COMPLEX8	Object COMPLEX8 of type Datatype
COMPLEX16	Object COMPLEX16 of type Datatype
COMPLEX32	Object COMPLEX32 of type Datatype
UNSIGNED_INT	Object UNSIGNED_INT of type Datatype
SIGNED_SHORT	Object SIGNED_SHORT of type Datatype
SIGNED_INT	Object SIGNED_INT of type Datatype
SIGNED_LONG	Object SIGNED_LONG of type Datatype
SIGNED_LONG_LONG	Object SIGNED_LONG_LONG of type Datatype
BOOL	Object BOOL of type Datatype
SINT8_T	Object SINT8_T of type Datatype
SINT16_T	Object SINT16_T of type Datatype
SINT32_T	Object SINT32_T of type Datatype
SINT64_T	Object SINT64_T of type Datatype
F_BOOL	Object F_BOOL of type Datatype
F_INT	Object F_INT of type Datatype
F_FLOAT	Object F_FLOAT of type Datatype
F_DOUBLE	Object F_DOUBLE of type Datatype
F_COMPLEX	Object F_COMPLEX of type Datatype
F_FLOAT_COMPLEX	Object F_FLOAT_COMPLEX of type Datatype
F_DOUBLE_COMPLEX	Object F_DOUBLE_COMPLEX of type Datatype
REQUEST_NULL	Object REQUEST_NULL of type Request
MESSAGE_NULL	Object MESSAGE_NULL of type Message
MESSAGE_NO_PROC	Object MESSAGE_NO_PROC of type Message
OP_NULL	Object OP_NULL of type <i>Op</i>
MAX	Object MAX of type Op
MIN	Object MIN of type <i>Op</i>
SUM	Object SUM of type <i>Op</i>
PROD	Object PROD of type <i>Op</i>
LAND	Object LAND of type <i>Op</i>
BAND	Object BAND of type Op
LOR	Object LOR of type <i>Op</i>
BOR	Object BOR of type <i>Op</i>
LXOR	Object LXOR of type <i>Op</i>
BXOR	Object BXOR of type <i>Op</i>
MAXLOC	Object MAXLOC of type <i>Op</i>
MINLOC	Object MINLOC of type <i>Op</i>
REPLACE	Object REPLACE of type <i>Op</i>
NO_OP	Object NO_OP of type Op
	continues on next page

Table 8 – continued from previous page

GROUP_NULL	Object GROUP_NULL of type Group
GROUP_EMPTY	Object GROUP_EMPTY of type Group
INFO_NULL	Object INFO_NULL of type Info
INFO_ENV	Object INFO_ENV of type Info
ERRHANDLER_NULL	Object ERRHANDLER_NULL of type Errhandler
ERRORS_RETURN	Object ERRORS_RETURN of type Errhandler
ERRORS_ABORT	Object ERRORS_ABORT of type Errhandler
ERRORS_ARE_FATAL	Object ERRORS_ARE_FATAL of type Errhandler
SESSION_NULL	Object SESSION_NULL of type Session
COMM_NULL	Object COMM_NULL of type Comm
COMM_SELF	Object COMM_SELF of type Intracomm
COMM_WORLD	Object COMM_WORLD of type Intracomm
WIN_NULL	Object WIN_NULL of type Win
FILE_NULL	Object FILE_NULL of type File
pickle	Object pickle of type Pickle

mpi4py.MPI.UNDEFINED

mpi4py.MPI.UNDEFINED: int = UNDEFINED
Constant UNDEFINED of type int

mpi4py.MPI.ANY_SOURCE

mpi4py.MPI.ANY_SOURCE: int = ANY_SOURCE
Constant ANY_SOURCE of type int

mpi4py.MPI.ANY_TAG

mpi4py.MPI.ANY_TAG: int = ANY_TAG
Constant ANY_TAG of type int

$mpi4py.MPI.PROC_NULL$

mpi4py.MPI.PROC_NULL: int = PROC_NULL
Constant PROC_NULL of type int

mpi4py.MPI.ROOT

mpi4py.MPI.BOTTOM

mpi4py.MPI.BOTTOM: BottomType = BOTTOM
 Constant BOTTOM of type BottomType

mpi4py.MPI.IN_PLACE

mpi4py.MPI.IN_PLACE: InPlaceType = IN_PLACE
 Constant IN_PLACE of type InPlaceType

mpi4py.MPI.KEYVAL_INVALID

mpi4py.MPI.KEYVAL_INVALID: int = KEYVAL_INVALID
Constant KEYVAL_INVALID of type int

mpi4py.MPI.TAG_UB

mpi4py.MPI.IO

mpi4py.MPI.IO: int = IO
 Constant IO of type int

mpi4py.MPI.WTIME_IS_GLOBAL

mpi4py.MPI.WTIME_IS_GLOBAL: int = WTIME_IS_GLOBAL
Constant WTIME_IS_GLOBAL of type int

mpi4py.MPI.UNIVERSE_SIZE

mpi4py.MPI.UNIVERSE_SIZE: int = UNIVERSE_SIZE
Constant UNIVERSE_SIZE of type int

mpi4py.MPI.APPNUM

mpi4py.MPI.APPNUM: int = APPNUM
Constant APPNUM of type int

mpi4py.MPI.LASTUSEDCODE

mpi4py.MPI.LASTUSEDCODE: int = LASTUSEDCODE
 Constant LASTUSEDCODE of type int

mpi4py.MPI.WIN_BASE

mpi4py.MPI.WIN_BASE: int = WIN_BASE
Constant WIN_BASE of type int

mpi4py.MPI.WIN_SIZE

mpi4py.MPI.WIN_SIZE: int = WIN_SIZE
Constant WIN_SIZE of type int

mpi4py.MPI.WIN_DISP_UNIT

mpi4py.MPI.WIN_DISP_UNIT: int = WIN_DISP_UNIT
Constant WIN_DISP_UNIT of type int

mpi4py.MPI.WIN_CREATE_FLAVOR

mpi4py.MPI.WIN_FLAVOR

mpi4py.MPI.WIN_MODEL

mpi4py.MPI.WIN_MODEL: int = WIN_MODEL
Constant WIN_MODEL of type int

mpi4py.MPI.SUCCESS

mpi4py.MPI.SUCCESS: int = SUCCESS
Constant SUCCESS of type int

mpi4py.MPI.ERR LASTCODE

mpi4py.MPI.ERR_LASTCODE: int = ERR_LASTCODE
Constant ERR_LASTCODE of type int

mpi4py.MPI.ERR_TYPE

mpi4py.MPI.ERR_TYPE: int = ERR_TYPE
Constant ERR_TYPE of type int

mpi4py.MPI.ERR_REQUEST

mpi4py.MPI.ERR_REQUEST: int = ERR_REQUEST
Constant ERR_REQUEST of type int

mpi4py.MPI.ERR_OP

mpi4py.MPI.ERR_OP: int = ERR_OP
 Constant ERR_OP of type int

mpi4py.MPI.ERR_GROUP

mpi4py.MPI.ERR_GROUP: int = ERR_GROUP
Constant ERR_GROUP of type int

mpi4py.MPI.ERR_INFO

mpi4py.MPI.ERR_INFO: int = ERR_INFO
Constant ERR_INFO of type int

mpi4py.MPI.ERR_ERRHANDLER

mpi4py.MPI.ERR_ERRHANDLER: int = ERR_ERRHANDLER
Constant ERR_ERRHANDLER of type int

mpi4py.MPI.ERR_SESSION

mpi4py.MPI.ERR_SESSION: int = ERR_SESSION
 Constant ERR_SESSION of type int

mpi4py.MPI.ERR COMM

mpi4py.MPI.ERR_COMM: int = ERR_COMM
 Constant ERR_COMM of type int

mpi4py.MPI.ERR_WIN

mpi4py.MPI.ERR_WIN: int = ERR_WIN
Constant ERR_WIN of type int

mpi4py.MPI.ERR_FILE

mpi4py.MPI.ERR_FILE: int = ERR_FILE
Constant ERR_FILE of type int

mpi4py.MPI.ERR_BUFFER

mpi4py.MPI.ERR_BUFFER: int = ERR_BUFFER
Constant ERR_BUFFER of type int

mpi4py.MPI.ERR_COUNT

mpi4py.MPI.ERR_COUNT: int = ERR_COUNT
Constant ERR_COUNT of type int

mpi4py.MPI.ERR_TAG

mpi4py.MPI.ERR_TAG: int = ERR_TAG
Constant ERR_TAG of type int

mpi4py.MPI.ERR_RANK

mpi4py.MPI.ERR_RANK: int = ERR_RANK
Constant ERR_RANK of type int

mpi4py.MPI.ERR_ROOT

mpi4py.MPI.ERR_ROOT: int = ERR_ROOT
 Constant ERR_ROOT of type int

mpi4py.MPI.ERR TRUNCATE

mpi4py.MPI.ERR_TRUNCATE: int = ERR_TRUNCATE
Constant ERR_TRUNCATE of type int

mpi4py.MPI.ERR_IN_STATUS

mpi4py.MPI.ERR_IN_STATUS: int = ERR_IN_STATUS
 Constant ERR_IN_STATUS of type int

mpi4py.MPI.ERR_PENDING

mpi4py.MPI.ERR_PENDING: int = ERR_PENDING
Constant ERR_PENDING of type int

mpi4py.MPI.ERR_TOPOLOGY

mpi4py.MPI.ERR_TOPOLOGY: int = ERR_TOPOLOGY
 Constant ERR_TOPOLOGY of type int

mpi4py.MPI.ERR_DIMS

mpi4py.MPI.ERR_DIMS: int = ERR_DIMS
Constant ERR_DIMS of type int

mpi4py.MPI.ERR_ARG

mpi4py.MPI.ERR_ARG: int = ERR_ARG
Constant ERR_ARG of type int

mpi4py.MPI.ERR_OTHER

mpi4py.MPI.ERR_OTHER: int = ERR_OTHER
Constant ERR_OTHER of type int

mpi4py.MPI.ERR_UNKNOWN

mpi4py.MPI.ERR_UNKNOWN: int = ERR_UNKNOWN
 Constant ERR_UNKNOWN of type int

mpi4py.MPI.ERR INTERN

mpi4py.MPI.ERR_INTERN: int = ERR_INTERN
Constant ERR_INTERN of type int

mpi4py.MPI.ERR_KEYVAL

mpi4py.MPI.ERR_KEYVAL: int = ERR_KEYVAL
Constant ERR_KEYVAL of type int

mpi4py.MPI.ERR_NO_MEM

mpi4py.MPI.ERR_NO_MEM: int = ERR_NO_MEM
Constant ERR_NO_MEM of type int

mpi4py.MPI.ERR_INFO_KEY

mpi4py.MPI.ERR_INFO_KEY: int = ERR_INFO_KEY
Constant ERR_INFO_KEY of type int

mpi4py.MPI.ERR_INFO_VALUE

mpi4py.MPI.ERR_INFO_VALUE: int = ERR_INFO_VALUE
Constant ERR_INFO_VALUE of type int

mpi4py.MPI.ERR_INFO_NOKEY

mpi4py.MPI.ERR_INFO_NOKEY: int = ERR_INFO_NOKEY
 Constant ERR_INFO_NOKEY of type int

mpi4py.MPI.ERR_SPAWN

mpi4py.MPI.ERR_SPAWN: int = ERR_SPAWN
Constant ERR_SPAWN of type int

mpi4py.MPI.ERR_PORT

mpi4py.MPI.ERR_PORT: int = ERR_PORT
Constant ERR_PORT of type int

mpi4py.MPI.ERR SERVICE

mpi4py.MPI.ERR_SERVICE: int = ERR_SERVICE
Constant ERR_SERVICE of type int

mpi4py.MPI.ERR_NAME

mpi4py.MPI.ERR_NAME: int = ERR_NAME
Constant ERR_NAME of type int

mpi4py.MPI.ERR_PROC_ABORTED

mpi4py.MPI.ERR_PROC_ABORTED: int = ERR_PROC_ABORTED
Constant ERR_PROC_ABORTED of type int

mpi4py.MPI.ERR_BASE

mpi4py.MPI.ERR_BASE: int = ERR_BASE
Constant ERR_BASE of type int

mpi4py.MPI.ERR_SIZE

mpi4py.MPI.ERR_SIZE: int = ERR_SIZE
Constant ERR_SIZE of type int

mpi4py.MPI.ERR_DISP

mpi4py.MPI.ERR_DISP: int = ERR_DISP
Constant ERR_DISP of type int

mpi4py.MPI.ERR_ASSERT

mpi4py.MPI.ERR_ASSERT: int = ERR_ASSERT
Constant ERR_ASSERT of type int

mpi4py.MPI.ERR_LOCKTYPE

mpi4py.MPI.ERR_LOCKTYPE: int = ERR_LOCKTYPE
Constant ERR_LOCKTYPE of type int

mpi4py.MPI.ERR_RMA_CONFLICT

mpi4py.MPI.ERR RMA SYNC

mpi4py.MPI.ERR_RMA_SYNC: int = ERR_RMA_SYNC
Constant ERR_RMA_SYNC of type int

mpi4py.MPI.ERR_RMA_RANGE

mpi4py.MPI.ERR_RMA_RANGE: int = ERR_RMA_RANGE
Constant ERR_RMA_RANGE of type int

mpi4py.MPI.ERR_RMA_ATTACH

mpi4py.MPI.ERR_RMA_ATTACH: int = ERR_RMA_ATTACH
 Constant ERR_RMA_ATTACH of type int

mpi4py.MPI.ERR_RMA_SHARED

mpi4py.MPI.ERR_RMA_SHARED: int = ERR_RMA_SHARED
Constant ERR_RMA_SHARED of type int

mpi4py.MPI.ERR_RMA_FLAVOR

mpi4py.MPI.ERR_BAD_FILE

mpi4py.MPI.ERR_BAD_FILE: int = ERR_BAD_FILE
Constant ERR_BAD_FILE of type int

mpi4py.MPI.ERR_NO_SUCH_FILE

mpi4py.MPI.ERR_NO_SUCH_FILE: int = ERR_NO_SUCH_FILE
Constant ERR_NO_SUCH_FILE of type int

mpi4py.MPI.ERR FILE EXISTS

mpi4py.MPI.ERR_FILE_EXISTS: int = ERR_FILE_EXISTS
 Constant ERR_FILE_EXISTS of type int

mpi4py.MPI.ERR_FILE_IN_USE

mpi4py.MPI.ERR_FILE_IN_USE: int = ERR_FILE_IN_USE
 Constant ERR_FILE_IN_USE of type int

mpi4py.MPI.ERR_AMODE

mpi4py.MPI.ERR_AMODE: int = ERR_AMODE
Constant ERR_AMODE of type int

mpi4py.MPI.ERR_ACCESS

mpi4py.MPI.ERR_ACCESS: int = ERR_ACCESS
Constant ERR_ACCESS of type int

mpi4py.MPI.ERR_READ_ONLY

mpi4py.MPI.ERR_READ_ONLY: int = ERR_READ_ONLY
Constant ERR_READ_ONLY of type int

mpi4py.MPI.ERR_NO_SPACE

mpi4py.MPI.ERR_NO_SPACE: int = ERR_NO_SPACE
Constant ERR_NO_SPACE of type int

mpi4py.MPI.ERR_QUOTA

mpi4py.MPI.ERR_QUOTA: int = ERR_QUOTA
Constant ERR_QUOTA of type int

mpi4py.MPI.ERR_NOT_SAME

mpi4py.MPI.ERR_NOT_SAME: int = ERR_NOT_SAME
Constant ERR_NOT_SAME of type int

mpi4py.MPI.ERR IO

mpi4py.MPI.ERR UNSUPPORTED OPERATION

mpi4py.MPI.ERR UNSUPPORTED DATAREP

mpi4py.MPI.ERR_UNSUPPORTED_DATAREP: int = ERR_UNSUPPORTED_DATAREP
Constant ERR_UNSUPPORTED_DATAREP of type int

mpi4py.MPI.ERR_CONVERSION

mpi4py.MPI.ERR_CONVERSION: int = ERR_CONVERSION
 Constant ERR_CONVERSION of type int

mpi4py.MPI.ERR_DUP_DATAREP

mpi4py.MPI.ERR_DUP_DATAREP: int = ERR_DUP_DATAREP
Constant ERR_DUP_DATAREP of type int

mpi4py.MPI.ERR_VALUE_TOO_LARGE

mpi4py.MPI.ERR_REVOKED

mpi4py.MPI.ERR_REVOKED: int = ERR_REVOKED
Constant ERR_REVOKED of type int

mpi4py.MPI.ERR_PROC_FAILED

mpi4py.MPI.ERR_PROC_FAILED: int = ERR_PROC_FAILED
Constant ERR_PROC_FAILED of type int

mpi4py.MPI.ERR PROC FAILED PENDING

mpi4py.MPI.ERR_PROC_FAILED_PENDING: int = ERR_PROC_FAILED_PENDING
Constant ERR_PROC_FAILED_PENDING of type int

mpi4py.MPI.ORDER_C

mpi4py.MPI.ORDER_C: int = ORDER_C
Constant ORDER_C of type int

mpi4py.MPI.ORDER_FORTRAN

mpi4py.MPI.ORDER_FORTRAN: int = ORDER_FORTRAN
Constant ORDER_FORTRAN of type int

mpi4py.MPI.ORDER_F

mpi4py.MPI.ORDER_F: int = ORDER_F
Constant ORDER_F of type int

mpi4py.MPI.TYPECLASS_INTEGER

mpi4py.MPI.TYPECLASS_INTEGER: int = TYPECLASS_INTEGER
Constant TYPECLASS_INTEGER of type int

mpi4py.MPI.TYPECLASS_REAL

mpi4py.MPI.TYPECLASS_REAL: int = TYPECLASS_REAL
Constant TYPECLASS_REAL of type int

mpi4py.MPI.TYPECLASS_COMPLEX

mpi4py.MPI.TYPECLASS_COMPLEX: int = TYPECLASS_COMPLEX
Constant TYPECLASS_COMPLEX of type int

mpi4py.MPI.DISTRIBUTE_NONE

mpi4py.MPI.DISTRIBUTE_NONE: int = DISTRIBUTE_NONE
Constant DISTRIBUTE_NONE of type int

mpi4py.MPI.DISTRIBUTE_BLOCK

mpi4py.MPI.DISTRIBUTE CYCLIC

mpi4py.MPI.DISTRIBUTE_CYCLIC: int = DISTRIBUTE_CYCLIC
Constant DISTRIBUTE_CYCLIC of type int

mpi4py.MPI.DISTRIBUTE DFLT DARG

mpi4py.MPI.DISTRIBUTE_DFLT_DARG: int = DISTRIBUTE_DFLT_DARG
Constant DISTRIBUTE_DFLT_DARG of type int

mpi4py.MPI.COMBINER_NAMED

mpi4py.MPI.COMBINER_NAMED: int = COMBINER_NAMED
Constant COMBINER_NAMED of type int

mpi4py.MPI.COMBINER_DUP

mpi4py.MPI.COMBINER_DUP: int = COMBINER_DUP
Constant COMBINER_DUP of type int

mpi4py.MPI.COMBINER_CONTIGUOUS

mpi4py.MPI.COMBINER_CONTIGUOUS: int = COMBINER_CONTIGUOUS
 Constant COMBINER_CONTIGUOUS of type int

mpi4py.MPI.COMBINER_VECTOR

mpi4py.MPI.COMBINER_VECTOR: int = COMBINER_VECTOR
 Constant COMBINER_VECTOR of type int

mpi4py.MPI.COMBINER_HVECTOR

mpi4py.MPI.COMBINER_INDEXED

mpi4py.MPI.COMBINER_INDEXED: int = COMBINER_INDEXED
Constant COMBINER_INDEXED of type int

mpi4py.MPI.COMBINER HINDEXED

mpi4py.MPI.COMBINER_HINDEXED: int = COMBINER_HINDEXED
Constant COMBINER_HINDEXED of type int

mpi4py.MPI.COMBINER_INDEXED_BLOCK

mpi4py.MPI.COMBINER_INDEXED_BLOCK: int = COMBINER_INDEXED_BLOCK
 Constant COMBINER_INDEXED_BLOCK of type int

mpi4py.MPI.COMBINER_HINDEXED_BLOCK

mpi4py.MPI.COMBINER_HINDEXED_BLOCK: int = COMBINER_HINDEXED_BLOCK
 Constant COMBINER_HINDEXED_BLOCK of type int

mpi4py.MPI.COMBINER_STRUCT

mpi4py.MPI.COMBINER_STRUCT: int = COMBINER_STRUCT
 Constant COMBINER_STRUCT of type int

mpi4py.MPI.COMBINER_SUBARRAY

mpi4py.MPI.COMBINER_SUBARRAY: int = COMBINER_SUBARRAY
 Constant COMBINER_SUBARRAY of type int

mpi4py.MPI.COMBINER_DARRAY

mpi4py.MPI.COMBINER_DARRAY: int = COMBINER_DARRAY
 Constant COMBINER_DARRAY of type int

mpi4py.MPI.COMBINER_RESIZED

mpi4py.MPI.COMBINER_RESIZED: int = COMBINER_RESIZED
Constant COMBINER_RESIZED of type int

mpi4py.MPI.COMBINER_VALUE_INDEX

mpi4py.MPI.COMBINER F90 INTEGER

mpi4py.MPI.COMBINER_F90_INTEGER: int = COMBINER_F90_INTEGER
Constant COMBINER_F90_INTEGER of type int

mpi4py.MPI.COMBINER_F90_REAL

mpi4py.MPI.COMBINER_F90_REAL: int = COMBINER_F90_REAL
Constant COMBINER_F90_REAL of type int

mpi4py.MPI.COMBINER_F90_COMPLEX

mpi4py.MPI.COMBINER_F90_COMPLEX: int = COMBINER_F90_COMPLEX
Constant COMBINER_F90_COMPLEX of type int

mpi4py.MPI.F_SOURCE

mpi4py.MPI.F_SOURCE: int = F_SOURCE
Constant F_SOURCE of type int

mpi4py.MPI.F_TAG

mpi4py.MPI.F_TAG: int = F_TAG
Constant F_TAG of type int

mpi4py.MPI.F_ERROR

mpi4py.MPI.F_ERROR: int = F_ERROR
 Constant F_ERROR of type int

mpi4py.MPI.F_STATUS_SIZE

mpi4py.MPI.F_STATUS_SIZE: int = F_STATUS_SIZE
 Constant F_STATUS_SIZE of type int

mpi4py.MPI.IDENT

mpi4py.MPI.IDENT: int = IDENT
 Constant IDENT of type int

mpi4py.MPI.CONGRUENT

mpi4py.MPI.CONGRUENT: int = CONGRUENT
 Constant CONGRUENT of type int

mpi4py.MPI.SIMILAR

mpi4py.MPI.SIMILAR: int = SIMILAR
 Constant SIMILAR of type int

mpi4py.MPI.UNEQUAL

mpi4py.MPI.UNEQUAL: int = UNEQUAL
Constant UNEQUAL of type int

mpi4py.MPI.CART

mpi4py.MPI.GRAPH

mpi4py.MPI.GRAPH: int = GRAPH
 Constant GRAPH of type int

mpi4py.MPI.DIST_GRAPH

mpi4py.MPI.DIST_GRAPH: int = DIST_GRAPH
 Constant DIST_GRAPH of type int

mpi4py.MPI.UNWEIGHTED

mpi4py.MPI.UNWEIGHTED: int = UNWEIGHTED
Constant UNWEIGHTED of type int

mpi4py.MPI.WEIGHTS EMPTY

mpi4py.MPI.WEIGHTS_EMPTY: int = WEIGHTS_EMPTY
 Constant WEIGHTS_EMPTY of type int

mpi4py.MPI.COMM TYPE SHARED

mpi4py.MPI.COMM_TYPE_SHARED: int = COMM_TYPE_SHARED
Constant COMM_TYPE_SHARED of type int

mpi4py.MPI.COMM TYPE HW GUIDED

mpi4py.MPI.COMM_TYPE_HW_GUIDED: int = COMM_TYPE_HW_GUIDED
Constant COMM_TYPE_HW_GUIDED of type int

mpi4py.MPI.COMM_TYPE_HW_UNGUIDED

mpi4py.MPI.COMM_TYPE_HW_UNGUIDED: int = COMM_TYPE_HW_UNGUIDED
Constant COMM_TYPE_HW_UNGUIDED of type int

mpi4py.MPI.COMM_TYPE_RESOURCE_GUIDED

mpi4py.MPI.COMM_TYPE_RESOURCE_GUIDED: int = COMM_TYPE_RESOURCE_GUIDED
Constant COMM_TYPE_RESOURCE_GUIDED of type int

mpi4py.MPI.BSEND_OVERHEAD

mpi4py.MPI.BSEND_OVERHEAD: int = BSEND_OVERHEAD
Constant BSEND_OVERHEAD of type int

mpi4py.MPI.BUFFER_AUTOMATIC

mpi4py.MPI.BUFFER_AUTOMATIC: BufferAutomaticType = BUFFER_AUTOMATIC
Constant BUFFER_AUTOMATIC of type BufferAutomaticType

mpi4py.MPI.WIN_FLAVOR_CREATE

mpi4py.MPI.WIN_FLAVOR_CREATE: int = WIN_FLAVOR_CREATE
Constant WIN_FLAVOR_CREATE of type int

mpi4py.MPI.WIN_FLAVOR_ALLOCATE

mpi4py.MPI.WIN_FLAVOR_ALLOCATE: int = WIN_FLAVOR_ALLOCATE
Constant WIN_FLAVOR_ALLOCATE of type int

mpi4py.MPI.WIN FLAVOR DYNAMIC

mpi4py.MPI.WIN_FLAVOR_SHARED

mpi4py.MPI.WIN_FLAVOR_SHARED: int = WIN_FLAVOR_SHARED
Constant WIN_FLAVOR_SHARED of type int

mpi4py.MPI.WIN_SEPARATE

mpi4py.MPI.WIN_SEPARATE: int = WIN_SEPARATE
Constant WIN_SEPARATE of type int

mpi4py.MPI.WIN_UNIFIED

mpi4py.MPI.WIN_UNIFIED: int = WIN_UNIFIED
Constant WIN_UNIFIED of type int

mpi4py.MPI.MODE_NOCHECK

mpi4py.MPI.MODE_NOCHECK: int = MODE_NOCHECK
 Constant MODE_NOCHECK of type int

mpi4py.MPI.MODE_NOSTORE

mpi4py.MPI.MODE_NOSTORE: int = MODE_NOSTORE
Constant MODE_NOSTORE of type int

mpi4py.MPI.MODE_NOPUT

mpi4py.MPI.MODE_NOPUT: int = MODE_NOPUT
Constant MODE_NOPUT of type int

mpi4py.MPI.MODE NOPRECEDE

mpi4py.MPI.MODE_NOPRECEDE: int = MODE_NOPRECEDE
Constant MODE_NOPRECEDE of type int

mpi4py.MPI.MODE_NOSUCCEED

mpi4py.MPI.MODE_NOSUCCEED: int = MODE_NOSUCCEED
Constant MODE_NOSUCCEED of type int

mpi4py.MPI.LOCK_EXCLUSIVE

mpi4py.MPI.LOCK_EXCLUSIVE: int = LOCK_EXCLUSIVE
Constant LOCK_EXCLUSIVE of type int

mpi4py.MPI.LOCK_SHARED

mpi4py.MPI.LOCK_SHARED: int = LOCK_SHARED
Constant LOCK_SHARED of type int

mpi4py.MPI.MODE_RDONLY

mpi4py.MPI.MODE_RDONLY: int = MODE_RDONLY
Constant MODE_RDONLY of type int

mpi4py.MPI.MODE_WRONLY

mpi4py.MPI.MODE_WRONLY: int = MODE_WRONLY
Constant MODE_WRONLY of type int

mpi4py.MPI.MODE_RDWR

mpi4py.MPI.MODE_RDWR: int = MODE_RDWR
Constant MODE_RDWR of type int

mpi4py.MPI.MODE_CREATE

mpi4py.MPI.MODE_CREATE: int = MODE_CREATE
Constant MODE_CREATE of type int

mpi4py.MPI.MODE EXCL

mpi4py.MPI.MODE_EXCL: int = MODE_EXCL
Constant MODE_EXCL of type int

mpi4py.MPI.MODE_DELETE_ON_CLOSE

mpi4py.MPI.MODE_UNIQUE_OPEN

mpi4py.MPI.MODE_UNIQUE_OPEN: int = MODE_UNIQUE_OPEN
Constant MODE_UNIQUE_OPEN of type int

mpi4py.MPI.MODE_SEQUENTIAL

mpi4py.MPI.MODE_SEQUENTIAL: int = MODE_SEQUENTIAL
Constant MODE_SEQUENTIAL of type int

mpi4py.MPI.MODE_APPEND

mpi4py.MPI.MODE_APPEND: int = MODE_APPEND
Constant MODE_APPEND of type int

mpi4py.MPI.SEEK_SET

mpi4py.MPI.SEEK_SET: int = SEEK_SET
Constant SEEK_SET of type int

mpi4py.MPI.SEEK_CUR

mpi4py.MPI.SEEK_CUR: int = SEEK_CUR
Constant SEEK_CUR of type int

mpi4py.MPI.SEEK_END

mpi4py.MPI.SEEK_END: int = SEEK_END
Constant SEEK_END of type int

mpi4py.MPI.DISPLACEMENT_CURRENT

mpi4py.MPI.DISPLACEMENT_CURRENT: int = DISPLACEMENT_CURRENT
Constant DISPLACEMENT_CURRENT of type int

mpi4py.MPI.DISP_CUR

mpi4py.MPI.DISP_CUR: int = DISP_CUR
Constant DISP_CUR of type int

mpi4py.MPI.THREAD_SINGLE

mpi4py.MPI.THREAD_SINGLE: int = THREAD_SINGLE
Constant THREAD_SINGLE of type int

mpi4py.MPI.THREAD_FUNNELED

mpi4py.MPI.THREAD_FUNNELED: int = THREAD_FUNNELED
Constant THREAD_FUNNELED of type int

mpi4py.MPI.THREAD_SERIALIZED

mpi4py.MPI.THREAD_SERIALIZED: int = THREAD_SERIALIZED
Constant THREAD_SERIALIZED of type int

mpi4py.MPI.THREAD_MULTIPLE

mpi4py.MPI.THREAD_MULTIPLE: int = THREAD_MULTIPLE
Constant THREAD_MULTIPLE of type int

mpi4py.MPI.VERSION

mpi4py.MPI.VERSION: int = VERSION
 Constant VERSION of type int

mpi4py.MPI.SUBVERSION

mpi4py.MPI.SUBVERSION: int = SUBVERSION
 Constant SUBVERSION of type int

mpi4py.MPI.MAX_PROCESSOR_NAME

mpi4py.MPI.MAX_PROCESSOR_NAME: int = MAX_PROCESSOR_NAME
 Constant MAX_PROCESSOR_NAME of type int

mpi4py.MPI.MAX ERROR STRING

mpi4py.MPI.MAX_PORT_NAME

mpi4py.MPI.MAX_PORT_NAME: int = MAX_PORT_NAME
Constant MAX_PORT_NAME of type int

mpi4py.MPI.MAX_INFO_KEY

mpi4py.MPI.MAX_INFO_KEY: int = MAX_INFO_KEY
Constant MAX_INFO_KEY of type int

mpi4py.MPI.MAX_INFO_VAL

mpi4py.MPI.MAX_INFO_VAL: int = MAX_INFO_VAL
Constant MAX_INFO_VAL of type int

mpi4py.MPI.MAX_OBJECT_NAME

mpi4py.MPI.MAX_OBJECT_NAME: int = MAX_OBJECT_NAME
Constant MAX_OBJECT_NAME of type int

mpi4py.MPI.MAX_DATAREP_STRING

mpi4py.MPI.MAX_DATAREP_STRING: int = MAX_DATAREP_STRING
 Constant MAX_DATAREP_STRING of type int

mpi4py.MPI.MAX_LIBRARY_VERSION_STRING

mpi4py.MPI.MAX_LIBRARY_VERSION_STRING: int = MAX_LIBRARY_VERSION_STRING
 Constant MAX_LIBRARY_VERSION_STRING of type int

mpi4py.MPI.MAX_PSET_NAME_LEN

mpi4py.MPI.MAX_PSET_NAME_LEN: int = MAX_PSET_NAME_LEN
Constant MAX_PSET_NAME_LEN of type int

mpi4py.MPI.MAX_STRINGTAG_LEN

mpi4py.MPI.MAX_STRINGTAG_LEN: int = MAX_STRINGTAG_LEN
Constant MAX_STRINGTAG_LEN of type int

mpi4py.MPI.DATATYPE_NULL

mpi4py.MPI.DATATYPE_NULL: Datatype = DATATYPE_NULL
Object DATATYPE_NULL of type Datatype

mpi4py.MPI.PACKED

mpi4py.MPI.PACKED: Datatype = PACKED
 Object PACKED of type Datatype

mpi4py.MPI.BYTE

mpi4py.MPI.BYTE: Datatype = BYTE
 Object BYTE of type Datatype

mpi4py.MPI.AINT

mpi4py.MPI.AINT: Datatype = AINT
 Object AINT of type Datatype

mpi4py.MPI.OFFSET

mpi4py.MPI.OFFSET: Datatype = OFFSET
 Object OFFSET of type Datatype

mpi4py.MPI.COUNT

mpi4py.MPI.COUNT: Datatype = COUNT
 Object COUNT of type Datatype

mpi4py.MPI.CHAR

mpi4py.MPI.CHAR: Datatype = CHAR
 Object CHAR of type Datatype

mpi4py.MPI.WCHAR

mpi4py.MPI.WCHAR: Datatype = WCHAR
 Object WCHAR of type Datatype

mpi4py.MPI.SIGNED_CHAR

mpi4py.MPI.SIGNED_CHAR: Datatype = SIGNED_CHAR
 Object SIGNED_CHAR of type Datatype

mpi4py.MPI.SHORT

mpi4py.MPI.SHORT: Datatype = SHORT
 Object SHORT of type Datatype

mpi4py.MPI.INT

mpi4py.MPI.INT: Datatype = INT
 Object INT of type Datatype

mpi4py.MPI.LONG

mpi4py.MPI.LONG: Datatype = LONG
 Object LONG of type Datatype

mpi4py.MPI.LONG_LONG

mpi4py.MPI.UNSIGNED_CHAR

mpi4py.MPI.UNSIGNED_CHAR: Datatype = UNSIGNED_CHAR
 Object UNSIGNED_CHAR of type Datatype

mpi4py.MPI.UNSIGNED SHORT

mpi4py.MPI.UNSIGNED_SHORT: Datatype = UNSIGNED_SHORT
 Object UNSIGNED_SHORT of type Datatype

mpi4py.MPI.UNSIGNED

mpi4py.MPI.UNSIGNED: Datatype = UNSIGNED
 Object UNSIGNED of type Datatype

mpi4py.MPI.UNSIGNED_LONG

mpi4py.MPI.UNSIGNED_LONG: Datatype = UNSIGNED_LONG
 Object UNSIGNED_LONG of type Datatype

mpi4py.MPI.UNSIGNED_LONG_LONG

mpi4py.MPI.UNSIGNED_LONG_LONG: Datatype = UNSIGNED_LONG_LONG
Object UNSIGNED_LONG_LONG of type Datatype

mpi4py.MPI.FLOAT

mpi4py.MPI.FLOAT: Datatype = FLOAT
 Object FLOAT of type Datatype

mpi4py.MPI.DOUBLE

mpi4py.MPI.DOUBLE: Datatype = DOUBLE
 Object DOUBLE of type Datatype

mpi4py.MPI.LONG_DOUBLE

mpi4py.MPI.LONG_DOUBLE: Datatype = LONG_DOUBLE
 Object LONG_DOUBLE of type Datatype

mpi4py.MPI.C_BOOL

mpi4py.MPI.C_BOOL: Datatype = C_BOOL
Object C_BOOL of type Datatype

mpi4py.MPI.INT8_T

mpi4py.MPI.INT8_T: Datatype = INT8_T
 Object INT8_T of type Datatype

mpi4py.MPI.INT16_T

mpi4py.MPI.INT16_T: Datatype = INT16_T
 Object INT16_T of type Datatype

mpi4py.MPI.INT32_T

mpi4py.MPI.INT32_T: Datatype = INT32_T
 Object INT32_T of type Datatype

mpi4py.MPI.INT64_T

mpi4py.MPI.INT64_T: Datatype = INT64_T
 Object INT64_T of type Datatype

mpi4py.MPI.UINT8_T

mpi4py.MPI.UINT8_T: Datatype = UINT8_T
 Object UINT8_T of type Datatype

mpi4py.MPI.UINT16_T

mpi4py.MPI.UINT16_T: Datatype = UINT16_T
 Object UINT16_T of type Datatype

mpi4py.MPI.UINT32_T

mpi4py.MPI.UINT32_T: Datatype = UINT32_T
 Object UINT32_T of type Datatype

mpi4py.MPI.UINT64_T

mpi4py.MPI.UINT64_T: Datatype = UINT64_T
 Object UINT64_T of type Datatype

mpi4py.MPI.C COMPLEX

mpi4py.MPI.C_COMPLEX: Datatype = C_COMPLEX
Object C_COMPLEX of type Datatype

mpi4py.MPI.C FLOAT COMPLEX

mpi4py.MPI.C_FLOAT_COMPLEX: Datatype = C_FLOAT_COMPLEX
 Object C_FLOAT_COMPLEX of type Datatype

mpi4py.MPI.C DOUBLE COMPLEX

mpi4py.MPI.C_DOUBLE_COMPLEX: Datatype = C_DOUBLE_COMPLEX
 Object C_DOUBLE_COMPLEX of type Datatype

mpi4py.MPI.C_LONG_DOUBLE_COMPLEX

mpi4py.MPI.C_LONG_DOUBLE_COMPLEX: Datatype = C_LONG_DOUBLE_COMPLEX
 Object C_LONG_DOUBLE_COMPLEX of type Datatype

mpi4py.MPI.CXX_BOOL

mpi4py.MPI.CXX_BOOL: Datatype = CXX_BOOL
 Object CXX_BOOL of type Datatype

mpi4py.MPI.CXX_FLOAT_COMPLEX

mpi4py.MPI.CXX_FLOAT_COMPLEX: Datatype = CXX_FLOAT_COMPLEX
Object CXX_FLOAT_COMPLEX of type Datatype

mpi4py.MPI.CXX_DOUBLE_COMPLEX

mpi4py.MPI.CXX_DOUBLE_COMPLEX: Datatype = CXX_DOUBLE_COMPLEX
 Object CXX_DOUBLE_COMPLEX of type Datatype

mpi4py.MPI.CXX_LONG_DOUBLE_COMPLEX

mpi4py.MPI.CXX_LONG_DOUBLE_COMPLEX: Datatype = CXX_LONG_DOUBLE_COMPLEX
 Object CXX_LONG_DOUBLE_COMPLEX of type Datatype

mpi4py.MPI.SHORT INT

mpi4py.MPI.SHORT_INT: Datatype = SHORT_INT
 Object SHORT_INT of type Datatype

mpi4py.MPI.INT INT

mpi4py.MPI.INT_INT: Datatype = INT_INT
 Object INT_INT of type Datatype

mpi4py.MPI.TWOINT

mpi4py.MPI.TWOINT: Datatype = TWOINT
 Object TWOINT of type Datatype

mpi4py.MPI.LONG_INT

mpi4py.MPI.LONG_INT: Datatype = LONG_INT
 Object LONG_INT of type Datatype

mpi4py.MPI.FLOAT_INT

mpi4py.MPI.FLOAT_INT: Datatype = FLOAT_INT
 Object FLOAT_INT of type Datatype

mpi4py.MPI.DOUBLE_INT

mpi4py.MPI.DOUBLE_INT: Datatype = DOUBLE_INT
 Object DOUBLE_INT of type Datatype

mpi4py.MPI.LONG_DOUBLE_INT

mpi4py.MPI.LONG_DOUBLE_INT: Datatype = LONG_DOUBLE_INT
 Object LONG_DOUBLE_INT of type Datatype

mpi4py.MPI.CHARACTER

mpi4py.MPI.CHARACTER: Datatype = CHARACTER
Object CHARACTER of type Datatype

mpi4py.MPI.LOGICAL

mpi4py.MPI.LOGICAL: Datatype = LOGICAL
 Object LOGICAL of type Datatype

mpi4py.MPI.INTEGER

mpi4py.MPI.INTEGER: Datatype = INTEGER
 Object INTEGER of type Datatype

mpi4py.MPI.REAL

mpi4py.MPI.REAL: Datatype = REAL
 Object REAL of type Datatype

mpi4py.MPI.DOUBLE_PRECISION

mpi4py.MPI.DOUBLE_PRECISION: Datatype = DOUBLE_PRECISION
 Object DOUBLE_PRECISION of type Datatype

mpi4py.MPI.COMPLEX

mpi4py.MPI.COMPLEX: Datatype = COMPLEX
 Object COMPLEX of type Datatype

mpi4py.MPI.DOUBLE_COMPLEX

mpi4py.MPI.DOUBLE_COMPLEX: Datatype = DOUBLE_COMPLEX
 Object DOUBLE_COMPLEX of type Datatype

mpi4py.MPI.LOGICAL1

mpi4py.MPI.LOGICAL1: Datatype = LOGICAL1
Object LOGICAL1 of type Datatype

mpi4py.MPI.LOGICAL2

mpi4py.MPI.LOGICAL2: Datatype = LOGICAL2
Object LOGICAL2 of type Datatype

mpi4py.MPI.LOGICAL4

mpi4py.MPI.LOGICAL4: Datatype = LOGICAL4
Object LOGICAL4 of type Datatype

mpi4py.MPI.LOGICAL8

mpi4py.MPI.LOGICAL8: Datatype = LOGICAL8
Object LOGICAL8 of type Datatype

mpi4py.MPI.INTEGER1

mpi4py.MPI.INTEGER1: Datatype = INTEGER1
Object INTEGER1 of type Datatype

mpi4py.MPI.INTEGER2

mpi4py.MPI.INTEGER2: Datatype = INTEGER2
Object INTEGER2 of type Datatype

mpi4py.MPI.INTEGER4

mpi4py.MPI.INTEGER4: Datatype = INTEGER4
Object INTEGER4 of type Datatype

mpi4py.MPI.INTEGER8

mpi4py.MPI.INTEGER8: Datatype = INTEGER8
Object INTEGER8 of type Datatype

mpi4py.MPI.INTEGER16

mpi4py.MPI.INTEGER16: Datatype = INTEGER16
Object INTEGER16 of type Datatype

mpi4py.MPI.REAL2

mpi4py.MPI.REAL2: Datatype = REAL2
Object REAL2 of type Datatype

mpi4py.MPI.REAL4

mpi4py.MPI.REAL4: Datatype = REAL4
Object REAL4 of type Datatype

mpi4py.MPI.REAL8

mpi4py.MPI.REAL8: Datatype = REAL8
Object REAL8 of type Datatype

mpi4py.MPI.REAL16

mpi4py.MPI.REAL16: Datatype = REAL16
Object REAL16 of type Datatype

mpi4py.MPI.COMPLEX4

mpi4py.MPI.COMPLEX4: Datatype = COMPLEX4
Object COMPLEX4 of type Datatype

mpi4py.MPI.COMPLEX8

mpi4py.MPI.COMPLEX8: Datatype = COMPLEX8
Object COMPLEX8 of type Datatype

mpi4py.MPI.COMPLEX16

mpi4py.MPI.COMPLEX16: Datatype = COMPLEX16
Object COMPLEX16 of type Datatype

mpi4py.MPI.COMPLEX32

mpi4py.MPI.COMPLEX32: Datatype = COMPLEX32
Object COMPLEX32 of type Datatype

mpi4py.MPI.UNSIGNED_INT

mpi4py.MPI.UNSIGNED_INT: Datatype = UNSIGNED_INT
 Object UNSIGNED_INT of type Datatype

mpi4py.MPI.SIGNED SHORT

mpi4py.MPI.SIGNED_SHORT: Datatype = SIGNED_SHORT
 Object SIGNED_SHORT of type Datatype

mpi4py.MPI.SIGNED_INT

mpi4py.MPI.SIGNED_INT: Datatype = SIGNED_INT
 Object SIGNED_INT of type Datatype

mpi4py.MPI.SIGNED_LONG

mpi4py.MPI.SIGNED_LONG: Datatype = SIGNED_LONG
 Object SIGNED_LONG of type Datatype

mpi4py.MPI.SIGNED_LONG_LONG

mpi4py.MPI.SIGNED_LONG_LONG: Datatype = SIGNED_LONG_LONG
Object SIGNED_LONG_LONG of type Datatype

mpi4py.MPI.BOOL

mpi4py.MPI.BOOL: Datatype = BOOL
 Object BOOL of type Datatype

mpi4py.MPI.SINT8 T

mpi4py.MPI.SINT8_T: Datatype = SINT8_T
 Object SINT8_T of type Datatype

mpi4py.MPI.SINT16_T

mpi4py.MPI.SINT16_T: Datatype = SINT16_T
 Object SINT16_T of type Datatype

mpi4py.MPI.SINT32_T

mpi4py.MPI.SINT32_T: Datatype = SINT32_T
 Object SINT32_T of type Datatype

mpi4py.MPI.SINT64 T

mpi4py.MPI.SINT64_T: Datatype = SINT64_T
 Object SINT64_T of type Datatype

mpi4py.MPI.F BOOL

mpi4py.MPI.F_BOOL: Datatype = F_BOOL
 Object F_BOOL of type Datatype

mpi4py.MPI.F_INT

mpi4py.MPI.F_INT: Datatype = F_INT
 Object F_INT of type Datatype

mpi4py.MPI.F_FLOAT

mpi4py.MPI.F_FLOAT: Datatype = F_FLOAT
 Object F_FLOAT of type Datatype

mpi4py.MPI.F_DOUBLE

mpi4py.MPI.F_DOUBLE: Datatype = F_DOUBLE
Object F_DOUBLE of type Datatype

mpi4py.MPI.F_COMPLEX

mpi4py.MPI.F_COMPLEX: Datatype = F_COMPLEX
 Object F_COMPLEX of type Datatype

mpi4py.MPI.F_FLOAT_COMPLEX

mpi4py.MPI.F_FLOAT_COMPLEX: Datatype = F_FLOAT_COMPLEX
Object F_FLOAT_COMPLEX of type Datatype

mpi4py.MPI.F_DOUBLE_COMPLEX

mpi4py.MPI.F_DOUBLE_COMPLEX: Datatype = F_DOUBLE_COMPLEX
Object F_DOUBLE_COMPLEX of type Datatype

```
mpi4py.MPI.REQUEST_NULL
```

mpi4py.MPI.REQUEST_NULL: Request = REQUEST_NULL
 Object REQUEST_NULL of type Request

mpi4py.MPI.MESSAGE_NULL

mpi4py.MPI.MESSAGE_NULL: Message = MESSAGE_NULL
 Object MESSAGE_NULL of type Message

mpi4py.MPI.MESSAGE_NO_PROC

mpi4py.MPI.MESSAGE_NO_PROC: Message = MESSAGE_NO_PROC
 Object MESSAGE_NO_PROC of type Message

mpi4py.MPI.OP_NULL

mpi4py.MPI.OP_NULL: Op = OP_NULL
Object OP_NULL of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.MAX

mpi4py.MPI.MAX: Op = MAXObject MAX of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.MIN

mpi4py.MPI.MIN: Op = MINObject MIN of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.SUM

mpi4py.MPI.SUM: Op = SUMObject SUM of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.PROD

mpi4py.MPI.PROD: Op = PRODObject PROD of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.LAND

mpi4py.MPI.LAND: Op = LANDObject LAND of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.BAND

mpi4py.MPI.BAND: Op = BANDObject BAND of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.LOR

mpi4py.MPI.LOR: Op = LORObject LOR of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.BOR

mpi4py.MPI.BOR: Op = BORObject BOR of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.LXOR

mpi4py.MPI.LXOR: Op = LXORObject LXOR of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.BXOR

mpi4py.MPI.BXOR: Op = BXORObject BXOR of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.MAXLOC

mpi4py.MPI.MAXLOC: Op = MAXLOCObject MAXLOC of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.MINLOC

mpi4py.MPI.MINLOC: Op = MINLOCObject MINLOC of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.REPLACE

mpi4py.MPI.REPLACE: Op = REPLACEObject REPLACE of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.NO_OP

mpi4py.MPI.NO_OP: Op = NO_OP
 Object NO_OP of type Op

Parameters

- **x** (Any)
- **y** (Any)

Return type

Any

mpi4py.MPI.GROUP NULL

mpi4py.MPI.GROUP_NULL: Group = GROUP_NULL
Object GROUP_NULL of type Group

mpi4py.MPI.GROUP EMPTY

mpi4py.MPI.GROUP_EMPTY: Group = GROUP_EMPTY
 Object GROUP_EMPTY of type Group

mpi4py.MPI.INFO_NULL

mpi4py.MPI.INFO_NULL: Info = INFO_NULL
Object INFO_NULL of type Info

mpi4py.MPI.INFO_ENV

mpi4py.MPI.INFO_ENV: Info = INFO_ENV
 Object INFO_ENV of type Info

mpi4py.MPI.ERRHANDLER_NULL

mpi4py.MPI.ERRHANDLER_NULL: Errhandler = ERRHANDLER_NULL
Object ERRHANDLER_NULL of type Errhandler

mpi4py.MPI.ERRORS_RETURN

mpi4py.MPI.ERRORS_RETURN: Errhandler = ERRORS_RETURN
Object ERRORS_RETURN of type Errhandler

mpi4py.MPI.ERRORS_ABORT

mpi4py.MPI.ERRORS_ABORT: Errhandler = ERRORS_ABORT
 Object ERRORS_ABORT of type Errhandler

mpi4py.MPI.ERRORS_ARE_FATAL

mpi4py.MPI.ERRORS_ARE_FATAL: Errhandler = ERRORS_ARE_FATAL
 Object ERRORS_ARE_FATAL of type Errhandler

mpi4py.MPI.SESSION NULL

```
mpi4py.MPI.SESSION_NULL: Session = SESSION_NULL
Object SESSION_NULL of type Session
```

mpi4py.MPI.COMM NULL

```
mpi4py.MPI.COMM_NULL: Comm = COMM_NULL
Object COMM_NULL of type Comm
```

mpi4py.MPI.COMM SELF

```
mpi4py.MPI.COMM_SELF: Intracomm = COMM_SELF
   Object COMM_SELF of type Intracomm
```

mpi4py.MPI.COMM_WORLD

```
mpi4py.MPI.COMM_WORLD: Intracomm = COMM_WORLD
Object COMM_WORLD of type Intracomm
```

mpi4py.MPI.WIN_NULL

```
mpi4py.MPI.WIN_NULL: Win = WIN_NULL
Object WIN_NULL of type Win
```

mpi4py.MPI.FILE_NULL

```
mpi4py.MPI.FILE_NULL: File = FILE_NULL
Object FILE_NULL of type File
```

mpi4py.MPI.pickle

```
mpi4py.MPI.pickle: Pickle = <mpi4py.MPI.Pickle object>
    Object pickle of type Pickle
```

12 Citation

If MPI for Python been significant to a project that leads to an academic publication, please acknowledge that fact by citing the project.

- M. Rogowski, S. Aseeri, D. Keyes, and L. Dalcin, mpi4py.futures: MPI-Based Asynchronous Task Execution for Python, IEEE Transactions on Parallel and Distributed Systems, 34(2):611-622, 2023. https://doi.org/10.1109/ TPDS.2022.3225481
- L. Dalcin and Y.-L. L. Fang, *mpi4py: Status Update After 12 Years of Development*, Computing in Science & Engineering, 23(4):47-54, 2021. https://doi.org/10.1109/MCSE.2021.3083216

- L. Dalcin, P. Kler, R. Paz, and A. Cosimo, Parallel Distributed Computing using Python, Advances in Water Resources, 34(9):1124-1139, 2011. https://doi.org/10.1016/j.advwatres.2011.04.013
- L. Dalcin, R. Paz, M. Storti, and J. D'Elia, MPI for Python: performance improvements and MPI-2 extensions, Journal of Parallel and Distributed Computing, 68(5):655-662, 2008. https://doi.org/10.1016/j.jpdc.2007.09.005
- L. Dalcin, R. Paz, and M. Storti, *MPI for Python*, Journal of Parallel and Distributed Computing, 65(9):1108-1115, 2005. https://doi.org/10.1016/j.jpdc.2005.03.010

13 Installation

13.1 Build backends

mpi4py supports three different build backends: setuptools (default), scikit-build-core (CMake-based), and meson-python (Meson-based). The build backend can be selected by setting the MPI4PY_BUILD_BACKEND environment variable.

MPI4PY_BUILD_BACKEND

```
Choices
    "setuptools", "scikit-build-core", "meson-python"

Default
    "setuptools"
```

Request a build backend for building mpi4py from sources.

Using setuptools

Tip

Set the MPI4PY_BUILD_BACKEND environment variable to "setuptools" to use the setuptools build backend.

When using the default setuptools build backend, mpi4py relies on the legacy Python distutils framework to build C extension modules. The following environment variables affect the build configuration.

MPI4PY_BUILD_MPICC

The **mpicc** compiler wrapper command is searched for in the executable search path (PATH environment variable) and used to compile the *mpi4py.MPI* C extension module. Alternatively, use the *MPI4PY_BUILD_MPICC* environment variable to the full path or command corresponding to the MPI-aware C compiler.

MPI4PY_BUILD_MPILD

The **mpicc** compiler wrapper command is also used for linking the *mpi4py.MPI* C extension module. Alternatively, use the *MPI4PY_BUILD_MPILD* environment variable to specify the full path or command corresponding to the MPI-aware C linker.

MPI4PY_BUILD_MPICFG

If the MPI implementation does not provide a compiler wrapper, or it is not installed in a default system location, all relevant build information like include/library locations and library lists can be provided in an ini-style configuration file under a [mpi] section. mpi4py can then be asked to use the custom build information by setting the MPI4PY_BUILD_MPICFG environment variable to the full path of the configuration file. As an example, see the mpi.cfg file located in the top level mpi4py source directory.

MPI4PY_BUILD_CONFIGURE

Some vendor MPI implementations may not provide complete coverage of the MPI standard, or may provide partial features of newer MPI standard versions while advertising support for an older version. Setting the MPI4PY_BUILD_CONFIGURE environment variable to a non-empty string will trigger the run of exhaustive checks for the availability of all MPI constants, predefined handles, and routines.

The following environment variables are aliases for the ones described above. Having shorter names, they are convenient for occasional use in the command line. Its usage is not recommended in automation scenarios like packaging recipes, deployment scripts, and container image creation.

MPICC

Convenience alias for MPI4PY_BUILD_MPICC.

MPILD

Convenience alias for MPI4PY_BUILD_MPILD.

MPICFG

Convenience alias for MPI4PY_BUILD_MPICFG.

Using scikit-build-core

Tip

Set the MPI4PY_BUILD_BACKEND environment variable to "scikit-build-core" to use the scikit-build-core build backend.

When using the scikit-build-core build backend, mpi4py delegates all of MPI build configuration to CMake's FindMPI module. Besides the obvious advantage of cross-platform support, this delegation to CMake may be convenient in build environments exposing vendor software stacks via intricate module systems. Note however that mpi4py will not be able to look for MPI routines available beyond the MPI standard version the MPI implementation advertises to support (via the MPI_VERSION and MPI_SUBVERSION macro constants in the mpi.h header file), any missing MPI constant or symbol will prevent a successful build.

Using meson-python

Tip

Set the MPI4PY_BUILD_BACKEND environment variable to "meson-python" to use the meson-python build backend.

When using the meson-python build backend, mpi4py delegates build tasks to the Meson build system.

Warning

mpi4py support for the meson-python build backend is experimental. For the time being, users must set the CC environment variable to the command or path corresponding to the **mpicc** C compiler wrapper.

13.2 Using pip

You can install the latest mpi4py release from its source distribution at PyPI using pip:

```
$ python -m pip install mpi4py
```

You can also install the in-development version with:

```
$ python -m pip install git+https://github.com/mpi4py/mpi4py
```

or:

```
$ python -m pip install https://github.com/mpi4py/mpi4py/tarball/master
```

Note

Installing mpi4py from its source distribution (available at PyPI) or Git source code repository (available at GitHub) requires a C compiler and a working MPI implementation with development headers and libraries.

Warning

pip keeps previously built wheel files on its cache for future reuse. If you want to reinstall the mpi4py package using a different or updated MPI implementation, you have to either first remove the cached wheel file with:

```
$ python -m pip cache remove mpi4py
```

or ask pip to disable the cache:

```
$ python -m pip install --no-cache-dir mpi4py
```

13.3 Using conda

The conda-forge community provides ready-to-use binary packages from an ever growing collection of software libraries built around the multi-platform *conda* package manager. Four MPI implementations are available on condaforge: Open MPI (Linux and macOS), MPICH (Linux and macOS), Intel MPI (Linux and Windows) and Microsoft MPI (Windows). You can install mpi4py and your preferred MPI implementation using the conda package manager:

• to use MPICH do:

```
$ conda install -c conda-forge mpi4py mpich
```

• to use Open MPI do:

```
$ conda install -c conda-forge mpi4py openmpi
```

• to use Intel MPI do:

```
$ conda install -c conda-forge mpi4py impi_rt
```

• to use Microsoft MPI do:

```
$ conda install -c conda-forge mpi4py msmpi
```

MPICH and many of its derivatives are ABI-compatible. You can provide the package specification mpich=X.Y. *=external_* (where X and Y are the major and minor version numbers) to request the conda package manager to use system-provided MPICH (or derivative) libraries. Similarly, you can provide the package specification openmpi=X.Y.*=external_* to use system-provided Open MPI libraries.

The openmpi package on conda-forge has built-in CUDA support, but it is disabled by default. To enable it, follow the instruction outlined during conda install. Additionally, UCX support is also available once the ucx package is installed.

Warning

Binary conda-forge packages are built with a focus on compatibility. The MPICH and Open MPI packages are build in a constrained environment with relatively dated OS images. Therefore, they may lack support for high-performance features like cross-memory attach (XPMEM/CMA). In production scenarios, it is recommended to use external (either custom-built or system-provided) MPI installations. See the relevant conda-forge documentation about using external MPI libraries .

13.4 Linux

On **Fedora Linux** systems (as well as **RHEL** and their derivatives using the EPEL software repository), you can install binary packages with the system package manager:

• using dnf and the mpich package:

```
$ sudo dnf install python3-mpi4py-mpich
```

• using dnf and the openmpi package:

```
$ sudo dnf install python3-mpi4py-openmpi
```

Please remember to load the correct MPI module for your chosen MPI implementation:

• for the mpich package do:

```
$ module load mpi/mpich-$(arch)
$ python -c "from mpi4py import MPI"
```

• for the openmpi package do:

```
$ module load mpi/openmpi-$(arch)
$ python -c "from mpi4py import MPI"
```

On **Ubuntu Linux** and **Debian Linux** systems, binary packages are available for installation using the system package manager:

```
$ sudo apt install python3-mpi4py
```

Note that on Ubuntu/Debian systems, the mpi4py package uses Open MPI. To use MPICH, install the libmpich-dev and python3-dev packages (and any other required development tools). Afterwards, install mpi4py from sources using pip.

13.5 macOS

macOS users can install mpi4py using the Homebrew package manager:

```
$ brew install mpi4py
```

Note that the Homebrew mpi4py package uses Open MPI. Alternatively, install the mpich package and next install mpi4py from sources using pip.

13.6 Windows

Windows users can install mpi4py from binary wheels hosted on the Python Package Index (PyPI) using pip:

```
$ python -m pip install mpi4py
```

The Windows wheels available on PyPI are specially crafted to work with either the Intel MPI or the Microsoft MPI runtime, therefore requiring a separate installation of any one of these packages.

Intel MPI is under active development and supports recent version of the MPI standard. Intel MPI can be installed with pip (see the impi-rt package on PyPI), being therefore straightforward to get it up and running within a Python environment. Intel MPI can also be installed system-wide as part of the Intel HPC Toolkit for Windows or via standalone online/offline installers.

14 Development

14.1 Prerequisites

You need to have the following software properly installed to develop MPI for Python:

- Python 3.6 or above.
- The Cython compiler.
- A working MPI implementation like MPICH or Open MPI, preferably supporting MPI-4 and built with shared/dynamic libraries.

Optionally, consider installing the following packages:

- NumPy for enabling comprehensive testing of MPI communication.
- CuPy for enabling comprehensive testing with a GPU-aware MPI.
- Sphinx to build the documentation.

Tip

Most routine development tasks like building, installing in editable mode, testing, and generating documentation can be performed with the spin developer tool. Run **spin** at the top level source directory for a list of available subcommands.

14.2 Building

MPI for Python uses **setuptools**-based build system that relies on the **setup.py** file. Some setuptools commands (e.g., *build*) accept additional options:

--**mpi**=

Lets you pass a section with MPI configuration within a special configuration file. Alternatively, you can use the MPICFG environment variable.

--mpicc=

Specify the path or name of the **mpicc** C compiler wrapper. Alternatively, use the MPICC environment variable.

--mpild=

Specify the full path or name for the MPI-aware C linker. Alternatively, use the MPILD environment variable. If not set, the mpicc C compiler wrapper is used for linking.

--configure

Runs exhaustive tests for checking about missing MPI types, constants, and functions. This option should be passed in order to build *MPI for Python* against old MPI-1, MPI-2, or MPI-3 implementations, possibly providing a subset of MPI-4.

If you use a MPI implementation providing a **mpicc** C compiler wrapper (e.g., MPICH or Open MPI), it will be used for compilation and linking. This is the preferred and easiest way to build *MPI for Python*.

If **mpicc** is found in the executable search path (PATH environment variable), simply run the *build* command:

```
$ python setup.py build
```

If **mpicc** is not in your search path or the compiler wrapper has a different name, you can run the *build* command specifying its location, either via the *--mpicc* command option or using the *MPICC* environment variable:

```
$ python setup.py build --mpicc=/path/to/mpicc
$ env MPICC=/path/to/mpicc python setup.py build
```

Alternatively, you can provide all the relevant information about your MPI implementation by editing the mpi.cfg file located in the top level source directory. You can use the default section [mpi] or add a new custom section, for example [vendor_mpi] (see the examples provided in the mpi.cfg file as a starting point to write your own section):

```
[mpi]
include_dirs
                   = /usr/local/mpi/include
libraries
                   = mpi
library_dirs
                   = /usr/local/mpi/lib
runtime_library_dirs = /usr/local/mpi/lib
[vendor_mpi]
include dirs
                   = /opt/mpi/include ...
libraries
                   = mpi ...
library_dirs
                   = /opt/mpi/lib ...
runtime_library_dirs = /opt/mpi/lib ...
```

and then run the build command specifying you custom configuration section:

```
$ python setup.py build --mpi=vendor_mpi
$ env MPICFG=vendor_mpi python setup.py build
```

14.3 Installing

MPI for Python can be installed in editable mode:

```
$ python -m pip install --editable .
```

After modifying Cython sources, an in-place rebuild is needed:

```
$ python setup.py build --inplace
```

14.4 Testing

To quickly test the installation:

```
$ mpiexec -n 5 python -m mpi4py.bench helloworld
Hello, World! I am process 0 of 5 on localhost.
Hello, World! I am process 1 of 5 on localhost.
Hello, World! I am process 2 of 5 on localhost.
Hello, World! I am process 3 of 5 on localhost.
Hello, World! I am process 4 of 5 on localhost.

$ mpiexec -n 5 python -m mpi4py.bench ringtest -l 10 -n 1048576
time for 10 loops = 0.00361614 seconds (5 processes, 1048576 bytes)
```

If you installed from a git clone or the source distribution, issuing at the command line:

```
$ mpiexec -n 5 python demo/helloworld.py
```

will launch a five-process run of the Python interpreter and run the demo script demo/helloworld.py from the source distribution.

You can also run all the *unittest* scripts:

```
$ mpiexec -n 5 python test/main.py
```

or, if you have the pytest unit testing framework installed:

```
$ mpiexec -n 5 pytest
```

15 Guidelines

15.1 Fair play

Summary

This section defines Rules of Play for companies and outside developers that engage with the mpi4py project. It covers:

- Restrictions on use of the mpi4py name.
- How and whether to publish a modified distribution.
- How to make us aware of patched versions.

After reading this section, companies and developers will know what kinds of behavior the mpi4py developers and contributors would like to see, and which we consider troublesome, bothersome, and unacceptable.

This document is a close adaptation of NumPy NEP 36.

Motivation

Occasionally, we learn of modified mpi4py versions and binary distributions circulated by outsiders. These patched versions can cause problems to mpi4py users (see, e.g., mpi4py/mpi4py#508). When issues like these arise, our developers waste time identifying the problematic release, locating alterations, and determining an appropriate course of action.

In addition, packages on the Python Packaging Index are sometimes named such that users assume they are sanctioned or maintained by the mpi4py developers. We wish to reduce the number of such incidents.

Scope

This document aims to define a minimal set of rules that, when followed, will be considered good-faith efforts in line with the expectations of the mpi4py developers and contributors.

Our hope is that companies and outside developers who feel they need to modify mpi4py will first consider contributing to the project, or use alternative mechanisms for patching and extending mpi4py.

When in doubt, please talk to us first. We may suggest an alternative; at minimum, we'll be informed and we may even grant an exception if deemed appropriate.

Fair play rules

1. Do not reuse the mpi4py name for projects not affiliated with the mpi4py project.

At time of writing, there are only a handful of mpi4py-named packages developed by the mpi4py project, including mpi4py and mpi4py-fft. We ask that outside packages not include the phrase mpi4py, i.e., avoid names such as mycompany-mpi4py or mpi4py-mycompany.

To be clear, this rule only applies to modules (package names); it is perfectly acceptable to have a *submodule* of your own package named mycompany.mpi4py.

2. Do not publish binary mpi4py wheels on PyPI (https://pypi.org/).

We ask companies and outside developers to not publish binary mpi4py wheels in the main Python Package Index (https://pypi.org/) under names such mpi4py-mpich, mpi4py-openmpi, or mpi4py-vendor_mpi.

The usual approaches to build binary Python wheels involve the embedding of dependent shared libraries. While such an approach may seem convenient and often is, in the particular case of MPI and mpi4py it is ultimately harmful to end users. Embedding the MPI shared libraries would prevent the use of external, system-provided MPI installations with hardware-specific optimizations and site-specific tweaks.

The MPI Forum is currently discussing the standardization of a proposal for an Application Binary Interface (ABI) for MPI, see [mpi-abi-paper] and [mpi-abi-issue]. Such standardization will allow for any binary dependent on the MPI library to be used with multiple MPI backends. Once this proposal becomes part of the MPI standard, the mpi4py project will consider publishing on PyPI binary wheels capable of using any backend MPI implementation supporting the new MPI ABI specification. In the mean time, mpi4py is currently distributing experimental MPI and mpi4py binary wheels on https://anaconda.org/mpi4py.

3. Do not republish modified versions of mpi4py.

Modified versions of mpi4py make it very difficult for the developers to address bug reports, since we typically do not know which parts of mpi4py have been modified.

If you have to break this rule (and we implore you not to!), then make it clear in the __version__ tag that you have modified mpi4py, e.g.:

```
>>> print(mpi4py.__version__)
'4.0.0+mycompany.13`
```

We understand that minor patches are often required to make a library work inside of a package ecosystem. This is totally acceptable, but we ask that no substantive changes are made.

4. Do not extend or modify mpi4py's API.

If you absolutely have to break the previous rule, please do not add additional functions to the namespace, or modify the API of existing functions. Having additional functions exposed in distributed versions is confusing for users and developers alike.

16 LICENSE

Copyright (c) 2024, Lisandro Dalcin

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

17 CHANGES

17.1 Release 4.0.1 [2024-10-11]

- Update support for Python 3.13:
 - Enable Cython 3.1 support for free-threaded CPython.
 - Allow compiling Cython-generated C sources with the full Python C-API.
 - Fix MPI DLL path workarounds on Windows after changes to locals().
- Enhancements to test suite:
 - Support XML reports via unittest-xml-reporting.

- Add command line options to exclude tests by patterns and files.
- Refactor Python 2 code to use Python 3 constructs using pyupgrade.
- · Miscellaneous:
 - Minor and mostly inconsequential subclass fix in mpi4py.util.pkl5.
 - Update compatibility workarounds for legacy MPICH 3.0 release.

17.2 Release 4.0.0 [2024-07-28]

- New features:
 - Add support for the MPI-4.0 standard.
 - * Use large count MPI-4 routines.
 - * Add persistent collective communication.
 - * Add partitioned point-to-point communication.
 - * Add new communicator constructors.
 - * Add the Session class and its methods.
 - Add support for the MPI-4.1 standard.
 - * Add non-destructive completion test for multiple requests.
 - * Add value-index datatype constructor.
 - * Add communicator/session buffer attach/detach/flush.
 - * Support for removal of error classes/codes/strings.
 - * Support for querying hardware resource information.
 - Add preliminary support for the upcoming MPI-5.0 standard.
 - * User-level failure mitigation (ULFM).
 - mpi4py.util.pool: New drop-in replacement for multiprocessing.pool.
 - mpi4py.util.sync: New synchronization utilities.
 - Add runtime check for mismatch between mpiexec and MPI library.
 - Support scikit-build-core as an alternative build backend.
 - Support meson-python as an alternative build backend.
- Enhancements:
 - mpi4py.futures: Support for parallel tasks.
 - mpi4py.futures: Report exception tracebacks in workers.
 - mpi4py.util.pkl5: Add support for collective communication.
 - Add methods Datatype.fromcode(), Datatype.tocode() and attributes Datatype.typestr,
 Datatype.typechar to simplify NumPy interoperability for simple cases.
 - Add methods Comm.Create_errhandler(), Win.Create_errhandler(), and File.
 Create_errhandler() to create custom error handlers.

- Add support for pickle serialization of instances of MPI types. All instances of Datatype, Info, and Status can be serialized. Instances of Op can be serialized only if created through mpi4py by calling Op.Create(). Instances of other MPI types can be serialized only if they reference predefined handles.
- Add handle attribute and fromhandle() class method to MPI classes to ease interoperability with external code. The handle value is an unsigned integer guaranteed to fit on the platform's uintptr_t C type.
- Add lowercase free() method to MPI classes to ease MPI object deallocation and cleanup. This method
 eventually attempts to call Free(), but only if the object's MPI handle is not a null or predefined handle,
 and such call is allowed within the World Model init/finalize.

• Backward-incompatible changes:

- Python 2 is no longer supported, Python 3.6+ is required, but typing stubs are supported for Python 3.8+.
- The Intracomm. Create_group() method is no longer defined in the base Comm class.
- Group.Compare() and Comm.Compare() are no longer class methods but instance methods. Existing codes using the former class methods are expected to continue working.
- Group.Translate_ranks() is no longer a class method but an instance method. Existing codes using
 the former class method are expected to continue working.
- The LB and UB datatypes are no longer available, use Datatype.Create_resized() instead.
- The HOST predefined attribute key is no longer available.
- The MPI.memory class has been renamed to MPI.buffer. The old name is still available as an alias to the new name.
- The mpi4py.dl module is no longer available.
- The mpi4py.get_config function returns an empty dictionary.

• Miscellaneous:

- The project is now licensed under the BSD-3-Clause license. This change is fairly inconsequential for users and distributors. It simply adds an additional clause against using contributor names for promotional purposes without their consent.
- Add a new guidelines section to documentation laying out new fair play rules. These rules ask companies and outside developers to refrain from reusing the mpi4py name in unaffiliated projects, publishing binary mpi4py wheels on the main Python Package Index (PyPI), and distributing modified versions with incompatible or extended API changes. The primary motivation of these rules is to avoid fragmentation and end-user confusion.

17.3 Release 3.1.6 [2024-04-14]

Warning

This is the last release supporting Python 2.

• Fix various build issues.

17.4 Release 3.1.5 [2023-10-04]

Warning

This is the last release supporting Python 2.

• Rebuild C sources with Cython 0.29.36 to support Python 3.12.

17.5 Release 3.1.4 [2022-11-02]

Warning

This is the last release supporting Python 2.

- Rebuild C sources with Cython 0.29.32 to support Python 3.11.
- Fix contiguity check for DLPack and CAI buffers.
- Workaround build failures with setuptools v60.

17.6 Release 3.1.3 [2021-11-25]

Warning

This is the last release supporting Python 2.

• Add missing support for MPI.BOTTOM to generalized all-to-all collectives.

17.7 Release 3.1.2 [2021-11-04]

Warning

This is the last release supporting Python 2.

- mpi4py.futures: Add _max_workers property to MPIPoolExecutor.
- mpi4py.util.dtlib: Fix computation of alignment for predefined datatypes.
- mpi4py.util.pkl5: Fix deadlock when using ssend() + mprobe().
- mpi4py.util.pkl5: Add environment variable MPI4PY_PICKLE_THRESHOLD.
- mpi4py.rc: Interpret "y" and "n" strings as boolean values.
- Fix/add typemap/typestr for MPI.WCHAR/MPI.COUNT datatypes.
- Minor fixes and additions to documentation.
- Minor fixes to typing support.

• Support for local version identifier (PEP-440).

17.8 Release 3.1.1 [2021-08-14]

Warning

This is the last release supporting Python 2.

- Fix typo in Requires-Python package metadata.
- Regenerate C sources with Cython 0.29.24.

17.9 Release 3.1.0 [2021-08-12]

Warning

This is the last release supporting Python 2.

- · New features:
 - mpi4py.util: New package collecting miscellaneous utilities.
- Enhancements:
 - Add pickle-based Request.waitsome() and Request.testsome().
 - Add lowercase methods Request.get_status() and Request.cancel().
 - Support for passing Python GPU arrays compliant with the DLPack data interchange mechanism (link) and the __cuda_array_interface__ (CAI) standard (link) to uppercase methods. This support requires that mpi4py is built against CUDA-aware MPI implementations. This feature is currently experimental and subject to future changes.
 - mpi4py.futures: Add support for initializers and canceling futures at shutdown. Environment variables names now follow the pattern MPI4PY_FUTURES_*, the previous MPI4PY_* names are deprecated.
 - Add type annotations to Cython code. The first line of the docstring of functions and methods displays a signature including type annotations.
 - Add companion stub files to support type checkers.
 - Support for weak references.
- · Miscellaneous:
 - Add a new mpi4py publication (link) to the citation listing.

17.10 Release 3.0.3 [2019-11-04]

• Regenerate Cython wrappers to support Python 3.8.

17.11 Release 3.0.2 [2019-06-11]

- Bug fixes:
 - Fix handling of readonly buffers in support for Python 2 legacy buffer interface. The issue triggers only when using a buffer-like object that is readonly and does not export the new Python 3 buffer interface.
 - Fix build issues with Open MPI 4.0.x series related to removal of many MPI-1 symbols deprecated in MPI-2 and removed in MPI-3.
 - Minor documentation fixes.

17.12 Release 3.0.1 [2019-02-15]

- Bug fixes:
 - Fix Comm.scatter() and other collectives corrupting input send list. Add safety measures to prevent related issues in global reduction operations.
 - Fix error-checking code for counts in Op.Reduce_local().
- Enhancements:
 - Map size-specific Python/NumPy typecodes to MPI datatypes.
 - Allow partial specification of target list/tuple arguments in the various Win RMA methods.
 - Workaround for removal of MPI_{LB|UB} in Open MPI 4.0.
 - Support for Microsoft MPI v10.0.

17.13 Release 3.0.0 [2017-11-08]

- · New features:
 - mpi4py.futures: Execute computations asynchronously using a pool of MPI processes. This package is based on concurrent.futures from the Python standard library.
 - mpi4py.run: Run Python code and abort execution in case of unhandled exceptions to prevent deadlocks.
 - mpi4py.bench: Run basic MPI benchmarks and tests.
- Enhancements:
 - Lowercase, pickle-based collective communication calls are now thread-safe through the use of fine-grained locking.
 - The MPI module now exposes a memory type which is a lightweight variant of the builtin memoryview type, but exposes both the legacy Python 2 and the modern Python 3 buffer interface under a Python 2 runtime.
 - The MPI.Comm.Alltoallw() method now uses count=1 and displ=0 as defaults, assuming that messages are specified through user-defined datatypes.
 - The Request.Wait[all]() methods now return True to match the interface of Request.Test[all]().
 - The Win class now implements the Python buffer interface.

- Backward-incompatible changes:
 - The buf argument of the MPI.Comm.recv() method is deprecated, passing anything but None emits a warning.
 - The MPI.Win.memory property was removed, use the MPI.Win.tomemory() method instead.
 - Executing python -m mpi4py in the command line is now equivalent to python -m mpi4py.run. For the former behavior, use python -m mpi4py.bench.
 - Python 2.6 and 3.2 are no longer supported. The mpi4py.MPI module may still build and partially work, but other pure-Python modules under the mpi4py namespace will not.
 - Windows: Remove support for legacy MPICH2, Open MPI, and DeinoMPI.

17.14 Release 2.0.0 [2015-10-18]

- Support for MPI-3 features.
 - Matched probes and receives.
 - Nonblocking collectives.
 - Neighborhood collectives.
 - New communicator constructors.
 - Request-based RMA operations.
 - New RMA communication and synchronisation calls.
 - New window constructors.
 - New datatype constructor.
 - New C++ boolean and floating complex datatypes.
- Support for MPI-2 features not included in previous releases.
 - Generalized All-to-All collective (Comm.Alltoallw())
 - User-defined data representations (Register_datarep())
- New scalable implementation of reduction operations for Python objects. This code is based on binomial tree algorithms using point-to-point communication and duplicated communicator contexts. To disable this feature, use mpi4py.rc.fast_reduce = False.
- Backward-incompatible changes:
 - Python 2.4, 2.5, 3.0 and 3.1 are no longer supported.
 - Default MPI error handling policies are overridden. After import, mpi4py sets the ERRORS_RETURN error handler in COMM_SELF and COMM_WORLD, as well as any new Comm, Win, or File instance created through mpi4py, thus effectively ignoring the MPI rules about error handler inheritance. This way, MPI errors translate to Python exceptions. To disable this behavior and use the standard MPI error handling rules, use mpi4py.rc.errors = 'default'.
 - Change signature of all send methods, dest is a required argument.
 - Change signature of all receive and probe methods, source defaults to ANY_SOURCE, tag defaults to ANY_TAG.
 - Change signature of send lowercase-spelling methods, obj arguments are not mandatory.
 - Change signature of recv lowercase-spelling methods, renamed 'obj' arguments to 'buf'.

- Change Request. Waitsome() and Request. Testsome() to return None or list.
- Change signature of all lowercase-spelling collectives, sendobj arguments are now mandatory, recvobj arguments were removed.
- Reduction operations MAXLOC and MINLOC are no longer special-cased in lowercase-spelling methods Comm.[all]reduce() and Comm.[ex]scan(), the input object must be specified as a tuple (obj, location).
- Change signature of name publishing functions. The new signatures are Publish_name(service_name, port_name, info=INFO_NULL) and Unpublish_name(service_name, port_name, info=INFO_NULL)`.
- Win instances now cache Python objects exposing memory by keeping references instead of using MPI attribute caching.
- Change signature of Win.Lock(). The new signature is Win.Lock(rank, lock_type=LOCK_EXCLUSIVE, assertion=0).
- Move Cartcomm.Map() to Intracomm.Cart_map().
- Move Graphcomm.Map() to Intracomm.Graph_map().
- Remove the mpi4py.MPE module.
- Rename the Cython definition file for use with cimport statement from mpi_c.pxd to libmpi.pxd.

17.15 Release 1.3.1 [2013-08-07]

- Regenerate C wrappers with Cython 0.19.1 to support Python 3.3.
- Install *.pxd files in <site-packages>/mpi4py to ease the support for Cython's cimport statement in code requiring to access mpi4py internals.
- As a side-effect of using Cython 0.19.1, ancient Python 2.3 is no longer supported. If you really need it, you can install an older Cython and run python setup.py build_src --force.

17.16 Release 1.3 [2012-01-20]

- Now Comm.recv() accept a buffer to receive the message.
- Add Comm.irecv() and Request.{wait|test}[any|all]().
- Add Intracomm.Spawn_multiple().
- Better buffer handling for PEP 3118 and legacy buffer interfaces.
- Add support for attribute attribute caching on communicators, datatypes and windows.
- Install MPI-enabled Python interpreter as <path>/mpi4py/bin/python-mpi.
- Windows: Support for building with Open MPI.

17.17 Release 1.2.2 [2010-09-13]

- Add mpi4py.get_config() to retrieve information (compiler wrappers, includes, libraries, etc) about the MPI implementation employed to build mpi4py.
- · Workaround Python libraries with missing GILState-related API calls in case of non-threaded Python builds.
- Windows: look for MPICH2, DeinoMPI, Microsoft HPC Pack at their default install locations under %Program-Files.
- MPE: fix hacks related to old API's, these hacks are broken when MPE is built with a MPI implementations
 other than MPICH2.
- HP-MPI: fix for missing Fortran datatypes, use dlopen() to load the MPI shared library before MPI_Init()
- Many distutils-related fixes, cleanup, and enhancements, better logics to find MPI compiler wrappers.
- Support for pip install mpi4py.

17.18 Release 1.2.1 [2010-02-26]

- Fix declaration in Cython include file. This declaration, while valid for Cython, broke the simple-minded parsing used in conf/mpidistutils.py to implement configure-tests for availability of MPI symbols.
- Update SWIG support and make it compatible with Python 3. Also generate an warning for SWIG < 1.3.28.
- Fix distutils-related issues in Mac OS X. Now ARCHFLAGS environment variable is honored of all Python's config/Makefile variables.
- Fix issues with Open MPI < 1.4.2 related to error checking and MPI_XXX_NULL handles.

17.19 Release 1.2 [2009-12-29]

- Automatic MPI datatype discovery for NumPy arrays and PEP-3118 buffers. Now buffer-like objects can be messaged directly, it is no longer required to explicitly pass a 2/3-list/tuple like [data, MPI.DOUBLE], or [data, count, MPI.DOUBLE]. Only basic types are supported, i.e., all C/C99-native signed/unsigned integral types and single/double precision real/complex floating types. Many thanks to Eilif Muller for the initial feedback.
- Nonblocking send of pickled Python objects. Many thanks to Andreas Kloeckner for the initial patch and enlightening discussion about this enhancement.
- Request instances now hold a reference to the Python object exposing the buffer involved in point-to-point communication or parallel I/O. Many thanks to Andreas Kloeckner for the initial feedback.
- Support for logging of user-defined states and events using MPE. Runtime (i.e., without requiring a recompile!) activation of logging of all MPI calls is supported in POSIX platforms implementing dlopen().
- Support for all the new features in MPI-2.2 (new C99 and F90 datatypes, distributed graph topology, local reduction operation, and other minor enhancements).
- Fix the annoying issues related to Open MPI and Python dynamic loading of extension modules in platforms supporting dlopen().
- Fix SLURM dynamic loading issues on SiCortex. Many thanks to Ian Langmore for providing me shell access.

17.20 Release 1.1.0 [2009-06-06]

- Fix bug in Comm. Iprobe() that caused segfaults as Python C-API calls were issued with the GIL released (issue #2).
- Add Comm.bsend() and Comm.ssend() for buffered and synchronous send semantics when communicating general Python objects.
- Now the call Info.Get(key) return a *single* value (i.e, instead of a 2-tuple); this value is None if key is not in the Info object, or a string otherwise. Previously, the call redundantly returned (None, False) for missing key-value pairs; None is enough to signal a missing entry.
- Add support for parametrized Fortran datatypes.
- Add support for decoding user-defined datatypes.
- Add support for user-defined reduction operations on memory buffers. However, at most 16 user-defined reduction operations can be created. Ask the author for more room if you need it.

17.21 Release 1.0.0 [2009-03-20]

This is the fist release of the all-new, Cython-based, implementation of *MPI for Python*. Unfortunately, this implementation is not backward-compatible with the previous one. The list below summarizes the more important changes that can impact user codes.

- Some communication calls had *overloaded* functionality. Now there is a clear distinction between communication of general Python object with *pickle*, and (fast, near C-speed) communication of buffer-like objects (e.g., NumPy arrays).
 - for communicating general Python objects, you have to use all-lowercase methods, like send(), recv(), bcast(), etc.
 - for communicating array data, you have to use Send(), Recv(), Bcast(), etc. methods. Buffer arguments to these calls must be explicitly specified by using a 2/3-list/tuple like [data, MPI.DOUBLE], or [data, count, MPI.DOUBLE] (the former one uses the byte-size of data and the extent of the MPI datatype to define the count).
- Indexing a communicator with an integer returned a special object associating the communication with a target rank, alleviating you from specifying source/destination/root arguments in point-to-point and collective communications. This functionality is no longer available, expressions like:

```
MPI.COMM_WORLD[0].Send(...)
MPI.COMM_WORLD[0].Recv(...)
MPI.COMM_WORLD[0].Bcast(...)
```

have to be replaced by:

```
MPI.COMM_WORLD.Send(..., dest=0)
MPI.COMM_WORLD.Recv(..., source=0)
MPI.COMM_WORLD.Bcast(..., root=0)
```

- Automatic MPI initialization (i.e., at import time) requests the maximum level of MPI thread support (i.e., it is done by calling MPI_Init_thread() and passing MPI_THREAD_MULTIPLE). In case you need to change this behavior, you can tweak the contents of the mpi4py.rc module.
- In order to obtain the values of predefined attributes attached to the world communicator, now you have to use the Get_attr() method on the MPI.COMM_WORLD instance:

- In the previous implementation, MPI.COMM_WORLD and MPI.COMM_SELF were associated to **duplicates** of the (Clevel) MPI_COMM_WORLD and MPI_COMM_SELF predefined communicator handles. Now this is no longer the case, MPI.COMM_WORLD and MPI.COMM_SELF proxies the **actual** MPI_COMM_WORLD and MPI_COMM_SELF handles.
- Convenience aliases MPI.WORLD and MPI.SELF were removed. Use instead MPI.COMM_WORLD and MPI. COMM_SELF.
- Convenience constants MPI.WORLD_SIZE and MPI.WORLD_RANK were removed. Use instead MPI. COMM_WORLD.Get_size() and MPI.COMM_WORLD.Get_rank().

References

- [mpi-std1] MPI Forum. MPI: A Message Passing Interface Standard. International Journal of Supercomputer Applications, volume 8, number 3-4, pages 159-416, 1994.
- [mpi-std2] MPI Forum. MPI: A Message Passing Interface Standard. High Performance Computing Applications, volume 12, number 1-2, pages 1-299, 1998.
- [mpi-using] William Gropp, Ewing Lusk, and Anthony Skjellum. Using MPI: portable parallel programming with the message-passing interface. MIT Press, 1994.
- [mpi-ref] Mark Snir, Steve Otto, Steven Huss-Lederman, David Walker, and Jack Dongarra. MPI The Complete Reference, volume 1, The MPI Core. MIT Press, 2nd. edition, 1998.
- [mpi-mpich] W. Gropp, E. Lusk, N. Doss, and A. Skjellum. A high-performance, portable implementation of the MPI message passing interface standard. Parallel Computing, 22(6):789-828, September 1996.
- [mpi-openmpi] Edgar Gabriel, Graham E. Fagg, George Bosilca, Thara Angskun, Jack J. Dongarra, Jeffrey M. Squyres, Vishal Sahay, Prabhanjan Kambadur, Brian Barrett, Andrew Lumsdaine, Ralph H. Castain, David J. Daniel, Richard L. Graham, and Timothy S. Woodall. Open MPI: Goals, Concept, and Design of a Next Generation MPI Implementation. In Proceedings, 11th European PVM/MPI Users' Group Meeting, Budapest, Hungary, September 2004.
- [Hinsen97] Konrad Hinsen. The Molecular Modelling Toolkit: a case study of a large scientific application in Python. In Proceedings of the 6th International Python Conference, pages 29-35, San Jose, Ca., October 1997.
- [Beazley97] David M. Beazley and Peter S. Lomdahl. Feeding a large-scale physics application to Python. In Proceedings of the 6th International Python Conference, pages 21-29, San Jose, Ca., October 1997.
- [mpi4py-futures] M. Rogowski, S. Aseeri, D. Keyes, and L. Dalcin, *mpi4py.futures: MPI-Based Asynchronous Task Execution for Python*, IEEE Transactions on Parallel and Distributed Systems, 34(2):611-622, 2023. https://doi.org/10.1109/TPDS.2022.3225481
- [mcs-paper] John M. Mellor-Crummey and Michael L. Scott. Algorithms for scalable synchronization on shared-memory multiprocessors. ACM Transactions on Computer Systems, 9(1):21-65, February 1991. https://doi.org/10.1145/103727.103729
- [uam-book] William Gropp, Torsten Hoefler, Rajeev Thakur, Ewing Lusk. Using Advanced MPI Modern Features of the Message-Passing Interface. Chapter 4, Section 4.7, Pages 130-131. The MIT Press, November 2014. https://mitpress.mit.edu/9780262527637/using-advanced-mpi/
- [mpi-abi-paper] J. Hammond, L. Dalcin, E. Schnetter, M. Pérache, J. B. Besnard, J. Brown, G. Brito Gadeschi, S. Byrne, J. Schuchart, and H. Zhou. MPI Application Binary Interface Standardization. EuroMPI 2023, Bristol, UK, September 2023. https://doi.org/10.1145/3615318.3615319
- [mpi-abi-issue] MPI Forum GitHub Issue: MPI needs a standard ABI. https://github.com/mpi-forum/mpi-issues/issues/751

Python Module Index

m

```
mpi4py,21
mpi4py.bench,71
mpi4py.futures,40
mpi4py.MPI,71
mpi4py.run,70
mpi4py.typing,37
mpi4py.util,50
mpi4py.util.dtlib,50
mpi4py.util.pkl5,51
mpi4py.util.pool,58
mpi4py.util.sync,62
```

Index

Symbols	command line option, 249
enter() (mpi4py.util.sync.Condition method), 66	mpicc
enter() (mpi4py.util.sync.Mutex method), 65	command line option, 249
enter() (mpi4py.util.sync.Semaphore method), 68	mpild
enter() (mpi4py.util.sync.Sequential method), 63	command line option, 249
exit() (mpi4py.util.sync.Condition method), 66	-C
exit() (mpi4py.util.sync.Condition method), 65	command line option, 71
exit() (mpi4py.util.sync.Semaphore method), 68	-m
exit() (mpi4py.util.sync.Semaphore method), 68 exit() (mpi4py.util.sync.Sequential method), 63	command line option, 71
exit() (mpi4py.util.sync.sequential method), 65 init() (mpi4py.util.pool.Pool method), 58	
	A
init() (mpi4py.util.sync.Condition method), 66	Abort() (mpi4py.MPI.Comm method), 78
init() (mpi4py.util.sync.Counter method), 63	Accept() (mpi4py.MPI.Intracomm method), 145
init() (mpi4py.util.sync.Mutex method), 64	Accumulate() (mpi4py.MPI.Win method), 177
init() (mpi4py.util.sync.Semaphore method), 68	
init() (mpi4py.util.sync.Sequential method), 62	Ack_failed() (mpi4py.MPI.Comm method), 78
iter() (mpi4py.util.sync.Counter method), 64	acquire() (mpi4py.util.sync.Condition method), 66
new() (mpi4py.MPI.BottomType static method), 72	acquire() (mpi4py.util.sync.Mutex method), 65
new() (mpi4py.MPI.BufferAutomaticType static	acquire() (mpi4py.util.sync.Semaphore method), 68
method), 72	Add_error_class() (in module mpi4py.MPI), 191
new() (mpi4py.MPI.Cartcomm static method), 73	Add_error_code() (in module mpi4py.MPI), 191
new() (mpi4py.MPI.Comm static method), 75	Add_error_string() (in module mpi4py.MPI), 191
new() (mpi4py.MPI.Datatype static method), 106	address (mpi4py.MPI.buffer attribute), 188
new() (mpi4py.MPI.Distgraphcomm static method),	Agree() (mpi4py.MPI.Comm method), 79
117	AINT (in module mpi4py.MPI), 227
new() (mpi4py.MPI.Errhandler static method), 117	Aint (in module mpi4py.typing), 38
new() (mpi4py.MPI.Exception static method), 189	Aint_add() (in module mpi4py.MPI), 192
new() (mpi4py.MPI.File static method), 119	Allgather() (in module mpi4py.MPI), 192
new() (mpi4py.MPI.Graphcomm static method),	Allgather() (mpi4py.MPI.Comm method), 79
132	allgather() (mpi4py.MPI.Comm method), 100
new() (mpi4py.MPI.Grequest static method), 133	allgather() (mpi4py.util.pkl5.Comm method), 56 Allgather_init() (mpi4py.MPI.Comm method), 79
new() (mpi4py.MPI.Group static method), 134	
new() (mpi4py.MPI.InPlaceType static method),	Allgathery() (mpi4py.MPI.Comm method), 79
138	Allgatherv_init() (mpi4py.MPI.Comm method), 79
new() (mpi4py.MPI.Info static method), 138	Alloc_mem() (in module mpi4py.MPI), 192 allocate() (mpi4py.MPI.buffer static method), 187
new() (mpi4py.MPI.Intercomm static method), 142	Allocate() (mpi4py.MPI.Win class method), 177
new() (mpi4py.MPI.Intracomm static method), 144	Allocate_shared() (mpi4py.MPI.Win class method), 1//
new() (mpi4py.MPI.Message static method), 149	178
new() (mpi4py.MPI.Op static method), 152	Allreduce() (mpi4py.MPI.Comm method), 80
new() (mpi4py.MPI.Pickle static method), 154	allreduce() (mpi4py.MPI.Comm method), 101
new() (mpi4py.MPI.Prequest static method), 156	Allreduce_init() (mpi4py.MPI.Comm method), 80
new() (mpi4py.MPI.Request static method), 157	Alltoall() (mpi4py.MPI.Comm method), 80
new() (mpi4py.MPI.Session static method), 164	alltoall() (mpi4py.MPI.Comm method), 101
new() (mpi4py.MPI.Status static method), 167	alltoall() (mpi4py.util.pkl5.Comm method), 56
new() (mpi4py.MPI.Topocomm static method), 170	Alltoall_init() (mpi4py.MPI.Comm method), 80
new() (mpi4py.MPI.Win static method), 175	Alltoallv() (mpi4py.MPI.Comm method), 80
new() (mpi4py.MPI.buffer static method), 186	Alltoallv_init() (mpi4py.MPI.Comm method), 81
next() (mpi4py.util.sync.Counter method), 64configure	Alltoallw() (mpi4py.MPI.Comm method), 81
•	Alltoallw_init() (mpi4py.MPI.Comm method), 81
command line option, 249	amode (mpi4py.MPI.File attribute), 131
mpi	amoue (mpi+py.mi i.rue auriome), 131

ANY_SOURCE (in module mpi4py.MPI), 205	Call_errhandler() (mpi4py.MPI.Session method),	
ANY_TAG (in module mpi4py.MPI), 205	165	
apply() (mpi4py.util.pool.Pool method), 58	Call_errhandler() (mpi4py.MPI.Win method), 178	
apply_async() (mpi4py.util.pool.Pool method), 59	Cancel() (mpi4py.MPI.Request method), 159	
ApplyResult (class in mpi4py.util.pool), 62	cancel() (mpi4py.MPI.Request method), 161	
APPNUM (in module mpi4py.MPI), 206	cancel() (mpi4py.util.pkl5.Request method), 51	
AsyncResult (class in mpi4py.util.pool), 61	cancelled (mpi4py.MPI.Status attribute), 170	
atomicity (mpi4py.MPI.File attribute), 131	CART (in module mpi4py.MPI), 220	
Attach() (mpi4py.MPI.Win method), 178	Cart_map() (mpi4py.MPI.Intracomm method), 145	
Attach_buffer() (in module mpi4py.MPI), 192	Cartcomm (class in mpi4py.MPI), 73	
Attach_buffer() (mpi4py.MPI.Comm method), 81	cast() (mpi4py.MPI.buffer method), 187	
Attach_buffer() (mpi4py.MPI.Session method), 165	CC, 245	
attrs (mpi4py.MPI.Win attribute), 186	CHAR (in module mpi4py.MPI), 228	
D	CHARACTER (in module mpi4py.MPI), 232	
В	clear() (mpi4py.MPI.Info method), 140	
BAND (in module mpi4py.MPI), 239	Clone() (mpi4py.MPI.Comm method), 83	
Barrier() (mpi4py.MPI.Comm method), 81	Close() (mpi4py.MPI.File method), 121	
barrier() (mpi4py.MPI.Comm method), 101	close() (mpi4py.util.pool.Pool method), 61	
Barrier_init() (mpi4py.MPI.Comm method), 82	Close_port() (in module mpi4py.MPI), 193	
Bcast() (mpi4py.MPI.Comm method), 82	<pre>collect() (in module mpi4py.futures), 46</pre>	
bcast() (mpi4py.MPI.Comm method), 101	combiner (mpi4py.MPI.Datatype attribute), 116	
bcast() (mpi4py.util.pkl5.Comm method), 55	COMBINER_CONTIGUOUS (in module mpi4py.MPI), 217	
Bcast_init() (mpi4py.MPI.Comm method), 82	COMBINER_DARRAY (in module mpi4py.MPI), 218	
begin() (mpi4py.util.sync.Sequential method), 63	COMBINER_DUP (in module mpi4py.MPI), 217	
BOOL (in module mpi4py.MPI), 236	COMBINER_F90_COMPLEX (in module mpi4py.MPI), 219	
bootup() (mpi4py.futures.MPIPoolExecutor method), 43	COMBINER_F90_INTEGER (in module mpi4py.MPI), 219	
BOR (in module mpi4py.MPI), 240	COMBINER_F90_REAL (in module mpi4py.MPI), 219	
BOTTOM (in module mpi4py.MPI), 206	COMBINER_HINDEXED (in module mpi4py.MPI), 218	
Bottom (in module mpi4py.typing), 38	COMBINER_HINDEXED_BLOCK (in module mpi4py.MPI),	
BottomType (class in mpi4py.MPI), 72	218	
Bsend() (mpi4py.MPI.Comm method), 82	COMBINER_HVECTOR (in module mpi4py.MPI), 217	
bsend() (mpi4py.MPI.Comm method), 101	COMBINER_INDEXED (in module mpi4py.MPI), 218	
bsend() (mpi4py.util.pkl5.Comm method), 53	COMBINER_INDEXED_BLOCK (in module mpi4py.MPI),	
Bsend_init() (mpi4py.MPI.Comm method), 82	218	
BSEND_OVERHEAD (in module mpi4py.MPI), 221	COMBINER_NAMED (in module mpi4py.MPI), 217	
buffer (class in mpi4py.MPI), 186	COMBINER_RESIZED (in module mpi4py.MPI), 218	
Buffer (in module mpi4py.typing), 38	COMBINER_STRUCT (in module mpi4py.MPI), 218	
BUFFER_AUTOMATIC (in module mpi4py.MPI), 221	COMBINER_SUBARRAY (in module mpi4py.MPI), 218	
BufferAutomaticType (class in mpi4py.MPI), 72	COMBINER_VALUE_INDEX (in module mpi4py.MPI), 219	
BufSpec (in module mpi4py.typing), 38	COMBINER_VECTOR (in module mpi4py.MPI), 217	
BufSpecB (in module mpi4py.typing), 39	Comm (class in mpi4py.MPI), 75	
BufSpecV (in module mpi4py.typing), 39	Comm (class in mpi4py.util.pkl5), 53	
BufSpecW (in module mpi4py.typing), 39	COMM_NULL (in module mpi4py.MPI), 243	
BXOR (in module mpi4py.MPI), 240	COMM_SELF (in module mpi4py.MPI), 243	
BYTE (in module mpi4py.MPI), 227	COMM_TYPE_HW_GUIDED (in module mpi4py.MPI), 221	
B11L (11 module mpi+py.M1 1), 227	COMM_TYPE_HW_UNGUIDED (in module mpi4py.MPI), 221	
C	COMM_TYPE_RESOURCE_GUIDED (in module	
	mpi4py.MPI), 221	
C_BOOL (in module mpi4py.MPI), 229	COMM_TYPE_SHARED (in module mpi4py.MPI), 221	
C_COMPLEX (in module mpi4py.MPI), 231	COMM_WORLD (in module mpi4py.MPI), 243	
C_DOUBLE_COMPLEX (in module mpi4py.MPI), 231	command line option	
C_FLOAT_COMPLEX (in module mpi4py.MPI), 231	configure, 249	
C_LONG_DOUBLE_COMPLEX (in module mpi4py.MPI), 231	mpi, 249	
Call_errhandler() (mpi4py.MPI.Comm method), 83	mpicc, 249	
Call errhandler() (mpi4py MPI File method) 121	mp + c c, = 12	

mpild, 249	<pre>Create_f90_integer() (mpi4py.MPI.Datatype class</pre>
-c, 71	method), 109
-m, 71	Create_f90_real() (mpi4py.MPI.Datatype class
Commit() (mpi4py.MPI.Datatype method), 108	method), 109
Compare() (mpi4py.MPI.Comm method), 83	<pre>Create_from_group() (mpi4py.MPI.Intracomm class</pre>
Compare() (mpi4py.MPI.Group method), 135	method), 146
Compare_and_swap() (mpi4py.MPI.Win method), 178	<pre>Create_from_groups() (mpi4py.MPI.Intercomm class</pre>
Complete() (mpi4py.MPI.Grequest method), 134	method), 143
<pre>complete() (mpi4py.MPI.Grequest method), 134</pre>	<pre>Create_from_session_pset() (mpi4py.MPI.Group</pre>
Complete() (mpi4py.MPI.Win method), 178	class method), 135
COMPLEX (in module mpi4py.MPI), 233	Create_graph() (mpi4py.MPI.Intracomm method), 146
COMPLEX16 (in module mpi4py.MPI), 235	Create_group() (mpi4py.MPI.Intracomm method), 146
COMPLEX32 (in module mpi4py.MPI), 235	Create_group() (mpi4py.MPI.Session method), 165
COMPLEX4 (in module mpi4py.MPI), 235	<pre>Create_hindexed() (mpi4py.MPI.Datatype method),</pre>
COMPLEX8 (in module mpi4py.MPI), 235	109
compose() (in module mpi4py.futures), 46	<pre>Create_hindexed_block() (mpi4py.MPI.Datatype</pre>
Compute_dims() (in module mpi4py.MPI), 193	method), 109
Condition (class in mpi4py.util.sync), 66	<pre>Create_hvector() (mpi4py.MPI.Datatype method),</pre>
CONGRUENT (in module mpi4py.MPI), 220	110
Connect() (mpi4py.MPI.Intracomm method), 145	<pre>Create_indexed() (mpi4py.MPI.Datatype method),</pre>
contents (mpi4py.MPI.Datatype attribute), 116	110
coords (mpi4py.MPI.Cartcomm attribute), 74	<pre>Create_indexed_block() (mpi4py.MPI.Datatype</pre>
copy() (mpi4py.MPI.Info method), 140	method), 110
COUNT (in module mpi4py.MPI), 227	Create_intercomm() (mpi4py.MPI.Intracomm
Count (in module mpi4py.typing), 38	method), 147
count (mpi4py.MPI.Status attribute), 170	Create_keyval() (mpi4py.MPI.Comm class method),
count() (mpi4py.util.sync.Mutex method), 65	83
Counter (class in mpi4py.util.sync), 63	Create_keyval() (mpi4py.MPI.Datatype class
Create() (mpi4py.MPI.Comm method), 83	method), 110
Create() (mpi4py.MPI.Info class method), 139	Create_keyval() (mpi4py.MPI.Win class method), 179
Create() (mpi4py.MPI.Op class method), 153	Create_resized() (mpi4py.MPI.Datatype method),
Create() (mpi4py.MPI.Win class method), 178	110
Create_cart() (mpi4py.MPI.Intracomm method), 145	Create_struct() (mpi4py.MPI.Datatype class
Create_contiguous() (mpi4py.MPI.Datatype	method), 111
method), 108	<pre>Create_subarray() (mpi4py.MPI.Datatype method),</pre>
Create_darray() (mpi4py.MPI.Datatype method), 108	111
Create_dist_graph() (mpi4py.MPI.Intracomm	<pre>Create_vector() (mpi4py.MPI.Datatype method), 111</pre>
method), 145	CXX_BOOL (in module mpi4py.MPI), 231
<pre>Create_dist_graph_adjacent()</pre>	CXX_DOUBLE_COMPLEX (in module mpi4py.MPI), 231
(mpi4py.MPI.Intracomm method), 146	CXX_FLOAT_COMPLEX (in module mpi4py.MPI), 231
Create_dynamic() (mpi4py.MPI.Win class method),	CXX_LONG_DOUBLE_COMPLEX (in module mpi4py.MPI),
179	231
Create_env() (mpi4py.MPI.Info class method), 139	_
Create_errhandler() (mpi4py.MPI.Comm class	D
method), 83	
	Datatype (class in mpi4py MPI), 106
	Datatype (class in mpi4py.MPI), 106 DATATYPE NULL (in module mpi4py.MPI), 227
Create_errhandler() (mpi4py.MPI.File class	DATATYPE_NULL (in module mpi4py.MPI), 227
Create_errhandler() (mpi4py.MPI.File class method), 121	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115
Create_errhandler() (mpi4py.MPI.File class method), 121 Create_errhandler() (mpi4py.MPI.Session class	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115 degrees (mpi4py.MPI.Topocomm attribute), 175
Create_errhandler()	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115 degrees (mpi4py.MPI.Topocomm attribute), 175 Delete() (mpi4py.MPI.File class method), 121
Create_errhandler()	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115 degrees (mpi4py.MPI.Topocomm attribute), 175 Delete() (mpi4py.MPI.File class method), 121 Delete() (mpi4py.MPI.Info method), 139
Create_errhandler()	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115 degrees (mpi4py.MPI.Topocomm attribute), 175 Delete() (mpi4py.MPI.File class method), 121 Delete() (mpi4py.MPI.Info method), 139 Delete_attr() (mpi4py.MPI.Comm method), 83
Create_errhandler()	DATATYPE_NULL (in module mpi4py.MPI), 227 decode() (mpi4py.MPI.Datatype method), 115 degrees (mpi4py.MPI.Topocomm attribute), 175 Delete() (mpi4py.MPI.File class method), 121 Delete() (mpi4py.MPI.Info method), 139

Detach_buffer() (in module mpi4py.MPI), 193	MPICFG, 245, 249
Detach_buffer() (mpi4py.MPI.Comm method), 84	MPIEXEC_UNIVERSE_SIZE, 48
Detach_buffer() (mpi4py.MPI.Session method), 165	MPILD, 245, 249
Difference() (mpi4py.MPI.Group class method), 136	PATH, 244, 249
dim (mpi4py.MPI.Cartcomm attribute), 74	ERR_ACCESS (in module mpi4py.MPI), 214
dims (mpi4py.MPI.Cartcomm attribute), 74	ERR_AMODE (in module mpi4py.MPI), 214
dims (mpi4py.MPI.Graphcomm attribute), 133	ERR_ARG (in module mpi4py.MPI), 210
Disconnect() (mpi4py.MPI.Comm method), 84	ERR_ASSERT (in module mpi4py.MPI), 212
DISP_CUR (in module mpi4py.MPI), 225	ERR_BAD_FILE (in module mpi4py.MPI), 213
Displ (in module mpi4py.typing), 38	ERR_BASE (in module mpi4py.MPI), 212
DISPLACEMENT_CURRENT (in module mpi4py.MPI), 225	ERR_BUFFER (in module mpi4py.MPI), 209
DIST_GRAPH (in module mpi4py.MPI), 220	ERR_COMM (in module mpi4py.MPI), 209
Distgraphcomm (class in mpi4py.MPI), 117	ERR_CONVERSION (in module mpi4py.MPI), 215
DISTRIBUTE_BLOCK (in module mpi4py.MPI), 217	ERR_COUNT (in module mpi4py.MPI), 209
DISTRIBUTE_CYCLIC (in module mpi4py.MPI), 217	ERR_DIMS (in module mpi4py.MPI), 210
DISTRIBUTE_DFLT_DARG (in module mpi4py.MPI), 217	ERR_DISP (in module mpi4py.MPI), 212
DISTRIBUTE_NONE (in module mpi4py.MPI), 216	ERR_DUP_DATAREP (in module mpi4py.MPI), 215
DOUBLE (in module mpi4py.MPI), 229	ERR_ERRHANDLER (in module mpi4py.MPI), 208
DOUBLE_COMPLEX (in module mpi4py.MPI), 233	ERR_FILE (in module mpi4py.MPI), 209
DOUBLE_INT (in module mpi4py.MPI), 232	ERR_FILE_EXISTS (in module mpi4py.MPI), 214
DOUBLE_PRECISION (in module mpi4py.MPI), 233	ERR_FILE_IN_USE (in module mpi4py.MPI), 214
dumps() (mpi4py.MPI.Pickle method), 155	ERR_GROUP (in module mpi4py.MPI), 208
dumps_oob() (mpi4py.MPI.Pickle method), 155	ERR_IN_STATUS (in module mpi4py.MPI), 210
Dup() (mpi4py.MPI.Comm method), 84	ERR_INFO (in module mpi4py.MPI), 208
Dup() (mpi4py.MPI.Datatype method), 111	ERR_INFO_KEY (in module mpi4py.MPI), 211
Dup() (mpi4py.MPI.Group method), 136	ERR_INFO_NOKEY (in module mpi4py.MPI), 211
Dup() (mpi4py.MPI.Info method), 140	ERR_INFO_VALUE (in module mpi4py.MPI), 211
Dup_with_info() (mpi4py.MPI.Comm method), 84	ERR_INTERN (in module mpi4py.MPI), 211
	ERR_IO (in module mpi4py.MPI), 215
E	ERR_KEYVAL (in module mpi4py.MPI), 211
edges (mpi4py.MPI.Graphcomm attribute), 133	ERR_LASTCODE (in module mpi4py.MPI), 208
end() (mpi4py.util.sync.Sequential method), 63	ERR_LOCKTYPE (in module mpi4py.MPI), 212
envelope (<i>mpi4py.MPI.Datatype attribute</i>), 116	ERR_NAME (in module mpi4py.MPI), 212
environment variable	ERR_NO_MEM (in module mpi4py.MPI), 211
CC, 245	ERR_NO_SPACE (in module mpi4py.MPI), 214
MPI4PY_BUILD_BACKEND, 244, 245	ERR_NO_SUCH_FILE (in module mpi4py.MPI), 213
MPI4PY_BUILD_CONFIGURE, 244, 245	ERR_NOT_SAME (in module mpi4py.MPI), 214
MPI4PY_BUILD_MPICC, 244, 245	ERR_OP (in module mpi4py.MPI), 208
MPI4PY_BUILD_MPICFG, 244, 245	ERR_OTHER (in module mpi4py.MPI), 210
MPI4PY_BUILD_MPILD, 244, 245	ERR_PENDING (in module mpi4py.MPI), 210
MPI4PY_FUTURES_BACKOFF, 42, 43	ERR_PORT (in module mpi4py.MPI), 211
MPI4PY_FUTURES_MAX_WORKERS, 41, 43, 48	ERR_PROC_ABORTED (in module mpi4py.MPI), 212
	ERR_PROC_FAILED (in module mpi4py.MPI), 215
MPI4PY_FUTURES_USE_PKL5, 42, 43	ERR_PROC_FAILED_PENDING (in module mpi4py.MPI)
MPI4PY_PICKLE_PROTOCOL, 12, 26	216
MPI4PY_PICKLE_THRESHOLD, 27	ERR_QUOTA (in module mpi4py.MPI), 214
MPI4PY_RC_ERRORS, 23, 26	ERR_RANK (in module mpi4py.MPI), 209
MPI4PY_RC_FAST_REDUCE, 23, 25	ERR_READ_ONLY (in module mpi4py.MPI), 214
MPI4PY_RC_FINALIZE, 22, 24	ERR_REQUEST (in module mpi4py.MPI), 208
MPI4PY_RC_INITIALIZE, 22, 24	ERR_REVOKED (in module mpi4py.MPI), 215
MPI4PY_RC_IRECV_BUFSZ, 23, 26	
MPI4PY_RC_RECV_MPROBE, 23, 25	ERR_RMA_ATTACH (in module mpi4py.MPI), 213
MPI4PY_RC_THREAD_LEVEL, 22, 25	ERR_RMA_CONFLICT (in module mpi4py.MPI), 213
MPI4PY_RC_THREADS, 22, 25	ERR_RMA_FLAVOR (in module mpi4py.MPI), 213
MPICC, 245, 249	ERR_RMA_RANGE (in module mpi4py.MPI), 213

ERR_RMA_SHARED (in module mpi4py.MPI), 213	F_FLOAT_COMPLEX (in module mpi4py.MPI), 237
ERR_RMA_SYNC (in module mpi4py.MPI), 213	F_INT (in module mpi4py.MPI), 237
ERR_ROOT (in module mpi4py.MPI), 209	F_SOURCE (in module mpi4py.MPI), 219
ERR_SERVICE (in module mpi4py.MPI), 212	F_STATUS_SIZE (in module mpi4py.MPI), 219
ERR_SESSION (in module mpi4py.MPI), 208	F_TAG (in module mpi4py.MPI), 219
ERR_SIZE (in module mpi4py.MPI), 212	<pre>fast_reduce (mpi4py.mpi4py.rc attribute), 22</pre>
ERR_SPAWN (in module mpi4py.MPI), 211	Fence() (mpi4py.MPI.Win method), 180
ERR_TAG (in module mpi4py.MPI), 209	Fetch_and_op() (mpi4py.MPI.Win method), 180
ERR_TOPOLOGY (in module mpi4py.MPI), 210	File (class in mpi4py.MPI), 119
ERR_TRUNCATE (in module mpi4py.MPI), 210	FILE_NULL (in module mpi4py.MPI), 243
ERR_TYPE (in module mpi4py.MPI), 208	finalize (mpi4py.mpi4py.rc attribute), 22
ERR_UNKNOWN (in module mpi4py.MPI), 210	Finalize() (in module mpi4py.MPI), 193
ERR_UNSUPPORTED_DATAREP (in module mpi4py.MPI),	Finalize() (mpi4py.MPI.Session method), 165
215	flavor (mpi4py.MPI.Win attribute), 186
ERR_UNSUPPORTED_OPERATION (in module	FLOAT (in module mpi4py.MPI), 229
mpi4py.MPI), 215	FLOAT_INT (in module mpi4py.MPI), 232
ERR_VALUE_TOO_LARGE (in module mpi4py.MPI), 215	Flush() (mpi4py.MPI.Win method), 180
ERR_WIN (in module mpi4py.MPI), 209	Flush_all() (mpi4py.MPI.Win method), 180
Errhandler (class in mpi4py.MPI), 117	Flush_buffer() (in module mpi4py.MPI), 193
ERRHANDLER_NULL (in module mpi4py.MPI), 242	Flush_buffer() (mpi4py.MPI.Comm method), 84
error (mpi4py.MPI.Status attribute), 170	Flush_buffer() (mpi4py.MPI.Session method), 165
error_class (mpi4py.MPI.Exception attribute), 190	Flush_local() (mpi4py.MPI.Win method), 180
error_code (mpi4py.MPI.Exception attribute), 190	Flush_local_all() (mpi4py.MPI.Win method), 180
error_string (mpi4py.MPI.Exception attribute), 190	format (mpi4py.MPI.buffer attribute), 188
errors (mpi4py.mpi4py.rc attribute), 23	Free() (mpi4py.MPI.Comm method), 84
ERRORS_ABORT (in module mpi4py.MPI), 242	free() (mpi4py.MPI.Comm method), 102
ERRORS_ARE_FATAL (in module mpi4py.MPI), 242	Free() (mpi4py.MPI.Datatype method), 112
ERRORS_RETURN (in module mpi4py.MPI), 242	free() (mpi4py.MPI.Datatype method), 115
Exception, 189	Free() (mpi4py.MPI.Errhandler method), 118
Excl() (mpi4py.MPI.Group method), 136	free() (mpi4py.MPI.Errhandler method), 118
Exscan() (mpi4py.MPI.Intracomm method), 147	free() (mpi4py.MPI.File method), 131
exscan() (mpi4py.MPI.Intracomm method), 149	Free() (mpi4py.MPI.Group method), 136
Exscan_init() (mpi4py.MPI.Intracomm method), 147	free() (mpi4py.MPI.Group method), 137
extent (mpi4py.MPI.Datatype attribute), 116	Free() (mpi4py.MPI.Info method), 140
	free() (mpi4py.MPI.Info method), 141
F	free() (mpi4py.MPI.Message method), 151
f2py() (mpi4py.MPI.Comm class method), 101	Free() (mpi4py.MPI.Op method), 153
f2py() (mpi4py.MPI.Datatype class method), 115	free() (mpi4py.MPI.Op method), 154
f2py() (mpi4py.MPI.Errhandler class method), 118	Free() (mpi4py.MPI.Request method), 159
f2py() (mpi4py.MPI.File class method), 130	free() (mpi4py.MPI.Request method), 161
f2py() (mpi4py.MPI.Group class method), 137	free() (mpi4py.MPI.Session method), 167
f2py() (mpi4py.MPI.Info class method), 141	Free() (mpi4py.MPI.Win method), 180
f2py() (mpi4py.MPI.Message class method), 151	free() (mpi4py.MPI.Win method), 185
f2py() (mpi4py.MPI.Op class method), 154	free() (mpi4py.util.pkl5.Message method), 52
f2py() (mpi4py.MPI.Request class method), 161	Free() (mpi4py.util.pkl5.Request method), 51
	free() (mpi4py.util.pkl5.Request method), 51
f2py() (mpi4py.MPI.Session class method), 167	free() (mpi4py.util.sync.Condition method), 67
f2py() (mpi4py.MPI.Status class method), 170 f2py() (mpi4py.MPI.Win class method), 185	free() (mpi4py.util.sync.Counter method), 64
f2py() (mpi4py.MPI.Win class method), 185	free() (mpi4py.util.sync.Mutex method), 65
F_BOOL (in module mpi4py.MPI), 237 E_COMPLEY (in module mpi4py.MPI), 237	free() (mpi4py.util.sync.Semaphore method), 69
F_COMPLEX (in module mpi4py.MPI), 237 F_DOUBLE (in module mpi4py.MPI), 237	Free_keyval() (mpi4py.MPI.Comm class method), 84
F_DOUBLE (in module mpi4py.MPI), 237 F_DOUBLE COMPLEY (in module mpi4py.MPI), 237	Free_keyval() (mpi4py.MPI.Datatype class method)
F_DOUBLE_COMPLEX (in module mpi4py.MPI), 237 F_ERROR (in module mpi4py.MPI), 219	112
F_ERROR (in module mpi4py.MF1), 219 F_ELOAT (in module mpi4py.MPI) 237	Free_keyval() (mpi4py.MPI.Win class method), 181

Free_mem() (in module mpi4py.MPI), 194 from_numpy_dtype() (in module mpi4py.util.dtlib), 50 fromaddress() (mpi4py.MPI.buffer static method), 187 frombuffer() (mpi4py.MPI.buffer static method), 187 fromcode() (mpi4py.MPI.Datatype class method), 115	Get_errhandler() (mpi4py.MPI.File method), 122 Get_errhandler() (mpi4py.MPI.Session method), 165 Get_errhandler() (mpi4py.MPI.Win method), 181 Get_error() (mpi4py.MPI.Status method), 168 Get_error_class() (in module mpi4py.MPI), 194
fromhandle() (mpi4py.MPI.Comm class method), 102 fromhandle() (mpi4py.MPI.Datatype class method), 115	Get_error_class() (mpi4py.MPI.Exception method), 189 Cot_error_code() (mpi4py.MPI.Exception method)
fromhandle() (mpi4py.MPI.Errhandler class method),	<pre>Get_error_code() (mpi4py.MPI.Exception method),</pre>
fromhandle() (mpi4py.MPI.File class method), 131 fromhandle() (mpi4py.MPI.Group class method), 137	Get_error_string() (mpi4py.MPI.Exception method), 189
fromhandle() (mpi4py.MPI.Info class method), 141 fromhandle() (mpi4py.MPI.Message class method), 151	Get_extent() (mpi4py.MPI.Datatype method), 112 Get_failed() (mpi4py.MPI.Comm method), 86 Get_group() (mpi4py.MPI.Comm method), 86
fromhandle() (mpi4py.MPI.Op class method), 154	Get_group() (mpi4py.MPI.File method), 122
fromhandle() (mpi4py.MPI.Request class method), 161 fromhandle() (mpi4py.MPI.Session class method), 167	Get_group() (mpi4py.MPI.Win method), 181 Get_hw_resource_info() (in module mpi4py.MPI),
fromhandle() (mpi4py.MPI.Win class method), 185	194
	<pre>get_include() (in module mpi4py), 27</pre>
G	Get_info() (mpi4py.MPI.Comm method), 86
Gather() (mpi4py.MPI.Comm method), 84	<pre>Get_info() (mpi4py.MPI.File method), 122</pre>
gather() (mpi4py.MPI.Comm method), 102	<pre>Get_info() (mpi4py.MPI.Session method), 166</pre>
gather() (mpi4py.util.pkl5.Comm method), 56	<pre>Get_info() (mpi4py.MPI.Win method), 181</pre>
Gather_init() (mpi4py.MPI.Comm method), 85	Get_library_version() (in module mpi4py.MPI), 195
Gatherv() (mpi4py.MPI.Comm method), 85	<pre>Get_name() (mpi4py.MPI.Comm method), 86</pre>
Gatherv_init() (mpi4py.MPI.Comm method), 85	Get_name() (mpi4py.MPI.Datatype method), 112
Get() (mpi4py.MPI.Info method), 140	Get_name() (mpi4py.MPI.Win method), 182
get() (mpi4py.MPI.Info method), 141	<pre>Get_neighbors() (mpi4py.MPI.Graphcomm method),</pre>
Get() (mpi4py.MPI.Win method), 181	132
get() (mpi4py.util.pool.AsyncResult method), 61	Get_neighbors_count() (mpi4py.MPI.Graphcomm
Get_accumulate() (mpi4py.MPI.Win method), 181	method), 132
Get_address() (in module mpi4py.MPI), 194	Get_nkeys() (mpi4py.MPI.Info method), 140
Get_amode() (<i>mpi4py.MPI.File method</i>), 121	Get_nth_pset() (mpi4py.MPI.Session method), 166
<pre>Get_atomicity() (mpi4py.MPI.File method), 121</pre>	Get_nthkey() (mpi4py.MPI.Info method), 140
Get_attr() (mpi4py.MPI.Comm method), 85	Get_num_psets() (mpi4py.MPI.Session method), 166
Get_attr() (mpi4py.MPI.Datatype method), 112	<pre>Get_parent() (mpi4py.MPI.Comm class method), 86 Get_position() (mpi4py.MPI.File method), 122</pre>
Get_attr() (mpi4py.MPI.Win method), 181	Get_position_shared() (mpi4py.MPI.File method),
Get_byte_offset() (mpi4py.MPI.File method), 122	122
Get_cart_rank() (mpi4py.MPI.Cartcomm method), 73	Get_processor_name() (in module mpi4py.MPI), 195
get_comm_workers() (in module mpi4py.futures), 46	Get_pset_info() (mpi4py.MPI.Session method), 166
<pre>get_config() (in module mpi4py), 27 Get_contents() (mpi4py.MPI.Datatype method), 112</pre>	Get_rank() (mpi4py.MPI.Comm method), 86
Get_contents() (mpi4py.MF1.Datatype method), 73 Get_coords() (mpi4py.MPI.Cartcomm method), 73	Get_rank() (mpi4py.MPI.Group method), 136
Get_count() (mpi4py.MPI.Status method), 168	Get_remote_group() (mpi4py.MPI.Intercomm
Get_dim() (mpi4py.MPI.Cartcomm method), 74	method), 143
Get_dim() (mpi4py.MPI.Graphcomm method), 132	<pre>Get_remote_size() (mpi4py.MPI.Intercomm method),</pre>
Get_dist_neighbors() (mpi4py.MPI.Distgraphcomm	143
method), 117	<pre>Get_size() (mpi4py.MPI.Comm method), 86</pre>
Get_dist_neighbors_count()	<pre>Get_size() (mpi4py.MPI.Datatype method), 112</pre>
(mpi4py.MPI.Distgraphcomm method), 117	<pre>Get_size() (mpi4py.MPI.File method), 122</pre>
Get_elements() (mpi4py.MPI.Status method), 168	<pre>Get_size() (mpi4py.MPI.Group method), 136</pre>
Get_envelope() (mpi4py.MPI.Datatype method), 112	<pre>Get_source() (mpi4py.MPI.Status method), 168</pre>
Get errhandler() (mni/nv MPI Comm method) 85	<pre>Get_status() (mpi4py.MPI.Request method), 159</pre>

	MPI.Request method), 161		handle (mpi4py.MPI.Win attrib	bute), 186
	util.pkl5.Request method),		1	
Get_status_all()	(mpi4py.MPI.Request	class	1	
method), 159	(: 1 MDI D	-1	<pre>Iagree() (mpi4py.MPI.Comm</pre>	
get_status_all()	(mpi4py.MPI.Request	class	<pre>Iallgather() (mpi4py.MPI.C</pre>	
method), 161	: 1	-1	<pre>Iallgatherv() (mpi4py.MPI.</pre>	* *
	mpi4py.util.pkl5.Request	class	<pre>Iallreduce() (mpi4py.MPI.C</pre>	
method), 52	(mmi/mm MDI Dogmost	alaaa	Ialltoall() (mpi4py.MPI.Co	
Get_status_any()	(mpi4py.MPI.Request	class	Ialltoallv() (mpi4py.MPI.C	
method), 159	(mni/m MDI Paguagt	alass	Ialltoallw() (mpi4py.MPI.C	
<pre>get_status_any() method), 162</pre>	(mpi4py.MPI.Request	class	<pre>Ibarrier() (mpi4py.MPI.Com</pre>	
Get_status_some()	(mpi4py.MPI.Request	class	<pre>Ibcast() (mpi4py.MPI.Comm</pre>	
method), 159	(mpi+py.mi i.Kequesi	ciuss	<pre>Ibsend() (mpi4py.MPI.Comm</pre>	
get_status_some()	(mpi4py.MPI.Request	class	ibsend() (mpi4py.MPI.Comm	
method), 162	(трі+ру.ті і.кециезі	ciuss	ibsend() (mpi4py.util.pkl5.Co	
Get_tag() (mpi4py.MPI	I Status method) 169		IDENT (in module mpi4py.MPI)	
	PI.Cartcomm method), 74		Idup() (mpi4py.MPI.Comm me	
	PI.Graphcomm method), 1	33	Idup_with_info() (mpi4py.M	
	py.MPI.Comm method), 80		<pre>Iexscan() (mpi4py.MPI.Intract If luck buffer() (in module)</pre>	
	mpi4py.MPI.Datatype me		Iflush_buffer() (in module	
112	npi ipyinii iibaianype me	inou),	Iflush_buffer() (mpi4py.Ml	
	pi4py.MPI.File method),	123	<pre>Iflush_buffer() (mpi4py.MI Igather() (mpi4py.MPI.Comm</pre>	
	(mpi4py.MPI.Datatype	class	Igatherv() (mpi4py.MPI.Com	* *
method), 113	(
<pre>get_vendor() (in modu</pre>	le mpi4py.MPI), 199		<pre>imap() (mpi4py.util.pool.Pool method), 59 imap_unordered() (mpi4py.util.pool.Pool method), 60</pre>	
Get_version() (in mod			Improbe() (mpi4py.MPI.Comm	
Get_view() (mpi4py.MPI.File method), 123		improbe() (mpi4py.MPI.Comm		
GRAPH (in module mpi4py.MPI), 220		improbe() (mpi4py.util.pkl5.C		
Graph_map() (mpi4py.MPI.Intracomm method), 147		IN_PLACE (in module mpi4py.M.		
Graphcomm (class in mpi4py.MPI), 132		Incl() (mpi4py.MPI.Group me		
Grequest (class in mpi4py.MPI), 133		indegree (mpi4py.MPI.Topoco		
Group (class in mpi4py.MPI), 134		index (mpi4py.MPI.Graphcom		
group (mpi4py.MPI.Com	ım attribute), 105		inedges (mpi4py.MPI.Topocom	
group (mpi4py.MPI.File	attribute), 131		<pre>Ineighbor_allgather()</pre>	(mpi4py.MPI.Topocomm
group (mpi4py.MPI.Win	attribute), 186		method), 172	(1 · F)
GROUP_EMPTY (in module	e mpi4py.MPI), 242		<pre>Ineighbor_allgatherv()</pre>	(mpi4py.MPI.Topocomm
GROUP_NULL (in module i			method), 172	(1 1)
<pre>group_rank (mpi4py.MF</pre>	PI.File attribute), 131		<pre>Ineighbor_alltoall()</pre>	(mpi4py.MPI.Topocomm
<pre>group_rank (mpi4py.MI</pre>			method), 172	
<pre>group_size (mpi4py.MI</pre>			<pre>Ineighbor_alltoallv()</pre>	(mpi4py.MPI.Topocomm
<pre>group_size (mpi4py.MI</pre>	PI.Win attribute), 186		method), 172	
1.1			<pre>Ineighbor_alltoallw()</pre>	(mpi4py.MPI.Topocomm
Н			method), 172	
handle (mpi4py.MPI.Co			Info (class in mpi4py.MPI), 13	38
handle (mpi4py.MPI.Da			info (mpi4py.MPI.Comm attrib	bute), 105
handle (mpi4py.MPI.Errhandler attribute), 119		info (mpi4py.MPI.File attribut		
handle (mpi4py.MPI.File attribute), 131		info (mpi4py.MPI.Win attribut		
handle (mpi4py.MPI.Group attribute), 138		INFO_ENV (in module mpi4py.M		
handle (mpi4py.MPI.Info			INFO_NULL (in module mpi4py.	
handle (mpi4py.MPI.Me	_		<pre>Init() (in module mpi4py.MP.</pre>	
handle (mpi4py.MPI.Op			<pre>Init() (mpi4py.MPI.Session class method), 166</pre>	
handle (<i>mpi4py</i> . <i>MPI</i> . <i>Red</i>			<pre>Init_thread() (in module mp</pre>	= -
handle (mpi4py.MPI.Session attribute), 167		initialize (mpi4py.mpi4py.re	c attribute), 21	

inoutedges (mpi4py.MPI.Topocomm attribute), 175	is_predefined (mpi4py.MPI.Datatype attribute), 116
InPlace (in module mpi4py.typing), 38	is_predefined (mpi4py.MPI.Op attribute), 154
InPlaceType (class in mpi4py.MPI), 138	<pre>Is_revoked() (mpi4py.MPI.Comm method), 91</pre>
INT (in module mpi4py.MPI), 228	<pre>Is_thread_main() (in module mpi4py.MPI), 196</pre>
INT16_T (in module mpi4py.MPI), 230	is_topo (mpi4py.MPI.Comm attribute), 106
INT32_T (in module mpi4py.MPI), 230	Iscan() (mpi4py.MPI.Intracomm method), 148
INT64_T (in module mpi4py.MPI), 230	<pre>Iscatter() (mpi4py.MPI.Comm method), 91</pre>
INT8_T (in module mpi4py.MPI), 230	Iscatterv() (mpi4py.MPI.Comm method), 91
INT_INT (in module mpi4py.MPI), 232	Isend() (mpi4py.MPI.Comm method), 91
INTEGER (in module mpi4py.MPI), 233	isend() (mpi4py.MPI.Comm method), 103
INTEGER1 (in module mpi4py.MPI), 234	isend() (mpi4py.util.pkl5.Comm method), 53
INTEGER16 (in module mpi4py.MPI), 234	Isendrecv() (mpi4py.MPI.Comm method), 91
INTEGER2 (in module mpi4py.MPI), 234	Isendrecv_replace() (mpi4py.MPI.Comm method),
INTEGERA (in module mpi4py.MPI), 234	92
INTEGERA (in module mpi4py.MPI), 234 INTEGER8 (in module mpi4py.MPI), 234	Ishrink() (mpi4py.MPI.Comm method), 92
Intercomm (class in mpi4py.MPI), 142	Issend() (mpi4py.MPI.Comm method), 92
Intercomm (class in mpi4py.util.pkl5), 56	issend() (mpi4py.MPI.Comm method), 103
Intersection() (mpi4py.MPI.Group class method),	issend() (mpi4py.util.pkl5.Comm method), 54
136	istarmap() (mpi4py.util.pool.Pool method), 61
Intracomm (class in mpi4py.MPI), 144	istarmap_unordered() (mpi4py.util.pool.Pool
Intracomm (class in mpi4py.util.pkl5), 56	method), 61
IO (in module mpi4py.MPI), 206	items() (mpi4py.MPI.Info method), 141
Iprobe() (mpi4py.MPI.Comm method), 89	itemsize (mpi4py.MPI.buffer attribute), 188
iprobe() (mpi4py.MPI.Comm method), 102	<pre>Iwrite() (mpi4py.MPI.File method), 124</pre>
Iprobe() (mpi4py.MPI.Message class method), 150	<pre>Iwrite_all() (mpi4py.MPI.File method), 124</pre>
iprobe() (mpi4py.MPI.Message class method), 151	<pre>Iwrite_at() (mpi4py.MPI.File method), 124</pre>
iprobe() (mpi4py.util.pkl5.Message class method), 53	<pre>Iwrite_at_all() (mpi4py.MPI.File method), 124</pre>
Iread() (mpi4py.MPI.File method), 123	<pre>Iwrite_shared() (mpi4py.MPI.File method), 124</pre>
Iread_all() (mpi4py.MPI.File method), 123	•
<pre>Iread_at() (mpi4py.MPI.File method), 123</pre>	J
<pre>Iread_at_all() (mpi4py.MPI.File method), 123</pre>	Join() (mpi4py.MPI.Comm class method), 93
Iread_shared() (mpi4py.MPI.File method), 123	join() (mpi4py.util.pool.Pool method), 61
Irecv() (mpi4py.MPI.Comm method), 89	
irecv() (mpi4py.MPI.Comm method), 103	K
Irecv() (mpi4py.MPI.Message method), 150	
irecv() (mpi4py.MPI.Message method), 151	keys() (mpi4py.MPI.Info method), 141
irecv() (mpi4py.util.pkl5.Comm method), 54	KEYVAL_INVALID (in module mpi4py.MPI), 206
irecv() (mpi4py.util.pkl5.Message method), 53	L
irecv_bufsz (mpi4py.mpi4py.rc attribute), 23	
Ireduce() (mpi4py.MPI.Comm method), 90	LAND (in module mpi4py.MPI), 239
Ireduce_scatter() (mpi4py.MPI.Comm method), 90	LASTUSEDCODE (in module mpi4py.MPI), 207
Ireduce_scatter_block() (mpi4py.MPI.Comm	1b (mpi4py.MPI.Datatype attribute), 116
method), 90	loads() (mpi4py.MPI.Pickle method), 155
Irsend() (mpi4py.MPI.Comm method), 90	loads_oob() (mpi4py.MPI.Pickle method), 155
Is_cancelled() (<i>mpi4py.MPI.Status method</i>), 169	Lock() (mpi4py.MPI.Win method), 182
is_commutative (mpi4py.MPI.Op attribute), 154	Lock_all() (mpi4py.MPI.Win method), 182
Is_commutative() (mpi4py.MPI.Op method), 153	LOCK_EXCLUSIVE (in module mpi4py.MPI), 223
Is_finalized() (in module mpi4py.MPI), 196	LOCK_SHARED (in module mpi4py.MPI), 223
	locked() (mpi4py.util.sync.Condition method), 66
Is_initialized() (in module mpi4py.MPI), 196	locked() (mpi4py.util.sync.Mutex method), 65
is_inter(mpi4py.MPI.Comm attribute), 105	LOGICAL (in module mpi4py.MPI), 233
Is_inter() (mpi4py.MPI.Comm method), 90	LOGICAL1 (in module mpi4py.MPI), 233
is_intra (mpi4py.MPI.Comm attribute), 106	LOGICAL2 (in module mpi4py.MPI), 233
Is_intra() (mpi4py.MPI.Comm method), 91	LOGICAL4 (in module mpi4py.MPI), 234
is named (mni4ny, MPL Datatype attribute), 116	(

LOGICAL8 (in module mpi4py.MPI), 234	mpi4py, 21
LONG (in module mpi4py.MPI), 228	mpi4py.bench,71
LONG_DOUBLE (in module mpi4py.MPI), 229	mpi4py.futures, 40
LONG_DOUBLE_INT (in module mpi4py.MPI), 232	mpi4py.MPI, 71
LONG_INT (in module mpi4py.MPI), 232	mpi4py.run,70
LONG_LONG (in module mpi4py.MPI), 228	mpi4py.typing, 37
Lookup_name() (in module mpi4py.MPI), 196	mpi4py.util, 50
LOR (in module mpi4py.MPI), 240	mpi4py.util.dtlib,50
LXOR (in module mpi4py.MPI), 240	mpi4py.util.pkl5,51
T. I.J.	mpi4py.util.pool,58
M	mpi4py.util.sync, 62
	mpi4py
map() (mpi4py.futures.MPIPoolExecutor method), 42	module, 21
map() (mpi4py.util.pool.Pool method), 59	mpi4py.bench
map_async() (mpi4py.util.pool.Pool method), 59	module, 71
MapResult (class in mpi4py.util.pool), 62	mpi4py.futures
Match_size() (mpi4py.MPI.Datatype class method),	module, 40
113	mpi4py.MPI
MAX (in module mpi4py.MPI), 238	module, 71
MAX_DATAREP_STRING (in module mpi4py.MPI), 226	mpi4py.rc (in module mpi4py), 21
MAX_ERROR_STRING (in module mpi4py.MPI), 226	mpi4py.run
MAX_INFO_KEY (in module mpi4py.MPI), 226	module, 70
MAX_INFO_VAL (in module mpi4py.MPI), 226	
MAX_LIBRARY_VERSION_STRING (in module	mpi4py.typing
mpi4py.MPI), 226	module, 37
MAX_OBJECT_NAME (in module mpi4py.MPI), 226	mpi4py.util
MAX_PORT_NAME (in module mpi4py.MPI), 226	module, 50
MAX_PROCESSOR_NAME (in module mpi4py.MPI), 226	mpi4py.util.dtlib
MAX_PSET_NAME_LEN (in module mpi4py.MPI), 227	module, 50
MAX_STRINGTAG_LEN (in module mpi4py.MPI), 227	mpi4py.util.pkl5
MAXLOC (in module mpi4py.MPI), 241	module, 51
memory (in module mpi4py.MPI), 188	mpi4py.util.pool
Merge() (mpi4py.MPI.Intercomm method), 143	module, 58
Message (class in mpi4py.MPI), 149	mpi4py.util.sync
Message (class in mpi4py.util.pkl5), 52	module, 62
MESSAGE_NO_PROC (in module mpi4py.MPI), 238	MPI4PY_BUILD_BACKEND, 244, 245
MESSAGE_NULL (in module mpi4py.MPI), 238	MPI4PY_BUILD_CONFIGURE, 245
MIN (in module mpi4py.MPI), 238	MPI4PY_BUILD_MPICC, 244, 245
MINLOC (in module mpi4py.MPI), 241	MPI4PY_BUILD_MPICFG, 244, 245
MODE_APPEND (in module mpi4py.MPI), 224	MPI4PY_BUILD_MPILD, 244, 245
MODE_CREATE (in module mpi4py.MPI), 223	MPI4PY_FUTURES_BACKOFF, 42, 43
MODE_DELETE_ON_CLOSE (in module mpi4py.MPI), 224	MPI4PY_FUTURES_MAX_WORKERS, 41, 43, 48
MODE_EXCL (in module mpi4py.MPI), 224	MPI4PY_FUTURES_USE_PKL5, 42, 43
MODE_NOCHECK (in module mpi4py.MPI), 222	MPI4PY_PICKLE_PROTOCOL, 12
MODE_NOPRECEDE (in module mpi4py.MPI), 223	MPI4PY_RC_ERRORS, 23
MODE_NOPUT (in module mpi4py.MPI), 222	MPI4PY_RC_FAST_REDUCE, 23
MODE_NOSTORE (in module mpi4py.MPI), 222	MPI4PY_RC_FINALIZE, 22
MODE_NOSUCCEED (in module mpi4py.MPI), 223	MPI4PY_RC_INITIALIZE, 22
MODE_RDONLY (in module mpi4py.MPI), 223	MPI4PY_RC_IRECV_BUFSZ, 23
MODE_RDWR (in module mpi4py.MPI), 223	MPI4PY_RC_RECV_MPROBE, 23
MODE_SEQUENTIAL (in module mpi4py.MPI), 224	MPI4PY_RC_THREAD_LEVEL, 22
MODE_UNIQUE_OPEN (in module mpi4py.MPI), 224	MPI4PY_RC_THREADS, 22
MODE_WRONLY (in module mpi4py.MPI), 223	MPICC, 249
model (mpi4py.MPI.Win attribute), 186	MPICFG, 249
module	MPICommExecutor (class in mpi4py.futures), 4

MPIEXEC_UNIVERSE_SIZE, 48 MPILD, 249 MPIPoolExecutor (class in mpi4py.futures), 41 Mprobe() (mpi4py.MPI.Comm method), 93 mprobe() (mpi4py.MPI.Comm method), 103 mprobe() (mpi4py.util.pkl5.Comm method), 55 Mutex (class in mpi4py.util.sync), 64	OP_NULL (in module mpi4py.MPI), 238 Open() (mpi4py.MPI.File class method), 124 Open_port() (in module mpi4py.MPI), 196 ORDER_C (in module mpi4py.MPI), 216 ORDER_F (in module mpi4py.MPI), 216 ORDER_FORTRAN (in module mpi4py.MPI), 216 outdegree (mpi4py.MPI.Topocomm attribute), 175 outedges (mpi4py.MPI.Topocomm attribute), 175
	Р
name (mpi4py.MPI.Comm attribute), 106 name (mpi4py.MPI.Datatype attribute), 116 name (mpi4py.MPI.Win attribute), 186 nbytes (mpi4py.MPI.buffer attribute), 188 ndim (mpi4py.MPI.Cartcomm attribute), 74	Pack() (mpi4py.MPI.Datatype method), 113 Pack_external() (mpi4py.MPI.Datatype method), 113 Pack_external_size() (mpi4py.MPI.Datatype method), 113
nedges (<i>mpi4py.MPI.Graphcomm attribute</i>), 133	Pack_size() (mpi4py.MPI.Datatype method), 114
Neighbor_allgather() (mpi4py.MPI.Topocomm	PACKED (in module mpi4py.MPI), 227
method), 172	Parrived() (mpi4py.MPI.Prequest method), 156
neighbor_allgather() (mpi4py.MPI.Topocomm	PATH, 244, 249
method), 174	Pcontrol() (in module mpi4py.MPI), 197
Neighbor_allgather_init()	periods (mpi4py.MPI.Cartcomm attribute), 74
(mpi4py.MPI.Topocomm method), 173	Pickle (class in mpi4py.MPI), 154
Neighbor_allgatherv() (mpi4py.MPI.Topocomm	pickle (in module mpi4py.MPI), 243
method), 173	Pool (class in mpi4py.util.pool), 58
Neighbor_allgatherv_init()	pop() (mpi4py.MPI.Info method), 141
(mpi4py.MPI.Topocomm method), 173	popitem() (mpi4py.MPI.Info method), 141
Neighbor_alltoall() (mpi4py.MPI.Topocomm	Post() (mpi4py.MPI. Win method), 182
<pre>method), 173 neighbor_alltoall()</pre>	Pready() (mpi4py.MPI.Prequest method), 156
neighbor_alltoall() (mpi4py.MPI.Topocomm method), 175	Pready_list() (mpi4py.MPI.Prequest method), 156 Pready_range() (mpi4py.MPI.Prequest method), 157
<pre>Neighbor_alltoall_init() (mpi4py.MPI.Topocomm</pre>	Preallocate() (mpi4py.MPI.File method), 125
method), 173	Precv_init() (mpi4py.MPI.Comm method), 93
Neighbor_alltoallv() (mpi4py.MPI.Topocomm	Prequest (class in mpi4py.MPI), 156
method), 174	Probe() (mpi4py.MPI.Comm method), 93
Neighbor_alltoallv_init()	probe() (mpi4py.MPI.Comm method), 104
(mpi4py.MPI.Topocomm method), 174	Probe() (mpi4py.MPI.Message class method), 150
Neighbor_alltoallw() (mpi4py.MPI.Topocomm	probe() (mpi4py.MPI.Message class method), 151
method), 174	probe() (mpi4py.util.pkl5.Message class method), 53
Neighbor_alltoallw_init()	PROC_NULL (in module mpi4py.MPI), 205
(mpi4py.MPI.Topocomm method), 174	PROD (in module mpi4py.MPI), 239
neighbors (mpi4py.MPI.Graphcomm attribute), 133	<pre>profile() (in module mpi4py), 27</pre>
next() (mpi4py.util.sync.Counter method), 64	PROTOCOL (mpi4py.MPI.Pickle attribute), 156
nneighbors (mpi4py.MPI.Graphcomm attribute), 133	<pre>Psend_init() (mpi4py.MPI.Comm method), 93</pre>
nnodes (mpi4py.MPI.Graphcomm attribute), 133	Publish_name() (in module mpi4py.MPI), 197
NO_OP (in module mpi4py.MPI), 241	Put() (mpi4py.MPI.Win method), 182
notify() (mpi4py.util.sync.Condition method), 67	py2f() (mpi4py.MPI.Comm method), 104
notify_all() (mpi4py.util.sync.Condition method), 67	py2f() (mpi4py.MPI.Datatype method), 116
num_workers (mpi4py.futures.MPIPoolExecutor at-	py2f() (mpi4py.MPI.Errhandler method), 118
tribute), 43	py2f() (mpi4py.MPI.File method), 131
0	py2f() (mpi4py.MPI.Group method), 138
	py2f() (mpi4py.MPI.Info method), 142
obj (mpi4py.MPI.buffer attribute), 188	py2f() (mpi4py.MPI.Message method), 152
OFFSET (in module mpi4py.MPI), 227	py2f() (mpi4py.MPI.Op method), 154 py2f() (mpi4py.MPI.Request method), 162
Offset (in module mpi4py.typing), 38	py2f() (mpi4py.MPI.Session method), 167
Op (class in mpi4py.MPI), 152	Pyar() (mpitpy.mi 1.session memou), 10/

<pre>py2f() (mpi4py.MPI.Status method), 170 py2f() (mpi4py.MPI.Win method), 185 Python Enhancement Proposals PEP 574, 51</pre>	release() (mpi4py.MPI.buffer method), 187 release() (mpi4py.util.sync.Condition method), 66 release() (mpi4py.util.sync.Mutex method), 65 release() (mpi4py.util.sync.Semaphore method), 68
Q	remote_group (mpi4py.MPI.Intercomm attribute), 144 remote_size (mpi4py.MPI.Intercomm attribute), 144
Query_thread() (in module mpi4py.MPI), 197	Remove_error_class() (in module mpi4py.MPI), 198
R	Remove_error_code() (in module mpi4py.MPI), 198 Remove_error_string() (in module mpi4py.MPI), 198
Raccumulate() (mpi4py.MPI.Win method), 182 Range_excl() (mpi4py.MPI.Group method), 137 Range_incl() (mpi4py.MPI.Group method), 137 rank (mpi4py.MPI.Comm attribute), 106 rank (mpi4py.MPI.Group attribute), 138 Read() (mpi4py.MPI.File method), 125 Read_all() (mpi4py.MPI.File method), 125 Read_all_end() (mpi4py.MPI.File method), 125 Read_all_end() (mpi4py.MPI.File method), 125 Read_al() (mpi4py.MPI.File method), 125 Read_al() (mpi4py.MPI.File method), 125	REPLACE (in module mpi4py.MPI), 241 Request (class in mpi4py.MPI), 157 Request (class in mpi4py.MPI), 157 REQUEST_NULL (in module mpi4py.MPI), 238 Revoke() (mpi4py.MPI.Comm method), 96 Rget() (mpi4py.MPI.Win method), 183 Rget_accumulate() (mpi4py.MPI.Win method), 183 ROOT (in module mpi4py.MPI), 205 Rput() (mpi4py.MPI.Win method), 183 Rsend() (mpi4py.MPI.Comm method), 96 Rsend_init() (mpi4py.MPI.Comm method), 96
Read_at_all() (mpi4py.MPI.File method), 126 Read_at_all_begin() (mpi4py.MPI.File method), 126	S
Read_at_all_end() (mpi4py.MPI.File method), 126 Read_ordered() (mpi4py.MPI.File method), 126 Read_ordered_begin() (mpi4py.MPI.File method),	S (in module mpi4py.typing), 40 Scan() (mpi4py.MPI.Intracomm method), 148
126 Read_ordered_end() (mpi4py.MPI.File method), 127 Read_shared() (mpi4py.MPI.File method), 127	<pre>scan() (mpi4py.MPI.Intracomm method), 149 Scan_init() (mpi4py.MPI.Intracomm method), 148 Scatter() (mpi4py.MPI.Comm method), 96</pre>
readonly (mpi4py.MPI.buffer attribute), 188	scatter() (mpi4py.MPI.Comm method), 104
ready() (mpi4py.util.pool.AsyncResult method), 62	scatter() (mpi4py.util.pkl5.Comm method), 56
REAL (in module mpi4py.MPI), 233	<pre>Scatter_init() (mpi4py.MPI.Comm method), 96</pre>
REAL16 (in module mpi4py.MPI), 235	Scatterv() (mpi4py.MPI.Comm method), 97
REAL2 (in module mpi4py.MPI), 234	Scatterv_init() (mpi4py.MPI.Comm method), 97
REAL4 (in module mpi4py.MPI), 235	Seek() (mpi4py.MPI.File method), 127
REAL8 (in module mpi4py.MPI), 235	SEEK_CUR (in module mpi4py.MPI), 224
Recv() (mpi4py.MPI.Comm method), 94	SEEK_END (in module mpi4py.MPI), 224
recv() (mpi4py.MPI.Comm method), 104	SEEK_SET (in module mpi4py.MPI), 224
Recv() (mpi4py.MPI.Message method), 151	Seek_shared() (mpi4py.MPI.File method), 127
recv() (mpi4py.MPI.Message method), 152	Semaphore (class in mpi4py.util.sync), 68
recv() (mpi4py.util.pkl5.Comm method), 54	Send() (mpi4py.MPI.Comm method), 97
recv() (mpi4py.util.pkl5.Message method), 52	send() (mpi4py.MPI.Comm method), 104
Recv_init() (mpi4py.MPI.Comm method), 94	send() (mpi4py.util.pkl5.Comm method), 53
recv_mprobe (mpi4py.mpi4py.rc attribute), 23	Send_init() (mpi4py.MPI.Comm method), 98
Reduce() (mpi4py.MPI.Comm method), 94	Sendrecv() (mpi4py.MPI.Comm method), 98
reduce() (mpi4py.MPI.Comm method), 104	sendrecv() (mpi4py.MPI.Comm method), 105
Reduce_init() (mpi4py.MPI.Comm method), 95	sendrecv() (mpi4py.util.pkl5.Comm method), 55
Reduce_local() (mpi4py.MPI.Op method), 153	Sendrecv_replace() (mpi4py.MPI.Comm method), 98
Reduce_scatter() (mpi4py.MPI.Comm method), 95	Sequential (class in mpi4py.util.sync), 62
Reduce_scatter_block() (mpi4py.MPI.Comm method), 95	Session (class in mpi4py.MPI), 164 SESSION_NULL (in module mpi4py.MPI), 243
Reduce_scatter_block_init() (mpi4py.MPI.Comm	Set() (mpi4py.MPI.Info method), 140
method), 95	Set_atomicity() (mpi4py.MPI.File method), 127
Reduce_scatter_init() (mpi4py.MPI.Comm	Set_attr() (mpi4py.MPI.Comm method), 99
method), 95	Set_attr() (mpi4py.MPI.Datatype method), 114
Register_datarep() (in module mpi4py.MPI), 197	Set_attr() (mpi4py.MPI.Win method), 183

Set_cancelled() (mpi4py.MPI.Status method), 169	Start() (mpi4py.MPI.Win method), 184
Set_elements() (mpi4py.MPI.Status method), 169	Startall() (mpi4py.MPI.Prequest class method), 157
Set_errhandler() (mpi4py.MPI.Comm method), 99	Status (class in mpi4py.MPI), 167
Set_errhandler() (mpi4py.MPI.File method), 127	Sub() (mpi4py.MPI.Cartcomm method), 74
Set_errhandler() (mpi4py.MPI.Session method), 166	<pre>submit() (mpi4py.futures.MPIPoolExecutor method), 42</pre>
Set_errhandler() (mpi4py.MPI.Win method), 183	SUBVERSION (in module mpi4py.MPI), 225
Set_error() (mpi4py.MPI.Status method), 169	SUCCESS (in module mpi4py.MPI), 207
Set_info() (mpi4py.MPI.Comm method), 99	<pre>successful() (mpi4py.util.pool.AsyncResult method),</pre>
Set_info() (mpi4py.MPI.File method), 128	62
Set_info() (mpi4py.MPI.Win method), 184	SUM (in module mpi4py.MPI), 239
Set_name() (mpi4py.MPI.Comm method), 99	SupportsBuffer (in module mpi4py.typing), 37
Set_name() (mpi4py.MPI.Datatype method), 114	SupportsCAI (in module mpi4py.typing), 37
Set_name() (mpi4py.MPI.Win method), 184	SupportsDLPack (in module mpi4py.typing), 37
Set_size() (mpi4py.MPI.File method), 128	Sync() (mpi4py.MPI.File method), 128
Set_source() (mpi4py.MPI.Status method), 169	Sync() (mpi4py.MPI.Win method), 184
Set_tag() (mpi4py.MPI.Status method), 170	T
Set_view() (mpi4py.MPI.File method), 128	Т
Shared_query() (mpi4py.MPI.Win method), 184	T (in module mpi4py.typing), 40
Shift() (mpi4py.MPI.Cartcomm method), 74	tag (mpi4py.MPI.Status attribute), 170
SHORT (in module mpi4py.MPI), 228	TAG_UB (in module mpi4py.MPI), 206
SHORT_INT (in module mpi4py.MPI), 232	TargetSpec (in module mpi4py.typing), 40
Shrink() (mpi4py.MPI.Comm method), 99	terminate() (mpi4py.util.pool.Pool method), 61
<pre>shutdown() (mpi4py.futures.MPIPoolExecutor method),</pre>	Test() (mpi4py.MPI.Request method), 160
43	test() (mpi4py.MPI.Request method), 162
SIGNED_CHAR (in module mpi4py.MPI), 228	Test() (mpi4py.MPI.Win method), 184
SIGNED_INT (in module mpi4py.MPI), 236	test() (mpi4py.util.pkl5.Request method), 52
SIGNED_LONG (in module mpi4py.MPI), 236	Testall() (mpi4py.MPI.Request class method), 160
SIGNED_LONG_LONG (in module mpi4py.MPI), 236	testall() (mpi4py.MPI.Request class method), 162
SIGNED_SHORT (in module mpi4py.MPI), 236	testall() (mpi4py.util.pkl5.Request class method), 52
SIMILAR (in module mpi4py.MPI), 220	Testany() (mpi4py.MPI.Request class method), 160
SINT16_T (in module mpi4py.MPI), 236	testany() (mpi4py.MPI.Request class method), 162
SINT32_T (in module mpi4py.MPI), 236	Testsome() (mpi4py.MPI.Request class method), 160
SINT64_T (in module mpi4py.MPI), 237	testsome() (mpi4py.MPI.Request class method), 163
SINT8_T (in module mpi4py.MPI), 236	THREAD_FUNNELED (in module mpi4py.MPI), 225
size (mpi4py.MPI.Comm attribute), 106	thread_level (<i>mpi4py.mpi4py.rc attribute</i>), 22
size (mpi4py.MPI.Datatype attribute), 116	THREAD_MULTIPLE (in module mpi4py.MPI), 225
size (mpi4py.MPI.File attribute), 131	THREAD_SERIALIZED (in module mpi4py.MPI), 225
size (mpi4py.MPI.Group attribute), 138	THREAD_SINGLE (in module mpi4py.MPI), 225
source (mpi4py.MPI.Status attribute), 170	ThreadPool (class in mpi4py.util.pool), 61
Spawn() (mpi4py.MPI.Intracomm method), 148	threads (mpi4py.mpi4py.rc attribute), 22
Spawn_multiple() (mpi4py.MPI.Intracomm method),	THRESHOLD (mpi4py.MPI.Pickle attribute), 156
149	to_numpy_dtype() (in module mpi4py.util.dtlib), 50
Split() (mpi4py.MPI.Comm method), 100	tobytes() (mpi4py.MPI.buffer method), 188
Split_type() (mpi4py.MPI.Comm method), 100	tocode() (mpi4py.MPI.Datatype method), 116
Ssend() (mpi4py.MPI.Comm method), 100	tomemory() (mpi4py.MPI.Win method), 185
ssend() (mpi4py.MPI.Comm method), 105	topo (mpi4py.MPI.Cartcomm attribute), 74
ssend() (mpi4py.util.pkl5.Comm method), 53	topo (mpi4py.MPI.Graphcomm attribute), 133
Ssend_init() (mpi4py.MPI.Comm method), 100	Topocomm (class in mpi4py.MPI), 170
<pre>starmap() (mpi4py.futures.MPIPoolExecutor method),</pre>	topology (mpi4py.MPI.Comm attribute), 106
42	toreadonly() (mpi4py.MPI.buffer method), 188
starmap() (mpi4py.util.pool.Pool method), 60	Translate_ranks() (mpi4py.MPI.Group method), 137
starmap_async() (mpi4py.util.pool.Pool method), 60	true_extent (mpi4py.MPI.Datatype attribute), 116
Start() (mpi4py.MPI.Grequest class method), 134	true_lb (mpi4py.MPI.Datatype attribute), 116
Start() (mpi4py.MPI.Prequest method), 157	true ub (mpi4py,MPI,Datatype attribute), 116

TWOINT (in module mpi4py.MPI), 232	<pre>waitsome() (mpi4py.MPI.Request class method), 163</pre>
typechar (mpi4py.MPI.Datatype attribute), 116	WCHAR (in module mpi4py.MPI), 228
TYPECLASS_COMPLEX (in module mpi4py.MPI), 216	WEIGHTS_EMPTY (in module mpi4py.MPI), 221
TYPECLASS_INTEGER (in module mpi4py.MPI), 216	Win (class in mpi4py.MPI), 175
TYPECLASS_REAL (in module mpi4py.MPI), 216	WIN_BASE (in module mpi4py.MPI), 207
TypeSpec (in module mpi4py.typing), 38	WIN_CREATE_FLAVOR (in module mpi4py.MPI), 207
typestr (mpi4py.MPI.Datatype attribute), 116	WIN_DISP_UNIT (in module mpi4py.MPI), 207
cypes to (pr.)pyllin ind uturype umrteure), 110	WIN_FLAVOR (in module mpi4py.MPI), 207
U	WIN_FLAVOR_ALLOCATE (in module mpi4py.MPI), 222
	WIN_FLAVOR_CREATE (in module mpi4py.MPI), 221
U (in module mpi4py.typing), 40	WIN_FLAVOR_DYNAMIC (in module mpi4py.MPI), 222
ub (mpi4py.MPI.Datatype attribute), 117	WIN_FLAVOR_SHARED (in module mpi4py.MPI), 222
UINT16_T (in module mpi4py.MPI), 230	WIN_MODEL (in module mpi4py.MPI), 207
UINT32_T (in module mpi4py.MPI), 230	WIN_NULL (in module mpi4py.MPI), 243
UINT64_T (in module mpi4py.MPI), 230	WIN_SEPARATE (in module mpi4py.MPI), 222
UINT8_T (in module mpi4py.MPI), 230	
UNDEFINED (in module mpi4py.MPI), 205	WIN_SIZE (in module mpi4py.MPI), 207
UNEQUAL (in module mpi4py.MPI), 220	WIN_UNIFIED (in module mpi4py.MPI), 222
Union() (mpi4py.MPI.Group class method), 137	Write() (mpi4py.MPI.File method), 128
UNIVERSE_SIZE (in module mpi4py.MPI), 206	Write_all() (mpi4py.MPI.File method), 128
Unlock() (mpi4py.MPI.Win method), 184	Write_all_begin() (mpi4py.MPI.File method), 129
Unlock_all() (mpi4py.MPI.Win method), 185	Write_all_end() (mpi4py.MPI.File method), 129
Unpack() (mpi4py.MPI.Datatype method), 114	Write_at() (mpi4py.MPI.File method), 129
<pre>Unpack_external() (mpi4py.MPI.Datatype method),</pre>	Write_at_all() (mpi4py.MPI.File method), 129
115	<pre>Write_at_all_begin() (mpi4py.MPI.File method)</pre>
Unpublish_name() (in module mpi4py.MPI), 198	129
UNSIGNED (in module mpi4py.MPI), 229	Write_at_all_end() (mpi4py.MPI.File method), 130
UNSIGNED_CHAR (in module mpi4py.MPI), 228	Write_ordered() (mpi4py.MPI.File method), 130
UNSIGNED_INT (in module mpi4py.MPI), 235	<pre>Write_ordered_begin() (mpi4py.MPI.File method)</pre>
UNSIGNED_LONG (in module mpi4py.MPI), 229	130
UNSIGNED_LONG_LONG (in module mpi4py.MPI), 229	Write_ordered_end() (mpi4py.MPI.File method), 130
UNSIGNED_SHORT (in module mpi4py.MPI), 229	<pre>Write_shared() (mpi4py.MPI.File method), 130</pre>
UNWEIGHTED (in module mpi4py.MPI), 220	Wtick() (in module mpi4py.MPI), 199
update() (mpi4py.MPI.Info method), 142	Wtime() (in module mpi4py.MPI), 199
	WTIME_IS_GLOBAL (in module mpi4py.MPI), 206
V	
V (in module mai/my typing) 10	
V (in module mpi4py.typing), 40	
values() (mpi4py.MPI.Info method), 142	
VERSION (in module mpi4py.MPI), 225	
W	
Wait() (mpi4py.MPI.Request method), 160	
wait() (mpi4py.MPI.Request method), 163	
Wait() (mpi4py.MPI.Win method), 185	
<pre>wait() (mpi4py.util.pkl5.Request method), 52</pre>	
<pre>wait() (mpi4py.util.pool.AsyncResult method), 62</pre>	
wait() (mpi4py.util.sync.Condition method), 67	
<pre>wait_for() (mpi4py.util.sync.Condition method), 67</pre>	
Waitall() (mpi4py.MPI.Request class method), 160	
waitall() (mpi4py.MPI.Request class method), 163	
waitall() (mpi4py.util.pkl5.Request class method), 52	
Waitany() (mpi4py.MPI.Request class method), 161	
waitany() (mpi4py.MPI.Request class method), 163	
Waitsome() (mpi4py.MPI.Request class method), 161	
· · · · · · · · · · · · · · · · · · ·	