HSplit interface

Inria TADaaM Team

18 septembre 2018

1 Communicator/group creation functions

1.1 MPIX_COMM_SPLIT_TYPE

MPI_COMM_SPLIT_TYPE is part of MPI 3.1 and is a communicator management routine defined in Chapter 6 of the standard (Groups, Contexts, Communicators and Caching), section 6.4 (Communicator Management).

MPI 3.1 defines a single value for split_type: MPI_COMM_TYPE_SHARED, that allows the function to split the original communicator into subcommunicators, which encompass MPI processes that can create a shared memory region with the other member processes.

Current extension/implementation:

— Introduces/relies on a new split_type value: MPI_COMM_TYPE_HW_DOMAIN Behaviour description: the input communicator is split into subcommunicators, each of which encompasses MPI processes that do share resources in the underlying physical topology (e.g. a network switch, a physical node, a L3 cache, a L2 cache, a core, etc.). In order to avoid the creation of redundant objects, the group of MPI processes supporting a new subcommunicator should be a strict subset of the group supporting the input (parent) communicator. More specifically, a call to MPI_COMM_COMPARE(comm,newcomm) should return MPI_UNEQUAL. In case of several possible levels, the lowest level in the hierarchy should be considered and intermediate levels

skipped. If no valid communicator can be created, the value MPI_COMM_NULL is returned, and this value can be used to assess if the last level of the hierarchy has been reached. In particular, it is possible for an implementation to not produce subcommunicators by directly returning the value MPI_COMM_NULL.

It is possible to capture the hierarchical nature of the underlying hardware by calling "recursively" MPI_COMM_SPLIT_TYPE with MPI_COMM_TYPE_HW_DOMAIN as split_type value on newly created subcommunicators. For instance :

The mapping and binding of MPI processes onto physical resources must be taken into account for subcommunicators creation. Indeed, the deepest hardware level corresponding to a subcommunicator should always correspond to the binding of the calling MPI process. For instance, if a process is bound to a certain cache level, no information below this cache level can be returned, as the MPI process can possibly use any of the caches below the level it is bound to. Any attempt to create a subcommunicator corresponding to a hardware level below the level the MPI process is bound to return MPI_COMM_NULL.

— Uses several keyvals:

- MPI_HW_DOMAIN_TYPE: If this key is defined (in the info parameter passed to the function), MPI_COMM_SPLIT_TYPE can then perform a split operation on a specific, desired hardware level, whose name is the value of the MPI_HW_DOMAIN_TYPE key. The levels names are not specified and are implementation-dependent. Such names can be queried by the MPIX_GET_HW_DOMAIN_INFO and MPIX_GET_HW_TOPOLOGY_INFO routines. For instance, an HWLOC-based implementation could use the HWLOC types names as domain types:
 - HWLOC_OBJ_MACHINE
 - HWLOC_OBJ_PACKAGE (former HWLOC_OBJ_SOCKET)
 - HWLOC_OBJ_CORE
 - HWLOC_OBJ_PU for hardware threads
 - HWLOC_OBJ_NUMANODE
 - HWLOC_OBJ_L1CACHE, ..., HWLOC_OBJ_L5CACHE (new terminology coming in future releases)
 - HWLOC_OBJ_GROUP for other hierarchy levels

Simpler names (e.g. CORE, SOCKET, Machine should be acceptable also. In this way, names are still not specified in the MPI standard but can be used nevertheless.

— MPI_HW_DOMAIN_NUM: This key is used internally and is never made available to tue

- user. It indicates the number of subcommunicators produced after a split operation at a specific level of the hardware hierarchy. This information can then be used to distribute data among the newly created subcommunicators. The value can be obtained by the user with a call to MPIX_GET_HW_DOMAIN_INFO.
- MPI_HW_DOMAIN_RANK: This key is used internally and is never made available to tue user. It indicates the "rank" of a subcommunicator produced after a split operation at a specific level of the hardware hierarchy. This information can then be used to distribute data among the newly created subcommunicators. The value can be obtained by the user with a call to MPIX_GET_HW_DOMAIN_INFO.

1.2 MPIX_GET_HW_DOMAIN_NEIGHBOURS

```
MPIX_GET_HW_DOMAIN_NEIGHBOURS(comm, hops, metric, newgroup)
```

```
IN comm communicator (handle)
```

IN hops number of hops in the topology, neighborhood extent (integer)

IN metric neighborhood type (integer)

OUT newgroup new group (handle)

C Prototype:

Current extension/implementation:

- Creates a *group* instead of a *communicator* since it is probably a local operation and the information should not propagate to other processes in the input communicator.
- Can possibly create neighborhood of various types, for instance memory/computing neighborhoods, network neighborhoods, etc.

2 Query functions

2.1 MPIX_GET_HW_DOMAIN_INFO

MPIX_GET_HW_DOMAIN_INFO(comm,num_subcomms,rank,type,info)

```
IN comm communicator (handle)
```

OUT num_subcomms number of subcommunicators (integer)

OUT rank domain "rank" (integer)

OUT type domain name (string)

```
IN info info object (handle)

C Prototype:
```

Current extension/implementation:

- Uses internally he MPI_HW_DOMAIN_TYPE, MPI_HW_DOMAIN_NUM, and MPI_HW_DOMAIN_RANK keys defined in MPI_COMM_SPLIT_TYPE, and returns their values to the user in a more usable form.
- Uses an info parameter that should not be in the final version of the interface, as this object should be attached to the input communicator with the MPI_Comm_set_info function in MPI_COMM_SPLIT_TYPE and retrieved with the MPI_Comm_get_info function in MPIX_GET_HW_DOMAIN_INFO.

2.2 MPIX_GET_HW_TOPOLOGY_INFO

```
MPIX_GET_HW_TOPOLOGY_INFO(numlevels,info)
```

OUT numlevels number of levels in the hardware hierarchy (integer)

OUT info info object (handle)

C Prototype:

```
int MPIX_Get_hw_topology_info(int *numlevels,MPI_Info info)
```

Current extension/implementation:

allows the calling MPI process to retrieve information about the underlying hardware topology. Two different types of information are available:

- the number of hardware levels in the hierarchy (the numlevels parameter)
- a set of keyvals (set in the info parameter). There are numlevels different keyvals, named MPI_HW_LEVELO, MPI_HW_LEVEL1, ... MPI_HW_LEVELnuml evels-1. These values are implementation-defined and can be the same as the ones used to define the MPI_HW_DOMAIN_TYPE key(s) in MPIX_COMM_SPLIT_TYPE.

Code example:

```
MPI_Info info;
char str[MPI_MAX_INFO_VAL-1] = {0};
char str2[MPI_MAX_INFO_VAL-1] = {0};
int numlevels;
int flag;
int idx;

MPI_Info_create(&info);
MPIX_Get_hw_topology_info(&numlevels,info);

fprintf(stdout,"========>> Number of levels: %i\n",numlevels);
```

```
for(idx = 0 ; idx < numlevels; idx++){</pre>
  sprintf(str,"MPI_HW_LEVEL%d",idx);
  MPI_Info_get(info,str,MPI_MAX_INFO_VAL-1,str2,&flag);
  if (flag)
   fprintf(stdout,"%s type is %s\n",str,str2);
}
2.3
     MPIX_GET_MIN_HW_DOMAIN
MPIX_GET_MIN_HW_DOMAIN(comm, size, ranks, type)
   IN
            comm communicator (handle)
   IN
            size size of ranks array (integer)
   IN
            ranks ranks (array of integer)
   OUT
            type hardware domain name (string)
   C Prototype:
int MPIX_Get_min_hw_domain(MPI_Comm comm, int size, int *ranks, char **type)
```

Current extension/implementation:

Returns the name of the *lowest* level in the hierarchy shared by all the MPI processes which ranks in the communicator comm are listed in the ranks array. If the calling process rank is not among the ranks listed in the array passed as an argument, the type returned should be "Unknown" or "Invalid".