Coherent Browser For Unity3D 2.6.2

Contents

1	Copy	yright	1						
2	Requ	Requirements							
	2.1	Software Requirements	3						
	2.2	Hardware Requirements	4						
3	Intro	duction	5						
	3.1	Brief overview of Coherent Browser	5						
	3.2	Differences between Desktop and Mobile version	5						
4	Insta	allation	7						
	4.1	Prerequisites	7						
	4.2	Package contents and structure	8						
	4.3	Usage of the package	8						
	4.4	Switching between build targets	10						
	4.5	Trial version registration	10						
5	Sam	ples	11						
	5.1	Hello, Coherent Browser	11						
	5.2	Facebook integration	13						
	5.3	Menu And HUD	14						
	5.4	Binding Demo	16						
	5.5	Archive resource	20						
	5.6	Mobile Input	21						
	5.7	Oculus	23						
	5.8	Mobile Surface	24						
	5.9	Live Game Views	24						
	5.10	IME Sample	24						
6	Prog	grammer's API	27						
	6.1	CoherentUISystem properties	27						
	6.2	CoherentUIView properties	27						
	6.3	CoherentUILiveGameView properties	29						

iv CONTENTS

7	Impo	ortant points	31
	7.1	Binding	31
	7.2	CoherentMethod attribute for .NET scripts	31
	7.3	Namespaces	33
	7.4	Subclassing CoherentUIView and UnityViewListener	33
	7.5	Coherent Browser system lifetime	34
	7.6	Customizing initialization of the Coherent Browser System	34
	7.7	Update cycle	35
	7.8	Input forwarding - Desktop	35
	7.9	Input forwarding - Mobile	35
	7.10	Mobile Preview	36
	7.11	Custom file handler	36
	7.12	UI Resources	37
	7.13	Click-to-focus Views - Desktop only	37
	7.14	View Filters - Desktop only	39
	7.15	Hit testing - Desktop only	39
	7.16	Mobile Surface Views	40
	7.17	Logging	40
	7.18	Live Game Views	40
	7.19	Font Rendering	41
8	Unity	y Script Binding	43
	8.1	Sample Unity Script Binding	43
9	Cohe	erent Browser Menu	45
	9.1	Binding actions to events	45
	9.2	Setting up the HTML	47
	9.3	JavaScript API	48
10	Nam	espace Index	49
	10.1	Namespace List	49
11	Hiera	archical Index	51
	11.1	Class Hierarchy	51
12	Clas	s Index	53
	12.1	Class List	53
13		espace Documentation	57
		Package Coherent	57
	13.2	Package Coherent.UI	57
		13.2.1 Enumeration Type Documentation	60

CONTENTS

			13.2.1.1 CertificateStatus	60
			13.2.1.2 ContextErrorType	60
			13.2.1.3 CursorTypes	60
			13.2.1.4 Direct3DInterfaceType	60
			13.2.1.5 DownloadErrorType	60
			13.2.1.6 FileSelectionMode	61
			13.2.1.7 JavaScriptMessageType	61
			13.2.1.8 MediaStreamType	61
			13.2.1.9 RenderingDeviceType	61
			13.2.1.10 ScriptCallErrorType	61
			13.2.1.11 SubscriptionErrorType	61
			13.2.1.12 TextInputControlType	61
			13.2.1.13 UserAgentType	61
			13.2.1.14 ViewErrorType	61
			13.2.1.15 ViewType	62
	13.3	Packag	e Coherent.UI.Binding	62
		13.3.1	Enumeration Type Documentation	63
			13.3.1.1 PropertyBindingFlags	63
			13.3.1.2 ValueType	63
	13.4	engine	Namespace Reference	63
		13.4.1	Detailed Description	64
		13.4.2	Function Documentation	64
			13.4.2.1 call	64
			13.4.2.2 createDeferred	64
			13.4.2.3 off	64
			13.4.2.4 on	65
			13.4.2.5 trigger	65
14	Class	s Docui	nentation	67
			nt.UI.Binding.BoundObject Struct Reference	67
			Detailed Description	67
				67
			14.1.2.1 BindMethods	67
	14.2	Cohere	nt.UI.BrowserView Class Reference	67
			Detailed Description	68
			Member Function Documentation	68
			14.2.2.1 GetHistory	68
			14.2.2.2 GetViewType	68
			14.2.2.3 GoBack	68
			14.2.2.4 GoForward	68

vi CONTENTS

14.3	Cohere	nt.UI.BrowserViewListener Class Reference	86
	14.3.1	Detailed Description	71
	14.3.2	Member Function Documentation	71
		14.3.2.1 CreateSurface	71
		14.3.2.2 DestroySurface	72
		14.3.2.3 OnAudioStreamClose	72
		14.3.2.4 OnAudioStreamCreated	72
		14.3.2.5 OnAudioStreamPause	72
		14.3.2.6 OnAudioStreamPlay	73
		14.3.2.7 OnBindingsReleased	73
		14.3.2.8 OnCallback	73
		14.3.2.9 OnCanCreateChildWindow	73
		14.3.2.10 OnCaretRectChanged	74
		14.3.2.11 OnCertificateError	75
		14.3.2.12 OnClientCertificateRequested	75
		14.3.2.13 OnCursorChanged	75
		14.3.2.14 OnDraw	75
		14.3.2.15 OnError	76
		14.3.2.16 OnFailLoad	76
		14.3.2.17 OnFileSelectRequest	76
		14.3.2.18 OnFinishLoad	76
		14.3.2.19 OnGetAuthCredentials	77
		14.3.2.20 OnIMEShouldCancelComposition	77
		14.3.2.21 OnJavaScriptMessage	77
		14.3.2.22 OnNavigateTo	77
		14.3.2.23 OnPrintToPDFReady	77
		14.3.2.24 OnReadyForBindings	78
		14.3.2.25 OnRequestMediaStream	78
		14.3.2.26 OnScriptMessage	78
		14.3.2.27 OnStartLoading	78
		14.3.2.28 OnStopLoading	78
		14.3.2.29 OnTextInputTypeChanged	79
		14.3.2.30 OnURLRequest	30
		14.3.2.31 OnViewCreated	30
		14.3.2.32 Release	30
	14.3.3	Event Documentation	30
		14.3.3.1 AudioStreamClose	30
		14.3.3.2 AudioStreamCreated	30
		14.3.3.3 AudioStreamPause	30
		14.3.3.4 AudioStreamPlay	30

CONTENTS vii

		14.3.3.5 BindingsReleased	81
		14.3.3.6 Callback	81
		14.3.3.7 CaretRectChanged	81
		14.3.3.8 CertificateError	81
		14.3.3.9 ClientCertificateRequested	81
		14.3.3.10 CursorChanged	81
		14.3.3.11 Draw	81
		14.3.3.12 Error	81
		14.3.3.13 FailLoad	81
		14.3.3.14 FileSelectRequest	81
		14.3.3.15 FinishLoad	81
		14.3.3.16 GetAuthCredentials	82
		14.3.3.17 IMEShouldCancelComposition	82
		14.3.3.18 JavaScriptMessage	82
		14.3.3.19 NavigateTo	82
		14.3.3.20 PrintToPDFReady	82
		14.3.3.21 ReadyForBindings	82
		14.3.3.22 RequestMediaStream	82
		14.3.3.23 ScriptMessage	82
		14.3.3.24 StartLoading	82
		14.3.3.25 StopLoading	82
		14.3.3.26 TextInputTypeChanged	82
		14.3.3.27 URLRequest	82
		14.3.3.28 ViewCreated	83
14.4	Cohere	ent.UI.BrowserViewListenerBase Class Reference	83
	14.4.1	Detailed Description	83
14.5	Cohere	ent.UI.Button Class Reference	83
	14.5.1	Detailed Description	83
	14.5.2	Member Function Documentation	84
		14.5.2.1 Initialize	84
	14.5.3	Member Data Documentation	85
		14.5.3.1 Click	85
		14.5.3.2 Disabled	85
		14.5.3.3 Label	85
14.6	Cohere	ent.UI.ButtonHandler Class Reference	85
	14.6.1	Detailed Description	85
	14.6.2	Member Function Documentation	86
		14.6.2.1 Initialize	86
		14.6.2.2 Invoke	87
		14.6.2.3 Invoker	87

viii CONTENTS

14.6.3	Member	Data Documentation	87
	14.6.3.1	Handler	87
	14.6.3.2	IsMessage	87
	14.6.3.3	Method	87
	14.6.3.4	Target	87
14.7 Cohere	ent.UI.Bind	ding.CallbackArguments Class Reference	87
14.7.1	Detailed	Description	87
14.7.2	Member	Data Documentation	87
	14.7.2.1	Arguments	87
14.8 Cohere	ent.UI.Cert	tificatePrincipal Class Reference	88
14.8.1	Detailed	Description	88
14.8.2	Property	Documentation	88
	14.8.2.1	CommonName	88
	14.8.2.2	CountryName	88
	14.8.2.3	DomainComponents	88
	14.8.2.4	LocalityName	88
	14.8.2.5	OrganizationNames	88
	14.8.2.6	OrganizationUnitNames	89
	14.8.2.7	StateOrProvinceName	89
	14.8.2.8	StreetAddresses	89
14.9 Cohere	ent.UI.Chile	dViewInfo Class Reference	89
14.9.1	Detailed	Description	89
14.9.2	Property	Documentation	89
	14.9.2.1	Listener	89
	14.9.2.2	NewViewInfo	89
14.10Cohere	ent.UI.Clie	ntCertificateResponse Class Reference	89
14.10.	1 Detailed	Description	90
14.10.	2 Member	Function Documentation	90
	14.10.2.1	1 CancelRequest	90
	14.10.2.2	2 ContinueRequest	90
14.11Cohere	ent.UI.Bind	ding.CoherentProperty Class Reference	90
14.11.	1 Detailed	Description	90
14.11.	2 Construc	ctor & Destructor Documentation	90
	14.11.2.1	1 CoherentProperty	90
	14.11.2.2	2 CoherentProperty	91
14.12Cohere	ent.UI.Bind	ding.CoherentType Class Reference	91
		Description	
		GameView Class Reference	
		Description	
14.14Cohere	entUISyste	em Class Reference	91

CONTENTS

14.14.1 Detailed Description	92
14.14.2 Member Function Documentation	92
14.14.2.1 IsReady	92
14.14.3 Member Data Documentation	92
14.14.3.1 FileHandlerFactoryFunc	92
14.14.3.2 m_MainCamera	93
14.14.3.3 SystemListenerFactoryFunc	93
14.14.4 Property Documentation	93
14.14.4.1 DiskCacheSize	93
14.14.4.2 HasFocusedView	93
14.14.4.3 IsUpdating	93
14.14.4.4 MemoryCacheSize	93
14.14.4.5 UISystem	93
14.14.4.6 UseURLCache	93
14.14.5 Event Documentation	94
14.14.5.1 OnViewFocused	94
14.15CoherentUIView Class Reference	94
14.15.1 Detailed Description	96
14.15.2 Member Function Documentation	96
14.15.2.1 DestroyView	96
14.15.2.2 GetCamDimensions	96
14.15.2.3 Reload	96
14.15.2.4 Resize	96
14.15.2.5 SetMousePosition	96
14.15.2.6 ViewDestroyedHandler	97
14.15.3 Property Documentation	97
14.15.3.1 ClickThroughAlphaThreshold	97
14.15.3.2 ClickToFocus	97
14.15.3.3 CorrectGamma	97
14.15.3.4 DisplayVirtualKeyboard	97
14.15.3.5 DrawAfterPostEffects	97
14.15.3.6 EnableBindingAttribute	97
14.15.3.7 EnableIME	98
14.15.3.8 EnableWebGLSupport	98
14.15.3.9 FlipY	98
14.15.3.10ForceSoftwareRendering	98
14.15.3.11Height	98
14.15.3.12gnoreDisplayDensity	98
14.15.3.13nitialScript	98
14.15.3.14InputState	98

X CONTENTS

14.15.3.15InterceptAllEvents	99
14.15.3.16sIndependentOfZBuffer	99
14.15.3.17lsSurfaceView	99
14.15.3.18sTransparent	99
14.15.3.19Listener	99
14.15.3.20OnReadyForBindings	99
14.15.3.21OnViewCreated	99
14.15.3.22Page	99
14.15.3.23ReceivesInput	100
14.15.3.24ScaleToFit	100
14.15.3.25ShowJavaScriptDialogs	100
14.15.3.26SupportClickThrough	100
14.15.3.27UseCameraDimensions	100
14.15.3.28View	100
14.15.3.29Width	100
14.15.3.30XPos	100
14.15.3.31YPos	101
14.15.4 Event Documentation	101
14.15.4.1 OnViewDestroyed	101
14.16Coherent.UI.ContextError Class Reference	101
14.16.1 Detailed Description	101
14.16.2 Property Documentation	101
14.16.2.1 Error	101
14.16.2.2 ErrorCode	101
14.17Coherent.UI.ContextListener Class Reference	101
14.17.1 Detailed Description	102
14.17.2 Member Function Documentation	102
14.17.2.1 ContextReady	102
14.17.2.2 OnCookiesSaved	102
14.17.2.3 OnDownloadComplete	102
14.17.2.4 OnDownloadFailed	102
14.17.2.5 OnDownloadStarted	102
14.17.2.6 OnError	102
14.17.2.7 OnSubscriptionCheckDone	103
14.18Coherent.UI.ContextSettings Class Reference	103
14.18.1 Detailed Description	103
14.18.2 Property Documentation	103
14.18.2.1 CachePath	103
14.18.2.2 CookiesResource	103
14.18.2.3 CustomUserAgentString	103

CONTENTS xi

14.18.2.4 HTML5LocalStoragePath	103
14.19Coherent.UI.ContextSettingsBase Class Reference	104
14.19.1 Detailed Description	104
14.19.2 Property Documentation	104
14.19.2.1 AdditionalHostOptions	104
14.19.2.2 AllowCookies	105
14.19.2.3 DebuggerPort	105
14.19.2.4 DisableWebSecurity	105
14.19.2.5 EnableClientAudioPlayback	105
14.19.2.6 EnableProxy	105
14.19.2.7 ForceDisablePluginFullscreen	105
14.19.2.8 SubscriptionEmail	105
14.19.2.9 SubscriptionKey	105
14.19.2.10UserAgent	105
14.20Coherent.UI.Download Class Reference	105
14.20.1 Detailed Description	106
14.20.2 Member Function Documentation	106
14.20.2.1 Cancel	106
14.20.2.2 Destroy	106
14.20.2.3 GetDownloadedBytesSoFar	107
14.20.2.4 GetFilename	107
14.20.2.5 Getld	107
14.20.2.6 GetReferrer	107
14.20.2.7 GetTotalBytes	107
14.20.2.8 GetURL	107
14.20.2.9 HasFailed	108
14.20.2.10sCancelled	108
14.20.2.11lsComplete	108
14.21 Coherent.UI. EventModifiersState Class Reference	108
14.21.1 Detailed Description	108
14.22Coherent.UI.EventMouseModifiersState Class Reference	108
14.22.1 Detailed Description	108
14.23Coherent.UI.FactorySettings Class Reference	108
14.23.1 Detailed Description	109
14.23.2 Property Documentation	109
14.23.2.1 AppGroupName	109
14.23.2.2 HostDirectory	109
14.23.2.3 MinidumpFolder	109
14.24Coherent.UI.FactorySettingsBase Class Reference	109
14.24.1 Detailed Description	110

xii CONTENTS

14.24.2 Property Documentation	110
14.24.2.1 EnableSupportForProprietaryCodecs	110
14.24.2.2 WriteMinidumps	110
14.25Coherent.UI.FileHandler Class Reference	110
14.25.1 Detailed Description	110
14.25.2 Member Function Documentation	110
14.25.2.1 ReadFile	110
14.25.2.2 WriteFile	111
14.26Coherent.UI.FileSelectionParams Class Reference	111
14.26.1 Detailed Description	111
14.26.2 Property Documentation	111
14.26.2.1 AcceptedMIMETypes	111
14.26.2.2 AcceptedMIMETypesCount	111
14.26.2.3 DefaultFileName	112
14.26.2.4 DialogTitle	112
14.26.2.5 Mode	112
14.27Coherent.UI.FileSelectRequest Class Reference	112
14.27.1 Detailed Description	112
14.27.2 Member Function Documentation	112
14.27.2.1 Add	112
14.27.2.2 Finish	112
14.27.2.3 GetFileSelectionParams	113
14.28Coherent.UI.HTTPHeader Class Reference	113
14.28.1 Detailed Description	114
14.28.2 Member Enumeration Documentation	114
14.28.2.1 FieldType	114
14.28.3 Member Function Documentation	114
14.28.3.1 GetHeaderField	114
14.28.4 Property Documentation	115
14.28.4.1 Content	115
14.28.4.2 Field	115
14.29 Coherent.UI.ILogHandler Class Reference	115
14.29.1 Detailed Description	115
14.29.2 Member Function Documentation	115
14.29.2.1 Assert	115
14.29.2.2 WriteLog	115
14.30 Coherent.UI.ImageData Class Reference	116
14.30.1 Detailed Description	116
14.30.2 Member Function Documentation	116
14.30.2.1 Destroy	116

CONTENTS xiii

14.30.2.2 Update	116
14.31Coherent.UI.Binding.InvalidValueCastException Class Reference	116
14.31.1 Detailed Description	116
14.32Coherent.UI.KeyEventData Class Reference	117
14.32.1 Detailed Description	117
14.32.2 Property Documentation	117
14.32.2.1 IsAutoRepeat	117
14.32.2.2 IsNumPad	117
14.32.2.3 IsSystemKey	117
14.32.2.4 KeyCode	117
14.32.2.5 Modifiers	117
14.32.2.6 Type	118
14.33Coherent.UI.MediaStreamDevice Class Reference	118
14.33.1 Detailed Description	118
14.33.2 Property Documentation	118
14.33.2.1 DeviceId	118
14.33.2.2 Name	118
14.33.2.3 Type	118
14.34Coherent.UI.MediaStreamRequest Class Reference	118
14.34.1 Detailed Description	119
14.34.2 Member Function Documentation	119
14.34.2.1 Respond	119
14.34.3 Property Documentation	119
14.34.3.1 Devices	119
14.35MobileSurfaceView Class Reference	119
14.35.1 Detailed Description	119
14.35.2 Member Function Documentation	120
14.35.2.1 UpdateView	120
14.36Coherent.UI.MouseEventData Class Reference	120
14.36.1 Detailed Description	120
14.36.2 Property Documentation	120
14.36.2.1 Button	120
14.36.2.2 Modifiers	120
14.36.2.3 MouseModifiers	120
14.36.2.4 Type	121
14.36.2.5 WheelX	121
14.36.2.6 WheelY	121
14.36.2.7 X	121
14.36.2.8 Y	121
14.37Coherent.UI.ResourceData Class Reference	121

XIV

14.37.1 Detailed Description	121
14.37.2 Member Function Documentation	121
14.37.2.1 GetBuffer	121
14.37.2.2 GetSize	122
14.37.2.3 SignalFailure	122
14.37.2.4 SignalSuccess	122
14.38Coherent.UI.ResourceResponse Class Reference	122
14.38.1 Detailed Description	122
14.38.2 Member Function Documentation	122
14.38.2.1 GetBuffer	122
14.38.2.2 SetResponseHeader	123
14.38.2.3 SetStatus	123
14.38.2.4 SignalFailure	123
14.38.2.5 SignalSuccess	123
14.39Coherent.UI.SubscriptionError Class Reference	123
14.39.1 Detailed Description	123
14.39.2 Property Documentation	124
14.39.2.1 Error	124
14.39.2.2 ErrorCode	124
14.40Coherent.UI.SurfaceResponse Class Reference	124
14.40.1 Detailed Description	124
14.40.2 Member Function Documentation	124
14.40.2.1 Signal	124
14.41Coherent.UI.TouchEventData Class Reference	124
14.41.1 Detailed Description	125
14.41.2 Property Documentation	125
14.41.2.1 HasRadiusInformation	125
14.41.2.2 ld	125
14.41.2.3 RadiusX	125
14.41.2.4 RadiusY	125
14.41.2.5 Type	125
14.41.2.6 X	125
14.41.2.7 Y	125
14.42Coherent.UI.Binding.UnsupportedPrimitiveTypeException Class Reference	125
14.42.1 Detailed Description	126
14.43Coherent.UI.URLRequest Class Reference	126
	126
14.43.2 Member Function Documentation	126
14.43.2.1 AppendExtraHeaderValue	
	126

CONTENTS xv

14.43.2.3 RemoveExtraHeader	127
14.43.2.4 SetExtraHeader	127
14.43.2.5 SetExtraHeaders	127
14.43.2.6 SetMethod	127
14.43.2.7 SetReferrer	127
14.43.2.8 SetURL	127
14.44Coherent.UI.URLRequestBase Class Reference	128
14.44.1 Detailed Description	128
14.44.2 Member Function Documentation	128
14.44.2.1 GetExtraHeader	128
14.44.2.2 GetExtraHeaderIndex	128
14.44.2.3 GetExtraHeaders	129
14.44.2.4 GetMethod	129
14.44.2.5 GetReferrer	129
14.44.2.6 GetURL	129
14.44.2.7 HasExtraHeader	129
14.45Coherent.UI.Binding.Value Class Reference	130
14.45.1 Detailed Description	131
14.45.2 Constructor & Destructor Documentation	131
14.45.2.1 Value	131
14.45.2.2 Value	131
14.45.2.3 Value	131
14.45.2.4 Value	131
14.45.2.5 Value	132
14.45.2.6 Value	132
14.45.2.7 Value	132
14.45.2.8 Value	132
14.45.2.9 Value	132
14.45.2.10Value	132
14.45.2.11Value	133
14.45.2.12Value	134
14.45.2.13Value	134
14.45.3 Member Function Documentation	134
14.45.3.1 Equals	134
14.45.3.2 GetHashCode	134
14.45.3.3 operator bool	134
14.45.3.4 operator byte	134
14.45.3.5 operator char	135
14.45.3.6 operator Dictionary< string, Value >	135
14.45.3.7 operator double	135

xvi CONTENTS

14.45.3.8 operator float	135
14.45.3.9 operator int	136
14.45.3.10operator sbyte	137
14.45.3.11operator string	137
14.45.3.12operator uint	137
14.45.3.13operator Value[]	137
14.45.3.14operator!=	138
14.45.3.15operator==	139
14.45.4 Member Data Documentation	139
14.45.4.1 Type	139
14.46Coherent.UI.Binding.ValueObject Class Reference	139
14.46.1 Detailed Description	139
14.47Coherent.UI.View Class Reference	139
14.47.1 Detailed Description	142
14.47.2 Member Function Documentation	142
14.47.2.1 AuthCredentialsResponse	142
14.47.2.2 BindCall	143
14.47.2.3 CreateImageData	143
14.47.2.4 Destroy	143
14.47.2.5 DownloadUrl	143
14.47.2.6 DrawSurface	143
14.47.2.7 ExecuteScript	143
14.47.2.8 FetchMouseOnUIQuery	144
14.47.2.9 FetchSurface	144
14.47.2.10GetAudioData	144
14.47.2.11GetClickThroughAlphaThreshold	144
14.47.2.12GetContext	144
14.47.2.13GetCurentViewPath	145
14.47.2.14GetHeight	145
14.47.2.15GetLastFailedPath	145
14.47.2.16GetLastLoadedPath	145
14.47.2.17GetLastRequestedPath	145
14.47.2.18GetTargetFramerate	145
14.47.2.19GetViewType	145
14.47.2.20GetWidth	146
14.47.2.21HasMouseQueryFinished	146
14.47.2.22MEActivate	146
14.47.2.23MECancelComposition	146
14.47.2.24MEConfirmComposition	146
14.47.2.25MEIsActive	146

CONTENTS xvii

14.47.2.26MESetComposition	 . 146
14.47.2.27InterceptURLRequests	 . 147
14.47.2.28sMouseOnView	 . 147
14.47.2.29sOnDemand	 . 147
14.47.2.30ssueMouseOnUIQuery	 . 147
14.47.2.31lsTransparent	 . 148
14.47.2.32KeyEvent	 . 148
14.47.2.33KillFocus	 . 148
14.47.2.34Load	 . 148
14.47.2.35MouseActivate	 . 148
14.47.2.36MouseEvent	 . 148
14.47.2.37PeekFrameReady	 . 148
14.47.2.38Print	 . 149
14.47.2.39Print	 . 149
14.47.2.40Redraw	 . 149
14.47.2.41RegisterForEvent	 . 149
14.47.2.42Reload	 . 149
14.47.2.43ReplyToJavaScriptMessage	 . 149
14.47.2.44RequestFrame	 . 150
14.47.2.45RequestFrame	 . 150
14.47.2.46Resize	 . 150
14.47.2.47SetClickThroughAlphaThreshold	 . 150
14.47.2.48SetFocus	 . 150
14.47.2.49SetMasterVolume	 . 150
14.47.2.50SetScriptError	 . 151
14.47.2.51SetTargetFramerate	 . 151
14.47.2.52SetZoomLevel	 . 151
14.47.2.53SupportsClickThrough	 . 151
14.47.2.54TouchEvent	 . 151
14.47.2.55TriggerEvent	 . 151
14.47.2.56UnbindCall	 . 152
14.47.2.57UnbindObject	 . 153
14.47.2.58UnregisterFromEvent	 . 153
14.47.2.59UsesSharedMemory	 . 153
14.48Coherent.UI.ViewContext Class Reference	 . 153
14.48.1 Detailed Description	 . 154
14.48.2 Member Function Documentation	 . 154
14.48.2.1 AddCrossOriginWhitelistEntry	 . 154
14.48.2.2 ClearCrossOriginWhitelist	
14.48.2.3 CreateView	 . 154

xviii CONTENTS

14.48.2.4 CreateView	154
14.48.2.5 FetchSurfaces	155
14.48.2.6 RemoveCrossOriginWhitelistEntry	155
14.48.2.7 SaveCookies	155
14.48.2.8 Uninitialize	155
14.48.2.9 Update	155
14.49Coherent.UI.ViewError Class Reference	155
14.49.1 Detailed Description	156
14.49.2 Property Documentation	156
14.49.2.1 Error	156
14.49.2.2 ErrorCode	156
14.50 Coherent.UI. ViewInfo Class Reference	156
14.50.1 Detailed Description	157
14.50.2 Property Documentation	157
14.50.2.1 ClickThroughAlphaThreshold	157
14.50.2.2 ControlTimeOnDemand	157
14.50.2.3 DisplayVirtualKeyboard	157
14.50.2.4 ForceSoftwareRendering	157
14.50.2.5 Height	157
14.50.2.6 IsOnDemand	157
14.50.2.7 IsTransparent	157
14.50.2.8 SupportClickThrough	157
14.50.2.9 TargetFrameRate	157
14.50.2.1@sesSharedMemory	158
14.50.2.11Width	158
14.51 Coherent.UI. ViewListener Class Reference	158
14.51.1 Detailed Description	161
14.51.2 Member Function Documentation	161
14.51.2.1 CreateSurface	161
14.51.2.2 DestroySurface	161
14.51.2.3 OnAudioStreamClose	162
14.51.2.4 OnAudioStreamCreated	163
14.51.2.5 OnAudioStreamPause	163
14.51.2.6 OnAudioStreamPlay	163
14.51.2.7 OnBindingsReleased	163
14.51.2.8 OnCallback	163
14.51.2.9 OnCanCreateChildWindow	164
14.51.2.1@nCaretRectChanged	164
14.51.2.11OnCertificateError	164
14.51.2.12OnClientCertificateRequested	164

CONTENTS xix

	14.51.2.13OnCursorChanged	166
	14.51.2.14OnDraw	166
	14.51.2.15OnError	166
	14.51.2.16OnFailLoad	166
	14.51.2.17OnFileSelectRequest	167
	14.51.2.18OnFinishLoad	168
	14.51.2.19OnGetAuthCredentials	168
	14.51.2.2@nIMEShouldCancelComposition	168
	14.51.2.21OnJavaScriptMessage	168
	14.51.2.22OnNavigateTo	169
	14.51.2.23OnPrintToPDFReady	170
	14.51.2.24OnReadyForBindings	170
	14.51.2.25OnRequestMediaStream	170
	14.51.2.2@nScriptMessage	170
	14.51.2.27OnStartLoading	170
	14.51.2.28OnStopLoading	171
	14.51.2.29OnTextInputTypeChanged	171
	14.51.2.3@nURLRequest	171
	14.51.2.31OnViewCreated	171
	14.51.2.32Release	171
14.51.3	B Event Documentation	171
	14.51.3.1 AudioStreamClose	171
	14.51.3.2 AudioStreamCreated	172
	14.51.3.3 AudioStreamPause	172
	14.51.3.4 AudioStreamPlay	172
	14.51.3.5 BindingsReleased	172
	14.51.3.6 Callback	172
	14.51.3.7 CaretRectChanged	172
	14.51.3.8 CertificateError	172
	14.51.3.9 ClientCertificateRequested	172
	14.51.3.1©ursorChanged	172
	14.51.3.11Draw	172
	14.51.3.1Ærror	172
	14.51.3.13FailLoad	173
	14.51.3.14FileSelectRequest	173
	14.51.3.15FinishLoad	173
	14.51.3.16GetAuthCredentials	173
	14.51.3.17IMEShouldCancelComposition	173
	14.51.3.1&JavaScriptMessage	173
	14.51.3.19NavigateTo	173

CONTENTS

Index					175
14.52.2.1 WessageL	evei		 	 	1/4
14.52.2 Member Enumeration					
14.52.2 Member Enumeration					
14.52.1 Detailed Description					
14.52Coherent.UI.ViewListenerBa	se Class Referenc	e	 	 	174
14.51.3.28ViewCreat	ed		 	 	174
14.51.3.27URLReque	est		 	 	174
14.51.3.26TextInputT	peChanged		 	 	174
14.51.3.25StopLoadi	ng		 	 	174
14.51.3.24StartLoadi	ng		 	 	173
14.51.3.23ScriptMes	sage		 	 	173
14.51.3.22RequestM	ediaStream		 	 	173
14.51.3.21ReadyFort	Bindings		 	 	173
14.51.3.20PrintToPD	FReady		 	 	173

Chapter 1

Copyright

Copyright © 2012-2014 Coherent Labs Limited and/or its licensors. All rights reserved in all media.

The coded instructions, statements, computer programs, and/or related material (collectively the "Data") in these files contain confidential and unpublished information proprietary Coherent Labs and/or its licensors, which is protected by United States of America federal copyright law and by international treaties.

This software or source code is supplied under the terms of a license agreement and nondisclosure agreement with Coherent Labs Limited and may not be copied, disclosed, or exploited except in accordance with the terms of that agreement. The Data may not be disclosed or distributed to third parties, in whole or in part, without the prior written consent of Coherent Labs Limited.

COHERENT LABS MAKES NO REPRESENTATION ABOUT THE SUITABILITY OF THIS SOURCE CODE FOR ANY PURPOSE. THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, NONINFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER, ITS AFFILIATES, PARENT COMPANIES, LICENSORS, SUPPLIERS, OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OR PERFORMANCE OF THIS SOFTWARE OR SOURCE CODE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

2 Copyright

Chapter 2

Requirements

To use Coherent Browser SDK in your project, please make sure that the following minimum system requirements are met by your development environment and are compatible with your project requirements for the end-users.

2.1 Software Requirements

Windows

- Windows XP (required Service Pack 3)
- · Windows Vista (required Service Pack 2)
- Windows 7 (required Service Pack 1)
- Windows 8
- · Windows 8.1

Visual Studio 2010, 2012, 2013 is required to build Coherent Browser SDK. DirectX SDK is required for older versions of Visual Studio to build some of the samples.

Note

- All Windows systems must have the latest Service Pack provided by Microsoft installed.
- DirectX shared textures require Windows Vista or later.
- Latest drivers provided by the hardware vendor are required.
- For Windows 8 and 8.1 only desktop mode applications are supported
- · WinRT is not supported
- The Coherent Browser Samples require the Microsoft DirectX End-User Runtime (June 2010) to work compile (or at least d3dx9_43.dll and D3DCompiler_43.dll should be added to the output folder).

Linux

Generally any distribution similar to Ubuntu 12.04 LTS.

- · glibc 2.14 or later
- · libstdc++6 or later
- GTK 2.24.10 or later
- · GCC 4.6.3 or later

4 Requirements

Note

Only the latest video card drivers are supported. OpenGL 3.0 support is required.

Mac OS X

- 10.7 or later
- · XCode 4.4 or later

Note

Limited support for Mac OS 10.6.8 is available, but extensive testing should be performed, and some features might not work.

2.2 Hardware Requirements

- · Intel or AMD CPU architectures are supported (no ARM support)
- · Dual-core CPU is recommended
- 512 MB RAM
- · 350 MB HDD space for development
- 40-80 MB HDD space for runtime libraries

Video adapter:

- · Support for shader model 3.0 is required
- · DirectX 9.0c or later support
- · OpenGL 3.0* or later support
- · Full non-power-of-two textures support
- · Dedicated video card recommended
- Certain features of Coherent Browser may be available on earlier versions of OpenGL but we don't test that configuration and results may be unpredictable.
- On configurations with multiple video cards SLI, Optimus, etc., the faster card should be enabled, and your users should make sure that the same adapter runs both your application and the Coherent Browser rendering processes.

Chapter 3

Introduction

This guide describes the features of the *Coherent Browser* integration in Unity3D. A basic understanding of the Unity3D engine, as well as HTML/JavaScript is assumed. Having basic knowledge of the C++ API and design of *Coherent Browser* may be advantageous. To familiarize yourself with *Coherent Browser*, please read the main documentation file or visit Coherent Browser website.

3.1 Brief overview of Coherent Browser

Coherent Browser is a modern user interface middleware solution that allows you to integrate HTML pages built with CSS and JavaScript in your game. The communication between your game and the HTML engine is done through the UI System component. Each HTML page is called a View. The View component allows you to perform operations on the page, such as resizing, navigating to a different URL, sending input events, executing custom JavaScript code and so on. You can create a view through the CreateView method of the UI System component. It requires you to supply some initialization parameters, such as width, height, initial URL, etc. It also requires an instance of a View Listener. Coherent Browser is highly asynchronous by design, meaning that when you change the URL of a View, for example, the function will return immediately and you will receive a notification when the URL has actually changed. The ViewListener is the class that receives such notifications for a specific view - when the URL was changed, the page you're trying to open requires authentication details, etc.

3.2 Differences between Desktop and Mobile version

Coherent Browser can be divided conceptually in two libraries - Coherent Browser Desktop (for Windows & MacO-SX) and Coherent Browser Mobile (for iOS and Android). Due to platform limitations the two have a different subset of features. Namely the Mobile version has some limitations while the Desktop version is fully featured.

Warning

The current version of Coherent Browser for Android has known issues when using the software keyboard alongside with Unity's one. Keyboards other than the default may not work as expected (e.g. Swype).

Mobile limitations on Coherent Browser Mobile include:

- You are only able to create 2D views on-top of your game for HUDs or in-game browsers. Views splatted on 3D surfaces in the game world are not supported due to platform limitations on iOS and Android.
- Input management must be implemented through minor changes in the HTML & JS and is not pixel perfect but HTML element-based.
- · Bound objects are currently missing from the binding
- · No on-demand views and frame-rate control

6 Introduction

• When writing scripts, the IDE's autocompletion will use the API for the Desktop version. There are a few methods that are available only for Desktop and others only for Mobile, so you won't see the mobile ones in your code editor. The classes for the mobile version are named the same as the desktop version but they're in a different namespace, *Coherent.UI.Mobile*. You can inspect the objects in that namespace to check the availability of the method you're looking for. In MonoDevelop you can inspect an object by using the "Go to declaration (F12)" feature.

Other that that the API has been kept 100% compatible between the Desktop & Mobile versions. The Core binding, Resource management and View management are the same. *Coherent Browser Mobile* supports both device builds and simulator ones.

Chapter 4

Installation

Coherent Browser for Unity3D is distributed in a **unitypackage** file. You can import this package in your project by either double-clicking on it, or by importing it through Unity in the *Project* window.

Note

Versions 1.5.3 and prior: After importing the package, you have to **install** the assets provided. This is done by the $Assets \rightarrow Coherent \ Browser \rightarrow Install \ Coherent \ Browser$ menu entry.

Versions 1.5.4 and later: The install step required for previous versions was removed in Coherent UI 1.5.4. The new structure places the UI Resources inside the WebPlayerTemplates folder since it's the only one that Unity ignores when compiling scripts. The files placed there are not actual web player templates but a collection of HTML/CSS/JS files that are used by the samples. These files won't interfere with actual Web Player Templates as long as there is no file named *index.html*. The default UI Resources path is no longer set (the installation step in previous versions did that) and the default file handler will try to find the assets in the WebPlayerTemplates folder when ran in the **Editor**. For built games you **must** set the UI Resources path using the $Edit \rightarrow Project Settings \rightarrow Coherent Browser \rightarrow Select UI Folder entry.$

Versions 2.4.4 and later: Coherent Browser 2.4.0.0 and later versions have support for Unity 4.x and 5 versions, but will no longer support Unity3D 3.5.7. In order to support the new Unity 5, the Coherent Browser package has been reorganized. So if you are upgrading to version 2.4.0.0 or later, it is recommended that you take the following steps before importing the new Coherent Browser unitypackage in your project:

- 1. Delete CoherentUI_Native.dll, CoherentUI_Native.pdb, libCoherentUI_Native.so and their meta files from the Assets/Plugins folder of your project.
- 2. Delete CoherentUINet.dll64, CoherentUI64_Native.dll and their meta files from the Assets/CoherentUI/Binaries folder of the project. Now you are ready to import the new Coherent
 Browser package.

4.1 Prerequisites

- · Unity3D 4 or later is required
- · Only Pro version of Unity is supported
- Coherent Browser *Mobile* supports iOS 5.1 and above.
- Coherent Browser Mobile supports Android 3.0 and above (API level 11).
- Mobile versions of Coherent Browser SDK for Unity3D work with the free version, but the Preview feature will
 not work.
- Java Development Kit (JDK) is required for exporting to Android. Referring to the folder you installed JD-K in as <JDK>, you need to have the <JDK>/bin folder in your PATH environment variable and set the JAVA_HOME environment variable to <JDK>.

8 Installation

Note

Coherent Browser SDK has different requirements than the requirements for Unity3D. Unity supports older hardware via fallbacks, which may prevent Coherent Browser SDK from running on older graphics cards. Please make sure that the requirements of Coherent Browser SDK match your client requirements for the project.

4.2 Package contents and structure

The package has the following structure:

- CoherentUI contains the UI debugger, samples, and documentation.
- CoherentUI/Editor contains editor classes for displaying the properties of Coherent Browser components
 plus a post-build step class. These classes provide utility functionality.
- · Plugins contains the Coherent Browser libraries. These are automatically copied when building.
- Standard Assets/Scripts/CoherentUI contains the Coherent Browser integration classes. You'll find a Detail folder inside which contains classes that are internal for the implementation and are used by the "public" classes. The interface you should be using is outside the Detail folder.
- StreamingAssets contains assets that need to be copied as-is in the build directory. These include the Coherent Browser host process executable, the libraries it needs, locales and UI resources.

4.3 Usage of the package

After importing the *CoherentUI.unitypackage* in your project, the two main scripts you'll be using are *Standard Assets/Scripts/CoherentUI/CoherentUISystem* and *Standard Assets/Scripts/CoherentUI/CoherentUIView*. The easiest way to use Coherent Browser is to drag the CoherentUIView component onto an object and hitting Play - that's it! Everything will be up and running. Actually, you can do the same for most of the usage scenarios - just drag the component and then configure it in the inspector. Here's a bit more detail about the two scripts.

The first script, CoherentUISystem, defines initialization parameters of the Coherent Browser System and should be placed no more than once in your project. The UI system is meant to be initialized in the first scene and live throughout the game's lifetime. You need to add this component to your scene only if you need custom initialization of the Coherent Browser System. For the most cases, using only CoherentUIViews is enough - they will automatically create an instance of the Coherent Browser System for you with reasonable default parameters. Check CoherentUISystem Lifetime for details.




Figure 4.1: CoherentUISystem properties

The second script, CoherentUIView, will represent a single HTML page. This is the component that renders your CSS and JavaScript animations and makes your game alive. This component can be placed on any object that is renderable and serves as its material. When placing it on an object all the needed components are automatically created, hidden from you, and the rendered output is bound to the mainTexture of a new material that is created at runtime. This material is set as the gameObject's renderer material so that you see the page rendered on your object.




Figure 4.2: CoherentUIView properties

You can also place views on cameras. When doing so, you get your page rendered on the whole viewport of the camera. This way you can easily add a heads-up display for your game. Don't forget to mark your HUD as transparent and make your HTML page transparent! There's even an option for drawing the HUD after the post-

10 Installation

effects if you like (The option is available for non-HUDs, too, but it results in a no-op because it doesn't make sense).

4.4 Switching between build targets

Coherent Browser Mobile has different properties and a restricted subset of features compared to the desktop versions. To switch between the desktop features and the mobile ones you must switch the current active target in Unity. This is done by clicking on File->Build Settings selecting the target platform and clicking "Switch Platform". After doing so the properties of the Views will change to reflect their capabilities specific to the selected platform. Even if the current target is iOS or Android and hence you'll build with Coherent Browser Mobile you can still preview your game in the Editor. The preview will use the desktop version of Coherent Browser. Keep in mind that in this case you might see some differences compared to the the mobile device after the build as the desktop version has more features. You should check often how your UI behaves and looks on the device itself (or the simulator).

4.5 Trial version registration

The trial version of Coherent Browser for Unity3D requires a simple registration. The registration requires:

- the email you used for downloading Coherent Browser
- · internet connection
- · outgoing connections to port 3000 to be allowed in your firewall

The registration is started automatically when you run the game. It shows a simple form that asks for your email.

You can register Coherent Browser on multiple machines, provided that they run different operating systems.

Games exported with the trial version of Coherent Browser also require registration. This means if you want to run your built game on a different computer, you'll have to register Coherent Browser on that computer, too. When building a game using the trial version of Coherent Browser the activator is packaged as well and ran when the game is started. For manual activation, copy the *CoherentUl/Activator* folder from your Unity3D project to the machine and run:

```
Activator.exe --unity3d --host \
"<FULL PATH TO GAME DATA FOLDER>/StreamingAssets/CoherentUI_Host/windows"
```

on Windows and:

```
Activator.app/Contents/MacOS/Activator --unity3d --host \
"<FULL PATH TO GAME APP>/Contents/Data/StreamingAssets/CoherentUI_Host/macosx"
```

on Mac OS X.

Chapter 5

Samples

Note

Some samples show Desktop-specific features while others focus on Mobile targets

The samples provide a starting point for you. They are located in Assets/CoherentUI/Samples and the required scripts are already configured.

The samples are based on a simple scene we've set up for you. The scene consists of a light, a floor, a cube, and a FPS controller so you can move around. There are a few key points in the base sample you should be aware of.

- The FPS controller's MouseLook script has been modified a bit you can toggle if it's active using the **Alt** key. This was done for convenience so you can navigate over the page, projected on the cube easily, without looking around. The CharacterMotor script has also been modified for the same reason.
- The cube's faces all have MeshCollider components. They are needed by Unity to produce texture coordinates in the raycast hit info. The texture coordinates, in turn, are needed to calculate the position of the hit point on the Coherent Browser View.
- The scenes that have interactive Coherent Browser surfaces placed on objects use the Click-to-focus feature
 of the Coherent Browser View. It allows the user to forward input to the view when she clicks on it and stop
 forwarding it when she clicks outside.

Note

In the case where the mesh collider does not coincide with the actual geometry of the object, the raycast and coordinate calculation must take place in the user code. In the samples we're only using simple geometry that is the same as the mesh collider so no further work is needed.

5.1 Hello, Coherent Browser

Just hit play - and you'll see a rotating cube and a sign, saying "Hello, Coherent Browser". The sample demonstrates the easiest possible setup for Coherent Browser for Unity3D. The scene is made of a cube in front of the camera with a script that rotates it, and a Coherent Browser component attached to the main camera. The component's URL is set to a local resource using our special coui:// protocol and the "Transparent" checkbox is ticked. You can preview the page displayed in your browser to see what you can expect.

Note

The **coui** protocol uses the folder selected by the $Edit \rightarrow Project\ Settings \rightarrow Coherent\ Browser \rightarrow Select\ UI$ folder menu item as a root for a virtual file system.

12 Samples

You can also add a *CoherentUIView* component to a 3D object if you like. To do so, locate the *CoherentUIView* script under **Standard Assets/Scripts/Coherent UI/CoherentUIView** in the *Project* window and then add it to the object of your choice. In Unity3D 4.x you can do that from the inspector windows by clicking "Add component".

Here's a sample where a Coherent Browser View component is added to a cube. Make sure you tick the "Click to focus" checkbox for the view to get input forwarding easily.




Figure 5.1: CoherentUIView on a texture

You can also try pages that show dialog boxes, such as

- http://www.w3schools.com/js/tryit.asp?filename=tryjs_alert
- http://www.w3schools.com/js/tryit.asp?filename=tryjs_confirm
- http://www.w3schools.com/js/tryit.asp?filename=tryjs_prompt
- http://www.httpwatch.com/httpgallery/authentication/ (scroll down and click Display Image)

If you do not handle the Listener events for dialog boxes by yourself they will be handled automatically by Coherent Browser.




Figure 5.2: CoherentUIView showing a prompt

5.2 Facebook integration

This sample uses a facebook application that shows some of your photos in a rotating circle. You'll see how to customize the <code>ViewIistener</code> behavior to suit your needs.

Note

If you're having trouble displaying the local resources, make sure you have selected the UIResources folder located in the root of the project using the $Edit \to Project\ Settings \to Coherent\ Browser \to Select\ UI\ folder$ menu in the editor. This folder will be used for resources addressed with coui://links.

14 Samples




Figure 5.3: CoherentUIView Facebook integration sample

You will find a new script - FacebookSampleScript. We need to modify the default behaviour of Unity-ViewListener for this sample. The key points are:

- In its Start method the FacebookSampleScript obtains the CoherentUIView component in the game object.
- In the Start method the script also attaches to the CoherentUIView.OnViewCreated event to enable intercepting URL requests and to the UnityViewListener.URLRequest event to redirect the Facebook login URL to the local HTML page.

This is the easiest way to handle events provided by the <code>UnityViewListener</code>. Another option is to derive the <code>UnityViewListener</code> and <code>CoherentUIView</code> but that is unnecessary.

The FacebookSampleScript.OnURLRequestHandler checks if the requested URL is the one that was registered in the Facebook Application settings (this might be any made up URL). If that's the case, we redirect it to the local page that uses our Facebook application. You will find the page we're redirecting to in the sample project folder under FacebookSample/facebook.html.

Now that we've explained what the class does, the only thing left is to hit play. You can press **Alt** to stop moving/looking so you can browse in the Facebook application.

5.3 Menu And HUD

This sample shows a game menu and HUD built with Coherent Browser.

5.3 Menu And HUD 15

Note

If you're having trouble displaying the local resources, make sure you have selected the *UIResources* folder located in the root of the project using the $Edit \rightarrow Project\ Settings \rightarrow Coherent\ Browser \rightarrow Select\ UI\ folder$ menu in the editor. This folder will be used for resources addressed with coui://links.

Double-click the *Menu* scene in the Project window (located in *Scenes*) to make it active, if it isn't already. In the *Menu* scene we have a MenuScript component attached to the camera. MenuScript does three things:

- sends the mouse position to the view every Update ()
- · registers the handlers for clicking on a menu button
- loads the game when the "New Game" button is clicked

Note

You have to add the game scene to the build settings of your project so Unity3D can load it.

In the game, we have another component for controlling the view - HUD, this time implemented in *UnityScript*. Each frame the component updates the compass orientation, based on its transformation.

In addition to updating the compass, the HUD component takes care of disabling the CharacterMotor component when the focus is on a *Click-to-focus* view. The HUD script attaches to CoherentUISystem::On-ViewFocused event and changes the canControl property of the selected CharacterMotor whenever a *Click-to-focus* view gains or loses focus. This allows typing in the focused view without moving the character. Here is the HUD component in code:

```
#pragma strict
#if UNITY_STANDALONE || UNITY_STANDALONE_WIN || UNITY_STANDALONE_OSX || UNITY_EDITOR
import Coherent.UI.Binding; // to use View.TriggerEvent with extra arguments
private var View : Coherent.UI.View;
private var CurrentDirection : float;
// CharacterMotor component to be disabled when a Click-To-Focus view has gained focus
public var characterMotor : CharacterMotor;
function Start () {
    var viewComponent = GetComponent(typeof(CoherentUIView)) as
      CoherentUIView;
    viewComponent.OnViewCreated += this.ViewCreated;
    viewComponent.OnViewDestroyed += this.ViewDestroyed;
    CurrentDirection = 0:
    var uiSystem = Component.FindObjectOfType(typeof(CoherentUISystem)) as
      CoherentUISystem;
    // get notified when a Click-to-focus view gains or loses focus
    uiSystem.OnViewFocused += this.ViewFocused;
function ViewCreated(view : Coherent.UI.View) {
    View = view;
    var viewComponent = GetComponent(typeof(CoherentUIView)) as CoherentUIView;
    Debug.LogWarning(String.Format("View {0} created", viewComponent.Page));
function ViewDestroyed() {
    View = null;
function ViewFocused(focused : boolean) {
    if (characterMotor) {
        // enable or disable the character movements
        characterMotor.canControl = !focused;
function Update ()
    if (View != null)
        var direction = this.transform.rotation.eulerAngles.y;
```

16 Samples

```
if (Mathf.Abs(direction - CurrentDirection) > 2)
{
        View.TriggerEvent("SetAbsoluteCompassRotation", direction);
        CurrentDirection = direction;
    }
}
#endif
```

In the game scene we have one more component - <code>ObjectPicker</code>, that takes care of directing the input to the correct <code>CoherentUIView</code>. First it checks whether the mouse is on a HUD element and if it is not, then raycasts and checks whether the mouse is over the browser window. Make sure the "Support Click Through" checkbox is ticked on the HUD <code>CoherentUIView</code> - this allows you to detect whether the mouse is over a transparent area in the View. If the property is left unchecked the input will never reach any objects in the world, because the system will think that the mouse is always over the HUD.




Figure 5.4: CoherentUIView HUD sample in action

5.4 Binding Demo

This sample will demonstrate communication between Unity3D and JavaScript used by the HTML page loaded in a Coherent Browser View.

Note

If you're having trouble displaying the local resources, make sure you have selected the *UIResources* folder located in the root of the project using the $Edit \rightarrow Project\ Settings \rightarrow Coherent\ Browser \rightarrow Select\ UI\ folder$ menu in the editor. This folder will be used for resources addressed with coui://links.

The sample shows a simple options dialog. The options are passed from JavaScript to Unity3D and back to exercise the binding. This walkthrough will give you a brief overview of the Coherent Browser Binding fundamentals but be

5.4 Binding Demo 17

sure to check out the Binding section in this guide, as well as the **Binding for .NET** section in the general reference document.

Note

This sample guide is written for C# Unity3D scripts, for UnityScript binding, please check the UnityScript section See the Unity Script Page

First, when passing custom object types between Unity3D and JavaScript, you must first inform Coherent Browser about the data in the type. You can do that using the CoherentType attribute:

```
using Coherent.UI.Binding;

// all properties / fields for Options will be visible to Coherent Browser
[CoherentType(PropertyBindingFlags.All)]
public struct GameOptions
{
    public string Backend;
    public uint Width;
    public uint Height;

    public string Username
    {
        get {
            return System.Security.Principal.WindowsIdentity.GetCurrent().Name.ToString();
        }
    }

    // rename the NetPort property to NetworkPort
    [CoherentProperty("NetworkPort")]
    public uint NetPort { get; set; }
}
```

Now the <code>GameOptions</code> structure will correspond to a JavaScript object having the same properties. Note that you can rename a property using the <code>CoherentProperty</code> attribute. In this case, the "NetPort" property will correspond to "NetworkPork" in JavaScript.

After exposing the properties, we need to register some event handlers. This can be done in two ways. The first way to bind event handlers is to add a handler for the ReadyForBindings event of the UnityViewListener (manual binding). The second way (.NET only) is to add a CoherentMethod attribute to the method you want to bind (automatic binding). See the CoherentMethod section in this guide for more details.

Note

The sample provides two scripts for binding - ManualBinding.cs and AutomaticBinding.cs. Make sure that only one of those scripts is active when exploring the sample.

We'll explore the manual binding first. Start by registering a handler for ReadyForBindings:

```
m_View = GetComponent<CoherentUIView>();
m_View.Listener.ReadyForBindings += HandleReadyForBindings;
```

The handler would look like this:

```
void HandleReadyForBindings (int frameId, string path, bool isMainFrame)
{
    if (isMainFrame)
    {
        // bind ApplyOptions to "ApplyOptions" in JavaScript
        m_View.View.BindCall("ApplyOptions", (Action<GameOptions>)this.ApplyOptions);
        m_View.View.BindCall("GetLatency", (Func<int>)this.GetNetworkLatency);
        m_View.View.BindCall("GetGameTime", (Func<int>)this.GetGameTime);

        m_View.View.BindCall("GetMath", (Func<BoundObject>)(() => {
            return BoundObject.BindMethods(new MyMath());
        }));

        // triggered by the view when it has loaded
        m_View.View.RegisterForEvent("ViewReady", (Action)this.ViewReady);
    }
}
```

18 Samples

Now, when JavaScript calls engine.call ("ApplyOptions", options), Unity3D will execute its handler - namely the (Action<GameOptions>) this.ApplyOptions method registered above.

The options structure passed as a parameter looks like this:

```
function onApplyButton() {
    var options = {};
    options.__Type = "GameOptions";
    options.Backend = $("#backend").text();
    options.Width = Number($("#gameWidth").val());
    options.Height = Number($("#gameHeight").val());
    options.Username = $("#user").text();
    options.NetworkPort = Number($("#netPort").val());

    // This will call the C++ engine code with the just created structure. It'll be correctly populated engine.call("ApplyOptions", options);
}
```

Note that there is one "internal" property - __Type. This property defines the mapped type and is essential for correct behavior of the binding provided by Coherent Browser.

The "ApplyOptions" handler just bounces the options back to JavaScript:

```
public void ApplyOptions(GameOptions options)
{
    m_View.View.TriggerEvent("gameConsole:Trace", options);
}
```

gameConsole: Trace will dump the options object in the console.




Figure 5.5: Binding sample in action

The automatic binding saves us the first two steps - instead of registering a handler in the UnityViewListener callback you can decorate a method with the CoherentMethod attribute:

```
[Coherent.UI.CoherentMethod("ApplyOptions", false)]
public void ApplyOptions(GameOptions options)
{
        m_View.View.TriggerEvent("gameConsole:Trace", options);
}
```

5.4 Binding Demo 19

The first argument of the attribute is the JavaScript function that we're binding. The second defines whether the function is an *event* (opposed to a *call - calls* are single-cast only).

Returning a value to JavaScript

Calls can also return a value. Let's inspect the "GetLatency" binding:

```
// By default, the second argument of CoherentMethod is false
[Coherent.UI.CoherentMethod("GetLatency")]
public int GetNetworkLatency()
{
    // not actual latency :)
    return (int)UnityEngine.Random.Range(0, 1000);
}
```

Since the execution of JavaScript is **not** synchronous you will receive the result in a callback. Coherent Browser provides a promise/future pattern for convenience. This is the "GetLatency" JavaScript call in all its glory:

```
function getLatency() {
    engine.call("GetLatency").then(function() {
        $("#latency").text(arguments[0]);
    });
}
```

As you can see from the script, the value returned by Unity3D will be passed to the callback as an argument.

Method Binding

This sample also shows how to use binding of .Net methods. For detailed explanation see "Exposing Methods" in the "Binding for .Net" chapter in the API documentation.

The sample exposes an instance of MyMath to JavaScript.

```
class MyMath
{
    public double Sum(double[] numbers)
    {
        return numbers.Sum();
    }
    public double Average(double[] numbers)
    {
        return numbers.Average();
    }
}
```

When the game is up and running, we request the MyMath instance, store it as a global object and register two console commands that use it.

```
engine.on('Ready', function () {
              //get the exposed MvMath object
              engine.call('GetMath').then(function (math) {
                              // store reference to the object
                            window.MyMath = math;
                              // register commands for the console
                            engine.trigger('gameConsole:AddCommand', 'sum', 'computes the sum of its arguments', function (line
                                            var numbers = line.split(/\s+/).map(Number);
                                            numbers.splice(0, 1);
                                            window.MyMath.Sum(numbers).then(function (sum) {
                                                          engine.trigger('gameConsole:Trace', 'The sum of', numbers, 'is', sum);
                                            });
                            });
                             engine.trigger('gameConsole:AddCommand', 'avg', 'computes the average of its arguments', function (its arguments') and the state of t
                      line) {
                                            var numbers = line.split(/s+/).map(Number);
                                           numbers.splice(0, 1);
                                            window.MyMath.Average(numbers).then(function (avg) {
```

20 Samples

```
engine.trigger('gameConsole:Trace', 'The average of', numbers, 'is', avg);
});
});
});
});
```

To try out the commands press \sim to open the game console and type sum 40 2.

Events

When you need multiple handlers for a JavaScript function you need to register an *event*. This can be done by the Coherent.UI.View.RegisterForEvent method for manual binding

```
m_View.View.RegisterForEvent("ViewReady", (Action)this.ViewReady);
```

and passing true as a second parameter of the CoherentMethod attribute for automatic binding.

```
[Coherent.UI.CoherentMethod("ViewReady", true)]
public void ViewReady()
{
    // show the options
    m_View.View.TriggerEvent("OpenOptions", m_GameOptions);
}
```

Bear in mind that events cannot return a value.

If you want to handle an event in JavaScript, you need to register a handler using the engine.on call.

```
engine.on('OpenOptions', function (options) {
    // Open an options dialog
});
```

An event can be triggered by JavaScript by using

```
engine.trigger("EventName", eventArgs);

or by Unity3D using

m_View.View.TriggerEvent("EventName", eventArgs);
```

This concludes the binding demo walkthrough.

where m_View is CoherentUIView.

5.5 Archive resource

This sample demonstrates reading resources from an archive through a custom file handler.

The scene is just a simple camera that has an attached CoherentUIView component and another one that forwards input to the view. The important component for this sample is CustomFileHandlerScript. It sets the CoherentUISystem factory function object in its Awake method so the system is initialized with the custom handler.

```
void Awake()
{
    CoherentUISystem.FileHandlerFactoryFunc = () => { return new CustomFileHandler("UIResources", "
    ArchiveResource.tar"); };
}
```

In fact, that's all the component has to do - set the CoherentUISystem.FileHandlerFactoryFunc prior to any Start method being called. The returned CustomFileHandler is the class that does the actual reading/writing. The methods the user needs to implement are:

5.6 Mobile Input 21

They will be called for all *coui://* links and for the cookies (if enabled).

Note

When reading/writing cookies, you may receive a URL that has a file://scheme.

The input URL can be interpreted in any way you see fit for your handler. In the example we try to open the link *coui://UIResources/mainmenu/menu.html*. The *mainmenu/menu.html* is actually compressed in an archive. First we verify that the host part of the URL (*UIResources*) is what we expect for compressed resources and then proceed to search the archive for the resource.

Since Coherent Browser supports asynchronous reading/writing of resources, when done with the I/O operations, you must use the ResourceResponse or ResourceData object to signal the outcome. You can do that by using the SignalSuccess and SignalFailure methods.

Note

At the moment the data you read/write must be converted to a native buffer before usage. This is done with the System.Runtime.InteropServices.Marshal class. Here's a short snippet that reads a file and then copies the managed buffer in an unmanaged buffer provided by the ResourceResponse object:

Make sure you check out the code in *CustomFileHandlerScript* for a complete example.

5.6 Mobile Input

Warning

Unity3D 3.5 doesn't support native plugins for iOS simulator builds. There are a couple of articles explaining how to workaround this limitation, but the most helpful is http://tech.enekochan.-com/2012/05/28/using-the-xcode-simulator-with-a-unity-3-native-ios-plug-in/

We have added a script with a post-process step that tries to fix the project, so it can be used with the iOS simulator. The script is in Editor/iOSSimulatorProjectFixer.cs.

This sample demonstrates how you can control what part of the input is forwarded to Unity3D by using JavaScript. The sample starts with an overlay that has 3 buttons on the left side, area for testing input forwarding on the right, and a red box in the world. The buttons enable/disable the input forwarding for touches on the right side of the overlay and the third one bumps the box upwards. When you touch the box a little force is applied and it should

22 Samples

move forward as if you pushed it. If you touch the box in the right area of the overlay the force is applied only if input forwarding is enabled.

There are also buttons for toggling the overlay and mouse look controller in the top left corner for convenience.

Warning

The HTML code for the sample is not designed for small displays so it may look out of proportion on a phone or a phone simulator. You can try lowering the font size in the accompanying *css* file.

Note

The Coherent Browser View used has its input state set to "Transparent". If you set it to "Take all" input is consumed before reaching Unity3D and if you set it to "Take none" it is sent directly to Unity3D.

Warning

Unfortunately, at the moment you can't see the actual behavior of the sample in the Unity3D Editor. Input is handled differently for the standalone and mobile versions so it recommended that you test your project either on a mobile device or an emulator.

Code-wise speaking, when you make a touch on a "Transparent" Coherent Browser View, the engine.check-ClickThrough function is called. You can check its code in coherent.js. Basically it obtains the DOM element from the touch coordinates and begins a series of checks. First, if the element is the *document body* or has the **coui-noinput** class, input is directly sent to the client (Unity3D). Otherwise, the element is checked for having a **coui-inputcallback** class. If it does, the element's <code>couiInputCallback</code> is invoked which determines whether the input is forwarded or consumed; if it doesn't have such class, input is consumed.

The sample enables/disables the input forwarding on the right area by removing/adding the **coui-noinput** class to the corresponding DOM element. In this sample, only the DOM element for the right area has the class **coui-inputcallback** and its <code>couiInputCallback</code> function is set when the engine has signaled it's ready. The function itself doesn't do anything special, it just always <code>returns true</code>, meaning that the input is consumed in JavaScript and never sent to the client (Unity3D).

You can also bump the box upwards which is a demonstration for the binding for Coherent Browser Mobile. It's very much the same as binding for .NET/Unity3D standalone so we'll not go in detail here.

Summing up:

- if you want the input forwarded to the client when touching an element, simply add the **coui-noinput** class to the element.
- if you want an element to consume input, ensure that it does **not** have the **coui-noinput**.
- if you want to have custom processing over an element, ensure that it does **not** have the **coui-noinput**, add a **coui-inputcallback**, and add a function <code>couiInputCallback</code> which ultimately returns true if you want to consume the input or false if you want to forward it to the client.

Note that for obtaining the element below the touch point we're currently using <code>document.elementFrom-Point</code>. In the sample, the right area is represented by a <code>div></code> and there's some text inside it as a child element. Only the <code>div></code> has the <code>coui-inputcallback</code> class. If you touch the text its element will be checked for the <code>coui-inputcallback</code> class and since it doesn't have one input will be consumed. Since we want to apply the logic for all touches inside the area this presents a problem. One solution is to add the <code>coui-inputcallback</code> class to all child elements and set their <code>couiInputCallback</code> functions to the same variable. Another solution is to use the <code>pointer-events CSS</code> property on the children elements, e.g.:

```
#menu-right > *
{
    pointer-events: none;
```

This is how the sample solves the problem. Note that this is an experimental CSS property and prevents elements from being the target of pointer events. This is fine in the sample but may have adverse effects in your code so use it with caution.

5.7 Oculus 23

5.7 Oculus

Note

It is not possible to create a sample scene for Oculus Rift for Unity3D 3.5 using the official Oculus SDK. So our Oculus Rift sample scene is created with Unity3D 4 and can not be packaged in our asset store packages. You can download a package with the scene from: https://s3.amazonaws.com/CoherentLabs/-Public/Coherent_UI_Oculus_Sample.unitypackage

This sample demonstrates how you can create UI elements in your games for the Oculus Rift, using the Coherent Browser and OculusVR integrations in Unity. The focus of the sample is on creating a HUD element that can be used with the Oculus headset.

Note

You should include the Oculus integration package for Unity in order to use Oculus in Unity3D (you need a Unity Pro 4.01 or higher version). For more information about the Oculus SDK and its integration with Unity, please visit http://www.oculusvr.com/.

You can get Oculus ready for use in Unity by following these steps:

- go to the official website of Oculus Rift http://www.oculusvr.com/;
- · download OculusUnityIntegration.unitypackage from there;
- open an Unity3D instance and go to Assets -> Import Package -> Custom Package. When the dialog box
 for choosing packages opens, go to the place with the downloaded package and select it. A new dialog box
 with a list of the files for import will open. Choose 'Import All'. After completing this step you should be able
 to see a new menu 'Oculus'.

Now we are ready to proceed with the sample. As you can see, there is an OVRPlayerController in the *Scene* menu (it can be added from Oculus -> Prefabs -> OVRPlayerController). The controller is comprised of two things: a simple character controller and another OVR prefab - OVRCameraController. The latter is used as an interface between Unity and the two cameras. Double-click it to reveal its children objects. Double-clicking the OVRCamera-Controller will show the cameras and a plane object attached to the right camera. This plane is used as a surface for drawing the HUD. There is an CoherentUIView component attached to it, which uses coui://UIResources/Menu-AndHUD/hud/hud.html as a page. It is suggested that for drawing HUD elements you attach the surface to the right camera for optimal results.

Note

To render a view on top of everything, we put an check mark in 'IsIndependentOfZBuffer'.

Warning

Whenever using a plane as a surface for views, choose a material for the plane and use a 'Transparent/Diffuse' shader for it.

Note

If you want to change the draw order of a Coherent Browser view, the Left eye camera and a Right eye camera, you can adjust the camera depth property of the camera component for all of the cameras you want to reorder. Cameras with larger depth value will be drawn on top of cameras with lower depth value. When rendering surface views, Coherent Browser creates a CoherentRenderingCamera (in the ViewListener.cs script) that has a default depth of 0.

This is basically all you need to draw the HUD. Hit play to see the result

24 Samples

5.8 Mobile Surface

The Mobile Surfaces sample shows how to use Coherent Browser views on surfaces for mobile platforms. The sample shows a texture with a Coherent Browser view on it that is rotating. Every 100 frames the view is changed and the texture is updated by calling the 'UpdateView' method of the view.

Note

To achive transparency of the surface *both* - the *IsTransparent* property of the view should be checked **and** the shader of the material should be set to *Transparent/Diffuse*.

5.9 Live Game Views

Note

Live Game Views are a Desktop-only feature.

The sample shows a simple scene with a Live Game View. The scene consists of a "game world" with a plane as ground, four rotating colored cubes and a light.

On the main Camera a Coherent Browser View is attached that serves as an in-game HUD(heads-up-display). The Live Game View is part of the HUD. A Coherent Browser Live Game View component is also attached to this camera and hence to the UI - it is the "link" between the View and the provider of the 3D images.

A second camera is fixed on the cubes and provides the source data. Everything this camera renders is automatically sent to the UI View linked to it as a dynamic "ImageData" object in the UI JavaScript Code. The HUD.html page draw the Live View with the following code:

```
window.onload = function() {
   var c = document.getElementById("myCanvas");
   c.onEngineImageDataUpdated = function (name, image) {
    var c = document.getElementById("myCanvas");
    var ctx = c.getContext("2d");

   ctx.clearRect(0, 0, c.width, c.height);
   ctx.putImageData(image, 0, 0);
   ctx.fillStyle = "white";
   ctx.font = "l6pt Arial";
   ctx.fillText("Live Game View!", 15, 25);
}
```

Every time a new frame is drawn by the "live" camera the "onEngineImageDataUpdated" is called on all "canvas" elements that define it in the page. There you can use the data in whatever fashion you need. In this sample we draw the image into the canvas and write some text on it. When you "Play" the game you'll see the four rotating cubes drawn in the HUD in the lower left corner as the "live" camera sees them.

Note that now the images of the camera are part of the UI DOM, so you can achieve all UI effects with it. The canvas elements can be animated, 3D transformed int the UI, post-effects can be applied on them, they can be interactive etc.

Via Live Game Views in a real game you can trivially have 3D animated unit portraits, animated items in the UI, 3D mini-maps, security cameras etc.

5.10 IME Sample

This sample demonstrates the usage of Input Method Editor for languages that require more complex input such as Chinese. To have IME enabled for a particular view you should just put a check on the *Enable IME* property of the **CoherentUIView** and this is all you need to do to have support for IME in your view.

Open the IME Sample, change your input language to one that requires IME, for example Chinese and hit play. Try to write something in the dialog that appears and hit 'Enter' or just press the 'Say' button. What you just wrote will appear in the dialog window.

5.10 IME Sample 25

Enabling IME does a few things:

• It subscribes for the OnCaretRectChanged, IMEShouldCancelComposition and OnTextInputControl-TypeChanged events.

- OnTextInputControlTypeChanged event is fired when the type of text input control changes. The method that subscribes for it determines from the new type of control whether IME composition mode in Unity should be turned off or on.
- OnCaretRectChanged event is fired when the caret has changed its position. It has arguments *x* and *y* for the top left position of the caret rectangle and *width* and *height* for its width and height, all of them measured in pixels, relatively to the view. This method will help you set the position of the candidate list window.

Note

If you want to set the candidate window on a specific screen position or make the calculations on your own, you can subscribe with a method for the **CalculateIMECandidateListPosition** handler, which has the same arguments as OnCaretRectChanged and should return the desired position of the candidate window in screen space. Please note that (0, 0) for the IME cursor position in Unity is in the upper left corner in spite of bottom left.

26 Samples

Chapter 6

Programmer's API

The Unity API is an extension of the normal .Net API, and it is contained in the main API Reference documentation.

6.1 CoherentUISystem properties

- **Proxy** Enables proxy support by autodetecting the system settings. This detection is usually very slow and this setting should be enabled only when the user is behind a proxy and you're accessing the Internet.
- · Cookies Enables support for cookies.
- · Cookies file A file that will be used for reading and writing cookies when they are enabled.
- Cache path Path for saving cached data. Leave null for in-memory caching only.
- Local storage path Path for saving HTML5 page local storage data. Leave null to forbid local storage.
- Disable fullscreen plugins Disables fullscreen mode for all plugins (e.g. Flash, Silverlight, etc.)
- · Disable web security Disable same origin policy. Use with caution.
- Debugger port The port that will be opened for the debugger to connect and debug your interface. A value
 of -1 means disabled.

The CoherentUISystem component also provides a static factory function object (FileHandlerFactory-Func) that the user can customize in order to make use of her own FileHandler. See the Custom file handler section for a detailed explanation.

6.2 CoherentUIView properties

General section:

- · URL Indicates the URL that will be initially loaded.
- Width The width of the Coherent Browser View.
- · Height The height of the Coherent Browser View.
- Transparent Defines if the View supports transparency.

Rendering section:

• **Draw order** - Defines whether the View is drawn before or after the post-effects. Available for Views attached to cameras.

28 Programmer's API

- Flip Y Flips the drawn image vertically.
- **Texture Filtering** The filtering mode used for rendering the views. The two available modes are Point Filtering and Linear Filtering. (View Filters Desktop only)
- Software only rendering The View will be rendered without hardware acceleration.
- Match camera size The View will be automatically resized to always match the size of the camera.

Advanced rendering section:

• On Demand - Provides perfect synchronization of the game frames and Coherent Browser frames. Use this when you need to synchronize the game and the interface, e.g. when displaying name tags over the players. Using standard views may introduce a delay of a few frames.

Note: The synchronization is done in Unity's LateUpdate() method, so updating of objects that have UI elements should be done in regular Update(), or updates of components should be re-arranged (via Script Execution Order Settings) so the update of CoherentUIView is last.

- Timer override The UI uses the in-game timer. (requires On-demand)
- Max. frame-rate Sets the maximum framerate for the View. The view will never exceed this framerate.
- Always on top Indicates whether this value is z-buffer independent. If it is set to true, the view is rendered on top of everything.
- Compensate gamma The View will have gamma corrected when linear color space is used. Whether you should use this property or not depends on the scene you are making are there any additional cameras, what kind of rendering path they use, etc. Generally, this property comes handy when you use linear color space and the view is attached to a camera with deferred lighting or if your main camera uses deferred lighting and the camera with the view does not.

Input section:

- Smart input Available for transparent Views. Enables support for queries whether the cursor is over a transparent pixel. A transparent pixel is considered one that has an alpha value below or equal to the click-through alpha threshold.
- Smart input alpha A value in the range [0-1]. inclusive that determines whether a pixel is transparent; A pixel is transparent if its alpha value is below or equal to the threshold.
- Lockable focus When enabled, the View takes the input focus when clicked and releases it when you click outside the View. See Click to focus Views
- Enable IME When enabled, this view will have Input Method Editor enabled for languages that have more complex input like Chinese.

Scripting section:

- Pre-load script The script will be executed before any other code in the UI View.
- Auto UI messages When enabled, any event triggered in *JavaScript* on the engine object is forwarded to the game object containing the View.
- Enable [CoherentMethodAttribute] Enables the usage of the [Coherent Method attribute]. (Coherent-Method attribute for .NET scripts)
- Show JS dialogs Automatically handle JavaScript messages and authentication requests. If enabled, a visual dialog will be shown; otherwise it's up to the programmer to make the appropriate response. If you do not respond to the message, the page will block until you do. Examine ViewListener.cs and CoherentDialog.cs for a sample reply logic.

6.3 CoherentUlLiveGameView properties

General section:

- Name This is the string used as an identifier for the Live Game View. In the UI JavaScript code this string can be used to apply specific logic to only certain live views.
- Width The Width of the Live Game View. The ImageData object created in the UI JavaScript DOM will have this width.
- **Height** The Height of the Live Game View. The ImageData object created in the UI JavaScript DOM will have this height.
- Source Camera The camera that will provide the images for the Live Game View. Everything rendered by this camera will be sent in the UI JavaScript universe and automatically updated every frame. If you omit a Source Camera than the source texture will be used.
- Source Texture A texture to be used as source for the Live Game View images. If both a camera and a texture are specified than the first frame in the live view will use the texture but all others will be provided by the Camera. If you omit specifing a Source Camera than only the texture will be used. If you change the content of the source texture and want to update the Live View linked to it you can do it by calling the "UpdateFromCurrentTexture" method of the Live Game View component.
- Read alpha Specifies if to read the alpha value drawn by the Source Camera.

30 Programmer's API

Chapter 7

Important points

7.1 Binding

Binding *C#*, *UnityScript* and *Boo* handlers to JavaScript callbacks is the same as binding for the .Net platform. You have to register handlers when the <code>UnityViewListener</code>'s <code>ReadyForBindings</code> event is fired. You can do that by using either <code>Coherent.UI.View.BindCall</code> (for single-cast delegates) and <code>Coherent.U-I.View.RegisterForEvent</code> (when you have multiple subscribers for the event). For more details see the general reference documentation, chapter <code>Binding</code> for <code>.Net</code>.

The Coherent.UI.View can be obtained using the View property of the CoherentUIView component.

To take advantage of the *Unity3D* component and message system each CoherentUIView has the Intercept—AllEvents property. If intercepting of all events is enabled, any event triggered in *JavaScript* on the engine object is forwarded to the game object containing the view. This is done by using SendMessage with Coherent.—UI.Binding.Value[] containing all the event arguments.

```
engine.trigger('Event', 42);
// will execute SendMessage('Event', [42])
```

Note

Using this method of handling triggered events has some additional overhead over the direct .Net Coherent.UI.View.RegisterForEvent method.

7.2 CoherentMethod attribute for .NET scripts

Instead of handling the ReadyForBindings event and doing BindCall or RegisterForEvent by yourself, you can use the CoherentMethod attribute to decorate methods in components.

32 Important points

Warning

This attribute only works if the CoherentUIView's Enable Binding Attribute is set to true. By default it is false.

The decorated methods will be automatically bound to the <code>View</code> owned by the <code>CoherentUIView</code> component in the Game Object. If the Game Object has no <code>CoherentUIView</code> component, the attribute has no effect. The <code>CoherentMethod</code> attribute has a string property for the JavaScript event name, and an optional boolean parameter that specifies whether the method is a <code>call</code> or <code>event</code> handler (<code>calls</code> can have only a single handler, while <code>events</code> may have many). Here's an example component using the attribute:

```
public class BindingComponent : MonoBehaviour {
    [Coherent.UI.CoherentMethod("NewGame")]
    void MyCallHandler()
    {
        Debug.Log("MyCallHandler called in response to engine.call('NewGame')");
    }
    [Coherent.UI.CoherentMethod("EnemySpotted", true)]
    void MyEventHandler()
    {
        Debug.Log("MyEventHandler called in response to engine.trigger('EnemySpotted')");
    }
}
```

See the Binding Sample for a complete example.

Warning

- * Binding methods using the CoherentMethod attribute is easier than doing it manually in ReadyFor-Bindings, but presents possible performance penalties during game startup. When the CoherentU-IView component is created, it searches all the other components in the host Game Object for methods marked with CoherentMethod using reflection. This can be a costly operation and to prevent undesirable slowdowns during startup the Enable Binding Attribute property for each CoherentUIView is set to false by default.
- * The CoherentMethod attribute currently does **NOT** support dynamically added components. Methods decorated with the attribute are only bound when the CoherentUIView component is created, which is usually when the Game Object it is part of is created.

JavaScript and Unity3D

Consult the *Binding for .NET* chapter in the general reference document. Check the *Binding Sample* and its walk-through in this guide for an example.

Briefly, Unity3D can call JavaScript using events; JavaScript can call Unity3D using events or calls.

Events

Events can be called by JavaScript

```
engine.trigger("MyEvent", args);

or Unity3D

coherentUIView.View.TriggerEvent("MyEvent", args);
```

The "MyEvent" will be handled by any registered method in JavaScript

```
engine.on("MyEvent", function() \{\ldots\});
```

or Unity3D

7.3 Namespaces 33

```
coherentUIView.View.RegisterForEvent("MyEvent", handlerMethod);
```

Calls

Calls, unlike events, can have only one handler. The can also return values. To execute a call from JavaScript use

```
engine.call("MyCall", args);
```

It will be handled by a method registered using

```
coherentUIView.View.BindCall("MyCall", handlerMethod);
```

7.3 Namespaces

Coherent Browser classes are placed in the Coherent.UI namespace for Desktop and Coherent.UI.Mobile for the Mobile version. You can check the Coherent Browser files - for instance CoherentUIView and take a look at the beginning of the file at how the namespaces are imported depending on the Unity platform targeted. Exceptions to that rule are classes that cannot be in a namespace because Unity doesn't allow it, such as components that derive from MonoBehaviour.

7.4 Subclassing CoherentUIView and UnityViewListener

The default CoherentUIView component and the UnityViewListener provide the most common functionality and are usually enough for normal usage of *Coherent Browser*. If you need custom behavior, you need to subclass them.

The class you derive from UnityViewListener would usually subscribe to various events that aren't handled by default. It is recommended not to override the OnViewCreated callbacks since the UnityViewListener class contains important logic that you would have to implement yourself otherwise.

The class you derive from CoherentUIView would only need to create an instance of your custom View Listener. This can be done by copying the Update method of CoherentUIView and editing it appropriately.

Note that when subclassing CoherentUIView you will no longer be able to view or edit the properties in the Inspector. That's because we're using C# properties in our component instead of fields and they are not automatically shown. To show the properties of a given C# script we need to make a new Editor script (inside the Editor folder of your Assets) that shows the properties for a specific type. We've already done that for CoherentUIView, but you'll have to do it yourself for derived classes. The script contents should be the following:

```
using UnityEngine;
using System.Collections;
using UnityEditor;

[CustomEditor(typeof(<YourType>))]
public class <YourType>ViewEditor : Editor {
    private <YourType> m_Target;
    private CoherentPropertyField[] m_Fields;

    public void OnEnable() {
        m_Target = target as <YourType>;
        m_Fields = CoherentExposeProperties.GetProperties(m_Target);
    }

    public override void OnInspectorGUI() {
        if(m_Target == null)
            return;
        this.DrawDefaultInspector();
        CoherentExposeProperties.Expose(m_Fields);
    }
}
```

Just replace < YourType> with the actual name of your class.

34 Important points

Note

In most cases, subclassing is unnecessary. See Facebook Sample for an example how to subscribe for UnityViewListener events.

7.5 Coherent Browser system lifetime

Since initialization of the CoherentUISystem component is a costly operation, it is designed to be done once in the first scene of your game. The component itself has the same lifetime as the application. Since Unity tears down the state of the game when you load a new scene, the component is marked not be destroyed using the DontDestroyOn-Load() function. This makes it persist through scenes and is available using the Object.FindObjectOfType function. Getting the system can be done with the following line of code:

```
var uiSystem = Object.FindObjectOfType(typeof(CoherentUISystem)) as
    CoherentUISystem;
```

7.6 Customizing initialization of the Coherent Browser System

When using only CoherentUIView components, the Coherent Browser System will be automatically initialized using the default parameters. These parameters define global system settings such as whether cookies are enabled, local storage and cache paths, debugger port and others. Check the CoherentUISystem component for a full list.

The Coherent Browser System can be initialized with parameters other than the defaults in the following ways. Either drag the CoherentUISystem component to any object and edit the properties in the Inspector window, or edit the CoherentUISystem.cs script located in Standard Assets/Scripts/CoherentUI to fit your needs.




Figure 7.1: Custom CoherentUISystem component

The CoherentUISystem component is designed to be only one in the whole game. Adding more than one

7.7 Update cycle 35

CoherentUISystems to your level will result in undefined behavior.

7.7 Update cycle

In a standard C++ or .NET application you need to poll Coherent Browser for surfaces each frame using the Update and FetchSurfaces API calls. In our Unity integration, this is all hidden from you and you don't have to worry about it. The CoherentUIViewRenderer component issues rendering events which are handled by our library. All that's left for you is to drag a CoherentUIView component on an object!

7.8 Input forwarding - Desktop

A CoherentUIView requires focus to receive user input. Usually you'd want to forward input to a single view, but for flexibility **Coherent Browser** supports multiple focused views. A CoherentUIView's focus is controlled by the ReceivesInput property. To avoid confusion with multiple views, the property is set to **false** by default, meaning no input will be forwarded to **Coherent Browser** unless you explicitly set it in your Game Object. It is **NOT** exposed in the Inspector, as it designed to be modified in code only.

Note

The forwarding happens in the CoherentUISystem's LateUpdate method, allowing you to do all your logic for input focus management in the Update methods of your components.

7.9 Input forwarding - Mobile

Due to differences in the input management for iOS/Android, Coherent Browser provides a helper class for getting the list of touches for the current frame. The Coherent touch structure is InputManager.Coherent—Touch - very much the same as Unity3D's Touch structure. The equivalent methods for Input.touch—Count and Input.GetTouch(index) are InputManager.TouchesCount and InputManager.—GetTouch(index), respectively.

For **iOS** there's practically no difference between the Coherent and Unity3D touches. For **Android**, however, Coherent touches contain only touches that reached the game (i.e. the touch wasn't filtered using the techniques described in the next paragraph). The Unity3D supplied touches on Android aren't filtered and you get all of them when using the Input.touches array, regardless of whether they are on the UI or not. When using Coherent Browser for mobile, it is recommended to use Coherent touches instead of Unity3D touches to avoid platform differences between iOS and Android.

On iOS/Android all *Coherent Browser* Views are composited in 2D on-top of your Unity3D application content. When the user start a touch event or performs a gesture there is a mechanism that decides if that event should be handled by the UI or the application. It works like this: in the properties of the View the user can select one of three input modes for a every View - "Take All", "Take None", "Transparent". Keep in mind that all those modifiers are in effect only for events that happend are in the bounds of the View. If the user touches outside a particular View the event is always handled by the game.

- "Take All" specifies that all events are handled by the View and nothing goes to the game. It is usable if you want to have for instance an in-game browser. All touches on it should be handled by itself and not influence the game.
- "Take None" specifies that the View passes all input to the game. This is usable if you need to just show some non-interactive views or disable their input completely in some situation.
- "Transparent" specifies that the input is either handled by the View or the game usable for HUDs, Menus etc. For Views with "Transparent" input mode the user is the one in charge of deciding if an element on the page is interactive hence should receive input or is 'input transparent'.

36 Important points

Note

iOS: Input "Transparent" views work correctly **ONLY** if you have included *coherent.js* in your HTML page.

Android: Input on any view works correctly ONLY if you have included coherent.js in your HTML page.

Upon touch within a View, Coherent Browser Mobile inspects the touched element:

- if the element has the CSS class *coui-noinput* it passes input to the game. The element does not accept input.
- if the element has the CSS class *coui-inputcallback*, a method called *couiInputCallback*(x, y) is called on the element with the coordinates of the event. It should return "true" if the user wants the element to handle the input and "false" if the game should handle it. This allows for custom fine-grained control in JavaScript on which elements are interactive.
- if the class *coui-noinput* and *coui-inputcallback* are missing from the element, it is assumed that it is interactable and takes the input.

To summarize: If a View has an Input State set to "Transparent" all elements are by default interactive and take input. You can mark elements with the CSS class *coui-noinput* to make them transparent to input. If you need more advanced logic when deciding if an element is interactive or not you can decorate it with *coui-inputcallback* and implement a method *couiInputCallback(x, y)* on it.

7.10 Mobile Preview

The preview for the mobile versions of Coherent Browser allows you to easily see how your page behaves without testing it on a device or simulator. There are a few notable differences, however. First, the input redirection is based on the Android version, meaning you need to import *coherent.js* in your HTML files for it to work. All other notes for the input regarding Android apply for the preview as well. Another difference is that on the devices the Coherent-UIView is always shown on top. Due to the specifics of Unity this is not easy to simulate automatically without interfering with some client functionality. That's why it's up to the user to simulate this behaviour in the preview. You should ensure that the camera you have your view on is always drawn last so the views are displayed the same, both in Editor preview and on the device.

7.11 Custom file handler

The CoherentUISystem component makes use of a static factory function object (FileHandlerFactory-Func) to create the FileHandler object that is used reading URLs with the *coui* scheme. The default function returns a handler that reads resources from the path set by $Edit \rightarrow Project \ Settings \rightarrow Coherent \ Browser \rightarrow Select \ UI \ folder$ for the Editor and in the Data folder for built games.

The factory function object is public and can be customized. The FileHandler it returns is passed to the UI initialization routine in the Start method of the CoherentUISystem component. That means the user should set the factory function prior to the invocation of the Start method of the components - e.g. in the Awake method.

Note

You can check the execution order of event function in Unity3D on this page

This is an example usage of a custom file handler:

7.12 UI Resources 37

```
// Implementation here
}

public override void WriteFile (string url, Coherent.UI.ResourceData resource)
{
    // Implementation here
}

//------

void Awake()
{
    CoherentUISystem.FileHandlerFactoryFunc = () => { return new CustomFileHandler(); };
}
```

See Archive resource demo for an example.

7.12 UI Resources

Files for Coherent Browser are by default selected from the folder set by Edit o Project Settings o Coherent Browser o Select UI folder. Resources found there will be used by the editor and will automatically be copied in your game upon build.

The selected UI resources folder is per-user so that different developers working on the game can have their UI folders wherever they want on their machine. You can also set a per-project folder for the UI resources. This is done by extending the CoherentPostProcessor class by setting a static const setting named ProjectUIResources:

```
public partial class CoherentPostProcessor {
    public static string ProjectUIResources = "relative/path/to/ui/resources";
}
```

The per-project path must be relative to the folder of the project and the extension class should live under the 'Editor' folder in Unity. This feature is very handy also if you build your game on machines that can't start Unity and you use the command line. The per-user setting overrides the per-project one so that developers can still put their resources wherever they want.

Warning

When using the "Build & run" option for Android, the required resources will **NOT** be packaged because this is done as a post-build step. Unity3D pushes the non-repacked APK first, and then executes the post-build step which results in an APK without UI resources and including unneeded files. To work around that, you should either use the "Build" option, which produces an APK on your computer that can be installed on a device using the ADB tool in the Android SDK, or generate an Eclipse project and run it from the IDE.

7.13 Click-to-focus Views - Desktop only

When the ClickToFocus property is enabled on a View, it will automatically take **all** the input focus when you click on it and lose it when you click somewhere else. When focused, all mouse and keyboard input will be forwarded to the View. "Click-to-focus" views have their ReceivesInput property managed by the CoherentUISystem and you should **NOT** set it manually. If you do so, you'll receive a warning message in Unity3D and the input forwarding behavior will be unexpected.

Warning

There is no way to prevent the standard Unity character controller scripts from moving the character, even when the input event is *used*. You have to manually disable your character controller when you want the user to type in in a view and stands still. For an explanation see the Menu And HUD sample.

38 Important points

Note

"Click-to-focus" views perform raycasts to obtain the object in the 3D world below the cursor. For a raycast to report the correct texture coordinates of the hitpoint, you need to set up a *Mesh Collider* on the objects with Coherent Browser Views placed.

"Click-to-focus" Views are useful in cases when you want keyboard input forwarded to a View regardless of the mouse position, e.g. input fields.

Note

To function properly, "Click-to-focus" views need to know which camera is the main camera in the scene. For simple scenes, this can be obtained from the Camera.main property in Unity3D. This is what Coherent Browser assumes is the main camera, and obtains it in the MonoBehaviour.OnEnable callback, which is executed when a scene is loaded. This is done only if there is no currently set camera for the m_Main-Camera field so it does not interfere with custom user code. For complex scenes with multiple cameras, however, it is up to you to set the public m_MainCamera field to the appropriate camera (also visible in the Inspector window).

Which CoherentUIViews receive input is up to your gameplay needs. Here we'll walk you through a simple script that you'll see used in the samples - it forwards input to the closest view under the cursor. First, it sets the ReceivesInput property to all views to false. Then it queries the CoherentUIView attached to the main camera (if any) whether the mouse is over a solid or transparent pixel (make sure to set the SupportClick-Through property of the HUD view to true to support this operation). If the mouse is over a solid pixel, then the HUD is focused and receives input. Otherwise, a raycast is generated that finds the object under the cursor. If that object has a CoherentUIView component, that's what gets the focus.

Here's the script itself:

```
#if UNITY_STANDALONE || UNITY_STANDALONE_WIN || UNITY_STANDALONE_OSX
#define COHERENT_UNITY_STANDALONE
#endif
using UnityEngine;
using System.Collections;
#if COHERENT_UNITY_STANDALONE || UNITY_EDITOR
public class ObjectPicker : MonoBehaviour {
    private Camera m_MainCamera;
    private CoherentUISystem m_UISystem;
    // Use this for initialization
    void Start () {
        m_MainCamera = GameObject.Find("Main Camera").GetComponent<Camera>();
        m_UISystem = Component.FindObjectOfType(typeof(CoherentUISystem)) as
      CoherentUISystem;
    // Update is called once per frame
    void Update () {
        if (m_UISystem.HasFocusedView)
        // Reset input processing for all views
        foreach (var item in m_UISystem.UIViews) {
            if (!item.ClickToFocus) {
                item.ReceivesInput = false;
        var cameraView = m_MainCamera.gameObject.GetComponent<CoherentUIView>();
        if (cameraView && !cameraView.ClickToFocus)
            var view = cameraView.View;
            if (view != null)
                var factorY = cameraView.Height / m_MainCamera.pixelHeight;
                //Normalize the view coordinates. We need this when we use view dimensions
                //are different than the camera ones
                var normX = Input.mousePosition.x / cameraView.Width;
                var normY = 1 - Input.mousePosition.y / cameraView.Height;
                //After the normalizations, the Normalized Y coordinate will be displaced because Y coords
```

```
//grow downwards and we have to put it back into the [0-1] range.
                //E.g. if the view height is two times smaller
                //than the camera height, the normalized Y coords will start from -1 and end to +1.
               //If the view's height is 4 times smaller, the normalized coords will start from -3 and end
      to +1
                //The formula puts the Y coord back in [0-1] range.
               normY = ( (normY * factorY) + (1 - factorY) ) / factorY;
                if (normX >= 0 && normX <= 1 && normY >= 0 && normY <= 1)
                    view.IssueMouseOnUIQuery(normX, normY);
                    view.FetchMouseOnUIQuery();
                    if (view.IsMouseOnView())
                        cameraView.ReceivesInput = true;
                        return;
               }
           }
        // Activate input processing for the view below the mouse cursor
       RaycastHit hitInfo;
          (Physics.Raycast(m_MainCamera.ScreenPointToRay(Input.mousePosition), out hitInfo))
            //Debug.Log (hitInfo.collider.name);
           CoherentUIView viewComponent = hitInfo.collider.gameObject.GetComponent(typeof(
     CoherentUIView)) as CoherentUIView;
            if (viewComponent == null)
               viewComponent = hitInfo.collider.gameObject.GetComponentInChildren(typeof(
     CoherentUIView)) as CoherentUIView;
            if (viewComponent != null && !viewComponent.ClickToFocus)
               viewComponent.ReceivesInput = true;
               viewComponent.SetMousePosition(
                    (int) (hitInfo.textureCoord.x * viewComponent.Width).
                    (int) (hitInfo.textureCoord.y * viewComponent.Height));
   }
#endif
```

To summarize, you can apply any logic you like for input forwarding - e.g. forward input to objects in the view frustum, HUD only, etc. Coherent Browser supports multiple focused views. View focus can be modified using the ReceivesInput property of CoherentUIView which is controlled only by the script code.

You can also mark views as "Click to focus" which makes them take all the focus when clicking them (and lose focus when clicking somewhere else). You should take care not to set the ReceivesInput property on "Click to focus"-enabled Views as it is automatically managed. Setting the ReceivesInput property on such views manually will result in unexpected behavior and will produce a warning message.

7.14 View Filters - Desktop only

Coherent Browser provides three types of filtering:

- Point Filtering applies point filtering to the view texture.
- · Linear Filtering applies linear filtering to the view texture.

7.15 Hit testing - Desktop only

40 Important points

Note

For and explanation about input forwarding for Mobile check Input Forwarding Mobile

Forwarding input to Views attached to the camera is straight-forward - you only have to mark your view as an input receiver using the ReceivesInput property of CoherentUIView. The mouse position will be obtained from the Input.mousePosition property.

If you want to forward an input event to a View that's attached on an object in the 3D world, you'll have to do a bit more work. You'll have to use a raycast to find the object below the cursor and then transform the texture coordinates of the hit point into the space of the Coherent Browser View. Note that Unity provides texture coordinates only when the object has a Mesh Collider component attached. The coordinates must be transformed from [0, 1] to [view.Width, view.Height]. This can usually be done simply by multiplying the coordinates by the dimensions of the View (which are available as properties). Then, you have to set the resulting coordinates to the CoherentUIView component using the SetMousePosition method. Check Input Forwarding for an example script that forwards input to the view on the object that is currently below the cursor. Note that in the samples the MeshCollider component has the same geometry as the renderable mesh. This may not always be true and in such cases you would have to make a transformation of the coordinates that works for you.

For a sample how hit testing works see the Menu and HUD sample.

7.16 Mobile Surface Views

Displaying Coherent Browser view on a surface is straightforward for Desktop platforms. Unfortunately the performance and API restrictions of the current platforms do not allow us to fully support views on surfaces for mobile. *Mobile Surface Views* allow displaying of HTML5 content on a surface in mobile games with the following limitations:

- the view must be explicitly updated using the MobileSurfaceView.UpdateView method.
- there is no input for the view. Input could be simulated using JavaScript.

To create a *Mobile Surface View*, simply add the component to a object with a renderer component. The Mobile-SurfaceView component will create a new texture for the renderer and replace the main texture of the material with the view.

See also the Mobile Surface Sample.

7.17 Logging

Coherent Browser logs are automatically redirected to the Unity console (or game log for built games) using the Debug.Log method. You can control the minimum severity of the Coherent Browser logs when initializing the Coherent Browser System.

7.18 Live Game Views

Note

Live Game Views are a Desktop-only feature.

Live Game Views are one of the most powerful yet easy to use features in Coherent Browser for Unity 3D. They allow you to have 3D rendered images (by a Unity3D Camera) as part of the UI itself. The images are automatically updated in a high-performance way and made available to the UI JavaScript code.

Via Live Game Views in a real game you can trivially have 3D animated unit portraits, animated items in the UI, 3D mini-maps, security cameras etc..

The steps to get a Live Game View are trivial:

7.19 Font Rendering 41

1. Add the Coherent Browser "Live Game View" Component to a GameObject that already has a Coherent Browser View.

- 2. Give the link a Name
- 3. Set the size
- 4. Drag a Camera that will send the data
- 5. (Optional) You can select a texture too in the Component. If you don't select a Camera this texture will be rendered instead. In this way you can send just textures in the UI.

The "Live Game View" Component represents a link between the View and a Unity Camera or a texture. When you attach it - it will automatically start sending the updated image drawn by the linked Camera to the JavaScript code of the page currently displayed by the View.

Every such link has a Name that is used to identify it inside the page's JS code. You can have as many Live Game Views attached to the same Coherent Browser View as you want.

After you press "Play", the Live Game View will be operational and everything the Camera "sees" will be available in the UI as an ImageData object.

To use it - add a "canvas" element in the page and a "onEngineImageDataUpdated" function to it. This function will be called every time the image is updated and the name will be passed so that you can identify just the one you need.

In the "onEngineImageDataUpdated" function you can do whatever you need with the image - draw it in the canvas, apply filters, write text etc..

This snippet shows a sample UI JavaScript function that draws the image in a "canvas" element and writes text on it-

```
window.onload = function() {
   var c = document.getElementById("myCanvas");
   c.onEngineImageDataUpdated = function (name, image) {
     var c = document.getElementById("myCanvas");
     var ctx = c.getContext("2d");

     ctx.clearRect(0, 0, c.width, c.height);
     ctx.putImageData(image, 0, 0);
     ctx.fillStyle = "white";
     ctx.font = "16pt Arial";
     ctx.fillText("Live Game View!", 15, 25);
   }
}
```

As you can see we just listen for when a new image has arrived and re-draw the content of the canvas named "my-Canvas". The "name" parameter received is the "Name" of the Live Game View as specified in the Unity Inspector and allows us to identify the different links.

Note

For a sample scene with Live Game Views check the "Sample_LiveGameViews" scene available in the Coherent Browser package.

7.19 Font Rendering

Coherent Browser uses ClearType on Microsoft Windows. This allows fonts to look the same way as they do in the operating system and the rest of applications.

However, there are fonts that look fuzzy in certain sizes when they are rendered with ClearType. Here is a screenshot of the Lato font using ClearType: 42 Important points

THE QUICK BROWN FOX JUMPS OVER THE LAZY DOG.

Figure 7.2: Lato font with ClearType

Coherent Browser has a CSS property -coherent-font-cleartype that gives you control over whether ClearType should be used or standard antialiasing. -coherent-font-cleartype has two values:

- on use ClearType if possible. This is the default value
- off do not use ClearType at all

To turn off ClearType for a certain element you can use

```
    Grumpy wizards make toxic brew for the evil Queen and Jack.
```

And here is the result with -coherent-font-cleartype: off:

THE QUICK BROWN FOX JUMPS OVER THE LAZY DOG.

Figure 7.3: Lato font without ClearType

Note that the result of using or turning off ClearType depends a lot on the font itself, the font size and weight.

Chapter 8

Unity Script Binding

8.1 Sample Unity Script Binding

This is a sample script that binds a function in Unity engine that is to be called from JavaScript. The interface used for the binding is exactly the same as in C#.

The first example shows how a manual binding is done.

```
#pragma strict
import Coherent.UI.Binding;
var m_View : CoherentUIView ;
// Use this for initialization
function Start ()
   m\_View = GetComponent(typeof(CoherentUIView)) as
     CoherentUIView;
    //Listen for the ReadyForBindings event
   m_View.Listener.ReadyForBindings += HandleReadyForBindings;
function HandleReadyForBindings ( frameId:int,
                                    path:String,
                                    isMainFrame : boolean)
    if (isMainFrame)
        /\star Bind FunctionInUnity so that JavaScript can call it \star/
       Debug.Log("Ready for bindings..");
       m_View.View.BindCall("CallFunctionInUnity", this.FunctionInUnity);
function FunctionInUnity()
    Debug.Log("SUCCESS! This function is called from Javascript!");
```

Here is another sample - the same code used to the binding in BindingSample, but in UnityScript and using the automatic binding feature of *Coherent Browser*.

```
#pragma strict
import Coherent.UI;
@Coherent.UI.Binding.CoherentType(Coherent.UI.Binding.PropertyBindingFlags.All)
class GameOptions extends System.ValueType
{
    var Backend : String;
    var Width : uint;
    var Height : uint;
    var Username : String;
    @Coherent.UI.Binding.CoherentProperty("NetworkPort")
    var NetPort : uint;
}
var m_View : CoherentUIView;
```

44 Unity Script Binding

```
var m_GameOptions : GameOptions;
function Start ()
    m_View = GetComponent(CoherentUIView);
    m_GameOptions = new GameOptions();
    m_GameOptions.Backend = "Unity3D";
    m_GameOptions.Width = 1024;
m_GameOptions.Height = 768;
    m_GameOptions.NetPort = 17777;
m_GameOptions.NetPort = 17777;
@Coherent.UI.CoherentMethod("ApplyOptions", false)
function ApplyOptions(options : GameOptions)
    m_View.View.TriggerEvent("gameConsole:Trace", options);
    var w : int = options.Width;
var h : int = options.Height;
    Screen.SetResolution(w, h, Screen.fullScreen);
@Coherent.UI.CoherentMethod("GetLatency")
function GetNetworkLatency()
    // not actual latency
    return UnityEngine.Random.Range(0, 1000);
@Coherent.UI.CoherentMethod("GetGameTime")
function GetGameTime()
    return Time.time;
@Coherent.UI.CoherentMethod("ViewReady", true)
function ViewReady()
    // show the options {\rm m\_View.View.TriggerEvent("OpenOptions", m\_GameOptions);}
```

Chapter 9

Coherent Browser Menu

Coherent Browser Menu Kit allows you to start immediately using *Coherent Browser* for the menus in your game. It also allows to create the menu and implement its logic without leaving Unity3D editor. This menu can be used for a quick prototype, as substitute for the final menus during development and even for the final game after some styling. You can see the menu in action in the *Sample_Menu* in the *CoherentUl/Samples/Scenes* folder.

To create a menu, you have to add the Coherent UIMenu component to any game object in the scene.

The properties of CoherentUIMenu are:

- View the CoherentUIView in which the menu should appear. If it is None CoherentUIMenu will look for its view in the same game object.
- MenuID the unique id of this menu in its view. This id is used internally by CoherentUIMenu, but can be used from your JavaScript code to manipulate the menu or to listen for its events. See the JavaScript API for more details.
- Parent the id of the element in which to show the menu. You can control the position of the menu by changing the position of the parent element.
- Visible whether the menu is visible by default or not. You can later change the visibility of the menu using the Show and Hide methods.
- Buttons the list of buttons in the menu. **Note**: currently the list of the buttons can not be changed after the menu has been created.

Then pick the CoherentUIView component in which the menu should be displayed, set its *ID* and parent element ID and add the buttons.

9.1 Binding actions to events

To add a button to the menu, simply increase the size of the *Buttons* array. Set its *Label* property to the label you want for the button. You can also mark the button as disabled by checking the *Disabled* property.

Note

Currently the enabled/disabled state of the buttons can not be changed after the menu has been created.

To make the button functional, edit the *Click* handler. It has three properties:

- Target the GameObject or MonoBehavior that is target for the event. It its value is *None*, the GameObject that owns the CoherentUIMenu component will be used.
- Method the name of the method or message to be called

46 Coherent Browser Menu

• IsMessage - if set to true, SendMessage will be used to execute all methods with name specified by Method in Target. Otherwise call a single method on the MonoBehavior specified by Target.

Here is how the final menu looks in the Unity3D Inspector:




Figure 9.1: Setting up CoherentUIMenu in the Inspector




Figure 9.2: Setting up CoherentUIMenu in the Inspector

9.2 Setting up the HTML

Using the Coherent Browser Menu requires some JavaScript and CSS styles to be present in the view.

The required stylesheets are:

```
<link rel="stylesheet" type="text/css" href="components/flat-ui-official/bootstrap/css/bootstrap.css" />
<link rel="stylesheet" type="text/css" href="components/flat-ui-official/css/flat-ui.css" />
<link rel="stylesheet" type="text/css" href="coherent/css/menu_style.css" />
```

And JavaScript resources:

```
<script type="text/javascript" src="coherent.js"></script>
<script type="text/javascript" src="coherent/js/game_menu.js"></script>
```

Note

Please note that game_menu.js depends on coherent.js, so it is included after coherent.js.

9.3 JavaScript API

The JavaScript API of the menu kit consist of the following events:

- cui.MenuButtonClicked triggered on button clicked with the *Id* of the menu and the *Label* of the button
- cui.ShowMenu triggered to show the menu with the menu ld
- cui . HideMenu triggered to hide the menu with the menu $\operatorname{\textit{Id}}$

You can attach to and trigger these events using the engine.on and engine.trigger functions.

Chapter 10

Namespace Index

10.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

nerent
nerent.UI
nerent.UI.Binding
Coherent Browser JavaScript interface. The engine module contains all functions for commu-
nication between the UI and the game / application

50 Namespace Index

Chapter 11

Hierarchical Index

11.1 Class Hierarchy

This in	heritance	list is	sorted	roughly,	but not	completel	y, al	phabetically	۷:

Coherent.UI.Binding.BoundObject	-
Coherent.UI.Button	
Coherent.UI.ButtonHandler	
Coherent.UI.Binding.CallbackArguments	
Coherent.UI.CertificatePrincipal	
Coherent.UI.ChildViewInfo	
Coherent.UI.ClientCertificateResponse	
Coherent.UI.Binding.CoherentProperty	
Coherent.UI.Binding.CoherentType	
CoherentUILiveGameView	
CoherentUISystem	
CoherentUIView	?
MobileSurfaceView	?
Coherent.UI.ContextError	?
Coherent.UI.ContextListener	?
Coherent.UI.ContextSettingsBase	?
Coherent.UI.ContextSettings	?
Coherent.UI.Download	?
Coherent.UI.EventModifiersState	?
Coherent.UI.EventMouseModifiersState	?
Coherent.UI.FactorySettingsBase	?
Coherent.UI.FactorySettings	?
Coherent.UI.FileHandler	?
Coherent.UI.FileSelectionParams	?
Coherent.UI.FileSelectRequest	?
Coherent.UI.HTTPHeader	?
Coherent.UI.ILogHandler	?
Coherent.UI.ImageData	?
Coherent.UI.Binding.InvalidValueCastException	?
Coherent.UI.KeyEventData	?
Coherent.UI.MediaStreamDevice	?
Coherent.UI.MediaStreamRequest	?
Coherent.UI.MouseEventData	?
Coherent.UI.ResourceData	?
Coherent.UI.ResourceResponse	?
Coherent.UI.SubscriptionError	?
Coherent.UI.SurfaceResponse	?

52 Hierarchical Index

Coherent.UI.TouchEventData	??
Coherent.UI.Binding.UnsupportedPrimitiveTypeException	??
Coherent.UI.URLRequestBase	??
Coherent.UI.URLRequest	??
Coherent.UI.Binding.Value	??
Coherent.UI.Binding.ValueObject	??
Coherent.UI.View	??
Coherent.UI.BrowserView	??
Coherent.UI.ViewContext	??
Coherent.UI.ViewError	??
Coherent.UI.ViewInfo	??
Coherent.UI.ViewListenerBase	??
Coherent.UI.BrowserViewListenerBase	??
Coherent.UI.BrowserViewListener	??
Coherent.UI.ViewListener	??

Chapter 12

Class Index

12.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Conerent. Ut. Binding. Bound Object	
Wrapper class for .Net objects exposed to Coherent Browser	??
Coherent.UI.BrowserView	
Class that encapsulates a browser Coherent::UI::View	??
Coherent.UI.BrowserViewListener	
Interface that allows clients to listen to Coherent::UI::ViewListener	??
Coherent.UI.BrowserViewListenerBase	
Interface all browser view listeners inherit. For an easier to use interface inherit instead. Coherent::UI::BrowserViewListener	??
Coherent.UI.Button	
Describes a button in a CoherentUIMenu instance	??
Coherent.UI.ButtonHandler	
Handler for button related events	??
Coherent.UI.Binding.CallbackArguments	
Holds the arguments for the generic callback not handled by a registered delegate	??
Coherent.UI.CertificatePrincipal	
Represents certificate principal.	??
Coherent.UI.ChildViewInfo	
Helper structure for creating child views.	??
Coherent.UI.ClientCertificateResponse	
Class used to respond to client certificate request from a https server	??
Coherent.UI.Binding.CoherentProperty	
Specify a property / field or method visible to Coherent Browser	??
Coherent.UI.Binding.CoherentType	
Specify which properties and fields of a type are visible to Coherent Browser	??
CoherentUILiveGameView	
Component that needs to be attached to a camera and creates a Coherent Browser Live Game	
View	??
CoherentUISystem	
Component controlling the CoherentUI System	??
CoherentUIView	
Component containing a Coherent Browser view.	??
Coherent.UI.ContextError	
Encapsulates a context-related error.	??
Coherent.UI.ContextListener	
Abstract interface to listen to Context-related events.	??
Coherent.UI.ContextSettings	
Encapsulates the settings of the	??

54 Class Index

Coherent.UI.ContextSettingsBase	
Encapsulates the settings of the	??
Coherent.UI.Download	
Encapsulates a download task	??
Coherent.UI.EventModifiersState	
The state of the key modifiers when an event happens.	??
Coherent.UI.EventMouseModifiersState	
The state of the mouse modifiers when an event happens.	??
Coherent.UI.FactorySettings	
Encapsulates the settings of the UIFactory.	??
Coherent.UI.FactorySettingsBase	
Encapsulates the settings of the UIFactory.	??
Coherent.UI.FileHandler	
Abstract interface that allows clients to provide their own file-handling functionality	??
Coherent.UI.FileSelectionParams	
Parameters for file selection request	??
Coherent.UI.FileSelectRequest	
File selection request.	??
Coherent.UI.HTTPHeader	• •
Encapsulates a HTTP header field with its content.	??
Coherent.UI.ILogHandler	
	??
Interface to allow custom logging.	"
Coherent.UI.ImageData	00
This class represents a link to a	??
Coherent.UI.Binding.InvalidValueCastException	
Thrown when casting a Value to an incompatible type	??
Coherent.UI.KeyEventData	
A keyboard event.	??
Coherent.UI.MediaStreamDevice	
Represents a media stream device.	??
Coherent.UI.MediaStreamRequest	
Represents a request for media stream.	??
MobileSurfaceView	
Component containing a Coherent Browser view for surfaces on mobile platforms	??
Coherent.UI.MouseEventData	
A mouse event	??
Coherent.UI.ResourceData	
Abstract interface providing data for storing resources	??
Coherent.UI.ResourceResponse	
Abstract interface for responding to read resource requests.	??
Coherent.UI.SubscriptionError	
Encapsulates a subscription-check-related error.	??
Coherent.UI.SurfaceResponse	
Interface that signals for creation of rendering surfaces.	??
Coherent.UI.TouchEventData	• •
A touch event.	??
Coherent.UI.Binding.UnsupportedPrimitiveTypeException	
Thrown when trying to bind a value of unsupported primitive type such as long	??
Coherent.UI.URLRequest	??
represents a single URL request Allows monitoring and modifications of URL requests	"
Coherent.UI.URLRequestBase	
represents a single URL request (read-only) Allows monitoring of URL requests	??
Coherent.UI.Binding.Value	
Type for representing generic JavaScript values	??
Coherent.UI.Binding.ValueObject	_
Class for compound JavaScript objects, behaves like a Dictionary <string, value=""></string,>	??
Coherent.UI.View	
Class that encapsulates a UI	??

12.1 Class List 55

Coherent.UI.ViewContext	
Encapsulates basic	??
Coherent.UI.ViewError	
Encapsulates a view-related error.	??
Coherent.UI.ViewInfo	
Encapsulates the options of a	??
Coherent.UI.ViewListener	
Interface that allows clients to listen to	??
Coherent.UI.ViewListenerBase	
Interface all view listeners inherit. For an easier to use interface inherit instead Coherent::UI::-	
ViewListener	??

56 Class Index

Chapter 13

Namespace Documentation

13.1 Package Coherent

Namespaces

package UI

13.2 Package Coherent.UI

Namespaces

· package Binding

Classes

· class HTTPHeader

Encapsulates a HTTP header field with its content.

class BrowserView

Class that encapsulates a browser Coherent::UI::View

· class BrowserViewListener

Interface that allows clients to listen to Coherent::UI::ViewListener

• class BrowserViewListenerBase

Interface all browser view listeners inherit. For an easier to use interface inherit instead. Coherent::UI::BrowserView-Listener

· class CertificatePrincipal

Represents certificate principal.

· class ChildViewInfo

Helper structure for creating child views.

• class ClientCertificateResponse

Class used to respond to client certificate request from a https server.

class ContextError

Encapsulates a context-related error.

· class ContextListener

Abstract interface to listen to Context-related events.

class ContextSettings

Encapsulates the settings of the

class ContextSettingsBase

Encapsulates the settings of the

class Download

Encapsulates a download task.

· class EventModifiersState

The state of the key modifiers when an event happens.

class EventMouseModifiersState

The state of the mouse modifiers when an event happens.

class FactorySettings

Encapsulates the settings of the UIFactory.

class FactorySettingsBase

Encapsulates the settings of the UIFactory.

· class FileHandler

Abstract interface that allows clients to provide their own file-handling functionality.

• class FileSelectionParams

Parameters for file selection request.

· class FileSelectRequest

File selection request.

· class ILogHandler

Interface to allow custom logging.

class ImageData

This class represents a link to a

class KeyEventData

A keyboard event.

• class MediaStreamDevice

Represents a media stream device.

• class MediaStreamRequest

Represents a request for media stream.

class MouseEventData

A mouse event.

· class ResourceData

Abstract interface providing data for storing resources.

class ResourceResponse

Abstract interface for responding to read resource requests.

class SubscriptionError

Encapsulates a subscription-check-related error.

· class SurfaceResponse

Interface that signals for creation of rendering surfaces.

class TouchEventData

A touch event.

class URLRequest

represents a single URL request Allows monitoring and modifications of URL requests

• class URLRequestBase

represents a single URL request (read-only) Allows monitoring of URL requests

class View

Class that encapsulates a UI

· class ViewContext

Encapsulates basic

class ViewError

Encapsulates a view-related error.

· class ViewInfo

Encapsulates the options of a

· class ViewListener

Interface that allows clients to listen to

· class ViewListenerBase

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener

· class ButtonHandler

Handler for button related events

· class Button

Describes a button in a CoherentUIMenu instance

Enumerations

· enum CertificateStatus

Enum containing the possible certificate validation errors.

```
    enum ContextErrorType {
        ContextErrorType.CE_Success,
        ContextErrorType.CE_InternalError,
        ContextErrorType.CE_InvalidKey,
        ContextErrorType.CE_MissingComponent,
        ContextErrorType.CE_VersionMismatch,
        ContextErrorType.CE_GPUProcessCrash,
        ContextErrorType.CE_GPUProcessDeviceMismatch }
```

Context-related error-codes.

enum CursorTypes

Enum containing all the cursor types that a view can signal.

enum Direct3DInterfaceType

Types of interface used for DirectX.

enum DownloadErrorType {
 DownloadErrorType.DET_Success,
 DownloadErrorType.DET_DownloadOperationFailed }

• enum FileSelectionMode

Enumeration for file selection modes.

enum JavaScriptMessageType

Enum containing the possible types of a javascript message.

enum MediaStreamType

Enumeration of media stream types.

enum RenderingDeviceType

Types of rendering backend.

enum ScriptCallErrorType {
 ScriptCallErrorType.SCE_Success,
 ScriptCallErrorType.SCE_ArgumentType,
 ScriptCallErrorType.SCE_NoSuchMethod,
 ScriptCallErrorType.SCE_NoResult }

enum SubscriptionErrorType {
 SubscriptionErrorType.SET_Success,
 SubscriptionErrorType.SET_SuccessNotify,
 SubscriptionErrorType.SET_OfflineGracePeriod,
 SubscriptionErrorType.SET_Error }

enum TextInputControlType

Enum containing the text input types reported for IME.

enum UserAgentType

Predefined values for the used User Agent. If you select "Custom" you also have to set the CustomUserAgentString If you select "CustomBrowserName" you have to set the CustomUserAgentString with valid name of the User Agent.

enum ViewErrorType {
 ViewErrorType.VE_Success,
 ViewErrorType.VE_FailedCreation,
 ViewErrorType.VE_FailedRenderingCreation,
 ViewErrorType.VE_ClickThroughFailed,
 ViewErrorType.VE_InvalidPath,
 ViewErrorType.VE_ChildCompositionFailed,
 ViewErrorType.VE_InvalidCall,
 ViewErrorType.VE_FrameAlreadyInFlight,
 ViewErrorType.VE_FrameNotReady,
 ViewErrorType.VE_FrameNotRequeted,
 ViewErrorType.VE_AbnormalTermination,
 ViewErrorType.VE_QueryNotReady }

View-related error codes.

enum ViewType

Enum containing the possible view types.

13.2.1 Enumeration Type Documentation

13.2.1.1 enum Coherent.UI.CertificateStatus

Enum containing the possible certificate validation errors.

13.2.1.2 enum Coherent.UI.ContextErrorType

Context-related error-codes.

Enumerator

- CE_Success Indicates no error.
- CE_InternalError Indicates a serious context internal error.
- CE_InvalidKey Indicates that the user supplied an invalid activation key for this version of the product.
- CE_MissingComponent Indicates that a component required by Coherent Browser is missing.
- **CE_VersionMismatch** Indicates that there is a mismatch between the Coherent Browser dynamic library and the Coherent Browser Host executable.
- CE_GPUProcessCrash Indicates that the GPU process has crashed.
- **CE_GPUProcessDeviceMismatch** Indicates that the GPU process is on different GPU device than the current process.

13.2.1.3 enum Coherent.UI.CursorTypes

Enum containing all the cursor types that a view can signal.

13.2.1.4 enum Coherent.UI.Direct3DInterfaceType

Types of interface used for DirectX.

13.2.1.5 enum Coherent.UI.DownloadErrorType

Enumerator

DET_Success Indicates everything went fine.

DET_DownloadOperationFailed Indicates the download operation failed.

13.2.1.6 enum Coherent.UI.FileSelectionMode

Enumeration for file selection modes.

13.2.1.7 enum Coherent.UI.JavaScriptMessageType

Enum containing the possible types of a javascript message.

13.2.1.8 enum Coherent.UI.MediaStreamType

Enumeration of media stream types.

13.2.1.9 enum Coherent.UI.RenderingDeviceType

Types of rendering backend.

13.2.1.10 enum Coherent.UI.ScriptCallErrorType

Enumerator

SCE_Success Indicates that the call was successful.

SCE_ArgumentType Indicates that a script provided argument has different type than the one expected.

SCE_NoSuchMethod Indicates that there is no such method.

SCE_NoResult Indicates that there is no result for this call.

13.2.1.11 enum Coherent.UI.SubscriptionErrorType

Enumerator

SET_Success Indicates everything went fine.

SET_SuccessNotify Indicates everything went fine and the user should be notified.

SET_OfflineGracePeriod Indicates that the subscribed client is offline and is granted a grace period to reactivate.

SET_Error Indicates some type of error. SubscriptionError::Error holds more information.

13.2.1.12 enum Coherent.UI.TextInputControlType

Enum containing the text input types reported for IME.

13.2.1.13 enum Coherent.UI.UserAgentType

Predefined values for the used User Agent. If you select "Custom" you also have to set the CustomUserAgentString If you select "CustomBrowserName" you have to set the CustomUserAgentString with valid name of the User Agent.

13.2.1.14 enum Coherent.UI.ViewErrorType

View-related error codes.

Enumerator

VE_Success Indicates no error.

- VE_FailedCreation Indicates failure to create a view.
- VE_FailedRenderingCreation Indicates failure to create the rendering resources associated with a view.
- VE_ClickThroughFailed Indicates an error during click-through a query.
- VE_InvalidPath Indicates that the view was redirected to an invalid path.
- VE_ChildCompositionFailed Indicates that the composition of a child widget failed.
- VE_InvalidCall Indicates a call on a type of view that is not called.
- **VE_FrameAlreadyInFlight** Indicates that a frame is already in-flight.
- VE_FrameNotReady Indicates that a frame is still being rendered.
- VE_FrameNotRequeted Indicates that a new frame was not requested.
- **VE_AbnormalTermination** Indicates an abnormal termination of the view.
- VE_QueryNotReady Indicates that the mouse query hasn't finished yet.

13.2.1.15 enum Coherent.UI.ViewType

Enum containing the possible view types.

13.3 Package Coherent.UI.Binding

Classes

· class CallbackArguments

Holds the arguments for the generic callback not handled by a registered delegate

struct BoundObject

Wrapper class for .Net objects exposed to Coherent Browser

class CoherentProperty

Specify a property / field or method visible to Coherent Browser

class CoherentType

Specify which properties and fields of a type are visible to Coherent Browser

class UnsupportedPrimitiveTypeException

Thrown when trying to bind a value of unsupported primitive type such as long

class InvalidValueCastException

Thrown when casting a Value to an incompatible type

· class Value

Type for representing generic JavaScript values

· class ValueObject

Class for compound JavaScript objects, behaves like a Dictionary<string, Value>

Enumerations

enum PropertyBindingFlags {
 PropertyBindingFlags.Explicit = 0,
 PropertyBindingFlags.Instance = 1,
 PropertyBindingFlags.Static = 2,
 PropertyBindingFlags.All = 3 }

Determines the set of the bound properties for this type

```
    enum ValueType {
        ValueType.Null,
        ValueType.Boolean,
        ValueType.Integer,
        ValueType.UInteger,
        ValueType.String,
        ValueType.String,
        ValueType.Array,
        ValueType.Object,
        ValueType.SByte = 10,
        ValueType.Byte,
        ValueType.Char }
```

Specifies the type of Coherent.UI.Binding.Value

13.3.1 Enumeration Type Documentation

13.3.1.1 enum Coherent.UI.Binding.PropertyBindingFlags

Determines the set of the bound properties for this type

Enumerator

Explicit Bind only properties and fields with CoherentProperty attribute

Instance Bind only instance properties and fields

Static Bind only static properties and fields

All Bind all instance and static properties and fields

13.3.1.2 enum Coherent.UI.Binding.ValueType

Specifies the type of Coherent.UI.Binding.Value

Enumerator

Null empty value

Boolean boolean value

Integer integer value

UInteger unsigned integer value

Number double value

String string value

Array array value

Object object value

SByte signed byte value

Byte unsigned byte value

Char char value

13.4 engine Namespace Reference

Coherent Browser JavaScript interface. The engine module contains all functions for communication between the UI and the game / application.

Functions

undefined on (String name, Function callback, Object context)

Register handler for and event.

• undefined off (String name, Function callback, Object context)

Remove handler for an event.

undefined trigger (String name,...)

Trigger an event This function will trigger any C++ handler registered for this event with Coherent::UI::View-::RegisterForEvent

• Deferred createDeferred ()

Create a new deferred object. Use this to create deferred / promises that can be used together with engine.call.

• Deferred call (String name,...)

Call asynchronously a C++ handler and retrieve the result The C++ handler must have been registered with Coherent::UI::View::BindCall

13.4.1 Detailed Description

Coherent Browser JavaScript interface. The engine module contains all functions for communication between the UI and the game / application.

13.4.2 Function Documentation

13.4.2.1 Deferred engine::call (String name, ...)

Call asynchronously a C++ handler and retrieve the result The C++ handler must have been registered with Coherent::UI::View::BindCall

Parameters

name	name of the C++ handler to be called
	any extra parameters to be passed to the C++ handler

Returns

deferred object whose promise is resolved with the result of the C++ handler

13.4.2.2 Deferred engine::createDeferred ()

Create a new deferred object. Use this to create deferred / promises that can be used together with engine.call.

Returns

a new deferred object

See Also

CustomizingPromises

13.4.2.3 undefined engine::off (String name, Function callback, Object context)

Remove handler for an event.

Parameters

name	name of the event, by default removes all events
callback	the callback function to be removed, by default removes all callbacks for a given event
context	this context for the function, by default all removes all callbacks, regardless of context

Warning

Removing all handlers for engine will remove some *Coherent Browser* internal events, breaking some functionality.

13.4.2.4 undefined engine::on (String name, Function callback, Object context)

Register handler for and event.

Parameters

name	name of the event
callback	callback function to be executed when the event has been triggered
context	this context for the function, by default the engine object

13.4.2.5 undefined engine::trigger (String name, ...)

Trigger an event This function will trigger any C++ handler registered for this event with Coherent::UI::View-::RegisterForEvent

Parameters

name	name of the event
	any extra arguments to be passed to the event handlers

Names	pace	Docur	ment	ation

Chapter 14

Class Documentation

14.1 Coherent.UI.Binding.BoundObject Struct Reference

Wrapper class for .Net objects exposed to Coherent Browser

Static Public Member Functions

static BoundObject BindMethods (object target)
 expose object's methods to Coherent Browser

14.1.1 Detailed Description

Wrapper class for .Net objects exposed to Coherent Browser

14.1.2 Member Function Documentation

14.1.2.1 static BoundObject Coherent.UI.Binding.BoundObject.BindMethods (object target) [inline], [static]

expose object's methods to Coherent Browser


Parameters

target	instance

Returns

14.2 Coherent.UI.BrowserView Class Reference

Class that encapsulates a browser Coherent::UI::View Inheritance diagram for Coherent.UI.BrowserView:



Public Member Functions

override ViewType GetViewType ()

Get The type of this view.

virtual void GoBack ()

Navigates back to the previous URL, if any.

virtual void GoForward ()

Navigates to the next URL, if any (i.e. available after navigating back)

• virtual void GetHistory ()

Issues a request for obtaining the navigation history for the view. BrowserViewListener::OnHistoryObtained

14.2.1 Detailed Description

Class that encapsulates a browser Coherent::UI::View

14.2.2 Member Function Documentation

```
14.2.2.1 virtual void Coherent.UI.BrowserView.GetHistory() [inline], [virtual]
```

Issues a request for obtaining the navigation history for the view. BrowserViewListener::OnHistoryObtained

```
14.2.2.2 override ViewType Coherent.UI.BrowserView.GetViewType ( ) [inline], [virtual]
```

Get The type of this view.

Returns

the type of the view

Reimplemented from Coherent.UI.View.

```
14.2.2.3 virtual void Coherent.UI.BrowserView.GoBack() [inline], [virtual]
```

Navigates back to the previous URL, if any.


```
14.2.2.4 virtual void Coherent.UI.BrowserView.GoForward() [inline], [virtual]
```

Navigates to the next URL, if any (i.e. available after navigating back)

14.3 Coherent.UI.BrowserViewListener Class Reference

Interface that allows clients to listen to Coherent::UI::ViewListener

Inheritance diagram for Coherent.UI.BrowserViewListener:



Public Member Functions

override void Release ()

Called when the listener is no longer needed by the UI context.

override void OnViewCreated (View view)

Called when the requested

override void OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height)

Called when a new surface has been drawn and is ready to use by the client.

 override void OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTP-Header[] headers)

Called when a frame has been successfully loaded.

override void OnFailLoad (int frameld, string validatedPath, bool isMainFrame, string error)

Called when a frame has been failed loading.

• override void OnURLRequest (URLRequest request)

Called before an URL request is made. The default implementation allows all requests.

• override void OnReadyForBindings (int frameld, string path, bool isMainFrame)

Called when a frame is ready for bindings.

override void OnBindingsReleased (int frameld, string path, bool isMainFrame)

Called when the bindings for frame are released.

• override void OnStartLoading ()

Called when a new path has started loading.

override void OnStopLoading ()

Called when all load operations have completed.

override void OnNavigateTo (string path)

Called when the view starts navigation to a new path.

override void OnError (ViewError error)

Called when an error occurs for this specific

 override void OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line)

Called when a message is sent from a script running in this specific

override void OnCursorChanged (CursorTypes cursor)

Called when the cursor has changed internally in the

· override void OnCallback (string eventName, Binding.CallbackArguments arguments)

Called by the UI when there is no registered handler for this event.

• override void OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType)

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

override void OnGetAuthCredentials (bool isProxy, string host, uint port, string realm, string scheme)

Called when a view requires authentication credentials.

• override void CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response)

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8_UNORM

· override void DestroySurface (CoherentHandle surface, bool usesSharedMemory)

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering.

 override void OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateError-Response response)

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

override void OnRequestMediaStream (MediaStreamRequest request)

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

override void OnClientCertificateRequested (string url, ClientCertificateResponse response)

Called when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

override void OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline)

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

override void OnCaretRectChanged (uint x, uint y, uint width, uint height)

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

override void OnIMEShouldCancelComposition ()

Called when the user must cancel the IME composition due to an event in the

override void OnFileSelectRequest (FileSelectRequest request)

Called when the view requests file selection. It could be either single file, directory or multiple files.

override bool OnCanCreateChildWindow (string openerUrl, string targetUrl, ChildViewInfo childViewInfo)

Called when the view wants to open a new window.

override void OnAudioStreamCreated (int streamId, int channels, int bitDepth, int frequency)

Called when a new WebAudio stream is created. This is usually when the page is loading (for < audio> HTML tags).

override void OnAudioStreamPlay (int streamId)

Called when a WebAudio stream is played.

override void OnAudioStreamPause (int streamId)

Called when a WebAudio stream is stopped.

override void OnAudioStreamClose (int streamId)

Called when a WebAudio stream is closed. This is usually called when the page is unloading.

override void OnPrintToPDFReady (IntPtr buffer, uint bufferSize)

Called when pdf data is needed.

Events

CoherentUI_OnViewCreated ViewCreated

Fired when the requested

· CoherentUI OnDraw Draw

Fired when a new surface has been drawn and is ready to use by the client.

CoherentUI_OnFinishLoad FinishLoad

Fired when a frame has been successfully loaded.

· CoherentUI OnFailLoad FailLoad

Fired when a frame has been failed loading.

CoherentUI_OnURLRequest URLRequest

Fired before an URL request is made. The default implementation allows all requests.

CoherentUI_OnReadyForBindings ReadyForBindings

Fired when a frame is ready for bindings.

CoherentUI_OnBindingsReleased BindingsReleased

Fired when the bindings for frame are released.

CoherentUI_OnStartLoading StartLoading

Fired when a new path has started loading.

CoherentUI OnStopLoading StopLoading

Fired when all load operations have completed.

CoherentUI_OnNavigateTo NavigateTo

Fired when the view starts navigation to a new path.

CoherentUI_OnError Error

Fired when an error occurs for this specific

CoherentUI OnScriptMessage ScriptMessage

Fired when a message is sent from a script running in this specific

CoherentUI_OnCursorChanged CursorChanged

Fired when the cursor has changed internally in the

CoherentUI OnCallback Callback

Fired by the UI when there is no registered handler for this event.

CoherentUI_OnJavaScriptMessage JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

CoherentUI OnGetAuthCredentials GetAuthCredentials

Fired when a view requires authentication credentials.

• CoherentUI_OnCertificateError CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

• CoherentUI OnRequestMediaStream RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

• CoherentUI_OnClientCertificateRequested ClientCertificateRequested

Fired when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

CoherentUI_OnTextInputTypeChanged TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

CoherentUI OnCaretRectChanged CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

• CoherentUI_OnIMEShouldCancelComposition IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

CoherentUI OnFileSelectRequest FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

• CoherentUI OnAudioStreamCreated AudioStreamCreated

Fired when a new WebAudio stream is created. This is usually when the page is loading (for < audio> HTML tags).

CoherentUI OnAudioStreamPlay AudioStreamPlay

Fired when a WebAudio stream is played.

• CoherentUI OnAudioStreamPause AudioStreamPause

Fired when a WebAudio stream is stopped.

CoherentUI_OnAudioStreamClose AudioStreamClose

Fired when a WebAudio stream is closed. This is usually called when the page is unloading.

CoherentUI_OnPrintToPDFReady PrintToPDFReady

Fired when pdf data is needed.

Additional Inherited Members

14.3.1 Detailed Description

Interface that allows clients to listen to Coherent::UI::ViewListener

14.3.2 Member Function Documentation

14.3.2.1 override void Coherent.UI.BrowserViewListener.CreateSurface (bool *sharedMemory*, uint *width*, uint *height*, SurfaceResponse *response*) [inline], [virtual]

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8 UNORM

Parameters

sharedMemory	true if the surface should be created in shared memory (4 $*$ width $*$ height bytes); false if a
	shared texture must be created.
width	the width of the surface in pixels
height	the height of the surface in pixels
response	
	object to hold the response when the surface is created or fails it's creation - must be signaled

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.2 override void Coherent.UI.BrowserViewListener.DestroySurface (CoherentHandle *surface*, bool *usesSharedMemory*) [inline], [virtual]

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering.

Parameters

surface	handle to the surface
usesShared-	determines whether the surface parameter is a handle to shared memory or shared texture
Memory	

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.3 override void Coherent.UI.BrowserViewListener.OnAudioStreamClose (int streamId) [inline], [virtual]

Called when a WebAudio stream is closed. This is usually called when the page is unloading.

Parameters

streamld	the ID of the stream that is closed

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.4 override void Coherent.UI.BrowserViewListener.OnAudioStreamCreated (int streamld, int channels, int bitDepth, int frequency) [inline], [virtual]

Called when a new WebAudio stream is created. This is usually when the page is loading (for <audio> HTML tags).

Parameters

streamld	the generated ID for the new stream
channels	the number of channels in the stream
bitDepth	bits per sample in the stream
frequency	the audio stream frequency, in Hz

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.5 override void Coherent.UI.BrowserViewListener.OnAudioStreamPause (int streamId) [inline], [virtual]

Called when a WebAudio stream is stopped.

Parameters

streamId	the ID of the stream that is stopped
----------	--------------------------------------

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.6 override void Coherent.UI.BrowserViewListener.OnAudioStreamPlay(int streamId) [inline], [virtual]

Called when a WebAudio stream is played.

Parameters

streamld	the ID of the stream that is played

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.7 override void Coherent.UI.BrowserViewListener.OnBindingsReleased (int frameld, string path, bool isMainFrame) [inline], [virtual]

Called when the bindings for frame are released.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.8 override void Coherent.Ul.BrowserViewListener.OnCallback (string eventName, Binding.CallbackArguments arguments) [inline], [virtual]

Called by the UI when there is no registered handler for this event.

Parameters

eventName	name of the event
arguments	arguments of the event invocation

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.9 override bool Coherent.UI.BrowserViewListener.OnCanCreateChildWindow (string *openerUrl*, string *targetUrl*, ChildViewInfo childViewInfo) [inline], [virtual]

Called when the view wants to open a new window.

Parameters

openerUrl	the URL that wants to open the new window
targetUrl	the target URL of the new window
childViewInfo	structure that the user should fill in if she's about to allow new view creation

Returns

true if you allow the creation of a new window, false otherwise (if false, the childViewInfo parameter is ignored)

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.10 override void Coherent.UI.BrowserViewListener.OnCaretRectChanged (uint x, uint y, uint width, uint height) [inline], [virtual]

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

Parameters

the	x position of the selection caret
the	y position of the selection caret
the	width of the selection caret
the	height of the selection caret

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.11 override void Coherent.UI.BrowserViewListener.OnCertificateError (string *url*, CertificateStatus *status*, Certificate *certificate*, CertificateErrorResponse *response*) [inline], [virtual]

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

Parameters

url	the url of the request
status	the error status of the certificate
certificate	the certificate details. This pointer will be valid only for this call
response	object to signal whether to continue loading the URL. This pointer will be valid only for this call

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.12 override void Coherent.UI.BrowserViewListener.OnClientCertificateRequested (string *url*, ClientCertificateResponse *response*) [inline], [virtual]

Called when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

Parameters

url	the url of the request
response	object used to provide certificate information or to cancel the request.

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.13 override void Coherent.UI.BrowserViewListener.OnCursorChanged (CursorTypes *cursor*) [inline], [virtual]

Called when the cursor has changed internally in the

Parameters

cursor	the new cursor

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.14 override void Coherent.UI.BrowserViewListener.OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height) [inline], [virtual]

Called when a new surface has been drawn and is ready to use by the client.

Parameters

handle	a handle to one of the buffers created by CreateSurface. May be a shared memory buffer or a shared texture depending on the way the View was created. The handle is valid only during this call
usesShared-	determines whether the handle parameter is a handle to shared memory or shared texture
Memory	
width	the width of the surface
height	the height of the surface

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.15 override void Coherent.UI.BrowserViewListener.OnError (ViewError error) [inline], [virtual]

Called when an error occurs for this specific

Parameters

error	error description

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.16 override void Coherent.UI.BrowserViewListener.OnFailLoad (int *frameld*, string *validatedPath*, bool *isMainFrame*, string *error*) [inline], [virtual]

Called when a frame has been failed loading.

Parameters

frameld	the id of the frame
validatedPath	the path in the frame
isMainFrame	true if this is the main frame of the View
error	error message for the failure

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.17 override void Coherent.UI.BrowserViewListener.OnFileSelectRequest (FileSelectRequest request) [inline], [virtual]

Called when the view requests file selection. It could be either single file, directory or multiple files.

Parameters

request	contains the file selection params for the request

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.18 override void Coherent.UI.BrowserViewListener.OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTPHeader[] headers) [inline], [virtual]

Called when a frame has been successfully loaded.

Parameters

frameld	the id of the loaded frame
validatedPath	the path loaded in the frame

isMainFrame	true if this is the main frame of the View
statusCode	the status code of the response
headers	an array of header fields
headersCount	the count of items in the headers array

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.19 override void Coherent.UI.BrowserViewListener.OnGetAuthCredentials (bool *isProxy*, string *host*, uint *port*, string *realm*, string *scheme*) [inline],[virtual]

Called when a view requires authentication credentials.

Parameters

isProxy	whether the request came from a server or a proxy
host	the host which triggered the request
port	the port at which the request was triggered
realm	realm of the authentication challenge. Encoded in UTF-8
scheme	the authentication scheme used, e.g. "basic" or "digest". Encoded in ASCII

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.20 override void Coherent.UI.BrowserViewListener.OnIMEShouldCancelComposition() [inline], [virtual]

Called when the user must cancel the IME composition due to an event in the

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.21 override void Coherent.UI.BrowserViewListener.OnJavaScriptMessage (string *message*, string *defaultPrompt*, string *frameUrl*, int *messageType*) [inline], [virtual]

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

Parameters

message	the JavaScript message
defaultPrompt	the default value of the prompt text box, in case the message type is prompt
frameUrl	the URL which created the message
messageType	the type of the message (alert/confirm/prompt)

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.22 override void Coherent.UI.BrowserViewListener.OnNavigateTo (string path) [inline], [virtual]

Called when the view starts navigation to a new path.

Parameters

path L	URL that the view is navigating to
----------	------------------------------------

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.23 override void Coherent.UI.BrowserViewListener.OnPrintToPDFReady (IntPtr buffer, uint bufferSize) [inline], [virtual]

Called when pdf data is needed.

Parameters

buffer	the container of the pdf data
bufferSize	size of the buffer

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.24 override void Coherent.UI.BrowserViewListener.OnReadyForBindings (int frameld, string path, bool isMainFrame)
[inline], [virtual]

Called when a frame is ready for bindings.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.25 override void Coherent.UI.BrowserViewListener.OnRequestMediaStream (MediaStreamRequest request) [inline], [virtual]

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

Parameters

request	contains the available media streams for the request

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.26 override void Coherent.Ul.BrowserViewListener.OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line) [inline], [virtual]

Called when a message is sent from a script running in this specific

Parameters

level	message level
message	the text of the message
sourceld	id of the script (usually file name)
line	the number of the line in which the message was sent

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.27 override void Coherent.UI.BrowserViewListener.OnStartLoading() [inline], [virtual]

Called when a new path has started loading.

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.28 override void Coherent.UI.BrowserViewListener.OnStopLoading() [inline], [virtual]

Called when all load operations have completed.

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.29 override void Coherent.Ul.BrowserViewListener.OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline) [inline], [virtual]

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

Parameters

type	the type of the currently focused text input control by the user
canCompose-	if the IME composition could be performed in-line in the control
Inline	

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.30 override void Coherent.UI.BrowserViewListener.OnURLRequest (URLRequest request) [inline], [virtual]

Called before an URL request is made. The default implementation allows all requests.

Parameters

request	the URLRequest object that can be used to modify the request. This pointer will be valid only
	for this call

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.31 override void Coherent.UI.BrowserViewListener.OnViewCreated (View view) [inline], [virtual]

Called when the requested

Parameters

view	the instance of the view containing all manipulation methods

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.2.32 override void Coherent.UI.BrowserViewListener.Release() [inline], [virtual]

Called when the listener is no longer needed by the UI context.

Reimplemented from Coherent.UI.ViewListenerBase.

14.3.3 Event Documentation

14.3.3.1 CoherentUI_OnAudioStreamClose Coherent.UI.BrowserViewListener.AudioStreamClose

Fired when a WebAudio stream is closed. This is usually called when the page is unloading.

14.3.3.2 CoherentUI_OnAudioStreamCreated Coherent.UI.BrowserViewListener.AudioStreamCreated

Fired when a new WebAudio stream is created. This is usually when the page is loading (for <audio> HTML tags).

 $14.3.3.3 \quad Coherent UI_On Audio Stream Pause\ Coherent. UI. Browser View Listener. Audio Stream Pause\ Coh$

Fired when a WebAudio stream is stopped.

14.3.3.4 CoherentUI_OnAudioStreamPlay Coherent.UI.BrowserViewListener.AudioStreamPlay

Fired when a WebAudio stream is played.

 $14.3.3.5 \quad Coherent UI_On Bindings Released\ Coherent. UI. Browser View Listener. Bindings Released\ Coherent. Bindings Released\ Coher$

Fired when the bindings for frame are released.

14.3.3.6 CoherentUI_OnCallback Coherent.UI.BrowserViewListener.Callback

Fired by the UI when there is no registered handler for this event.

14.3.3.7 CoherentUI_OnCaretRectChanged Coherent.UI.BrowserViewListener.CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

14.3.3.8 CoherentUI_OnCertificateError Coherent.UI.BrowserViewListener.CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

14.3.3.9 CoherentUI OnClientCertificateRequested Coherent.UI.BrowserViewListener.ClientCertificateRequested

Fired when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

14.3.3.10 CoherentUI_OnCursorChanged Coherent.UI.BrowserViewListener.CursorChanged

Fired when the cursor has changed internally in the

14.3.3.11 CoherentUI_OnDraw Coherent.UI.BrowserViewListener.Draw

Fired when a new surface has been drawn and is ready to use by the client.

14.3.3.12 CoherentUI_OnError Coherent.UI.BrowserViewListener.Error

Fired when an error occurs for this specific

14.3.3.13 CoherentUI_OnFailLoad Coherent.UI.BrowserViewListener.FailLoad

Fired when a frame has been failed loading.

14.3.3.14 CoherentUI_OnFileSelectRequest Coherent.UI.BrowserViewListener.FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

14.3.3.15 CoherentUI_OnFinishLoad Coherent.UI.BrowserViewListener.FinishLoad

Fired when a frame has been successfully loaded.

14.3.3.16 CoherentUI_OnGetAuthCredentials Coherent.UI.BrowserViewListener.GetAuthCredentials

Fired when a view requires authentication credentials.

14.3.3.17 CoherentUI_OnIMEShouldCancelComposition Coherent.UI.BrowserViewListener.IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

14.3.3.18 CoherentUI_OnJavaScriptMessage Coherent.UI.BrowserViewListener.JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

14.3.3.19 CoherentUI_OnNavigateTo Coherent.UI.BrowserViewListener.NavigateTo

Fired when the view starts navigation to a new path.

14.3.3.20 CoherentUI_OnPrintToPDFReady Coherent.UI.BrowserViewListener.PrintToPDFReady

Fired when pdf data is needed.

14.3.3.21 CoherentUI_OnReadyForBindings Coherent.UI.BrowserViewListener.ReadyForBindings

Fired when a frame is ready for bindings.

14.3.3.22 CoherentUI_OnRequestMediaStream Coherent.UI.BrowserViewListener.RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

14.3.3.23 CoherentUI_OnScriptMessage Coherent.UI.BrowserViewListener.ScriptMessage

Fired when a message is sent from a script running in this specific

14.3.3.24 CoherentUI_OnStartLoading Coherent.UI.BrowserViewListener.StartLoading

Fired when a new path has started loading.

14.3.3.25 CoherentUI_OnStopLoading Coherent.UI.BrowserViewListener.StopLoading

Fired when all load operations have completed.

14.3.3.26 CoherentUI_OnTextInputTypeChanged Coherent.UI.BrowserViewListener.TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

14.3.3.27 CoherentUI_OnURLRequest Coherent.UI.BrowserViewListener.URLRequest

Fired before an URL request is made. The default implementation allows all requests.


14.3.3.28 CoherentUI_OnViewCreated Coherent.UI.BrowserViewListener.ViewCreated

Fired when the requested

14.4 Coherent.UI.BrowserViewListenerBase Class Reference

Interface all browser view listeners inherit. For an easier to use interface inherit instead. Coherent::UI::Browser-ViewListener

Inheritance diagram for Coherent.UI.BrowserViewListenerBase:



Additional Inherited Members

14.4.1 Detailed Description

Interface all browser view listeners inherit. For an easier to use interface inherit instead. Coherent::UI::Browser-ViewListener

14.5 Coherent.UI.Button Class Reference

Describes a button in a CoherentUIMenu instance

Public Member Functions

• void Initialize (CoherentUIMenu owner)

Initialize this button

Public Attributes

string Label

The label of the button

· bool Disabled

Where the button is enabled or disabled. Currently this property cannot be changed

ButtonHandler Click

Specifies handler for the click event of the button

14.5.1 Detailed Description

Describes a button in a CoherentUIMenu instance

14.5.2 Member Function Documentation

14.5.2.1 void Coherent.UI.Button.Initialize (CoherentUIMenu owner) [inline]

Initialize this button

Parameters

owner the menu which contains this button

14.5.3 Member Data Documentation

14.5.3.1 ButtonHandler Coherent.UI.Button.Click

Specifies handler for the click event of the button

14.5.3.2 bool Coherent.UI.Button.Disabled

Where the button is enabled or disabled. Currently this property cannot be changed

14.5.3.3 string Coherent.UI.Button.Label

The label of the button

14.6 Coherent.UI.ButtonHandler Class Reference

Handler for button related events

Public Member Functions

• void Initialize (CoherentUIMenu owner)

Initializes the Handler delegate in the Start method. If you want to set a different delegate, you can set it from another component in the Awake method.

• void Invoke ()

Invokes the handler

• delegate void Invoker ()

Delegate signature for the event handler

Public Attributes

Object Target

Target GameObject or MonoBehavior for the event. None if using the current GameObject.

string Method

Method (or message) name to be called for the event

• bool IsMessage = true

Whether Method specifies a method or a message to be called

· Invoker Handler

The delegate that is executed when the event of this handler is triggered

14.6.1 Detailed Description

Handler for button related events

14.6.2 Member Function Documentation

14.6.2.1 void Coherent.UI.ButtonHandler.Initialize (CoherentUIMenu owner) [inline]

Initializes the Handler delegate in the Start method. If you want to set a different delegate, you can set it from another component in the Awake method.

Parameters

owner the menu that owns our button

14.6.2.2 void Coherent.Ul.ButtonHandler.Invoke() [inline]

Invokes the handler

14.6.2.3 delegate void Coherent.UI.ButtonHandler.Invoker ()

Delegate signature for the event handler

14.6.3 Member Data Documentation

14.6.3.1 Invoker Coherent, UI, Button Handler, Handler

The delegate that is executed when the event of this handler is triggered

14.6.3.2 bool Coherent.UI.ButtonHandler.IsMessage = true

Whether Method specifies a method or a message to be called

14.6.3.3 string Coherent.UI.ButtonHandler.Method

Method (or message) name to be called for the event

14.6.3.4 Object Coherent.UI.ButtonHandler.Target

Target GameObject or MonoBehavior for the event. None if using the current GameObject.

14.7 Coherent.UI.Binding.CallbackArguments Class Reference

Holds the arguments for the generic callback not handled by a registered delegate

Public Attributes

• Value[] Arguments

Arguments provided by JavaScript

14.7.1 Detailed Description

Holds the arguments for the generic callback not handled by a registered delegate

14.7.2 Member Data Documentation

14.7.2.1 Value [] Coherent.UI.Binding.CallbackArguments.Arguments

Arguments provided by JavaScript

14.8 Coherent.UI.CertificatePrincipal Class Reference

Represents certificate principal.

Inherits IDisposable.

Properties

```
• string[] StreetAddresses [get]
```

The list of street addresses of the principal

• string[] OrganizationNames [get]

The list of organization names of the principal

string[] OrganizationUnitNames [get]

The list of organization unit names of the principal

string[] DomainComponents [get]

The list of domain components storage of the principal

• string CommonName [get]

Null terminated string with the common name of the subject.

• string LocalityName [get]

Null terminated string with the locality name of the subject.

• string StateOrProvinceName [get]

Null terminated string with the state or province name of the subject.

• string CountryName [get]

Null terminated string with the country name of the subject.

14.8.1 Detailed Description

Represents certificate principal.

14.8.2 Property Documentation

```
14.8.2.1 string Coherent.UI.CertificatePrincipal.CommonName [get]
```

Null terminated string with the common name of the subject.

```
14.8.2.2 string Coherent.UI.CertificatePrincipal.CountryName [get]
```

Null terminated string with the country name of the subject.

```
14.8.2.3 string [] Coherent.UI.CertificatePrincipal.DomainComponents [get]
```

The list of domain components storage of the principal

```
\textbf{14.8.2.4} \quad \textbf{string Coherent.UI.CertificatePrincipal.LocalityName} \quad \texttt{[get]}
```

Null terminated string with the locality name of the subject.

14.8.2.5 string [] Coherent.UI.CertificatePrincipal.OrganizationNames [get]

The list of organization names of the principal

14.8.2.6 string [] Coherent.UI.CertificatePrincipal.OrganizationUnitNames [get]

The list of organization unit names of the principal

14.8.2.7 string Coherent.UI.CertificatePrincipal.StateOrProvinceName [get]

Null terminated string with the state or province name of the subject.

14.8.2.8 string [] Coherent.UI.CertificatePrincipal.StreetAddresses [get]

The list of street addresses of the principal

14.9 Coherent.UI.ChildViewInfo Class Reference

Helper structure for creating child views.

Inherits IDisposable.

Properties

• ViewInfo NewViewInfo [get, set]

An existing

• ViewListenerBase Listener [get, set]

View

14.9.1 Detailed Description

Helper structure for creating child views.

14.9.2 Property Documentation

14.9.2.1 ViewListenerBase Coherent.Ul.ChildViewInfo.Listener [get], [set]

View

14.9.2.2 ViewInfo Coherent.UI.ChildViewInfo.NewViewInfo [get], [set]

An existing

14.10 Coherent.UI.ClientCertificateResponse Class Reference

Class used to respond to client certificate request from a https server. Inherits IDisposable.

Public Member Functions

virtual void ContinueRequest (string keyStore, string certificate, string thumbprint)

Continue the request by specifying the store from which the certificate store from which the certificate will be loaded and either a certificate name or a thumbprint. When more than one certificate is available with the same name, providing a thumbprint is recommended, since uniquely identifies a certificate.

virtual void CancelRequest ()

Cancel the request.

14.10.1 Detailed Description

Class used to respond to client certificate request from a https server.

14.10.2 Member Function Documentation

14.10.2.1 virtual void Coherent.UI.ClientCertificateResponse.CancelRequest() [inline], [virtual]

Cancel the request.

14.10.2.2 virtual void Coherent.UI.ClientCertificateResponse.ContinueRequest (string *keyStore*, string *certificate*, string *thumbprint*) [inline], [virtual]

Continue the request by specifying the store from which the certificate store from which the certificate will be loaded and either a certificate name or a thumbprint. When more than one certificate is available with the same name, providing a thumbprint is recommended, since uniquely identifies a certificate.

Parameters

keystore	of the Current User
certificate	name (subject)
thumbprint	of the certificate

14.11 Coherent.UI.Binding.CoherentProperty Class Reference

Specify a property / field or method visible to Coherent Browser Inherits Attribute.

Public Member Functions

CoherentProperty ()

Make a property / field or method visible to Coherent Browser

CoherentProperty (string name)

Make a property / field or method visible to Coherent Browser

14.11.1 Detailed Description

Specify a property / field or method visible to Coherent Browser

14.11.2 Constructor & Destructor Documentation

14.11.2.1 Coherent.UI.Binding.CoherentProperty.CoherentProperty() [inline]

Make a property / field or method visible to Coherent Browser

14.11.2.2 Coherent.UI.Binding.CoherentProperty.CoherentProperty (string name) [inline]

Make a property / field or method visible to Coherent Browser

Parameters

name | name of the property / field / method

14.12 Coherent.UI.Binding.CoherentType Class Reference

Specify which properties and fields of a type are visible to Coherent Browser Inherits Attribute.

14.12.1 Detailed Description

Specify which properties and fields of a type are visible to Coherent Browser

14.13 CoherentUlLiveGameView Class Reference

Component that needs to be attached to a camera and creates a Coherent Browser Live Game View Inherits MonoBehaviour.

14.13.1 Detailed Description

Component that needs to be attached to a camera and creates a Coherent Browser Live Game View

14.14 CoherentUISystem Class Reference

Component controlling the CoherentUI System Inherits MonoBehaviour.

Public Member Functions

• bool IsReady ()

Determines whether this instance is ready.

Public Attributes

• Camera m_MainCamera = null

The main camera. Used for obtaining mouse position over the HUD and raycasting in the world.

Static Public Attributes

static System.Func < FileHandler > FileHandlerFactoryFunc
 Creates the FileHandler instance for the system. Change to allow usage of custom FileHandler

```
· static System.Func
```

< System.Action,

SystemListener > SystemListenerFactoryFunc

Creates the SystemListener instance for the system. Change to allow usage of custom EventListener

Properties

• bool IsUpdating [get, set]

Determines whether the Coherent UI System component is currently in its Update() method

• bool UseURLCache [get, set]

Sets if the system should use the URL Cache. NOTE: This should almost always be enabled. Disable it if you already set the URL cache yourself for the app

• int MemoryCacheSize [get, set]

Sets the in-memory size of the URL cache

• int DiskCacheSize [get, set]

Sets the on-disk size of the URL cache

• bool HasFocusedView [get]

Determines whether there is an focused Click-to-focus view

• ViewContext UISystem [get]

Gets the user interface system.

Events

• OnViewFocusedDelegate OnViewFocused

Occurs when a Click-to-focus view gains or loses focus

14.14.1 Detailed Description

Component controlling the CoherentUI System

14.14.2 Member Function Documentation

```
14.14.2.1 bool CoherentUlSystem.lsReady ( ) [inline]
```

Determines whether this instance is ready.

Returns

true if this instance is ready; otherwise, false.

14.14.3 Member Data Documentation

14.14.3.1 System.Func<FileHandler> CoherentUlSystem.FileHandlerFactoryFunc [static]

Initial value:

```
= () =>
{
    return new UnityFileHandler();
}
```

Creates the FileHandler instance for the system. Change to allow usage of custom FileHandler

14.14.3.2 Camera CoherentUISystem.m_MainCamera = null

The main camera. Used for obtaining mouse position over the HUD and raycasting in the world.

14.14.3.3 System.Func < System.Action, SystemListener > CoherentUISystem.SystemListener Factory Func [static]

Creates the SystemListener instance for the system. Change to allow usage of custom EventListener custom OnSystemReady override must call SystemListener.OnSystemReady

Action to be given to SystemListener constructor

14.14.4 Property Documentation

14.14.4.1 int CoherentUlSystem.DiskCacheSize [get], [set]

Sets the on-disk size of the URL cache

The maximum size of the on-disk cache

14.14.4.2 bool CoherentUISystem.HasFocusedView [get]

Determines whether there is an focused Click-to-focus view

true if there is an focused Click-to-focus view; otherwise, false.

14.14.4.3 bool CoherentUISystem.IsUpdating [get], [set]

Determines whether the Coherent UI System component is currently in its Update() method

Returns

true if this instance is updating; otherwise, false.

14.14.4.4 int CoherentUISystem.MemoryCacheSize [get], [set]

Sets the in-memory size of the URL cache

The maximum size of the in-memory cache

14.14.4.5 ViewContext CoherentUlSystem.UlSystem [get]

Gets the user interface system.

The user interface system.

14.14.4.6 bool CoherentUlSystem.UseURLCache [get], [set]

Sets if the system should use the URL Cache. NOTE: This should almost always be enabled. Disable it if you already set the URL cache yourself for the app

If to set the cache

14.14.5 Event Documentation


14.14.5.1 OnViewFocusedDelegate CoherentUISystem.OnViewFocused

Occurs when a Click-to-focus view gains or loses focus

14.15 CoherentUIView Class Reference

Component containing a Coherent Browser view.

Inheritance diagram for CoherentUIView:



Public Member Functions

void SetMousePosition (int x, int y)

Sets the mouse position. Note Coherent Browser (0,0) is the upper left corner of the screen.

void DestroyView ()

Destroy this view. Destroys the Coherent Browser view and removes the CoherentUIView component from its game object. Any usage of the view after this method is undefined behaviour.

delegate void ViewDestroyedHandler ()

Handler for ViewDestroyed event.

void Resize (int width, int height)

Resize the view to the specified width and height.

void Reload (bool ignoreCache)

Request reload of this view.

bool GetCamDimensions (out int x, out int y)

Returns the camera dimensions of the current view.

Properties

```
• string Page [get, set]
```

Gets or sets the URL of the view

• int Width [get, set]

Gets or sets the width of the view.

• int Height [get, set]

Gets or sets the height of the view.

• int XPos [get, set]

Gets or sets the X position of the overlay view.

• int YPos [get, set]

Gets or sets the Y position of the overlay view.

bool ScaleToFit [get, set]

Gets or sets if the view will scale it's content to fit it's size.

bool EnableWebGLSupport [get, set]

If enabled, WebGL will be supported in the view.

• string InitialScript [get, set]

Gets or sets the initial JavaScript code to be executed when the view JavaScript engine is created.

CoherentViewInputState InputState [get, set]

Gets or sets the inbput state of the overlay view.

bool IsTransparent [get, set]

Gets or sets a value indicating whether the view is transparent.

bool SupportClickThrough [get, set]

Gets or sets a value indicating whether this view CoherentUIView supports click through.

float ClickThroughAlphaThreshold [get, set]

Gets or sets the alpha threshold for click through checks.

• bool ClickToFocus [get, set]

When enabled, allows a view to take input focus when clicked with the left mouse button.

• bool DisplayVirtualKeyboard [get, set]

When enabled, allows a view to show virtual keyboard when a text input widget is focused on touch enabled devices running Windows 8 and later.

• DrawOrder DrawAfterPostEffects [get, set]

Gets or sets a value indicating whether this view is drawn after post effects.

bool FlipY [get, set]

Gets or sets a value indicating whether the Y axis of this view should be flipped.

• virtual bool ReceivesInput [get, set]

Gets or sets a value indicating whether this view receives input. All automatic processing and reading of this property is done in the LateUpdate() / OnGUI() callbacks in Unity, letting you do all your logic for View focus in Update().

• bool InterceptAllEvents [get, set]

Gets or sets a value indicating whether this view intercepts all events and sends a message for each event.

• bool EnableBindingAttribute [get, set]

Gets or sets a value indicating whether this CoherentUIView enables usage of the CoherentMethod attribute in components in the host GameObject. When true, the all components in the host GameObject are inspected for the CoherentMethod attribute (in the Awake() function) and the decorated methods are automatically bound when the ReadyForBindings event is received. When false, the attribute does nothing.

• bool lsIndependentOfZBuffer [get, set]

Gets or sets a value indicating whether this view is z-buffer independent. If it is set to true, the view is rendered on top of everything.

• bool ShowJavaScriptDialogs [get, set]

Gets or sets a value indicating whether dialogs will be drawn when a JavaScript message is received (e.g. alert, prompt, auth credentials).

• bool ForceSoftwareRendering [get, set]

Forces the view to use software rendering. For GPU-bound applications software views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software views. This option doesn't work with OnDemand.

• bool IgnoreDisplayDensity [get, set]

Defines whether the Android device's display density will affect the scale of the View. When set to true, the displayed content in the view will match its pixel size. For example, a device with 1.5 scale factor will display a div of 100px in a 200px View on about 75% of surface if IgnoreDisplayDensity is set to false. If IgnoreDisplayDensity is set to true, the same div of 100px displayed in a 200px View will occupy exactly 50% of the View.

• bool UseCameraDimensions [get, set]

If checked, the view will use the camera's width and height

bool CorrectGamma [get, set]

Gets or sets a value indicating whether this view should have gamma corrected.

• bool EnableIME [get, set]

Gets or sets a value indicating whether the view should have IME enabled

• View View [get]

Gets the underlying Coherent.UI.View instance.

• UnityViewListener.CoherentUI_OnViewCreated OnViewCreated

Occurs when the underlying Coherent.UI. View is created

UnityViewListener.CoherentUI_OnReadyForBindings OnReadyForBindings

Occurs when the view bindings should be registered.

• UnityViewListener Listener [get]

Gets the underlying UnityViewListener for this view.

• virtual bool IsSurfaceView [get]

whether this is a mobile surface view

Events

ViewDestroyedHandler OnViewDestroyed

Occurs when the view has been destroyed and the CoherentUIView component is going to be removed from the game object.

14.15.1 Detailed Description

Component containing a Coherent Browser view.

14.15.2 Member Function Documentation

```
14.15.2.1 void CoherentUlView.DestroyView ( ) [inline]
```

Destroy this view. Destroys the Coherent Browser view and removes the CoherentUIView component from its game object. Any usage of the view after this method is undefined behaviour.

```
14.15.2.2 bool CoherentUIView.GetCamDimensions ( out int x, out int y ) [inline]
```

Returns the camera dimensions of the current view.

```
14.15.2.3 void CoherentUIView.Reload ( bool ignoreCache ) [inline]
```

Request reload of this view.

Parameters

ignoreCache	Ignore cache for the reload.

14.15.2.4 void CoherentUIView.Resize (int width, int height) [inline]

Resize the view to the specified width and height.

Parameters

width	New width for the view.
height	New height for the view.

14.15.2.5 void CoherentUIView.SetMousePosition (int x, int y) [inline]

Sets the mouse position. Note Coherent Browser (0,0) is the upper left corner of the screen.

Parameters

X	X coordinate of the mouse.
у	Y coordinate of the mouse.

14.15.2.6 delegate void CoherentUIView.ViewDestroyedHandler ()

Handler for ViewDestroyed event.

14.15.3 Property Documentation

14.15.3.1 float CoherentUIView.ClickThroughAlphaThreshold [get], [set]

Gets or sets the alpha threshold for click through checks.

The alpha threshold for click through checks.

```
14.15.3.2 bool CoherentUIView.ClickToFocus [get], [set]
```

When enabled, allows a view to take input focus when clicked with the left mouse button.

true if this view takes input focus when clicked; otherwise, false.

```
14.15.3.3 bool CoherentUIView.CorrectGamma [get], [set]
```

Gets or sets a value indicating whether this view should have gamma corrected.

true if gamma is corrected; otherwise, false.

```
14.15.3.4 bool CoherentUIView.DisplayVirtualKeyboard [get], [set]
```

When enabled, allows a view to show virtual keyboard when a text input widget is focused on touch enabled devices running Windows 8 and later.

 $\verb|true| if this view should show the virtual keyboard; otherwise, \verb|false|.|$

14.15.3.5 DrawOrder CoherentUIView.DrawAfterPostEffects [get], [set]

Gets or sets a value indicating whether this view is drawn after post effects.

AfterPostEffects if the view is drawn after post effects; otherwise, false.

Exceptions

System.Application-	Is thrown when the application exception.
Exception	

14.15.3.6 bool CoherentUIView.EnableBindingAttribute [get], [set]

Gets or sets a value indicating whether this CoherentUIView enables usage of the CoherentMethod attribute in components in the host GameObject. When true, the all components in the host GameObject are inspected for the CoherentMethod attribute (in the Awake() function) and the decorated methods are automatically bound when the ReadyForBindings event is received. When false, the attribute does nothing.

true if usage of the CoherentMethod is enabled; otherwise, false.

```
14.15.3.7 bool CoherentUIView.EnableIME [get], [set]
```

Gets or sets a value indicating whether the view should have IME enabled

true if IME is enabled; otherwise, false.

```
14.15.3.8 bool CoherentUIView.EnableWebGLSupport [get], [set]
```

If enabled, WebGL will be supported in the view.

The EnableWebGLSupport property.

```
14.15.3.9 bool CoherentUlView.FlipY [get], [set]
```

Gets or sets a value indicating whether the Y axis of this view should be flipped.

true if the Y axis is flipped; otherwise, false.

```
14.15.3.10 bool CoherentUIView.ForceSoftwareRendering [get], [set]
```

Forces the view to use software rendering. For GPU-bound applications software views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software views. This option doesn't work with OnDemand.

Not available for iOS.

true if the view is to use software rendering; otherwise false.

```
14.15.3.11 int CoherentUlView.Height [get], [set]
```

Gets or sets the height of the view.

The height.

```
14.15.3.12 bool CoherentUIView.lgnoreDisplayDensity [get], [set]
```

Defines whether the Android device's display density will affect the scale of the View. When set to *true*, the displayed content in the view will match its pixel size. For example, a device with 1.5 scale factor will display a div of 100px in a 200px View on about 75% of surface if IgnoreDisplayDensity is set to false. If IgnoreDisplayDensity is set to true, the same div of 100px displayed in a 200px View will occupy exactly 50% of the View.

true if the view ignores the device's display density; otherwise false.

```
14.15.3.13 string CoherentUlView.InitialScript [get], [set]
```

Gets or sets the initial JavaScript code to be executed when the view JavaScript engine is created.

The script.

```
14.15.3.14 CoherentViewInputState CoherentUIView.InputState [get], [set]
```

Gets or sets the inbput state of the overlay view.

The new input state.

14.15.3.15 bool CoherentUIView.InterceptAllEvents [get], [set]

Gets or sets a value indicating whether this view intercepts all events and sends a message for each event.

true if view intercepts all events; otherwise, false.

Exceptions

System.Application-	Is thrown when the property is modified and the view has already been created
Exception	

14.15.3.16 bool CoherentUIView.lsIndependentOfZBuffer [get], [set]

Gets or sets a value indicating whether this view is z-buffer independent. If it is set to true, the view is rendered on top of everything.

true if it is independent; otherwise false.

14.15.3.17 virtual bool CoherentUIView.lsSurfaceView [get]

whether this is a mobile surface view

14.15.3.18 bool CoherentUIView.lsTransparent [get], [set]

Gets or sets a value indicating whether the view is transparent.

true if this instance is transparent; otherwise, false.

Exceptions

System.Application-	Is thrown when the property is modified and the view has already been created
Exception	

14.15.3.19 UnityViewListener CoherentUIView.Listener [get]

Gets the underlying UnityViewListener for this view.

The listener.

14.15.3.20 UnityViewListener.CoherentUI_OnReadyForBindings CoherentUIView.OnReadyForBindings [add], [remove]

Occurs when the view bindings should be registered.

14.15.3.21 UnityViewListener.CoherentUI_OnViewCreated CoherentUIView.OnViewCreated [add], [remove]

Occurs when the underlying Coherent.UI.View is created

14.15.3.22 string CoherentUIView.Page [get], [set]

Gets or sets the URL of the view

The loaded URL of view

```
14.15.3.23 virtual bool CoherentUIView.ReceivesInput [get], [set]
```

Gets or sets a value indicating whether this view receives input. All automatic processing and reading of this property is done in the LateUpdate() / OnGUI() callbacks in Unity, letting you do all your logic for View focus in Update().

true if this view receives input; otherwise, false.

```
14.15.3.24 bool CoherentUIView.ScaleToFit [get], [set]
```

Gets or sets if the view will scale it's content to fit it's size.

The scale-to-fit property.

```
14.15.3.25 bool CoherentUIView.ShowJavaScriptDialogs [get], [set]
```

Gets or sets a value indicating whether dialogs will be drawn when a JavaScript message is received (e.g. alert, prompt, auth credentials).

true if a dialog is to be shown automatically; otherwise false.

```
14.15.3.26 bool CoherentUIView.SupportClickThrough [get], [set]
```

Gets or sets a value indicating whether this view CoherentUIView supports click through.

true if supports click through; otherwise, false.

Exceptions

System.Application-	Is thrown when the property is modified and the view has already been created
Exception	

```
14.15.3.27 bool CoherentUIView.UseCameraDimensions [get], [set]
```

If checked, the view will use the camera's width and height

true if we want to use camera's width and height; otherwise false.

```
14.15.3.28 View CoherentUIView.View [get]
```

Gets the underlying Coherent.UI.View instance.

The underlying Coherent.UI.View instance.

```
14.15.3.29 int CoherentUIView.Width [get], [set]
```

Gets or sets the width of the view.

The width.

```
14.15.3.30 int CoherentUlView.XPos [get], [set]
```

Gets or sets the X position of the overlay view.

The X position.

```
14.15.3.31 int CoherentUlView.YPos [get], [set]
```

Gets or sets the Y position of the overlay view.

The Y position.

14.15.4 Event Documentation

14.15.4.1 ViewDestroyedHandler CoherentUlView.OnViewDestroyed

Occurs when the view has been destroyed and the CoherentUIView component is going to be removed from the game object.

14.16 Coherent.UI.ContextError Class Reference

Encapsulates a context-related error.

Inherits IDisposable.

Properties

```
• ContextErrorType ErrorCode [get, set]

Indicates an error code.
```

• string Error [get, set]

Error description.

14.16.1 Detailed Description

Encapsulates a context-related error.

14.16.2 Property Documentation

```
14.16.2.1 string Coherent.UI.ContextError.Error [get], [set]
```

Error description.

14.16.2.2 ContextErrorType Coherent.Ul.ContextError.ErrorCode [get], [set]

Indicates an error code.

14.17 Coherent.UI.ContextListener Class Reference

Abstract interface to listen to Context-related events.

Inherits IDisposable.

Public Member Functions

virtual void ContextReady ()

Called when the context is fully initialized. Creating Views is now permitted.

virtual void OnError (ContextError arg0)

Called when an error in the context occurs.

virtual bool OnDownloadStarted (Download downloadItem)

Called when the context tries to start a new download. Return true to allow for the download to begin or false to cancel it.

virtual void OnDownloadComplete (Download downloadItem, System.IntPtr data, uint size)

Called when a download is complete.

virtual void OnDownloadFailed (Download downloadItem, DownloadErrorType error)

Called when a download has failed.

• virtual void OnSubscriptionCheckDone (SubscriptionError arg0)

Called when the check for the subscription version of the product is completed.

virtual void OnCookiesSaved (string cookiesResource)

Called when the write request for the cookies resource was completed.

14.17.1 Detailed Description

Abstract interface to listen to Context-related events.

14.17.2 Member Function Documentation

```
14.17.2.1 virtual void Coherent.UI.ContextListener.ContextReady() [inline], [virtual]
```

Called when the context is fully initialized. Creating Views is now permitted.

```
14.17.2.2 virtual void Coherent.UI.ContextListener.OnCookiesSaved ( string cookiesResource ) [inline], [virtual]
```

Called when the write request for the cookies resource was completed.

```
14.17.2.3 virtual void Coherent.UI.ContextListener.OnDownloadComplete ( Download downloadItem, System.IntPtr data, uint size ) [inline], [virtual]
```

Called when a download is complete.

```
14.17.2.4 virtual void Coherent.UI.ContextListener.OnDownloadFailed ( Download downloadItem, DownloadErrorType error ) [inline], [virtual]
```

Called when a download has failed.

```
14.17.2.5 virtual bool Coherent.UI.ContextListener.OnDownloadStarted ( Download downloadItem ) [inline], [virtual]
```

Called when the context tries to start a new download. Return true to allow for the download to begin or false to cancel it.

```
14.17.2.6 virtual void Coherent.Ul.ContextListener.OnError ( ContextError arg0 ) [inline], [virtual]
```

Called when an error in the context occurs.


14.17.2.7 virtual void Coherent.UI.ContextListener.OnSubscriptionCheckDone (SubscriptionError arg0) [inline], [virtual]

Called when the check for the subscription version of the product is completed.

14.18 Coherent.UI.ContextSettings Class Reference

Encapsulates the settings of the

Inheritance diagram for Coherent.UI.ContextSettings:



Properties

new string CookiesResource [get, set]

Resource name to be used for storing and loading cookies. Leave nullptr to disable persistence of cookies.

new string CachePath [get, set]

Path (relative to the host executable) where to save cached data. Leave nullptr for in-memory only caching.

• new string HTML5LocalStoragePath [get, set]

Path (relative to the host executable) where to allow pages to save their HTML5 local data. Leave nullptr to forbid local storage.

new string CustomUserAgentString [get, set]

The user agent string that will be used if you select "UAT_Custom" for UserAgent.

14.18.1 Detailed Description

Encapsulates the settings of the

14.18.2 Property Documentation

14.18.2.1 new string Coherent.UI.ContextSettings.CachePath [get], [set]

Path (relative to the host executable) where to save cached data. Leave nullptr for in-memory only caching.

14.18.2.2 new string Coherent.UI.ContextSettings.CookiesResource [get], [set]

Resource name to be used for storing and loading cookies. Leave nullptr to disable persistence of cookies.

14.18.2.3 new string Coherent.UI.ContextSettings.CustomUserAgentString [get], [set]

The user agent string that will be used if you select "UAT Custom" for UserAgent.


14.18.2.4 new string Coherent.UI.ContextSettings.HTML5LocalStoragePath [get], [set]

Path (relative to the host executable) where to allow pages to save their HTML5 local data. Leave nullptr to forbid local storage.

14.19 Coherent.UI.ContextSettingsBase Class Reference

Encapsulates the settings of the

Inheritance diagram for Coherent.UI.ContextSettingsBase:



Properties

• bool EnableProxy [get, set]

Enables/disables proxy support. Proxy settings are auto-detected when proxy support is enabled. Enable proxy support only when the user really has a proxy, because otherwise the auto-detection is very slow.

• bool AllowCookies [get, set]

Enables/disables cookies when accessing the web.

bool ForceDisablePluginFullscreen [get, set]

Disables 'Fullscreen mode' on all Plugins(Flash etc.)

bool DisableWebSecurity [get, set]

Disable Same-Origin Policy. Use with caution.

int DebuggerPort [get, set]

Port to use for remote debugging. Use -1 to disable debugging.

• bool EnableClientAudioPlayback [get, set]

Enable notifications for client audio playback. When this setting is enabled, the ViewListeners will receive notifications for audio streams and the client can request more PCM data using the corresponding

• UserAgentType UserAgent [get, set]

The type of the user agent. If you select "UAT_Custom", you MUST also specify the user agent string - defaults to Chrome.

• string SubscriptionEmail [get, set]

The client e-mail for the subscription version of the product. Leave empty for production builds and non-subscription versions.

string SubscriptionKey [get, set]

The client activation key for the subscription version of the product. Leave empty for production builds and non-subscription versions.

• string AdditionalHostOptions [get, set]

Additional host options that should be supplied to the

14.19.1 Detailed Description

Encapsulates the settings of the

14.19.2 Property Documentation

14.19.2.1 string Coherent.UI.ContextSettingsBase.AdditionalHostOptions [get], [set]

Additional host options that should be supplied to the

14.19.2.2 bool Coherent.UI.ContextSettingsBase.AllowCookies [get], [set]

Enables/disables cookies when accessing the web.

14.19.2.3 int Coherent.UI.ContextSettingsBase.DebuggerPort [get], [set]

Port to use for remote debugging. Use -1 to disable debugging.

14.19.2.4 bool Coherent.Ul.ContextSettingsBase.DisableWebSecurity [get], [set]

Disable Same-Origin Policy. Use with caution.

14.19.2.5 bool Coherent.UI.ContextSettingsBase.EnableClientAudioPlayback [get], [set]

Enable notifications for client audio playback. When this setting is enabled, the ViewListeners will receive notifications for audio streams and the client can request more PCM data using the corresponding

14.19.2.6 bool Coherent.UI.ContextSettingsBase.EnableProxy [get], [set]

Enables/disables proxy support. Proxy settings are auto-detected when proxy support is enabled. Enable proxy support only when the user really has a proxy, because otherwise the auto-detection is very slow.

14.19.2.7 bool Coherent.UI.ContextSettingsBase.ForceDisablePluginFullscreen [get], [set]

Disables 'Fullscreen mode' on all Plugins(Flash etc.)

14.19.2.8 string Coherent.UI.ContextSettingsBase.SubscriptionEmail [get], [set]

The client e-mail for the subscription version of the product. Leave empty for production builds and non-subscription versions.

14.19.2.9 string Coherent.UI.ContextSettingsBase.SubscriptionKey [get], [set]

The client activation key for the subscription version of the product. Leave empty for production builds and non-subscription versions.

14.19.2.10 UserAgentType Coherent.Ul.ContextSettingsBase.UserAgent [get], [set]

The type of the user agent. If you select "UAT_Custom", you MUST also specify the user agent string - defaults to Chrome.

14.20 Coherent.UI.Download Class Reference

Encapsulates a download task.

Inherits IDisposable.

Public Member Functions

• virtual void Destroy ()

Must be called when the client is ready with the download to free the resources associated with it If the download is not yet complete this implies a Cancel operation Calling any method after Finish is undefined.

• virtual uint Getld ()

An opaque id of the download. Ids are unique per-context per-session and can be used to distinguish downloads poiniting to the same resource.

• virtual bool Cancel ()

Cancels a download task.

• virtual string GetURL ()

The download url.

virtual string GetFilename ()

The name of the downloaded file.

virtual string GetReferrer ()

The referrer of the download.

virtual uint GetTotalBytes ()

The estimated size of the download.

virtual uint GetDownloadedBytesSoFar ()

The bytes downloaded so far. NB. Downloads are completed asynchronously, this is an estimation and might not be up-to-date.

virtual bool IsComplete ()

Tells if the download is complete.

virtual bool IsCancelled ()

Tells if the download has been cancelled.

• virtual bool HasFailed ()

Tells if the download has failed.

14.20.1 Detailed Description

Encapsulates a download task.

14.20.2 Member Function Documentation

```
14.20.2.1 virtual bool Coherent.UI.Download.Cancel() [inline], [virtual]
```

Cancels a download task.

Returns

true if the task has been cancelled. Calling Cancel on an already finished or stopped task will return false

```
14.20.2.2 virtual void Coherent.UI.Download.Destroy() [inline], [virtual]
```

Must be called when the client is ready with the download to free the resources associated with it If the download is not yet complete this implies a Cancel operation Calling any method after Finish is undefined.

```
14.20.2.3 virtual uint Coherent.UI.Download.GetDownloadedBytesSoFar() [inline], [virtual]
The bytes downloaded so far. NB. Downloads are completed asynchronously, this is an estimation and might not
be up-to-date.
Returns
     the bytes downloaded so far
14.20.2.4 virtual string Coherent.UI.Download.GetFilename() [inline], [virtual]
The name of the downloaded file.
Returns
     the name of the file being doenloaded
14.20.2.5 virtual uint Coherent.Ul.Download.Getld() [inline], [virtual]
An opaque id of the download. Ids are unique per-context per-session and can be used to distinguish downloads
poinitng to the same resource.
Returns
     a unique id of the download
14.20.2.6 virtual string Coherent.UI.Download.GetReferrer() [inline], [virtual]
The referrer of the download.
Returns
     the referrer
14.20.2.7 virtual uint Coherent.UI.Download.GetTotalBytes ( ) [inline], [virtual]
The estimated size of the download.
Returns
     the estimated size in bytes
14.20.2.8 virtual string Coherent.UI.Download.GetURL() [inline], [virtual]
The download url.
Returns
     the url to download
```

```
14.20.2.9 virtual bool Coherent.UI.Download.HasFailed() [inline], [virtual]
```

Tells if the download has failed.

Returns

if the download has failed

```
14.20.2.10 virtual bool Coherent.UI.Download.IsCancelled() [inline], [virtual]
```

Tells if the download has been cancelled.

Returns

if the download has been cancelled

14.20.2.11 virtual bool Coherent.UI.Download.lsComplete() [inline], [virtual]

Tells if the download is complete.

Returns

if the download is complete

14.21 Coherent, UI. Event Modifiers State Class Reference

The state of the key modifiers when an event happens.

Inherits IDisposable.

14.21.1 Detailed Description

The state of the key modifiers when an event happens.

14.22 Coherent.UI.EventMouseModifiersState Class Reference

The state of the mouse modifiers when an event happens.

Inherits IDisposable.


14.22.1 Detailed Description

The state of the mouse modifiers when an event happens.

14.23 Coherent.UI.FactorySettings Class Reference

Encapsulates the settings of the UIFactory.

Inheritance diagram for Coherent.UI.FactorySettings:



Properties

• new string HostDirectory [get, set]

Points to the folder where the host application and it's libraries

new string MinidumpFolder [get, set]

The folder where eventual minidumps will be saved (Windows only)

new string AppGroupName [get, set]

Set application group name (Mac OS only) If you want to create an sandboxed app, you must set this to the application group identifier

14.23.1 Detailed Description

Encapsulates the settings of the UIFactory.

14.23.2 Property Documentation

14.23.2.1 new string Coherent.UI.FactorySettings.AppGroupName [get], [set]

Set application group name (Mac OS only) If you want to create an sandboxed app, you must set this to the application group identifier

14.23.2.2 new string Coherent.UI.FactorySettings.HostDirectory [get], [set]

Points to the folder where the host application and it's libraries


14.23.2.3 new string Coherent.UI.FactorySettings.MinidumpFolder [get], [set]

The folder where eventual minidumps will be saved (Windows only)

14.24 Coherent.UI.FactorySettingsBase Class Reference

Encapsulates the settings of the UIFactory.

Inheritance diagram for Coherent.UI.FactorySettingsBase:



Properties

• bool WriteMinidumps [get, set]

If a

• bool EnableSupportForProprietaryCodecs [get, set]

Enable support for proprietary codecs. Playing proprietary codecs requires ffmpegsumo library that is capable of playing them as well. Note that distributing such ffmpegsumo library requires license from the repspective rights holder.

14.24.1 Detailed Description

Encapsulates the settings of the UIFactory.

14.24.2 Property Documentation

14.24.2.1 bool Coherent.UI.FactorySettingsBase.EnableSupportForProprietaryCodecs [get], [set]

Enable support for proprietary codecs. Playing proprietary codecs requires ffmpegsumo library that is capable of playing them as well. Note that distributing such ffmpegsumo library requires license from the repspective rights holder.

14.24.2.2 bool Coherent.UI.FactorySettingsBase.WriteMinidumps [get], [set]

If a

14.25 Coherent.UI.FileHandler Class Reference

Abstract interface that allows clients to provide their own file-handling functionality. Inherits IDisposable.

Public Member Functions

- virtual void ReadFile (string url, URLRequestBase request, ResourceResponse response)
 Requests to read a resource.
- · virtual void WriteFile (string url, ResourceData resource)

Request to write to a resource.

14.25.1 Detailed Description

Abstract interface that allows clients to provide their own file-handling functionality.

14.25.2 Member Function Documentation

14.25.2.1 virtual void Coherent.UI.FileHandler.ReadFile (string *url*, URLRequestBase *request*, ResourceResponse *response*) [inline], [virtual]

Requests to read a resource.

Parameters

url	the coui url of the resource
request	the request object for the resource.
response	the response object for the resource
response	the response to be filled with the resource data or notified for failure

14.25.2.2 virtual void Coherent.UI.FileHandler.WriteFile (string *url*, ResourceData *resource*) [inline], [virtual]

Request to write to a resource.

Parameters

url	the coui url of the resource.
resource	the resource data that has to be written

14.26 Coherent.UI.FileSelectionParams Class Reference

Parameters for file selection request.

Inherits IDisposable.

Properties

• string[] AcceptedMIMETypes [get]

The list of street addresses of the principal

• FileSelectionMode Mode [get]

The file selection mode - it determines whether multiple files or folders can be selected.

• string DialogTitle [get, set]

Title for the dialog.

• string DefaultFileName [get]

Default file name to select in the dialog.

• uint AcceptedMIMETypesCount [get]

The count of items in the AcceptedMIMETypes array.

14.26.1 Detailed Description

Parameters for file selection request.

14.26.2 Property Documentation

14.26.2.1 string [] Coherent.UI.FileSelectionParams.AcceptedMIMETypes [get]

The list of street addresses of the principal

14.26.2.2 uint Coherent.UI.FileSelectionParams.AcceptedMIMETypesCount [get]

The count of items in the AcceptedMIMETypes array.

14.26.2.3 string Coherent.UI.FileSelectionParams.DefaultFileName [get]

Default file name to select in the dialog.

14.26.2.4 string Coherent.UI.FileSelectionParams.DialogTitle [get], [set]

Title for the dialog.

14.26.2.5 FileSelectionMode Coherent.UI.FileSelectionParams.Mode [get]

The file selection mode - it determines whether multiple files or folders can be selected.

14.27 Coherent.UI.FileSelectRequest Class Reference

File selection request.

Inherits IDisposable.

Public Member Functions

· virtual FileSelectionParams GetFileSelectionParams ()

Get the file selection params for the current request. These are useful for creating the file chooser dialog with accurate params - what mime Types are accepted, whether user can choose multiple files or directories, etc.

virtual void Add (string fullPath)

Adds a file to the current request.

· virtual void Finish ()

Complete the request. This method should be called when you are done with adding files to this file selection request.

14.27.1 Detailed Description

File selection request.

14.27.2 Member Function Documentation

14.27.2.1 virtual void Coherent.UI.FileSelectRequest.Add (string fullPath) [inline], [virtual]

Adds a file to the current request.

Parameters

fullPath The full path to the chosen file or directory

14.27.2.2 virtual void Coherent.UI.FileSelectRequest.Finish() [inline], [virtual]

Complete the request. This method should be called when you are done with adding files to this file selection request.

```
14.27.2.3 virtual FileSelectionParams Coherent.UI.FileSelectRequest.GetFileSelectionParams ( ) [inline], [virtual]
```

Get the file selection params for the current request. These are useful for creating the file chooser dialog with accurate params - what mimeTypes are accepted, whether user can choose multiple files or directories, etc.

Returns

the file selection params for this request

14.28 Coherent.UI.HTTPHeader Class Reference

Encapsulates a HTTP header field with its content.

Inherits IDisposable.

Public Types

```
enum FieldType {
 FieldType.Accept,
 FieldType.AcceptCharset,
 FieldType.AcceptEncoding,
 FieldType.AcceptLanguage,
 FieldType.AcceptRanges,
 FieldType.Authorization,
 FieldType.CacheControl,
 FieldType.Connection,
 FieldType.ContentLength,
 FieldType.ContentRange,
 FieldType.ContentType,
 FieldType.Cookie,
 FieldType.Host,
 FieldType.IfModifiedSince,
 FieldType.IfNoneMatch,
 FieldType.IfRange,
 FieldType.Origin,
 FieldType.Pragma,
 FieldType.ProxyAuthorization,
 FieldType.ProxyConnection,
 FieldType.Range,
 FieldType.Referer,
 FieldType.UserAgent,
 FieldType.TransferEncoding }
```

Static Public Member Functions

static string GetHeaderField (HTTPHeader.FieldType type)
 Gets a string representation of the requested header field type.

Enumeration that defines various HTTP header types.

Properties

```
• string Field [get, set]

The name (key) of the HTTP header field.
```

string Content [get, set]

The value of the HTTP header field.

14.28.1 Detailed Description

Encapsulates a HTTP header field with its content.

14.28.2 Member Enumeration Documentation

14.28.2.1 enum Coherent.UI.HTTPHeader.FieldType

Enumeration that defines various HTTP header types.

Enumerator

Accept Key for the Accept header field.

AcceptCharset Key for the AcceptCharset header field.

AcceptEncoding Key for the AcceptEncoding header field.

AcceptLanguage Key for the AcceptLanguage header field.

AcceptRanges Key for the AcceptRanges header field.

Authorization Key for the Authorization header field.

CacheControl Key for the CacheControl header field.

Connection Key for the Connection header field.

ContentLength Key for the ContentLength header field.

ContentRange Key for the ContentRange header field.

ContentType Key for the ContentType header field.

Cookie Key for the Cookie header field.

Host Key for the Host header field.

IfModifiedSince Key for the IfModifiedSince header field.

IfNoneMatch Key for the IfNoneMatch header field.

IfRange Key for the IfRange header field.

Origin Key for the Origin header field.

Pragma Key for the Pragma header field.

ProxyAuthorization Key for the ProxyAuthorization header field.

ProxyConnection Key for the ProxyConnection header field.

Range Key for the Range header field.

Referer Key for the Referer header field.

UserAgent Key for the UserAgent header field.

TransferEncoding Key for the TransferEncoding header field.

14.28.3 Member Function Documentation

14.28.3.1 static string Coherent.UI.HTTPHeader.GetHeaderField (HTTPHeader.FieldType *type*) [inline], [static]

Gets a string representation of the requested header field type.

Parameters

type	the HTTP header field type
------	----------------------------

Returns

a string representation for the requested header field type

14.28.4 Property Documentation

```
14.28.4.1 string Coherent.UI.HTTPHeader.Content [get], [set]
```

The value of the HTTP header field.

```
14.28.4.2 string Coherent.UI.HTTPHeader.Field [get], [set]
```

The name (key) of the HTTP header field.

14.29 Coherent.UI.ILogHandler Class Reference

Interface to allow custom logging.

Inherits IDisposable.

Public Member Functions

virtual void WriteLog (Severity severity, string message, uint length)

Called when a log message has to be written.

· virtual void Assert (string message)

Called when an assert is triggered.

14.29.1 Detailed Description

Interface to allow custom logging.

14.29.2 Member Function Documentation

```
14.29.2.1 virtual void Coherent.UI.ILogHandler.Assert ( string message ) [inline], [virtual]
```

Called when an assert is triggered.

Parameters

message | a message that describes the reason for the assertion

14.29.2.2 virtual void Coherent.UI.ILogHandler.WriteLog (Severity severity, string message, uint length) [inline], [virtual]

Called when a log message has to be written.

Parameters

severity	the severity of the message
message	the log message itself
length	the length of the message

14.30 Coherent.UI.ImageData Class Reference

This class represents a link to a

Inherits IDisposable.

Public Member Functions

virtual void Update (IntPtr data, bool flipY)

Updates the content of the

• virtual void Destroy ()

Destroys the

14.30.1 Detailed Description

This class represents a link to a

14.30.2 Member Function Documentation

14.30.2.1 virtual void Coherent.UI.ImageData.Destroy() [inline], [virtual]

Destroys the

14.30.2.2 virtual void Coherent.UI.ImageData.Update (IntPtr data, bool flipY) [inline], [virtual]

Updates the content of the

Parameters

data	a pointer to the new data to copy in the object the size of the data must equal to the total size of the ImageData
flipY	tells if to flip vertically when copying

14.31 Coherent.UI.Binding.InvalidValueCastException Class Reference

Thrown when casting a Value to an incompatible type Inherits InvalidCastException.

14.31.1 Detailed Description

Thrown when casting a Value to an incompatible type

14.32 Coherent.UI.KeyEventData Class Reference

A keyboard event.

Inherits IDisposable.

Properties

```
• int KeyCode [get, set]
```

The key code.

• KeyEventData.EventType Type [get, set]

The type of the event.

• EventModifiersState Modifiers [get, set]

The current key modifiers.

bool IsAutoRepeat [get, set]

Is it an auto-repeat event (the user is holding the key down). This value isn't crucial and you can set it to false if you don't have the information, however you might experience incorrect repeat behavior in such case.

• bool IsNumPad [get, set]

Is it a key from the num-pad.

• bool IsSystemKey [get, set]

This identifies whether this event was tagged by the system as being a "system key" event (see

14.32.1 Detailed Description

A keyboard event.

14.32.2 Property Documentation

```
14.32.2.1 bool Coherent.UI.KeyEventData.IsAutoRepeat [get], [set]
```

Is it an auto-repeat event (the user is holding the key down). This value isn't crucial and you can set it to false if you don't have the information, however you might experience incorrect repeat behavior in such case.

```
14.32.2.2 bool Coherent.UI.KeyEventData.IsNumPad [get], [set]
```

Is it a key from the num-pad.

```
14.32.2.3 bool Coherent.Ul.KeyEventData.lsSystemKey [get], [set]
```

This identifies whether this event was tagged by the system as being a "system key" event (see

```
14.32.2.4 int Coherent.UI.KeyEventData.KeyCode [get], [set]
```

The key code.

14.32.2.5 EventModifiersState Coherent.Ul.KeyEventData.Modifiers [get], [set]

The current key modifiers.

14.32.2.6 KeyEventData.EventType Coherent.UI.KeyEventData.Type [get], [set]

The type of the event.

14.33 Coherent, Ul. Media Stream Device Class Reference

Represents a media stream device.

Inherits IDisposable.

Properties

```
• MediaStreamType Type [get]
```

type of the device

• string DeviceId [get]

Null terminated string with the unique id of the device.

• string Name [get]

Null terminated string with the device name. It may not be unique.

14.33.1 Detailed Description

Represents a media stream device.

14.33.2 Property Documentation

```
14.33.2.1 string Coherent.UI.MediaStreamDevice.DeviceId [get]
```

Null terminated string with the unique id of the device.

```
14.33.2.2 string Coherent.UI.MediaStreamDevice.Name [get]
```

Null terminated string with the device name. It may not be unique.

14.33.2.3 MediaStreamType Coherent.UI.MediaStreamDevice.Type [get]

type of the device

14.34 Coherent.UI.MediaStreamRequest Class Reference

Represents a request for media stream.

Inherits IDisposable.

Public Member Functions

void Respond (uint[] devices)

Respond to the media stream request.

Properties

• MediaStreamDevice[] Devices [get]

Get the list of available devices for the request. The list contains only devices of the requested types.

14.34.1 Detailed Description

Represents a request for media stream.

14.34.2 Member Function Documentation

14.34.2.1 void Coherent.UI.MediaStreamRequest.Respond (uint[] devices) [inline]

Respond to the media stream request.

Parameters

devices array of indices of the media stream devices to use for the request

Only a single device per stream type must be allowed. After a call to Respond calling any method on the instance results in undefined behavior. Must be called on the thread that owns the Coherent::UI::ViewContext instance.

14.34.3 Property Documentation


14.34.3.1 MediaStreamDevice [] Coherent.UI.MediaStreamRequest.Devices [get]

Get the list of available devices for the request. The list contains only devices of the requested types.

14.35 MobileSurfaceView Class Reference

Component containing a Coherent Browser view for surfaces on mobile platforms.

Inheritance diagram for MobileSurfaceView:



Public Member Functions

• bool UpdateView ()

Update the view. This method triggers the view to be rendered to the underlaying texture.

Additional Inherited Members

14.35.1 Detailed Description

Component containing a Coherent Browser view for surfaces on mobile platforms.

14.35.2 Member Function Documentation

```
14.35.2.1 bool MobileSurfaceView.UpdateView ( ) [inline]
```

Update the view. This method triggers the view to be rendered to the underlaying texture.

Returns

true if the view was actually updated

14.36 Coherent.UI.MouseEventData Class Reference

A mouse event.

Inherits IDisposable.

Properties

```
• MouseEventData.EventType Type [get, set]
```

The type of the event.

• MouseEventData.MouseButton Button [get, set]

The mouse button that triggered the event.

int X [get, set]

The X position of the mouse in pixels in the space of the view.

• int Y [get, set]

The Y position of the mouse in pixels in the space of the view.

• float WheelX [get, set]

Scroll Delta X in wheel ticks. Positive numbers mean scrolling left.

• float WheelY [get, set]

Scroll Delta Y in wheel ticks. Positive numbers mean scrolling up.

• EventModifiersState Modifiers [get, set]

Key modifiers.

• EventMouseModifiersState MouseModifiers [get, set]

Mouse modifiers.

14.36.1 Detailed Description

A mouse event.

14.36.2 Property Documentation

```
14.36.2.1 MouseEventData.MouseButton Coherent.Ul.MouseEventData.Button [get], [set]
```

The mouse button that triggered the event.

```
14.36.2.2 EventModifiersState Coherent.Ul.MouseEventData.Modifiers [get], [set]
```

Key modifiers.

14.36.2.3 EventMouseModifiersState Coherent.UI.MouseEventData.MouseModifiers [get], [set]

Mouse modifiers.

14.36.2.4 MouseEventData.EventType Coherent.UI.MouseEventData.Type [get], [set]

The type of the event.

14.36.2.5 float Coherent.UI.MouseEventData.WheelX [get], [set]

Scroll Delta X in wheel ticks. Positive numbers mean scrolling left.

14.36.2.6 float Coherent.UI.MouseEventData.WheelY [get], [set]

Scroll Delta Y in wheel ticks. Positive numbers mean scrolling up.

14.36.2.7 int Coherent.UI.MouseEventData.X [get], [set]

The X position of the mouse in pixels in the space of the view.

14.36.2.8 int Coherent.UI.MouseEventData.Y [get], [set]

The Y position of the mouse in pixels in the space of the view.

14.37 Coherent.UI.ResourceData Class Reference

Abstract interface providing data for storing resources.

Inherits IDisposable.

Public Member Functions

• virtual IntPtr GetBuffer ()

Get the buffer with the resource data.

• virtual uint GetSize ()

Get the size of the data.

· virtual void SignalSuccess ()

Report that writing to resource was successful. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

· virtual void SignalFailure ()

Report that resource writing has failed. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

14.37.1 Detailed Description

Abstract interface providing data for storing resources.

14.37.2 Member Function Documentation

14.37.2.1 virtual IntPtr Coherent.UI.ResourceData.GetBuffer() [inline], [virtual]

Get the buffer with the resource data.

Returns

pointer to the beginning of the data. May return nullptr when acquiring the buffer has failed

14.37.2.2 virtual uint Coherent.UI.ResourceData.GetSize() [inline], [virtual]

Get the size of the data.

Returns

the size of the data

```
14.37.2.3 virtual void Coherent.UI.ResourceData.SignalFailure( ) [inline], [virtual]
```

Report that resource writing has failed. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

```
14.37.2.4 virtual void Coherent.UI.ResourceData.SignalSuccess() [inline], [virtual]
```

Report that writing to resource was successful. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

14.38 Coherent.UI.ResourceResponse Class Reference

Abstract interface for responding to read resource requests.

Inherits IDisposable.

Public Member Functions

• virtual IntPtr GetBuffer (uint size)

Request buffer for resource data. GetBuffer must be called only once. GetBuffer may be called in any thread.

• virtual void SignalSuccess ()

Report that the resource is read successfully. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

• virtual void SignalFailure ()

Report that resource reading has failed. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

virtual void SetResponseHeader (string key, string value)

Set a key-value pair in the response headers.

virtual void SetStatus (int status)

Set the status for the response.

14.38.1 Detailed Description

Abstract interface for responding to read resource requests.

14.38.2 Member Function Documentation

14.38.2.1 virtual IntPtr Coherent.UI.ResourceResponse.GetBuffer (uint size) [inline], [virtual]

Request buffer for resource data. GetBuffer must be called only once. GetBuffer may be called in any thread.

Parameters

size	the size of the resource
------	--------------------------

Returns

pointer to the beginning of the buffer. It may return nullptr when allocating the buffer has failed

14.38.2.2 virtual void Coherent.UI.ResourceResponse.SetResponseHeader (string key, string value) [inline], [virtual]

Set a key-value pair in the response headers.

Parameters

key	the key for the response header
value	the value for the response header

14.38.2.3 virtual void Coherent.UI.ResourceResponse.SetStatus (int status) [inline], [virtual]

Set the status for the response.

Parameters

status	the response status

```
14.38.2.4 virtual void Coherent.UI.ResourceResponse.SignalFailure() [inline], [virtual]
```

Report that resource reading has failed. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

```
14.38.2.5 virtual void Coherent.UI.ResourceResponse.SignalSuccess ( ) [inline], [virtual]
```

Report that the resource is read successfully. This should be executed in the thread that all Coherent Browser methods are executed. After this method is called, any calls to any method of the instance are undefined behavior.

14.39 Coherent.UI.SubscriptionError Class Reference

Encapsulates a subscription-check-related error.

Inherits IDisposable.

Properties

• SubscriptionErrorType ErrorCode [get, set]

Indicates an error code.

• string Error [get, set]

Error description.

14.39.1 Detailed Description

Encapsulates a subscription-check-related error.

14.39.2 Property Documentation

14.39.2.1 string Coherent.UI.SubscriptionError.Error [get], [set]

Error description.

14.39.2.2 SubscriptionErrorType Coherent.UI.SubscriptionError.ErrorCode [get], [set]

Indicates an error code.

14.40 Coherent.UI.SurfaceResponse Class Reference

Interface that signals for creation of rendering surfaces.

Inherits IDisposable.

Public Member Functions

virtual void Signal (CoherentHandle handle)
 Signals that the operation was completed. You should call this function in the same thread that updates the UI context.

14.40.1 Detailed Description

Interface that signals for creation of rendering surfaces.

14.40.2 Member Function Documentation

```
14.40.2.1 virtual void Coherent.Ul.SurfaceResponse.Signal (CoherentHandle handle) [inline], [virtual]
```

Signals that the operation was completed. You should call this function in the same thread that updates the UI context.

Parameters

handle the created surface handle or a NULL handle if the operation fails

14.41 Coherent.UI.TouchEventData Class Reference

A touch event.

Inherits IDisposable.

Properties

int X [get, set]

The X position where the touch happened in pixels in the space of the view.

int Y [get, set]

The Y position where the touch happened in pixels in the space of the view.

• uint ld [get, set]

Identifies a particular touch input. This value must stay consistent in a touch contact sequence.

• TouchEventData.EventType Type [get, set]

The type of the touch event.

• bool HasRadiusInformation [get, set]

Flags if there is contact radius information for this event.

• uint RadiusX [get, set]

The X radius of the contact (must be set only if HasRadiusInformation == true)

• uint RadiusY [get, set]

The Y radius of the contact (must be set only if HasRadiusInformation == true)

14.41.1 Detailed Description

A touch event.

14.41.2 Property Documentation

```
14.41.2.1 bool Coherent.UI.TouchEventData.HasRadiusInformation [get], [set]
```

Flags if there is contact radius information for this event.

```
14.41.2.2 uint Coherent.UI.TouchEventData.ld [get], [set]
```

Identifies a particular touch input. This value must stay consistent in a touch contact sequence.

```
14.41.2.3 uint Coherent.UI.TouchEventData.RadiusX [get], [set]
```

The X radius of the contact (must be set only if HasRadiusInformation == true)

```
14.41.2.4 uint Coherent.UI.TouchEventData.RadiusY [get], [set]
```

The Y radius of the contact (must be set only if HasRadiusInformation == true)

```
14.41.2.5 TouchEventData.EventType Coherent.UI.TouchEventData.Type [get], [set]
```

The type of the touch event.

```
14.41.2.6 int Coherent.UI.TouchEventData.X [get], [set]
```

The X position where the touch happened in pixels in the space of the view.

```
14.41.2.7 int Coherent.UI.TouchEventData.Y [get], [set]
```

The Y position where the touch happened in pixels in the space of the view.

14.42 Coherent.UI.Binding.UnsupportedPrimitiveTypeException Class Reference


Thrown when trying to bind a value of unsupported primitive type such as long Inherits Exception.

14.42.1 Detailed Description

Thrown when trying to bind a value of unsupported primitive type such as long

14.43 Coherent.UI.URLRequest Class Reference

represents a single URL request Allows monitoring and modifications of URL requests Inheritance diagram for Coherent.UI.URLRequest:



Public Member Functions

void SetExtraHeaders (HTTPHeader[] headers)

Set the extra headers.

virtual void SetURL (string url)

Replace the URL of the request.

virtual void SetMethod (string method)

Set the method of the request.

virtual void SetReferrer (string referrer)

Set the referrer of the request.

virtual void SetExtraHeader (string field, string content)

Set extra header for the request. If there is already a header with that field name its content will be replaced.

virtual void AppendExtraHeaderValue (string field, string content)

Append extra header for the request. If there is already a header with that field name the content will be appended to the header current content with a comma as a separator between the values. If there is not such header it will be added.

· virtual void RemoveExtraHeader (string field)

Remove extra header from the request.

• virtual void Deny ()

Deny the request.

14.43.1 Detailed Description

represents a single URL request Allows monitoring and modifications of URL requests

14.43.2 Member Function Documentation

14.43.2.1 virtual void Coherent.UI.URLRequest.AppendExtraHeaderValue (string *field*, string *content*) [inline], [virtual]

Append extra header for the request. If there is already a header with that field name the content will be appended to the header current content with a comma as a separator between the values. If there is not such header it will be added.

field	name of the header
content	content of the header

14.43.2.2 virtual void Coherent.UI.URLRequest.Deny() [inline], [virtual]

Deny the request.

14.43.2.3 virtual void Coherent.UI.URLRequest.RemoveExtraHeader(string field) [inline], [virtual]

Remove extra header from the request.

Parameters

field	field of the header to be removed

14.43.2.4 virtual void Coherent.UI.URLRequest.SetExtraHeader (string field, string content) [inline], [virtual]

Set extra header for the request. If there is already a header with that field name its content will be replaced.

Parameters

field	name of the header
content	new content of the header

14.43.2.5 void Coherent.UI.URLRequest.SetExtraHeaders (HTTPHeader[] headers) [inline]

Set the extra headers.

Parameters

heade	rs	the array of new headers

14.43.2.6 virtual void Coherent.UI.URLRequest.SetMethod (string method) [inline], [virtual]

Set the method of the request.

Parameters

method	the new method as string. method must be a valid HTTP method name

14.43.2.7 virtual void Coherent.UI.URLRequest.SetReferrer (string referrer) [inline], [virtual]

Set the referrer of the request.

Parameters


referrer	the new referrer URL for the request

14.43.2.8 virtual void Coherent.UI.URLRequest.SetURL(string url) [inline], [virtual]

Replace the URL of the request.

14.44 Coherent.UI.URLRequestBase Class Reference

represents a single URL request (read-only) Allows monitoring of URL requests Inheritance diagram for Coherent.UI.URLRequestBase:



Public Member Functions

HTTPHeader[] GetExtraHeaders ()

Get extra request headers

virtual string GetURL ()

Get the URL of the request.

virtual string GetMethod ()

Get the method of the request.

· virtual string GetReferrer ()

Get the referrer of the request.

virtual string GetExtraHeader (string field)

Get extra header value.

virtual int GetExtraHeaderIndex (string field)

Get extra header value.

• virtual bool HasExtraHeader (string field)

Checks if a header with the specified key is present in the headers collection.

14.44.1 Detailed Description

represents a single URL request (read-only) Allows monitoring of URL requests

14.44.2 Member Function Documentation

14.44.2.1 virtual string Coherent.UI.URLRequestBase.GetExtraHeader (string field) [inline], [virtual]

Get extra header value.

Parameters

field	field of the header
-------	---------------------

Returns

the value of the header or nullptr if there is such header in the request

14.44.2.2 virtual int Coherent.UI.URLRequestBase.GetExtraHeaderIndex (string field) [inline], [virtual]

Get extra header value.

field | field of the header

Returns

the index of the header with the specified key in the headers collection, or a negative number if no such key exists

14.44.2.3 HTTPHeader[]Coherent.UI.URLRequestBase.GetExtraHeaders() [inline]

Get extra request headers

Returns

array of the extra request headers

14.44.2.4 virtual string Coherent.UI.URLRequestBase.GetMethod() [inline], [virtual]

Get the method of the request.

Returns

the method as a string

14.44.2.5 virtual string Coherent.UI.URLRequestBase.GetReferrer() [inline], [virtual]

Get the referrer of the request.

Returns

the referrer of the request

14.44.2.6 virtual string Coherent.UI.URLRequestBase.GetURL() [inline], [virtual]

Get the URL of the request.

Returns

the URL of the request

14.44.2.7 virtual bool Coherent.UI.URLRequestBase.HasExtraHeader(string field) [inline], [virtual]

Checks if a header with the specified key is present in the headers collection.

Parameters

field | field of the header

Returns

true if a header with the specified key is present, false otherwise

14.45 Coherent.UI.Binding.Value Class Reference

Type for representing generic JavaScript values

Public Member Functions

• Value ()

Create a null value

• Value (bool value)

Create a boolean value

• Value (int value)

Create an integer value

• Value (uint value)

Create an unsigned integer value

• Value (sbyte value)

Create a signed byte value

• Value (byte value)

Create a byte value

• Value (char value)

Create a char value

· Value (float value)

Create a float value

• Value (double value)

Create a double value

• Value (string value)

Create a string value

• Value (Value[] value)

Create an array value

Value (Dictionary< string, Value > value)

Create an object value

· Value (ValueObject value)

Create an object value

override bool Equals (object obj)

Compare to another object

· override int GetHashCode ()

Hash code for Value

Static Public Member Functions

• static implicit operator bool (Value value)

cast a value to a boolean

static implicit operator int (Value value)

cast a value to an int

• static implicit operator uint (Value value)

cast a value to an uint

• static implicit operator sbyte (Value value)

cast a value to a signed byte

static implicit operator byte (Value value)

cast a value to a byte

static implicit operator char (Value value)

cast a value to a char

• static implicit operator float (Value value)

cast a value to a float

• static implicit operator double (Value value)

cast a value to a double

• static implicit operator string (Value value)

cast a value to a string

• static implicit operator Value[] (Value value)

cast a value to an array

• static implicit operator Dictionary< string, Value > (Value value)

cast a value to a dictionary of properties

static bool operator== (Value lhs, Value rhs)

Compares two Value objects

static bool operator!= (Value lhs, Value rhs)

Compares two Value objects

Public Attributes

ValueType Type

The type of the data stored in this Value instance

14.45.1 Detailed Description

Type for representing generic JavaScript values

14.45.2 Constructor & Destructor Documentation

14.45.2.1 Coherent.UI.Binding.Value.Value() [inline]

Create a null value

14.45.2.2 Coherent.UI.Binding.Value.Value (bool value) [inline]

Create a boolean value

Parameters

value the integer value of the Value object

14.45.2.3 Coherent.UI.Binding.Value.Value(int value) [inline]

Create an integer value

Parameters

value the integer value of the Value object

14.45.2.4 Coherent.UI.Binding.Value.Value (uint value) [inline]

Create an unsigned integer value

Parameters

value the unsigned integer value of the Value object

14.45.2.5 Coherent.UI.Binding.Value.Value (sbyte value) [inline]

Create a signed byte value

Parameters

value the signed byte value of the Value object

14.45.2.6 Coherent.UI.Binding.Value.Value (byte value) [inline]

Create a byte value

Parameters

value the byte value of the Value object

14.45.2.7 Coherent.UI.Binding.Value.Value (char value) [inline]

Create a char value

Parameters

value the char value of the Value object

14.45.2.8 Coherent.UI.Binding.Value.Value (float value) [inline]

Create a float value

Parameters

value the float value of the Value object

14.45.2.9 Coherent.UI.Binding.Value.Value (double value) [inline]

Create a double value

Parameters

value the double value of the Value object

14.45.2.10 Coherent.UI.Binding.Value.Value (string value) [inline]

Create a string value

Parameters

value the string value of the Value object

 $\textbf{14.45.2.11} \quad \textbf{Coherent.UI.Binding.Value.Value(Value[]\textit{value})} \quad \texttt{[inline]}$

Create an array value

Parameters

value the array value of the Value object

14.45.2.12 Coherent.UI.Binding.Value.Value (Dictionary < string, Value > value) [inline]

Create an object value

Parameters

value dictionary of properties of the Value object

14.45.2.13 Coherent.UI.Binding.Value.Value (ValueObject value) [inline]

Create an object value

Parameters

value dictionary of properties of the Value object

14.45.3 Member Function Documentation

14.45.3.1 override bool Coherent.UI.Binding.Value.Equals (object obj) [inline]

Compare to another object

Parameters

obj

Returns

true if obj is a Value instance equal to this one

14.45.3.2 override int Coherent.UI.Binding.Value.GetHashCode () [inline]

Hash code for Value

Returns

hash code for the current instance

14.45.3.3 static implicit Coherent.UI.Binding.Value.operator bool (Value value) [inline], [static]

cast a value to a boolean

Parameters

value value to be casted

Returns

the boolean stored in the value

14.45.3.4 static implicit Coherent.UI.Binding.Value.operator byte (Value value) [inline], [static]

cast a value to a byte

value value to be cast

Returns

the byte stored in the value

14.45.3.5 static implicit Coherent.UI.Binding.Value.operator char (Value value) [inline], [static]

cast a value to a char

Parameters

value | value to be cast

Returns

the char stored in the value

14.45.3.6 static implicit Coherent.UI.Binding.Value.operator Dictionary < string, Value > (Value value) [inline], [static]

cast a value to a dictionary of properties

Parameters

value | value to be casted

Returns

the dictionary of properties of the value

14.45.3.7 static implicit Coherent.UI.Binding.Value.operator double (Value value) [inline], [static]

cast a value to a double

Parameters

value value to be casted

Returns

the double stored in the value

14.45.3.8 static implicit Coherent.UI.Binding.Value.operator float (Value value) [inline], [static]

cast a value to a float

Parameters

value value to be casted

Returns

the float stored in the value

14.45.3.9 static implicit Coherent.UI.Binding.Value.operator int (Value value) [inline], [static] cast a value to an int

value value to be casted

Returns

the int stored in the value

14.45.3.10 static implicit Coherent.UI.Binding.Value.operator sbyte (Value value) [inline], [static]

cast a value to a signed byte

Parameters

value | value to be cast

Returns

the signed byte stored in the value

14.45.3.11 static implicit Coherent.UI.Binding.Value.operator string (Value value) [inline], [static]

cast a value to a string

Parameters

value value to be casted

Returns

the string stored in the value

14.45.3.12 static implicit Coherent.UI.Binding.Value.operator uint (Value value) [inline], [static]

cast a value to an uint

Parameters

value value to be casted

Returns

the unsigned int stored in the value

14.45.3.13 static implicit Coherent.UI.Binding.Value.operator Value[](Value value) [inline], [static]

cast a value to an array

Parameters

value value to be casted

Returns

the array of Value objects stored in the value

14.45.3.14 static bool Coherent.UI.Binding.Value.operator!=(Value Ihs, Value rhs) [inline], [static]

Compares two Value objects

lhs	object to be compared
rhs	object to be compared

Returns

false if the objects are from the same type and have the same values

14.45.3.15 static bool Coherent.UI.Binding.Value.operator== (Value Ihs, Value rhs) [inline], [static]

Compares two Value objects

Parameters

lhs	object to be compared
rhs	object to be compared

Returns

true if the objects are from the same type and have the same values

14.45.4 Member Data Documentation

14.45.4.1 ValueType Coherent.UI.Binding.Value.Type

The type of the data stored in this Value instance

14.46 Coherent.UI.Binding.ValueObject Class Reference

Class for compound JavaScript objects, behaves like a Dictionary<string, Value> Inherits IDictionary< string, Value>, and IDictionary.


14.46.1 Detailed Description

Class for compound JavaScript objects, behaves like a Dictionary<string, Value>

14.47 Coherent.UI.View Class Reference

Class that encapsulates a UI

Inheritance diagram for Coherent.UI.View:



Public Member Functions

BoundEventHandle BindCall (string name, System.Delegate handler)

Expose C++ handler to be called from UI.

BoundEventHandle RegisterForEvent (string name, System.Delegate handler)

Expose C++ handler to be called when a specific event occurs.

void UnregisterFromEvent (BoundEventHandle handle)

Remove a registered C++ handler.

void UnbindCall (BoundEventHandle handle)

Remove a bound C++ handler.

void UnbindObject (object target)

Remove all handlers bound to a specific object.

virtual ViewContext GetContext ()

Get the view context.

virtual ViewType GetViewType ()

Get the type of the view.

virtual void Destroy ()

Destroys this view. After a call to Destroy calling any other method except the destructor results in undefined behavior

virtual void SetFocus ()

Sets this view on focus.

virtual void KillFocus ()

Removes the focus from this view.

virtual void MouseEvent (MouseEventData arg0)

Sends a mouse event to the UI renderer.

virtual void KeyEvent (KeyEventData arg0)

Sends a key event to the UI renderer.

virtual void TouchEvent (TouchEventData events, uint count)

Sends a touch event to the UI renderer.

virtual void MouseActivate ()

Sends a mouse event to the UI renderer.

virtual int GetWidth ()

Gets the width of the

virtual int GetHeight ()

Gets the height of the

virtual void Resize (uint width, uint height)

Send a resize event to the UI renderer. Resize will result in multiple calls to CreateBuffers and DestroyBuffers in the listener

virtual void IssueMouseOnUIQuery (float normX, float normY)

Issues a query on the Calling IsMouseOnView while a query is in-flight is an error and will be logged - the result returned by IsMouseOnView in that case is undefined.

virtual ViewErrorType HasMouseQueryFinished ()

Returns the status of the mouse query.

· virtual void FetchMouseOnUIQuery ()

Ends a mouse-on-UI query. Waits for the result. Should be called as far apart from IssueMouseOnUIQuery in order to maximize the chances that the query has finished at the time of this call and no waiting will be performed

virtual bool IsMouseOnView ()

Checks if the mouse is currently on the logical view (a part of the view that has elements on it) or not (click-through). Uses the coordinates last set in IssueMouseOnUIQuery. Calling the method while a query is in-flight (between a call to IssueMouseOnUIQuery and FetchMouseOnUIQuery) results in a warning and the return result is undefined

virtual void SetClickThroughAlphaThreshold (float threshold)

The alpha value of the pixels is used to determine if the mouse is on an element or on the background (click-through). All pixels below or equal to the alpha threshold (default = 0) are marked as not-belonging to the

virtual float GetClickThroughAlphaThreshold ()

Get the currently set alpha threshold for click-through queries.

virtual void SetTargetFramerate (int target)

Sets the target frame-rate for the

virtual int GetTargetFramerate ()

Get the currently set target frame-rate for the

virtual bool IsOnDemand ()

Tells if this is an on-demand view. Frames must be explicitly requested for on-demand views (available only in Full versions of 'Coherent::Ul::View::RequestFrame'

virtual ViewErrorType RequestFrame ()

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of This function must be called on the ViewContext thread. This overload let's Coherent Browser control the time in the view. You should have set ViewInfo::ControlTimeOnDemand to false to use it. If you need to control timing - use the other overload and create the view with ViewInfo::ControlTimeOnDemand set to true.

virtual ViewErrorType RequestFrame (double timeSinceArbitraryMoment)

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of This function must be called on the ViewContext thread. This overload let's Coherent Browser control the time in the view. You should have set ViewInfo::ControlTimeOnDemand to false to use it. If you need to control timing - use the other overload and create the view with ViewInfo::ControlTimeOnDemand set to true.

virtual ViewErrorType PeekFrameReady ()

Tells if the last requested frame is ready or not. Does not block. This call must always be made between calls to RequestFrame and FetchSurface. (available only in Full versions of 'Coherent::UI::View::RequestFrame' 'Coherent::-UI::View::FetchSurface'

virtual ViewErrorType FetchSurface ()

Returns the requested surface. Works only for on-demand views. All buffered view should use the context's Fetch-Surfaces method. This call will block until the surface is ready. (available only in Full versions of

• virtual ViewErrorType DrawSurface ()

[EXPERIMENTAL - DO NOT USE]

virtual bool UsesSharedMemory ()

Tells if this view uses shared memory for image transport.

virtual bool IsTransparent ()

Tells if this view is transparent or not.

virtual bool SupportsClickThrough ()

Tells if this view supports click-through queries or not.

virtual void Redraw ()

Request a redraw of the current view.

virtual void DownloadUrl (string path)

Initiates a download request on the specified path.

virtual void Load (string path)

Loads a new path in the

· virtual void Reload (bool ignoreCache)

Reloads the last requested or navigated-to path.

virtual string GetCurentViewPath ()

Get the last requested or navigated-to path.

virtual string GetLastRequestedPath ()

Get the last requested path to load for the

virtual string GetLastLoadedPath ()

Get the last successfully loaded path for the

· virtual string GetLastFailedPath ()

Get the last failed path for the

virtual void ExecuteScript (string script)

Execute arbitrary JavaScript code.

virtual void TriggerEvent (string eventName)

Triggers a UI event.

virtual void ReplyToJavaScriptMessage (bool success, string userInput)

Sends a reply to a javascript message triggered for the view.

virtual void AuthCredentialsResponse (string username, string password, bool success)

Sends credentials for a pending authentication request for the view.

virtual void SetScriptError (ScriptCallErrorType error, string message)

Sets an error for the currently executing handler.

virtual void InterceptURLRequests (bool intercept)

Controls intercepting URL requests. For each request

virtual void IMEActivate (bool active)

Sets if the

virtual bool IMEIsActive ()

Tells if IME events are currently active for this view.

virtual bool IMESetComposition (string composition, uint cursorPos, uint targetStart, uint targetEnd)

Updates the internal state of the IME composition in the

virtual bool IMEConfirmComposition (string composition)

Confirms the current IME composition.

virtual bool IMECancelComposition ()

Cancels the current IME composition.

virtual ImageData CreateImageData (string name, int width, int height, IntPtr data, bool flipY)

Create an

virtual int GetAudioData (int streamId, IntPtr buffer, int bufferSize, int timeoutMs)

Obtains audio data for the specified stream in the current view and copies it into the client-provided buffer.

virtual void SetZoomLevel (double zoomLevel)

Sets the page zoom level. Specifying 0.0 will reset to the default zoom level. The API works with "levels", not factors. Each level represents 20% zoom. Negative values mean "zoom out", while positive values mean "zoom in". You can pass fractional levels as well. If you want to convert a factor to a level that you can pass to the API, you can use the following formula: level = $\log N(1.2, factor)$. In terms of C++ that would be the same as " $\log (factor) / \log (1.2)$ ". For example, if you want to make the content 50% smaller, you'll need a level of $\log N(1.2, 0.5) \sim = -3.8$. If you want to make it 50% larger, you'll have $\log N(1.2, 1.5) \sim = 2.2$. The zoom factor operates on protocol and host level, meaning that all views with the same protocol and host as the current URL will be scaled as well.

virtual void SetMasterVolume (double volume)

Sets the master volume for all audio and video streams.

virtual void Print (bool printToPDF)

Prints the contents of a view. Works identically to window.print() in Javascript (both can be used to print an HTML page). When the method is called, a pop-up window will be shown with the available print settings. Its possible to get the result in PDF format by calling the function with the value true.

virtual void Print ()

Prints the contents of a view. Works identically to window.print() in Javascript (both can be used to print an HTML page). When the method is called, a pop-up window will be shown with the available print settings. Its possible to get the result in PDF format by calling the function with the value true.

14.47.1 Detailed Description

Class that encapsulates a UI

14.47.2 Member Function Documentation

14.47.2.1 virtual void Coherent.UI.View.AuthCredentialsResponse (string *username*, string *password*, bool *success*) [inline], [virtual]

Sends credentials for a pending authentication request for the view.

username	the username
password	the password
success	defines whether the response is valid, i.e. if the request should be answered or canceled

14.47.2.2 BoundEventHandle Coherent.UI.View.BindCall (string name, System.Delegate handler) [inline]

Expose C++ handler to be called from UI.

Parameters

name	name for the handler in the UI
handler	handler to be executed

Returns

bound handle so the handler can be unbound later

14.47.2.3 virtual ImageData Coherent.UI.View.CreateImageData (string *name*, int *width*, int *height*, IntPtr *data*, bool *flipY*)

[inline], [virtual]

Create an

Parameters

name	the name of the image data object
width	the width of the image
height	the height of the image
data	initial data to fill the image data with
flipY	flips vertically the content of the source image

Returns

the image data object created in the DOM of this View

14.47.2.4 virtual void Coherent.UI.View.Destroy() [inline], [virtual]

Destroys this view. After a call to Destroy calling any other method except the destructor results in undefined behavior

14.47.2.5 virtual void Coherent.UI.View.DownloadUrl(string path) [inline], [virtual]

Initiates a download request on the specified path.

14.47.2.6 virtual ViewErrorType Coherent.UI.View.DrawSurface() [inline], [virtual]

[EXPERIMENTAL - DO NOT USE]

14.47.2.7 virtual void Coherent.UI.View.ExecuteScript (string script) [inline], [virtual]

Execute arbitrary JavaScript code.

Parameters

script	code to be evaluated in the context of the main frame of the view

14.47.2.8 virtual void Coherent.UI.View.FetchMouseOnUIQuery() [inline], [virtual]

Ends a mouse-on-UI query. Waits for the result. Should be called as far apart from IssueMouseOnUIQuery in order to maximize the chances that the query has finished at the time of this call and no waiting will be performed

```
14.47.2.9 virtual ViewErrorType Coherent.UI.View.FetchSurface() [inline], [virtual]
```

Returns the requested surface. Works only for on-demand views. All buffered view should use the context's Fetch-Surfaces method. This call will block until the surface is ready. (available only in Full versions of

Returns

the outcome of the operation

14.47.2.10 virtual int Coherent.UI.View.GetAudioData (int *streamId*, IntPtr *buffer*, int *bufferSize*, int *timeoutMs*) [inline], [virtual]

Obtains audio data for the specified stream in the current view and copies it into the client-provided buffer.

Parameters

streamld	the stream for which to get PCM data
buffer	the client buffer into which the data is copied
bufferSize	the size of the client buffer
timeoutMs	the timeout in milliseconds to wait for audio data. Use 0 to wait indefinitely.

Returns

the actual number of bytes read. A negative number is returned if the stream is exhausted or does not exist.

14.47.2.11 virtual float Coherent.UI.View.GetClickThroughAlphaThreshold() [inline], [virtual]

Get the currently set alpha threshold for click-through queries.

Returns

the currently set alpha threshold

14.47.2.12 virtual ViewContext Coherent.UI.View.GetContext() [inline], [virtual]

Get the view context.

Returns

pointer to the view context used for creating this view

```
14.47.2.13 virtual string Coherent.UI.View.GetCurentViewPath() [inline], [virtual]
Get the last requested or navigated-to path.
Returns
     the path as null-terminated string
14.47.2.14 virtual int Coherent.UI.View.GetHeight ( ) [inline], [virtual]
Gets the height of the
Returns
     the height of the View
14.47.2.15 virtual string Coherent.UI.View.GetLastFailedPath() [inline], [virtual]
Get the last failed path for the
Returns
     the path as null-terminated string
14.47.2.16 virtual string Coherent.UI.View.GetLastLoadedPath() [inline], [virtual]
Get the last successfully loaded path for the
Returns
     the path as null-terminated string
14.47.2.17 virtual string Coherent.UI.View.GetLastRequestedPath() [inline], [virtual]
Get the last requested path to load for the
Returns
     the path as null-terminated string
14.47.2.18 virtual int Coherent.UI.View.GetTargetFramerate() [inline], [virtual]
Get the currently set target frame-rate for the
Returns
     the current target frame-rate (available only in Full versions of Coherent Browser)
14.47.2.19 virtual ViewType Coherent.UI.View.GetViewType() [inline], [virtual]
Get the type of the view.
Returns
     the type of the view
Reimplemented in Coherent.UI.BrowserView.
```

14.47.2.20 virtual int Coherent.UI.View.GetWidth() [inline], [virtual]

Gets the width of the

Returns

the width of the View

14.47.2.21 virtual ViewErrorType Coherent.UI.View.HasMouseQueryFinished() [inline], [virtual]

Returns the status of the mouse query.

Returns

the result will be Success if the query has finished, QueryNotReady otherwise. If no query has been issued InvalidCall will be returned.

14.47.2.22 virtual void Coherent.UI.View.IMEActivate (bool active) [inline], [virtual]

Sets if the

Parameters

active whether to activate IME handling for this view

14.47.2.23 virtual bool Coherent.UI.View.IMECancelComposition() [inline], [virtual]

Cancels the current IME composition.

Returns

the outcome of the operation (will fail if IME is inactive for this view)

14.47.2.24 virtual bool Coherent.UI.View.IMEConfirmComposition (string composition) [inline], [virtual]

Confirms the current IME composition.

Parameters

composition the string to confirm

Returns

the outcome of the operation (will fail if IME is inactive for this view)

14.47.2.25 virtual bool Coherent.UI.View.IMEIsActive() [inline], [virtual]

Tells if IME events are currently active for this view.

Returns

if the view has IME active

14.47.2.26 virtual bool Coherent.UI.View.IMESetComposition (string *composition*, uint *cursorPos*, uint *targetStart*, uint *targetEnd*) [inline], [virtual]

Updates the internal state of the IME composition in the

composition	the composition string so far
the	cursor position in the composition
targetStart	the index at the start of the selection
targetEnd	the index at the end of the selection

Returns

the outcome of the operation (will fail if IME is inactive for this view)

14.47.2.27 virtual void Coherent.UI.View.InterceptURLRequests (bool intercept) [inline], [virtual]

Controls intercepting URL requests. For each request

Parameters

intercept	whether to intercept all URL requests

14.47.2.28 virtual bool Coherent.UI.View.IsMouseOnView () [inline], [virtual]

Checks if the mouse is currently on the logical view (a part of the view that has elements on it) or not (click-through). Uses the coordinates last set in IssueMouseOnUIQuery. Calling the method while a query is in-flight (between a call to IssueMouseOnUIQuery and FetchMouseOnUIQuery) results in a warning and the return result is undefined

Returns

true if the mouse is on the view

14.47.2.29 virtual bool Coherent.UI.View.lsOnDemand() [inline], [virtual]

Tells if this is an on-demand view. Frames must be explicitly requested for on-demand views (available only in Full versions of 'Coherent::UI::View::RequestFrame'

Returns

true if this is an on-demand view

14.47.2.30 virtual void Coherent.UI.View.IssueMouseOnUIQuery (float normX, float normY) [inline], [virtual]

Issues a query on the Calling IsMouseOnView while a query is in-flight is an error and will be logged - the result returned by IsMouseOnView in that case is undefined.

Put as much processing as possible between IssueMouseOnUIQuery and the corresponding FetchMouseOnUIQuery, this allows leveraging the cost of the query and to reduce it to \sim 0. The best way to do this is call Issue-MouseOnUIQuery early in the frame, perform all game rendering and the call FetchMouseOnUIQuery followed by IsMouseOnView to update the needed data.

Parameters

	normX	the x coordinate of the mouse in the normalized space of the view [01]
--	-------	--

normY the y coordinate of the mouse in the normalized space of the view [0..1]

14.47.2.31 virtual bool Coherent.UI.View.IsTransparent() [inline], [virtual]

Tells if this view is transparent or not.

Returns

true if the view is transparent

14.47.2.32 virtual void Coherent.UI.View.KeyEvent(KeyEventData arg0) [inline], [virtual]

Sends a key event to the UI renderer.

Parameters

```
event the key event
```

14.47.2.33 virtual void Coherent.UI.View.KillFocus() [inline], [virtual]

Removes the focus from this view.

14.47.2.34 virtual void Coherent.UI.View.Load (string path) [inline], [virtual]

Loads a new path in the

Parameters

path	the path to load

14.47.2.35 virtual void Coherent.UI.View.MouseActivate() [inline], [virtual]

Sends a mouse event to the UI renderer.

14.47.2.36 virtual void Coherent.UI.View.MouseEvent(MouseEventData arg0) [inline], [virtual]

Sends a mouse event to the UI renderer.

Parameters

```
event the mouse event
```

```
14.47.2.37 virtual ViewErrorType Coherent.UI.View.PeekFrameReady() [inline], [virtual]
```

Tells if the last requested frame is ready or not. Does not block. This call must always be made between calls to RequestFrame and FetchSurface. (available only in Full versions of 'Coherent::UI::View::RequestFrame' 'Coherent::UI::View::FetchSurface'

Returns

VE_Success; VE_FrameNotReady; VE_FrameNotRequested; VE_InvalidCall

14.47.2.38 virtual void Coherent.UI.View.Print (bool printToPDF) [inline], [virtual]

Prints the contents of a view. Works identically to window.print() in Javascript (both can be used to print an HTML page). When the method is called, a pop-up window will be shown with the available print settings. Its possible to get the result in PDF format by calling the function with the value true.

Parameters

printToPDF	if this is set to true the function will print to PDF the default value is set to false

14.47.2.39 virtual void Coherent.UI.View.Print() [inline], [virtual]

Prints the contents of a view. Works identically to window.print() in Javascript (both can be used to print an HTML page). When the method is called, a pop-up window will be shown with the available print settings. Its possible to get the result in PDF format by calling the function with the value true.

Parameters

printToPDF	if this is set to true the function will print to PDF the default value is set to false

14.47.2.40 virtual void Coherent.UI.View.Redraw () [inline], [virtual]

Request a redraw of the current view.

14.47.2.41 BoundEventHandle Coherent.UI.View.RegisterForEvent (string name, System.Delegate handler) [inline]

Expose C++ handler to be called when a specific event occurs.

Parameters

name	name of the event
handler	handler to be executed

Returns

bound handle so the handler can be unregistered

14.47.2.42 virtual void Coherent.UI.View.Reload (bool ignoreCache) [inline], [virtual]

Reloads the last requested or navigated-to path.

Parameters

ignoreCache	whether to ignore the cache for the reload

14.47.2.43 virtual void Coherent.UI.View.ReplyToJavaScriptMessage (bool *success*, string *userInput*) [inline], [virtual]

Sends a reply to a javascript message triggered for the view.

Parameters

succe	defines whether the user replies positively to the message (i.e. clicks the OK button)	
userInp	ut the user reply message (only used in prompt messages)	

14.47.2.44 virtual ViewErrorType Coherent.UI.View.RequestFrame() [inline], [virtual]

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of This function must be called on the ViewContext thread. This overload let's Coherent Browser control the time in the view. You should have set ViewInfo::ControlTimeOnDemand to false to use it. If you need to control timing - use the other overload and create the view with ViewInfo::ControlTimeOnDemand set to true.

Returns

the outcome of the operation

14.47.2.45 virtual ViewErrorType Coherent.UI.View.RequestFrame (double timeSinceArbitraryMoment) [inline], [virtual]

Requests a new frame for rendering. All triggered events before this call will be accounted for in the rendered view. Only one frame per-view could be requested simultaneously (available only in Full versions of This function must be called on the ViewContext thread. This overload let's Coherent Browser control the time in the view. You should have set ViewInfo::ControlTimeOnDemand to false to use it. If you need to control timing - use the other overload and create the view with ViewInfo::ControlTimeOnDemand set to true.

Returns

the outcome of the operation

14.47.2.46 virtual void Coherent.UI.View.Resize (uint width, uint height) [inline], [virtual]

Send a resize event to the UI renderer. Resize will result in multiple calls to CreateBuffers and DestroyBuffers in the listener

Parameters

width	the new width of the View
height	the new height of the View

14.47.2.47 virtual void Coherent.UI.View.SetClickThroughAlphaThreshold (float threshold) [inline], [virtual]

The alpha value of the pixels is used to determine if the mouse is on an element or on the background (click-through). All pixels below or equal to the alpha threshold (default = 0) are marked as not-belonging to the

Parameters

threshold	sets the new alpha threshold

14.47.2.48 virtual void Coherent.UI.View.SetFocus() [inline], [virtual]

Sets this view on focus.

14.47.2.49 virtual void Coherent.UI.View.SetMasterVolume (double volume) [inline], [virtual]

Sets the master volume for all audio and video streams.

volume	coefficient between 0.0 and 1.0

14.47.2.50 virtual void Coherent.UI.View.SetScriptError (ScriptCallErrorType *error*, **string** *message* **)** [inline], [virtual]

Sets an error for the currently executing handler.

Parameters 4 6 1

error	the type of the error
message	the error message

14.47.2.51 virtual void Coherent.UI.View.SetTargetFramerate (int target) [inline], [virtual]

Sets the target frame-rate for the

Parameters

target	the new target frame-rate

14.47.2.52 virtual void Coherent.UI.View.SetZoomLevel (double zoomLevel) [inline], [virtual]

Sets the page zoom level. Specifying 0.0 will reset to the default zoom level. The API works with "levels", not factors. Each level represents 20% zoom. Negative values mean "zoom out", while positive values mean "zoom in". You can pass fractional levels as well. If you want to convert a factor to a level that you can pass to the API, you can use the following formula: level = logN(1.2, factor). In terms of C++ that would be the same as "log(factor) / log(1.2)". For example, if you want to make the content 50% smaller, you'll need a level of logN(1.2, 0.5) \sim = -3,8. If you want to make it 50% larger, you'll have logN(1.2, 1.5) \sim = 2.2. The zoom factor operates on protocol and host level, meaning that all views with the same protocol and host as the current URL will be scaled as well.

14.47.2.53 virtual bool Coherent.UI.View.SupportsClickThrough() [inline], [virtual]

Tells if this view supports click-through queries or not.

Returns

true if click-through is supported

14.47.2.54 virtual void Coherent.UI.View.TouchEvent (TouchEventData events, uint count) [inline], [virtual]

Sends a touch event to the UI renderer.

Parameters

events	array of touch events
count	the count of the passed touch events in the array

14.47.2.55 virtual void Coherent.UI.View.TriggerEvent (string eventName) [inline], [virtual]

Triggers a UI event.

14.47.2.56 void Coherent.UI.View.UnbindCall (BoundEventHandle handle) [inline]

Remove a bound C++ handler.

handle	the handle of the handler to be unbound
--------	---

14.47.2.57 void Coherent.UI.View.UnbindObject (object target) [inline]

Remove all handlers bound to a specific object.

Parameters

object the object whose handlers will be removed

14.47.2.58 void Coherent.UI.View.UnregisterFromEvent (BoundEventHandle handle) [inline]

Remove a registered C++ handler.

Parameters

handle the handle of the event handler to be unregistered

14.47.2.59 virtual bool Coherent.UI.View.UsesSharedMemory() [inline], [virtual]

Tells if this view uses shared memory for image transport.

Returns

true if the view uses shared memory, false if shared textures

14.48 Coherent.UI.ViewContext Class Reference

Encapsulates basic

Inherits IDisposable.

Public Member Functions

• virtual bool Uninitialize ()

Frees all resources used by the event system. the ViewContext object is unusable after this call

virtual void Update ()

Communicates with the UI context process and performs all updates. Must be called in the thread that owns the context. All registered callbacks will be called in here

• virtual void FetchSurfaces ()

Check if new surfaces have been drawn and are available. This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering. Fetches only the surfaces of buffered views; on-demand views must be fetched manually per-view

virtual void CreateView (ViewInfo info, string path, ViewListenerBase listener)

Creates a new UI Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::-ContextReady

• virtual void CreateView (ViewInfo info, string path, ViewListenerBase listener, string scriptToExecute)

Creates a new UI Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::-ContextReady

• virtual bool SaveCookies ()

Saves the cookies to disk. Must be called after the context has signaled that it is ready via Coherent::UI::Context-Listener::ContextReady

 virtual void AddCrossOriginWhitelistEntry (string sourceOrigin, string targetProtocol, string targetDomain, bool allowTargetSubdomains)

Add an entry to the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

 virtual void RemoveCrossOriginWhitelistEntry (string sourceOrigin, string targetProtocol, string target-Domain, bool allowTargetSubdomains)

Remove an entry from the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

virtual void ClearCrossOriginWhitelist ()

Remove all entries from the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

14.48.1 Detailed Description

Encapsulates basic

14.48.2 Member Function Documentation

14.48.2.1 virtual void Coherent.UI.ViewContext.AddCrossOriginWhitelistEntry (string sourceOrigin, string targetProtocol, string targetDomain, bool allowTargetSubdomains) [inline], [virtual]

Add an entry to the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

```
14.48.2.2 virtual void Coherent.UI.ViewContext.ClearCrossOriginWhitelist() [inline], [virtual]
```

Remove all entries from the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

14.48.2.3 virtual void Coherent.UI.ViewContext.CreateView (ViewInfo info, string path, ViewListenerBase listener) [inline], [virtual]

Creates a new UI Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::-ContextReady

Parameters

info	an instance of the ViewInfo struct that describes all the parameters of the view
path	the page to load when the view is created
listener	an instance of the ViewListenerBase interface to allow listening to all the events raised for
	this view

14.48.2.4 virtual void Coherent.UI.ViewContext.CreateView (ViewInfo info, string path, ViewListenerBase listener, string scriptToExecute) [inline], [virtual]

Creates a new UI Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::-ContextReady

Parameters

info	an instance of the ViewInfo struct that describes all the parameters of the view
path	the page to load when the view is created
listener	an instance of the ViewListenerBase interface to allow listening to all the events raised for
	this view

```
14.48.2.5 virtual void Coherent.UI.ViewContext.FetchSurfaces() [inline], [virtual]
```

Check if new surfaces have been drawn and are available. This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering. Fetches only the surfaces of buffered views; on-demand views must be fetched manually per-view

14.48.2.6 virtual void Coherent.UI.ViewContext.RemoveCrossOriginWhitelistEntry (string sourceOrigin, string targetProtocol, string targetDomain, bool allowTargetSubdomains) [inline], [virtual]

Remove an entry from the cross-origin access whitelist. Must be called after the context has signaled that it is ready via Coherent::UI::ContextListener::ContextReady

```
14.48.2.7 virtual bool Coherent.UI.ViewContext.SaveCookies() [inline], [virtual]
```

Saves the cookies to disk. Must be called after the context has signaled that it is ready via Coherent::UI::Context-Listener::ContextReady

Returns

true if cookies are enabled and a request for saving has been sent, false otherwise.

```
14.48.2.8 virtual bool Coherent.UI.ViewContext.Uninitialize() [inline], [virtual]
```

Frees all resources used by the event system. the ViewContext object is unusable after this call

Returns

true if the context has been properly uninitialized

```
14.48.2.9 virtual void Coherent.UI.ViewContext.Update() [inline], [virtual]
```

Communicates with the UI context process and performs all updates. Must be called in the thread that owns the context. All registered callbacks will be called in here

14.49 Coherent.UI.ViewError Class Reference

Encapsulates a view-related error.

Inherits IDisposable.

Properties

```
• ViewErrorType ErrorCode [get, set]

Indicates an error code.
```

```
• string Error [get, set]
```

Error description.

14.49.1 Detailed Description

Encapsulates a view-related error.

14.49.2 Property Documentation

```
14.49.2.1 string Coherent.UI.ViewError.Error [get], [set]
```

Error description.

```
14.49.2.2 ViewErrorType Coherent.UI.ViewError.ErrorCode [get], [set]
```

Indicates an error code.

14.50 Coherent.UI.ViewInfo Class Reference

Encapsulates the options of a

Inherits IDisposable.

Properties

```
• int Width [get, set]
```

The Width of a

• int Height [get, set]

The Height of a

• bool UsesSharedMemory [get, set]

Flags if a

bool SupportClickThrough [get, set]

Defines if the view should support click-through queries. Not supporting click-through increases performance slightly.

• float ClickThroughAlphaThreshold [get, set]

The alpha threshold for click-through queries.

• bool IsTransparent [get, set]

Defines if a view is transparent or not. A transparent view can be have transparent parts that will be correctly blended with the client's surfaces. Non-transparent views are always implicitly composited as if on a white background. Don't use transparent views unless you have transparent parts in the page because non-transparent view are slightly faster. Do not blend non-transparent views. Transparent Views are not supported in the Coherent In-Game Browser product

• int TargetFrameRate [get, set]

The frame-rate of the view will never exceed the target set here. It will also never exceed the rate at which the Context Update is called. (available only in Full versions of

• bool IsOnDemand [get, set]

Defines if a view is an on-demand view. On-demand views require explicit frame requests. (available only in Full versions of

• bool ControlTimeOnDemand [get, set]

Defines if the client controls the time of on-demand views himself. If not

• bool ForceSoftwareRendering [get, set]

Forces the view to use software rendering. If the application is GPU-bound pure software Views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software Views. Software Views are incompatible with the OnDemand option and work only with shared memory surfaces.

• bool DisplayVirtualKeyboard [get, set]

Display virtual keyboard when a text input widget is focused on touch enabled devices running Windows 8 and later.

14.50.1 Detailed Description

Encapsulates the options of a

14.50.2 Property Documentation

14.50.2.1 float Coherent.UI.ViewInfo.ClickThroughAlphaThreshold [get], [set]

The alpha threshold for click-through queries.

14.50.2.2 bool Coherent.UI.ViewInfo.ControlTimeOnDemand [get], [set]

Defines if the client controls the time of on-demand views himself. If not

14.50.2.3 bool Coherent.UI.ViewInfo.DisplayVirtualKeyboard [get], [set]

Display virtual keyboard when a text input widget is focused on touch enabled devices running Windows 8 and later.

```
14.50.2.4 bool Coherent.UI.ViewInfo.ForceSoftwareRendering [get], [set]
```

Forces the view to use software rendering. If the application is GPU-bound pure software Views might be a good choice. CSS 3D transforms, WebGL and accelerated Canvas don't work with software Views. Software Views are incompatible with the OnDemand option and work only with shared memory surfaces.

```
14.50.2.5 int Coherent.UI.ViewInfo.Height [get], [set]
```

The Height of a

```
14.50.2.6 bool Coherent.UI.ViewInfo.IsOnDemand [get], [set]
```

Defines if a view is an on-demand view. On-demand views require explicit frame requests. (available only in Full versions of

```
14.50.2.7 bool Coherent.UI.ViewInfo.IsTransparent [get], [set]
```

Defines if a view is transparent or not. A transparent view can be have transparent parts that will be correctly blended with the client's surfaces. Non-transparent views are always implicitly composited as if on a white background. Don't use transparent views unless you have transparent parts in the page because non-transparent view are slightly faster. Do not blend non-transparent views. Transparent Views are not supported in the Coherent In-Game Browser product

```
14.50.2.8 bool Coherent.UI.ViewInfo.SupportClickThrough [get], [set]
```

Defines if the view should support click-through queries. Not supporting click-through increases performance slightly.

```
14.50.2.9 int Coherent.UI.ViewInfo.TargetFrameRate [get], [set]
```

The frame-rate of the view will never exceed the target set here. It will also never exceed the rate at which the Context Update is called. (available only in Full versions of

14.50.2.10 bool Coherent.UI.ViewInfo.UsesSharedMemory [get], [set]

Flags if a


14.50.2.11 int Coherent.UI.ViewInfo.Width [get], [set]

The Width of a

14.51 Coherent.UI. ViewListener Class Reference

Interface that allows clients to listen to

Inheritance diagram for Coherent.UI.ViewListener:



Public Member Functions

• override void Release ()

Called when the listener is no longer needed by the UI context.

override void OnViewCreated (View view)

Called when the requested

override void OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height)

Called when a new surface has been drawn and is ready to use by the client.

 override void OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTP-Header[] headers)

Called when a frame has been successfully loaded.

· override void OnFailLoad (int frameld, string validatedPath, bool isMainFrame, string error)

Called when a frame has been failed loading.

override void OnURLRequest (URLRequest request)

Called before an URL request is made. The default implementation allows all requests.

• override void OnReadyForBindings (int frameld, string path, bool isMainFrame)

Called when a frame is ready for bindings.

• override void OnBindingsReleased (int frameld, string path, bool isMainFrame)

Called when the bindings for frame are released.

• override void OnStartLoading ()

Called when a new path has started loading.

• override void OnStopLoading ()

Called when all load operations have completed.

override void OnNavigateTo (string path)

Called when the view starts navigation to a new path.

override void OnError (ViewError error)

Called when an error occurs for this specific

 override void OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line)

Called when a message is sent from a script running in this specific

override void OnCursorChanged (CursorTypes cursor)

Called when the cursor has changed internally in the

· override void OnCallback (string eventName, Binding.CallbackArguments arguments)

Called by the UI when there is no registered handler for this event.

override void OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType)

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

override void OnGetAuthCredentials (bool isProxy, string host, uint port, string realm, string scheme)

Called when a view requires authentication credentials.

· override void CreateSurface (bool sharedMemory, uint width, uint height, SurfaceResponse response)

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8_UNORM

override void DestroySurface (CoherentHandle surface, bool usesSharedMemory)

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering.

override void OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateError-Response response)

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

override void OnClientCertificateRequested (string url, ClientCertificateResponse response)

Called when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

override void OnRequestMediaStream (MediaStreamRequest request)

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

override void OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline)

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

override void OnCaretRectChanged (uint x, uint y, uint width, uint height)

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

• override void OnIMEShouldCancelComposition ()

Called when the user must cancel the IME composition due to an event in the

override bool OnCanCreateChildWindow (string openerUrl, string targetUrl, ChildViewInfo childViewInfo)

Called when the view wants to open a new window.

override void OnFileSelectRequest (FileSelectRequest request)

Called when the view requests file selection. It could be either single file, directory or multiple files.

• override void OnAudioStreamCreated (int streamId, int channels, int bitDepth, int frequency)

Called when a new WebAudio stream is created. This is usually when the page is loading (for <audio> HTML tags).

override void OnAudioStreamPlay (int streamId)

Called when a WebAudio stream is played.

override void OnAudioStreamPause (int streamId)

Called when a WebAudio stream is stopped.

• override void OnAudioStreamClose (int streamId)

Called when a WebAudio stream is closed. This is usually called when the page is unloading.

override void OnPrintToPDFReady (IntPtr buffer, uint bufferSize)

Called when pdf data is needed.

Events

CoherentUI OnViewCreated ViewCreated

Fired when the requested

CoherentUI OnDraw Draw

Fired when a new surface has been drawn and is ready to use by the client.

CoherentUI OnFinishLoad FinishLoad

Fired when a frame has been successfully loaded.

CoherentUI OnFailLoad FailLoad

Fired when a frame has been failed loading.

CoherentUI_OnURLRequest URLRequest

Fired before an URL request is made. The default implementation allows all requests.

CoherentUI_OnReadyForBindings ReadyForBindings

Fired when a frame is ready for bindings.

• CoherentUI_OnBindingsReleased BindingsReleased

Fired when the bindings for frame are released.

CoherentUI OnStartLoading StartLoading

Fired when a new path has started loading.

· CoherentUI OnStopLoading StopLoading

Fired when all load operations have completed.

CoherentUI_OnNavigateTo NavigateTo

Fired when the view starts navigation to a new path.

• CoherentUI OnError Error

Fired when an error occurs for this specific

CoherentUI_OnScriptMessage ScriptMessage

Fired when a message is sent from a script running in this specific

CoherentUI OnCursorChanged CursorChanged

Fired when the cursor has changed internally in the

CoherentUI_OnCallback Callback

Fired by the UI when there is no registered handler for this event.

CoherentUI OnJavaScriptMessage JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

• CoherentUI OnGetAuthCredentials GetAuthCredentials

Fired when a view requires authentication credentials.

CoherentUI OnCertificateError CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

• CoherentUI_OnClientCertificateRequested ClientCertificateRequested

Fired when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

CoherentUI_OnRequestMediaStream RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

CoherentUI_OnTextInputTypeChanged TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

CoherentUI_OnCaretRectChanged CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

• CoherentUI OnIMEShouldCancelComposition IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

• CoherentUI_OnFileSelectRequest FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

CoherentUI_OnAudioStreamCreated AudioStreamCreated

Fired when a new WebAudio stream is created. This is usually when the page is loading (for < audio> HTML tags).

CoherentUI OnAudioStreamPlay AudioStreamPlay

Fired when a WebAudio stream is played.

CoherentUI OnAudioStreamPause AudioStreamPause

Fired when a WebAudio stream is stopped.

• CoherentUI OnAudioStreamClose AudioStreamClose

Fired when a WebAudio stream is closed. This is usually called when the page is unloading.

CoherentUI_OnPrintToPDFReady PrintToPDFReady

Fired when pdf data is needed.

Additional Inherited Members

14.51.1 Detailed Description

Interface that allows clients to listen to

14.51.2 Member Function Documentation

14.51.2.1 override void Coherent.UI.ViewListener.CreateSurface (bool *sharedMemory*, uint *width*, uint *height*, SurfaceResponse *response*) [inline], [virtual]

Called when the The format for DirectX9 must be D3DFMT_A8R8G8B8 The format for DirectX10 and DirectX11 must be B8G8R8A8_UNORM

Parameters

sharedMemory	true if the surface should be created in shared memory (4 * width * height bytes); false if a
	shared texture must be created.
width	the width of the surface in pixels
height	the height of the surface in pixels
response	
	object to hold the response when the surface is created or fails it's creation - must be signaled

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.2 override void Coherent.UI.ViewListener.DestroySurface (CoherentHandle *surface*, bool *usesSharedMemory*) [inline], [virtual]

Called when a surface is unneeded anymore and should be destroyed This function can be called from a thread different than the main UI context thread in order to support client applications with multi-threaded rendering.

Parameters

surface	handle to the surface
usesShared-	determines whether the surface parameter is a handle to shared memory or shared texture
Memory	

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.3 override void Coherent.UI.ViewListener.OnAudioStreamClose(int streamId) [inline], [virtual]

Called when a WebAudio stream is closed. This is usually called when the page is unloading.

Parameters

streamld	the ID of the stream that is closed
----------	-------------------------------------

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.4 override void Coherent.UI.ViewListener.OnAudioStreamCreated (int *streamId*, int *channels*, int *bitDepth*, int *frequency*) [inline], [virtual]

Called when a new WebAudio stream is created. This is usually when the page is loading (for <audio> HTML tags).

Parameters

streamld	the generated ID for the new stream
channels	the number of channels in the stream
bitDepth	bits per sample in the stream
frequency	the audio stream frequency, in Hz

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.5 override void Coherent.UI.ViewListener.OnAudioStreamPause (int streamId) [inline], [virtual]

Called when a WebAudio stream is stopped.

Parameters

streamld	the ID of the stream that is stopped

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.6 override void Coherent.UI.ViewListener.OnAudioStreamPlay (int streamId) [inline], [virtual]

Called when a WebAudio stream is played.

Parameters

streamld	the ID of the stream that is played

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.7 override void Coherent.UI.ViewListener.OnBindingsReleased (int *frameld*, string *path*, bool *isMainFrame*) [inline], [virtual]

Called when the bindings for frame are released.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.8 override void Coherent.UI.ViewListener.OnCallback (string eventName, Binding.CallbackArguments arguments) [inline], [virtual]

Called by the UI when there is no registered handler for this event.

Parameters

eventName	name of the event
arguments	arguments of the event invocation

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.9 override bool Coherent.UI.ViewListener.OnCanCreateChildWindow (string openerUrl, string targetUrl, ChildViewInfo childViewInfo) [inline], [virtual]

Called when the view wants to open a new window.

Parameters

openerUrl	the URL that wants to open the new window
targetUrl	the target URL of the new window
childViewInfo	structure that the user should fill in if she's about to allow new view creation

Returns

true if you allow the creation of a new window, false otherwise (if false, the childViewInfo parameter is ignored)

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.10 override void Coherent.UI.ViewListener.OnCaretRectChanged (uint x, uint y, uint width, uint height) [inline], [virtual]

Called when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

Parameters

the	x position of the selection caret
the	y position of the selection caret
the	width of the selection caret
the	height of the selection caret

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.11 override void Coherent.UI.ViewListener.OnCertificateError (string url, CertificateStatus status, Certificate certificate, CertificateErrorResponse response) [inline], [virtual]

Called when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

Parameters

url	the url of the request
status	the error status of the certificate
certificate	the certificate details. This pointer will be valid only for this call
response	object to signal whether to continue loading the URL. This pointer will be valid only for this
	call

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.12 override void Coherent.UI.ViewListener.OnClientCertificateRequested (string *url*, ClientCertificateResponse *response*) [inline], [virtual]

Called when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response

pointer is valid only for the duration of this call

Parameters

url	the url of the request
response	object used to provide certificate information or to cancel the request.

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.13 override void Coherent.UI.ViewListener.OnCursorChanged (CursorTypes *cursor*) [inline], [virtual]

Called when the cursor has changed internally in the

Parameters

cursor	the new cursor

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.14 override void Coherent.UI.ViewListener.OnDraw (CoherentHandle handle, bool usesSharedMemory, int width, int height) [inline], [virtual]

Called when a new surface has been drawn and is ready to use by the client.

Parameters

handle	a handle to one of the buffers created by CreateSurface. May be a shared memory buffer or
	a shared texture depending on the way the View was created. The handle is valid only during
	this call
usesShared-	determines whether the handle parameter is a handle to shared memory or shared texture
Memory	
width	the width of the surface
height	the height of the surface

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.15 override void Coherent.UI.ViewListener.OnError (ViewError error) [inline], [virtual]

Called when an error occurs for this specific

Parameters

error	error description

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.16 override void Coherent.UI.ViewListener.OnFailLoad (int *frameld*, string *validatedPath*, bool *isMainFrame*, string *error*) [inline], [virtual]

Called when a frame has been failed loading.

Parameters

_		
	frameld	the id of the frame
	validatedPath	the path in the frame
	isMainFrame	true if this is the main frame of the View
	error	error message for the failure

 $\label{lem:lemented_control_control} Reimplemented from \ Coherent. UI. View Listener Base.$

14.51.2.17 override void Coherent.UI.ViewListener.OnFileSelectRequest (FileSelectRequest request) [inline], [virtual]

Called when the view requests file selection. It could be either single file, directory or multiple files.

Parameters

request	contains the file selection params for the request

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.18 override void Coherent.UI.ViewListener.OnFinishLoad (int frameld, string validatedPath, bool isMainFrame, int statusCode, HTTPHeader[] headers) [inline], [virtual]

Called when a frame has been successfully loaded.

Parameters

frameld	the id of the loaded frame
validatedPath	the path loaded in the frame
isMainFrame	true if this is the main frame of the View
statusCode	the status code of the response
headers	an array of header fields
headersCount	the count of items in the headers array

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.19 override void Coherent.UI.ViewListener.OnGetAuthCredentials (bool *isProxy*, string *host*, uint *port*, string *realm*, string *scheme*) [inline], [virtual]

Called when a view requires authentication credentials.

Parameters

isProxy	whether the request came from a server or a proxy
host	the host which triggered the request
port	the port at which the request was triggered
realm	realm of the authentication challenge. Encoded in UTF-8
scheme	the authentication scheme used, e.g. "basic" or "digest". Encoded in ASCII

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.20 override void Coherent.UI.ViewListener.OnIMEShouldCancelComposition() [inline], [virtual]

Called when the user must cancel the IME composition due to an event in the

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.21 override void Coherent.UI.ViewListener.OnJavaScriptMessage (string message, string defaultPrompt, string frameUrl, int messageType) [inline], [virtual]

Called when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

Parameters

message	the JavaScript message
defaultPrompt	the default value of the prompt text box, in case the message type is prompt
frameUrl	the URL which created the message
messageType	the type of the message (alert/confirm/prompt)

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.22 override void Coherent.UI.ViewListener.OnNavigateTo (string path) [inline], [virtual]

Called when the view starts navigation to a new path.

Parameters

path	URL that the view is navigating to
------	------------------------------------

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.23 override void Coherent.UI.ViewListener.OnPrintToPDFReady (IntPtr *buffer*, uint *bufferSize*) [inline], [virtual]

Called when pdf data is needed.

Parameters

buffer	the container of the pdf data
bufferSize	size of the buffer

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.24 override void Coherent.UI.ViewListener.OnReadyForBindings (int *frameld*, string *path*, bool *isMainFrame*)
[inline], [virtual]

Called when a frame is ready for bindings.

Parameters

frameld	the id of the frame
path	the path in the frame
isMainFrame	true if this is the main frame of the view

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.25 override void Coherent.UI.ViewListener.OnRequestMediaStream (MediaStreamRequest request) [inline], [virtual]

Called when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

Parameters

request	contains the available media streams for the request
---------	--

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.26 override void Coherent.UI.ViewListener.OnScriptMessage (ViewListenerBase.MessageLevel level, string message, string sourceld, int line) [inline], [virtual]

Called when a message is sent from a script running in this specific

Parameters

level	message level
message	the text of the message
sourceld	id of the script (usually file name)
line	the number of the line in which the message was sent

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.27 override void Coherent.UI.ViewListener.OnStartLoading() [inline], [virtual]

Called when a new path has started loading.

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.28 override void Coherent.UI.ViewListener.OnStopLoading() [inline], [virtual]

Called when all load operations have completed.

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.29 override void Coherent.UI.ViewListener.OnTextInputTypeChanged (TextInputControlType type, bool canComposeInline) [inline], [virtual]

Called when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

Parameters

Ī	type	the type of the currently focused text input control by the user
	canCompose-	if the IME composition could be performed in-line in the control
	Inline	

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.30 override void Coherent.UI.ViewListener.OnURLRequest (URLRequest request) [inline], [virtual]

Called before an URL request is made. The default implementation allows all requests.

Parameters

request	the URLRequest object that can be used to modify the request. This pointer will be valid only
	for this call

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.31 override void Coherent.UI.ViewListener.OnViewCreated (View view) [inline], [virtual]

Called when the requested

Parameters

view	the instance of the view containing all manipulation methods

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.2.32 override void Coherent.UI.ViewListener.Release() [inline], [virtual]

Called when the listener is no longer needed by the UI context.

Reimplemented from Coherent.UI.ViewListenerBase.

14.51.3 Event Documentation

14.51.3.1 CoherentUI_OnAudioStreamClose Coherent.UI.ViewListener.AudioStreamClose

Fired when a WebAudio stream is closed. This is usually called when the page is unloading.

14.51.3.2 CoherentUI_OnAudioStreamCreated Coherent.UI.ViewListener.AudioStreamCreated

Fired when a new WebAudio stream is created. This is usually when the page is loading (for <audio> HTML tags).

14.51.3.3 CoherentUI_OnAudioStreamPause Coherent.UI.ViewListener.AudioStreamPause

Fired when a WebAudio stream is stopped.

14.51.3.4 CoherentUI_OnAudioStreamPlay Coherent.UI.ViewListener.AudioStreamPlay

Fired when a WebAudio stream is played.

14.51.3.5 CoherentUI_OnBindingsReleased Coherent.UI.ViewListener.BindingsReleased

Fired when the bindings for frame are released.

14.51.3.6 CoherentUI_OnCallback Coherent.UI.ViewListener.Callback

Fired by the UI when there is no registered handler for this event.

14.51.3.7 CoherentUI_OnCaretRectChanged Coherent.UI.ViewListener.CaretRectChanged

Fired when the caret changes during IME composition. You can use this method to correctly position a custom IME control & candidate list.

14.51.3.8 CoherentUI_OnCertificateError Coherent.UI.ViewListener.CertificateError

Fired when there is an error with the certificate of a particular URL. the certificate and response pointers are valid only for the duration of this call

14.51.3.9 CoherentUI OnClientCertificateRequested Coherent.UI.ViewListener.ClientCertificateRequested

Fired when in dual way SSL authentication the server prompts for user supplied certificate. The reponse object can be used to either provide information of of where the client certificate is, or cancel the request. the response pointer is valid only for the duration of this call

14.51.3.10 CoherentUI_OnCursorChanged Coherent.UI.ViewListener.CursorChanged

Fired when the cursor has changed internally in the

14.51.3.11 CoherentUI_OnDraw Coherent.UI.ViewListener.Draw

Fired when a new surface has been drawn and is ready to use by the client.

14.51.3.12 CoherentUI_OnError Coherent.UI.ViewListener.Error

Fired when an error occurs for this specific

14.51.3.13 CoherentUI_OnFailLoad Coherent.UI.ViewListener.FailLoad

Fired when a frame has been failed loading.

14.51.3.14 CoherentUI_OnFileSelectRequest Coherent.UI.ViewListener.FileSelectRequest

Fired when the view requests file selection. It could be either single file, directory or multiple files.

14.51.3.15 CoherentUI OnFinishLoad Coherent.UI.ViewListener.FinishLoad

Fired when a frame has been successfully loaded.

14.51.3.16 CoherentUI_OnGetAuthCredentials Coherent.UI.ViewListener.GetAuthCredentials

Fired when a view requires authentication credentials.

14.51.3.17 CoherentUI_OnIMEShouldCancelComposition Coherent.UI.ViewListener.IMEShouldCancelComposition

Fired when the user must cancel the IME composition due to an event in the

14.51.3.18 CoherentUI_OnJavaScriptMessage Coherent.UI.ViewListener.JavaScriptMessage

Fired when the view triggered a javascript message box, i.e. an alert, confirmation dialog or a prompt dialog.

14.51.3.19 CoherentUI_OnNavigateTo Coherent.UI.ViewListener.NavigateTo

Fired when the view starts navigation to a new path.

14.51.3.20 CoherentUI_OnPrintToPDFReady Coherent.UI.ViewListener.PrintToPDFReady

Fired when pdf data is needed.

14.51.3.21 CoherentUI_OnReadyForBindings Coherent.UI.ViewListener.ReadyForBindings

Fired when a frame is ready for bindings.

14.51.3.22 CoherentUI OnRequestMediaStream Coherent.UI.ViewListener.RequestMediaStream

Fired when the view requests access to a media stream. Media streams are the audio capture (microphone) and video capture (camera) devices on the system.

14.51.3.23 CoherentUI_OnScriptMessage Coherent.UI.ViewListener.ScriptMessage

Fired when a message is sent from a script running in this specific

14.51.3.24 CoherentUI_OnStartLoading Coherent.UI.ViewListener.StartLoading

Fired when a new path has started loading.

14.51.3.25 CoherentUI_OnStopLoading Coherent.UI.ViewListener.StopLoading

Fired when all load operations have completed.

14.51.3.26 CoherentUI_OnTextInputTypeChanged Coherent.UI.ViewListener.TextInputTypeChanged

Fired when the current text input control changes (i.e. the user click an edit-box). Use this methof to decide when to allow for IME input. the method will be called ONLY if IME is activated on this View. View::IMEActivate

14.51.3.27 CoherentUI_OnURLRequest Coherent.UI.ViewListener.URLRequest


Fired before an URL request is made. The default implementation allows all requests.

14.51.3.28 CoherentUI_OnViewCreated Coherent.UI.ViewListener.ViewCreated

Fired when the requested

14.52 Coherent.UI.ViewListenerBase Class Reference

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener Inheritance diagram for Coherent.UI.ViewListenerBase:



Public Types

• enum MessageLevel

Levels of script messages.

14.52.1 Detailed Description

Interface all view listeners inherit. For an easier to use interface inherit instead -. Coherent::UI::ViewListener

14.52.2 Member Enumeration Documentation

14.52.2.1 enum Coherent.UI.ViewListenerBase.MessageLevel

Levels of script messages.

Index

Accept	Coherent::UI::HTTPHeader, 114
Coherent::UI::HTTPHeader, 114	
AcceptCharset	BindCall
Coherent::UI::HTTPHeader, 114	Coherent::UI::View, 143
AcceptEncoding	BindMethods
Coherent::UI::HTTPHeader, 114	Coherent::UI::Binding::BoundObject, 67
AcceptLanguage	BindingsReleased
Coherent::UI::HTTPHeader, 114	Coherent::UI::BrowserViewListener, 80
AcceptRanges	Coherent::UI::ViewListener, 172
Coherent::UI::HTTPHeader, 114	Boolean
AcceptedMIMETypes	Coherent::UI::Binding, 63
Coherent::UI::FileSelectionParams, 111	Button
AcceptedMIMETypesCount	Coherent::UI::MouseEventData, 120
Coherent::UI::FileSelectionParams, 111	Byte
Add	Coherent::UI::Binding, 63
Coherent::UI::FileSelectRequest, 112	
AddCrossOriginWhitelistEntry	CE_GPUProcessCrash
Coherent::UI::ViewContext, 154	Coherent::UI, 60
AdditionalHostOptions	CE_GPUProcessDeviceMismatch
Coherent::UI::ContextSettingsBase, 104	Coherent::UI, 60
All	CE_InternalError
Coherent::UI::Binding, 63	Coherent::UI, 60
AllowCookies	CE_InvalidKey
Coherent::UI::ContextSettingsBase, 104	Coherent::UI, 60
AppGroupName	CE_MissingComponent
Coherent::UI::FactorySettings, 109	Coherent::UI, 60
AppendExtraHeaderValue	CE_Success
Coherent::UI::URLRequest, 126	Coherent::UI, 60
Arguments	CE_VersionMismatch
Coherent::UI::Binding::CallbackArguments, 87	Coherent::UI, 60
Array	CacheControl
Coherent::UI::Binding, 63	Coherent::UI::HTTPHeader, 114
Assert	CachePath
Coherent::UI::ILogHandler, 115	Coherent::UI::ContextSettings, 103
AudioStreamClose	call
Coherent::UI::BrowserViewListener, 80	engine, 64
Coherent::UI::ViewListener, 171	Callback
AudioStreamCreated	Coherent::UI::BrowserViewListener, 81
Coherent::UI::BrowserViewListener, 80	Coherent::UI::ViewListener, 172
Coherent::UI::ViewListener, 171	Cancel
AudioStreamPause	Coherent::UI::Download, 106
Coherent::UI::BrowserViewListener, 80	CancelRequest
	Coherent::UI::ClientCertificateResponse, 90
Coherent::UI::ViewListener, 172	CaretRectChanged
AudioStreamPlay	Coherent::UI::BrowserViewListener, 81
Coherent::UI::BrowserViewListener, 80	Coherent::UI::ViewListener, 172
Coherent::UI::ViewListener, 172	CertificateError
AuthCredentialsResponse	Coherent::UI::BrowserViewListener, 81
Coherent::UI::View, 142	Coherent::UI::ViewListener, 172
Authorization	CertificateStatus

Coherent::UI, 60	Coherent.UI.TouchEventData, 124
Char	Coherent.UI.URLRequest, 126
Coherent::UI::Binding, 63	Coherent.UI.URLRequestBase, 128
ClearCrossOriginWhitelist	Coherent.UI.View, 139
Coherent::UI::ViewContext, 154	Coherent.UI.ViewContext, 153
Click	Coherent.UI.ViewError, 155
Coherent::UI::Button, 85	Coherent.UI.ViewInfo, 156
ClickThroughAlphaThreshold	Coherent.UI.ViewListener, 158
Coherent::UI::ViewInfo, 157	Coherent.UI.ViewListenerBase, 174
CoherentUIView, 97	Coherent::UI
ClickToFocus	CE_GPUProcessCrash, 60
CoherentUIView, 97	CE_GPUProcessDeviceMismatch, 60
ClientCertificateRequested	CE_InternalError, 60
Coherent::UI::BrowserViewListener, 81	CE_InvalidKey, 60
Coherent::UI::ViewListener, 172	CE_MissingComponent, 60
Coherent, 57	CE_Success, 60
Coherent.UI, 57	CE_VersionMismatch, 60
Coherent.UI.Binding, 62	DET_DownloadOperationFailed, 60
Coherent.UI.Binding.BoundObject, 67	DET_Success, 60
Coherent.UI.Binding.CallbackArguments, 87	SCE_ArgumentType, 61
Coherent.UI.Binding.CoherentProperty, 90	SCE NoResult, 61
Coherent.UI.Binding.CoherentType, 91	SCE_NoSuchMethod, 61
Coherent.UI.Binding.InvalidValueCastException, 116	SCE_Success, 61
Coherent.UI.Binding.UnsupportedPrimitiveTypeException,	SET Error, 61
125	SET_OfflineGracePeriod, 61
Coherent.UI.Binding.Value, 130	SET_Success, 61
Coherent.UI.Binding.ValueObject, 139	SET SuccessNotify, 61
Coherent.UI.BrowserView, 67	VE AbnormalTermination, 62
Coherent.UI.BrowserViewListener, 68	VE_ChildCompositionFailed, 62
Coherent.UI.BrowserViewListenerBase, 83	VE_ClickThroughFailed, 62
Coherent.UI.Button, 83	VE FailedCreation, 61
Coherent.UI.ButtonHandler, 85	VE_FailedRenderingCreation, 62
Coherent.UI.CertificatePrincipal, 88	VE_FrameAlreadyInFlight, 62
Coherent.UI.ChildViewInfo, 89	VE FrameNotReady, 62
Coherent.UI.ClientCertificateResponse, 89	VE FrameNotRequeted, 62
Coherent.UI.ContextError, 101	VE_InvalidCall, 62
Coherent.UI.ContextListener, 101	VE InvalidPath, 62
Coherent.UI.ContextSettings, 103	VE_QueryNotReady, 62
Coherent.UI.ContextSettingsBase, 104	VE Success, 61
Coherent.UI.Download, 105	Coherent::UI::Binding
Coherent.UI.EventModifiersState, 108	All, 63
Coherent.UI.EventMouseModifiersState, 108	Array, 63
Coherent.UI.FactorySettings, 108	Boolean, 63
Coherent.UI.FactorySettingsBase, 109	Byte, 63
Coherent.UI.FileHandler, 110	Char, 63
Coherent.UI.FileSelectRequest, 112	Explicit, 63
Coherent.UI.FileSelectionParams, 111	Instance, 63
Coherent.UI.HTTPHeader, 113	Integer, 63
Coherent.UI.ILogHandler, 115	Null, 63
Coherent.UI.ImageData, 116	Number, 63
Coherent.UI.KeyEventData, 117	Object, 63
Coherent.UI.MediaStreamDevice, 118	SByte, 63
Coherent.UI.MediaStreamRequest, 118	Static, 63
Coherent.UI.MouseEventData, 120	String, 63
Coherent.UI.ResourceData, 121	UInteger, 63
Coherent.UI.ResourceResponse, 122	Coherent::UI::HTTPHeader
Coherent.UI.SubscriptionError, 123	Accept, 114
Coherent.UI.SurfaceResponse, 124	AcceptCharset, 114
·	

AcceptEncoding, 114	operator string, 137
AcceptLanguage, 114	operator uint, 137
AcceptRanges, 114	operator==, 139
Authorization, 114	Type, 139
CacheControl, 114	Value, 131, 132, 134
Connection, 114	Coherent::UI::BrowserView
ContentLength, 114	GetHistory, 68
ContentRange, 114	GetViewType, 68
ContentType, 114	GoBack, 68
Cookie, 114	GoForward, 68
Host, 114	Coherent::UI::BrowserViewListener
IfModifiedSince, 114	AudioStreamClose, 80
IfNoneMatch, 114	AudioStreamCreated, 80
IfRange, 114	AudioStreamPause, 80
Origin, 114	AudioStreamPlay, 80
Pragma, 114	BindingsReleased, 80
ProxyAuthorization, 114	Callback, 81
ProxyConnection, 114	CaretRectChanged, 81
Range, 114	CertificateError, 81
Referer, 114	ClientCertificateRequested, 81
TransferEncoding, 114	CreateSurface, 71
UserAgent, 114	CursorChanged, 81
Coherent::UI	DestroySurface, 72
CertificateStatus, 60	Draw, 81
ContextErrorType, 60	Error, 81
CursorTypes, 60	FailLoad, 81
Direct3DInterfaceType, 60	FileSelectRequest, 81
DownloadErrorType, 60	FinishLoad, 81
FileSelectionMode, 60	GetAuthCredentials, 81
JavaScriptMessageType, 61	IMEShouldCancelComposition, 82
MediaStreamType, 61	JavaScriptMessage, 82
RenderingDeviceType, 61	NavigateTo, 82
ScriptCallErrorType, 61	OnAudioStreamClose, 72
SubscriptionErrorType, 61	OnAudioStreamCreated, 72
TextInputControlType, 61	OnAudioStreamPause, 72
UserAgentType, 61	OnAudioStreamPlay, 73
	OnBindingsReleased, 73
ViewErrorType, 61 ViewType, 62	OnCallback, 73
Coherent::UI::Binding	OnCanCreateChildWindow, 73
PropertyBindingFlags, 63	OnCaretRectChanged, 73
ValueType, 63	OnCertificateError, 75
Coherent::UI::Binding::BoundObject	OnClientCertificateRequested, 75
BindMethods, 67	OnCursorChanged, 75
Coherent::UI::Binding::CallbackArguments	OnDraw, 75
Arguments, 87	OnError, 76
Coherent::UI::Binding::CoherentProperty	OnFailLoad, 76
CoherentProperty, 90	
	OnFileSelectRequest, 76 OnFinishLoad, 76
Coherent::UI::Binding::Value	,
Equals, 134	OnGetAuthCredentials, 77
GetHashCode, 134	OnIMEShouldCancelComposition, 77
operator bool, 134	OnJavaScriptMessage, 77
operator ober 135	OnNavigateTo, 77
operator char, 135	OnPrintToPDFReady, 77
operator Dictionary< string, Value >, 135	OnReadyForBindings, 78
operator double, 135	OnRequestMediaStream, 78
operator float, 135	OnScriptMessage, 78
operator int, 135	OnStartLoading, 78
operator sbyte, 137	OnStopLoading, 78

OnTextInputTypeChanged, 78	AdditionalHostOptions, 104
OnURLRequest, 80	AllowCookies, 104
OnViewCreated, 80	DebuggerPort, 105
PrintToPDFReady, 82	DisableWebSecurity, 105
ReadyForBindings, 82	EnableClientAudioPlayback, 105
Release, 80	EnableProxy, 105
RequestMediaStream, 82	ForceDisablePluginFullscreen, 105
ScriptMessage, 82	SubscriptionEmail, 105
StartLoading, 82	SubscriptionKey, 105
StopLoading, 82	UserAgent, 105
TextInputTypeChanged, 82	Coherent::UI::Download
URLRequest, 82	Cancel, 106
ViewCreated, 82	Destroy, 106
Coherent::UI::Button	GetDownloadedBytesSoFar, 106
Click, 85	GetFilename, 107
Disabled, 85	Getld, 107
Initialize, 84	GetReferrer, 107
Label, 85	GetTotalBytes, 107
Coherent::UI::ButtonHandler	GetURL, 107
Handler, 87	HasFailed, 107
Initialize, 86	IsCancelled, 108
Invoke, 87	IsComplete, 108
Invoker, 87	Coherent::UI::FactorySettings
IsMessage, 87	AppGroupName, 109
Method, 87	HostDirectory, 109
Target, 87	MinidumpFolder, 109
Coherent::UI::CertificatePrincipal	Coherent::UI::FactorySettingsBase
CommonName, 88	EnableSupportForProprietaryCodecs, 110
CountryName, 88	WriteMinidumps, 110
DomainComponents, 88	Coherent::UI::FileHandler
LocalityName, 88	ReadFile, 110
OrganizationNames, 88	WriteFile, 111
OrganizationUnitNames, 88	Coherent::UI::FileSelectRequest
StateOrProvinceName, 89	Add, 112
StreetAddresses, 89	Finish, 112
Coherent::UI::ChildViewInfo	GetFileSelectionParams, 112
Listener, 89	Coherent::UI::FileSelectionParams
NewViewInfo, 89	AcceptedMIMETypes, 111
Coherent::UI::ClientCertificateResponse	AcceptedMIMETypesCount, 111
CancelRequest, 90	DefaultFileName, 111
ContinueRequest, 90	DialogTitle, 112
Coherent::UI::ContextError	Mode, 112
Error, 101	Coherent::UI::HTTPHeader
ErrorCode, 101	Content, 115
Coherent::UI::ContextListener	Field, 115
ContextReady, 102	FieldType, 114
OnCookiesSaved, 102	GetHeaderField, 114
OnDownloadComplete, 102	Coherent::UI::ILogHandler
OnDownloadFailed, 102	Assert, 115
OnDownloadStarted, 102	WriteLog, 115
OnError, 102	Coherent::UI::ImageData
OnSubscriptionCheckDone, 102	Destroy, 116
Coherent::UI::ContextSettings	Update, 116
CachePath, 103	Coherent::UI::KeyEventData
CookiesResource, 103	IsAutoRepeat, 117
CustomUserAgentString, 103	IsNumPad, 117
HTML5LocalStoragePath, 103	IsSystemKey, 117
Coherent::UI::ContextSettingsBase	KeyCode, 117
Control in	10y000 0 , 117

Modifiers, 117	HasExtraHeader, 129
Type, 117	Coherent::UI::View
Coherent::UI::MediaStreamDevice	AuthCredentialsResponse, 142
DeviceId, 118	BindCall, 143
Name, 118	CreateImageData, 143
Type, 118	Destroy, 143
Coherent::UI::MediaStreamRequest	DownloadUrl, 143
Devices, 119	DrawSurface, 143
Respond, 119	ExecuteScript, 143
Coherent::UI::MouseEventData	FetchMouseOnUIQuery, 144
Button, 120	FetchSurface, 144
Modifiers, 120	GetAudioData, 144
MouseModifiers, 120	GetClickThroughAlphaThreshold, 144
Type, 120	GetContext, 144
WheelX, 121	GetCurentViewPath, 144
WheelY, 121	GetHeight, 145
X, 121	GetLastFailedPath, 145
Y, 121	GetLastLoadedPath, 145
Coherent::UI::ResourceData	GetLastRequestedPath, 145
GetBuffer, 121	GetTargetFramerate, 145
GetSize, 122	GetViewType, 145
SignalFailure, 122	GetWidth, 145
SignalSuccess, 122	HasMouseQueryFinished, 146
Coherent::UI::ResourceResponse	IMEActivate, 146
GetBuffer, 122	IMECancelComposition, 146
	•
SetResponseHeader, 123	IMEConfirmComposition, 146
SetStatus, 123	IMEIsActive, 146
SignalFailure, 123	IMESetComposition, 146
SignalSuccess, 123	InterceptURLRequests, 147
Coherent::UI::SubscriptionError	IsMouseOnView, 147
Error, 124	IsOnDemand, 147
ErrorCode, 124	IsTransparent, 148
Coherent::UI::SurfaceResponse	IssueMouseOnUIQuery, 147
Signal, 124	KeyEvent, 148
Coherent::UI::TouchEventData	KillFocus, 148
HasRadiusInformation, 125	Load, 148
ld, 125	MouseActivate, 148
RadiusX, 125	MouseEvent, 148
RadiusY, 125	PeekFrameReady, 148
Type, 125	Print, 148, 149
X, 125	Redraw, 149
Y, 125	RegisterForEvent, 149
Coherent::UI::URLRequest	Reload, 149
AppendExtraHeaderValue, 126	ReplyToJavaScriptMessage, 149
Deny, 127	RequestFrame, 150
RemoveExtraHeader, 127	Resize, 150
SetExtraHeader, 127	SetClickThroughAlphaThreshold, 150
SetExtraHeaders, 127	SetFocus, 150
SetMethod, 127	SetMasterVolume, 150
SetReferrer, 127	SetScriptError, 151
SetURL, 127	SetTargetFramerate, 151
Coherent::UI::URLRequestBase	SetZoomLevel, 151
GetExtraHeader, 128	SupportsClickThrough, 151
	TouchEvent, 151
GetExtraHeaderIndex, 128	
GetExtraHeaders, 129	TriggerEvent, 151
GetMethod, 129	UnbindCall, 151
GetReferrer, 129	UnbindObject, 153
GetURL, 129	UnregisterFromEvent, 153

UsesSharedMemory, 153	OnDraw, 166
Coherent::UI::ViewContext	OnError, 166
AddCrossOriginWhitelistEntry, 154	OnFailLoad, 166
ClearCrossOriginWhitelist, 154	OnFileSelectRequest, 166
CreateView, 154	OnFinishLoad, 168
FetchSurfaces, 155	OnGetAuthCredentials, 168
RemoveCrossOriginWhitelistEntry, 155	OnIMEShouldCancelComposition, 168
SaveCookies, 155	OnJavaScriptMessage, 168
Uninitialize, 155	OnNavigateTo, 168
Update, 155	OnPrintToPDFReady, 170
Coherent::UI::ViewError	OnReadyForBindings, 170
Error, 156	OnRequestMediaStream, 170
ErrorCode, 156	OnScriptMessage, 170
Coherent::UI::ViewInfo	OnStartLoading, 170
ClickThroughAlphaThreshold, 157	OnStopLoading, 171
ControlTimeOnDemand, 157	OnTextInputTypeChanged, 171
DisplayVirtualKeyboard, 157	OnURLRequest, 171
ForceSoftwareRendering, 157	OnViewCreated, 171
Height, 157	PrintToPDFReady, 173
IsOnDemand, 157	ReadyForBindings, 173
IsTransparent, 157	Release, 171
SupportClickThrough, 157	RequestMediaStream, 173
TargetFrameRate, 157	ScriptMessage, 173
UsesSharedMemory, 157	StartLoading, 173
Width, 158	StopLoading, 173
Coherent::UI::ViewListener	TextInputTypeChanged, 174
AudioStreamClose, 171	URLRequest, 174
AudioStreamCreated, 171	ViewCreated, 174
AudioStreamPause, 172	Coherent::UI::ViewListenerBase
AudioStreamPlay, 172	MessageLevel, 174
BindingsReleased, 172	CoherentProperty
Callback, 172	Coherent::UI::Binding::CoherentProperty, 90
CaretRectChanged, 172	CoherentUILiveGameView, 91
CertificateError, 172	CoherentUISystem, 91
ClientCertificateRequested, 172	DiskCacheSize, 93
CreateSurface, 161	FileHandlerFactoryFunc, 92
CursorChanged, 172	HasFocusedView, 93
DestroySurface, 161	IsReady, 92
Draw, 172	IsUpdating, 93
Error, 172	m_MainCamera, 93
FailLoad, 172	MemoryCacheSize, 93
FileSelectRequest, 173	OnViewFocused, 94
FinishLoad, 173	SystemListenerFactoryFunc, 93
GetAuthCredentials, 173	UISystem, 93
IMEShouldCancelComposition, 173	UseURLCache, 93
JavaScriptMessage, 173	CoherentUIView, 94
NavigateTo, 173	ClickThroughAlphaThreshold, 97
OnAudioStreamClose, 161	ClickToFocus, 97
OnAudioStreamCreated, 163	CorrectGamma, 97
OnAudioStreamPause, 163	DestroyView, 96
OnAudioStreamPlay, 163	DisplayVirtualKeyboard, 97
OnBindingsReleased, 163	DrawAfterPostEffects, 97
OnCallback, 163	EnableBindingAttribute, 97
OnCanCreateChildWindow, 164	EnableIME, 97
OnCaretRectChanged, 164	EnableWebGLSupport, 98
OnCertificateError, 164	FlipY, 98
OnClientCertificateRequested, 164	ForceSoftwareRendering, 98
OnCursorChanged, 166	GetCamDimensions, 96

Height, 98	CreateSurface
IgnoreDisplayDensity, 98	Coherent::UI::BrowserViewListener, 71
InitialScript, 98	Coherent::UI::ViewListener, 161
InputState, 98	CreateView
InterceptAllEvents, 98	Coherent::UI::ViewContext, 154
IsIndependentOfZBuffer, 99	CursorChanged
IsSurfaceView, 99	Coherent::UI::BrowserViewListener, 81
	Coherent::UI::ViewListener, 172
IsTransparent, 99	CursorTypes
Listener, 99	- ·
OnReadyForBindings, 99	Coherent::UI, 60
OnViewCreated, 99	CustomUserAgentString
OnViewDestroyed, 101	Coherent::UI::ContextSettings, 103
Page, 99	DET_DownloadOperationFailed
ReceivesInput, 99	Coherent::UI, 60
Reload, 96	DET Success
Resize, 96	_
ScaleToFit, 100	Coherent::UI, 60
SetMousePosition, 96	DebuggerPort
ShowJavaScriptDialogs, 100	Coherent::UI::ContextSettingsBase, 105
SupportClickThrough, 100	DefaultFileName
UseCameraDimensions, 100	Coherent::UI::FileSelectionParams, 111
View, 100	Deny
ViewDestroyedHandler, 97	Coherent::UI::URLRequest, 127
-	Destroy
Width, 100	Coherent::UI::Download, 106
XPos, 100	Coherent::UI::ImageData, 116
YPos, 100	Coherent::UI::View, 143
CommonName	DestroySurface
Coherent::UI::CertificatePrincipal, 88	Coherent::UI::BrowserViewListener, 72
Connection	Coherent::UI::ViewListener, 161
Coherent::UI::HTTPHeader, 114	DestroyView
Content	CoherentUIView, 96
Coherent::UI::HTTPHeader, 115	DeviceId
ContentLength	Coherent::UI::MediaStreamDevice, 118
Coherent::UI::HTTPHeader, 114	Devices
ContentRange	
Coherent::UI::HTTPHeader, 114	Coherent::UI::MediaStreamRequest, 119
ContentType	DialogTitle
Coherent::UI::HTTPHeader, 114	Coherent::UI::FileSelectionParams, 112
ContextErrorType	Direct3DInterfaceType
Coherent::UI, 60	Coherent::UI, 60
	DisableWebSecurity
ContextReady	Coherent::UI::ContextSettingsBase, 105
Coherent::UI::ContextListener, 102	Disabled
ContinueRequest	Coherent::UI::Button, 85
Coherent::UI::ClientCertificateResponse, 90	DiskCacheSize
ControlTimeOnDemand	CoherentUISystem, 93
Coherent::UI::ViewInfo, 157	DisplayVirtualKeyboard
Cookie	Coherent::UI::ViewInfo, 157
Coherent::UI::HTTPHeader, 114	CoherentUIView, 97
CookiesResource	DomainComponents
Coherent::UI::ContextSettings, 103	Coherent::UI::CertificatePrincipal, 88
CorrectGamma	DownloadErrorType
CoherentUIView, 97	Coherent::UI, 60
CountryName	DownloadUrl
Coherent::UI::CertificatePrincipal, 88	Coherent::UI::View, 143
createDeferred	Draw
engine, 64	
	Coherent::UI::BrowserViewListener, 81
CreateImageData	Coherent::UI::ViewListener, 172
Coherent::UI::View, 143	DrawAfterPostEffects

CoherentUIView, 97	Finish
DrawSurface	Coherent::UI::FileSelectRequest, 112
Coherent::UI::View, 143	FinishLoad
	Coherent::UI::BrowserViewListener, 81
EnableBindingAttribute	Coherent::UI::ViewListener, 173
CoherentUIView, 97	FlipY
EnableClientAudioPlayback	CoherentUIView, 98
Coherent::UI::ContextSettingsBase, 105	ForceDisablePluginFullscreen
EnableIME	Coherent::UI::ContextSettingsBase, 105
CoherentUIView, 97	ForceSoftwareRendering
EnableProxy	Coherent::UI::ViewInfo, 157
Coherent::UI::ContextSettingsBase, 105	CoherentUIView, 98
EnableSupportForProprietaryCodecs	, , , , , , , , , , , , , , , , , , , ,
Coherent::UI::FactorySettingsBase, 110	GetAudioData
EnableWebGLSupport	Coherent::UI::View, 144
CoherentUIView, 98	GetAuthCredentials
engine, 63	Coherent::UI::BrowserViewListener, 81
call, 64	Coherent::UI::ViewListener, 173
createDeferred, 64	GetBuffer
off, 64	Coherent::UI::ResourceData, 121
on, 65	Coherent::UI::ResourceResponse, 122
trigger, 65	GetCamDimensions
Equals	CoherentUIView, 96
•	GetClickThroughAlphaThreshold
Coherent::UI::Binding::Value, 134	Coherent::UI::View, 144
Error	GetContext
Coherent::UI::BrowserViewListener, 81	Coherent::UI::View, 144
Coherent::UI::ContextError, 101	GetCurentViewPath
Coherent::UI::SubscriptionError, 124	
Coherent::UI::ViewError, 156	Coherent::UI::View, 144
Coherent::UI::ViewListener, 172	GetDownloadedBytesSoFar
ErrorCode	Coherent::UI::Download, 106
Coherent::UI::ContextError, 101	GetExtraHeader
Coherent::UI::SubscriptionError, 124	Coherent::UI::URLRequestBase, 128
Coherent::UI::ViewError, 156	GetExtraHeaderIndex
ExecuteScript	Coherent::UI::URLRequestBase, 128
Coherent::UI::View, 143	GetExtraHeaders
Explicit	Coherent::UI::URLRequestBase, 129
Coherent::UI::Binding, 63	GetFileSelectionParams
	Coherent::UI::FileSelectRequest, 112
FailLoad	GetFilename
Coherent::UI::BrowserViewListener, 81	Coherent::UI::Download, 107
Coherent::UI::ViewListener, 172	GetHashCode
FetchMouseOnUIQuery	Coherent::UI::Binding::Value, 134
Coherent::UI::View, 144	GetHeaderField
FetchSurface	Coherent::UI::HTTPHeader, 114
Coherent::UI::View, 144	GetHeight
FetchSurfaces	Coherent::UI::View, 145
Coherent::UI::ViewContext, 155	GetHistory
Field	Coherent::UI::BrowserView, 68
Coherent::UI::HTTPHeader, 115	GetId
FieldType	Coherent::UI::Download, 107
Coherent::UI::HTTPHeader, 114	GetLastFailedPath
FileHandlerFactoryFunc	Coherent::View, 145
CoherentUISystem, 92	GetLastLoadedPath
FileSelectRequest	Coherent::UI::View, 145
Coherent::UI::BrowserViewListener, 81	GetLastRequestedPath
Coherent::UI::ViewListener, 173	Coherent::UI::View, 145
FileSelectionMode	GetMethod
Coherent::UI, 60	Coherent::UI::URLRequestBase, 129
	ConcretitOriOrichitequestbase, 129

GetReferrer	IfModifiedSince
Coherent::UI::Download, 107	Coherent::UI::HTTPHeader, 114
Coherent::UI::URLRequestBase, 129	IfNoneMatch
GetSize	Coherent::UI::HTTPHeader, 114
Coherent::UI::ResourceData, 122	IfRange
GetTargetFramerate	Coherent::UI::HTTPHeader, 114
Coherent::UI::View, 145	IgnoreDisplayDensity
GetTotalBytes	CoherentUIView, 98
Coherent::UI::Download, 107	InitialScript
GetURL	CoherentUIView, 98
Coherent::UI::Download, 107	Initialize
Coherent::UI::URLRequestBase, 129	Coherent::UI::Button, 84
GetViewType	Coherent::UI::ButtonHandler, 86
Coherent::UI::BrowserView, 68	InputState
Coherent::UI::View, 145	CoherentUIView, 98
GetWidth	Instance
Coherent::UI::View, 145	Coherent::UI::Binding, 63
GoBack	_
Coherent::UI::BrowserView, 68	Integer
GoForward	Coherent::UI::Binding, 63
Coherent::UI::BrowserView, 68	InterceptAllEvents
Controlled Drowood view, Co	CoherentUIView, 98
HTML5LocalStoragePath	InterceptURLRequests
Coherent::UI::ContextSettings, 103	Coherent::UI::View, 147
Handler	Invoke
Coherent::UI::ButtonHandler, 87	Coherent::UI::ButtonHandler, 87
HasExtraHeader	Invoker
Coherent::UI::URLRequestBase, 129	Coherent::UI::ButtonHandler, 87
HasFailed	IsAutoRepeat
Coherent::UI::Download, 107	Coherent::UI::KeyEventData, 117
HasFocusedView	IsCancelled
CoherentUISystem, 93	Coherent::UI::Download, 108
HasMouseQueryFinished	IsComplete
Coherent::UI::View, 146	Coherent::UI::Download, 108
HasRadiusInformation	IsIndependentOfZBuffer
Coherent::UI::TouchEventData, 125	CoherentUIView, 99
Height	IsMessage
Coherent::UI::ViewInfo, 157	Coherent::UI::ButtonHandler, 87
CoherentUIView, 98	IsMouseOnView
Host	Coherent::UI::View, 147
Coherent::UI::HTTPHeader, 114	IsNumPad
HostDirectory	Coherent::UI::KeyEventData, 117
Coherent::UI::FactorySettings, 109	IsOnDemand
Conerentorr actory Settings, 109	Coherent::UI::View, 147
IMEActivate	Coherent::UI::ViewInfo, 157
Coherent::UI::View, 146	IsReady
IMECancelComposition	CoherentUISystem, 92
Coherent::UI::View, 146	IsSurfaceView
IMEConfirmComposition	CoherentUIView, 99
Coherent::UI::View, 146	IsSystemKey
IMEIsActive	Coherent::UI::KeyEventData, 117
	IsTransparent
Coherent::UI::View, 146	Coherent::UI::View, 148
IMESetComposition	
Coherent::UI::View, 146	Coherent IIView 99
IMEShouldCancelComposition	CoherentUIView, 99
Coherent::UI::BrowserViewListener, 82	IsUpdating
Coherent::UI::ViewListener, 173	CoherentUISystem, 93
Id	IssueMouseOnUIQuery
Coherent::UI::TouchEventData, 125	Coherent::UI::View, 147

JavaScriptMessage	Coherent::UI::Binding, 63
Coherent::UI::BrowserViewListener, 82	
Coherent::UI::ViewListener, 173	Object
JavaScriptMessageType	Coherent::UI::Binding, 63
Coherent::UI, 61	off
	engine, 64
KeyCode	on
Coherent::UI::KeyEventData, 117	engine, 65
KeyEvent	OnAudioStreamClose
Coherent::UI::View, 148	Coherent::UI::BrowserViewListener, 72
KillFocus	Coherent::UI::ViewListener, 161
Coherent::UI::View, 148	OnAudioStreamCreated
	Coherent::UI::BrowserViewListener, 72
Label	Coherent::UI::ViewListener, 163
Coherent::UI::Button, 85	OnAudioStreamPause
Listener	Coherent::UI::BrowserViewListener, 72
Coherent::UI::ChildViewInfo, 89	Coherent::UI::ViewListener, 163
CoherentUIView, 99	OnAudioStreamPlay
Load	Coherent::UI::BrowserViewListener, 73
Coherent::UI::View, 148	Coherent::UI::ViewListener, 163
LocalityName	OnBindingsReleased
Coherent::UI::CertificatePrincipal, 88	Coherent::UI::BrowserViewListener, 73
	Coherent::UI::ViewListener, 163
m_MainCamera	OnCallback
CoherentUISystem, 93	Coherent::UI::BrowserViewListener, 73
MediaStreamType	Coherent::UI::ViewListener, 163
Coherent::UI, 61	OnCanCreateChildWindow
MemoryCacheSize	Coherent::UI::BrowserViewListener, 73
CoherentUISystem, 93	Coherent::UI::ViewListener, 164
MessageLevel	OnCaretRectChanged
Coherent::UI::ViewListenerBase, 174	Coherent::UI::BrowserViewListener, 73
Method	Coherent::UI::ViewListener, 164
Coherent::UI::ButtonHandler, 87	OnCertificateError
MinidumpFolder	Coherent::UI::BrowserViewListener, 75
Coherent::UI::FactorySettings, 109	Coherent::UI::ViewListener, 164
MobileSurfaceView, 119	OnClientCertificateRequested
UpdateView, 120	Coherent::UI::BrowserViewListener, 75
Mode	Coherent::UI::ViewListener, 164
Coherent::UI::FileSelectionParams, 112	OnCookiesSaved
Modifiers	Coherent::UI::ContextListener, 102
Coherent::UI::KeyEventData, 117	OnCursorChanged
Coherent::UI::MouseEventData, 120	Coherent::UI::BrowserViewListener, 75
MouseActivate	Coherent::UI::ViewListener, 166
Coherent::UI::View, 148	OnDownloadComplete
MouseEvent	Coherent::UI::ContextListener, 102
Coherent::UI::View, 148	OnDownloadFailed
MouseModifiers	Coherent::UI::ContextListener, 102
Coherent::UI::MouseEventData, 120	OnDownloadStarted
	Coherent::UI::ContextListener, 102
Name	OnDraw
Coherent::UI::MediaStreamDevice, 118	Coherent::UI::BrowserViewListener, 75
NavigateTo	Coherent::UI::ViewListener, 166
Coherent::UI::BrowserViewListener, 82	OnError
Coherent::UI::ViewListener, 173	Coherent::UI::BrowserViewListener, 76
NewViewInfo	Coherent::UI::ContextListener, 102
Coherent::UI::ChildViewInfo, 89	Coherent::UI::ViewListener, 166
Null	OnFailLoad
Coherent::UI::Binding, 63	Coherent::UI::BrowserViewListener, 76
Number	Coherent::UI::ViewListener, 166

OnFileSelectRequest	Coherent::UI::Binding::Value, 135
Coherent::UI::BrowserViewListener, 76	operator Dictionary< string, Value >
Coherent::UI::ViewListener, 166	Coherent::UI::Binding::Value, 135
OnFinishLoad	operator double
Coherent::UI::BrowserViewListener, 76	Coherent::UI::Binding::Value, 135
Coherent::UI::ViewListener, 168	operator float
OnGetAuthCredentials	Coherent::UI::Binding::Value, 135
Coherent::UI::BrowserViewListener, 77	operator int
Coherent::UI::ViewListener, 168	Coherent::UI::Binding::Value, 135
OnIMEShouldCancelComposition	operator sbyte
Coherent::UI::BrowserViewListener, 77	Coherent::UI::Binding::Value, 137
Coherent::UI::ViewListener, 168	operator string
OnJavaScriptMessage	Coherent::UI::Binding::Value, 137
Coherent::UI::BrowserViewListener, 77	operator uint
Coherent::UI::ViewListener, 168	Coherent::UI::Binding::Value, 137
OnNavigateTo	operator==
Coherent::UI::BrowserViewListener, 77	Coherent::UI::Binding::Value, 139
Coherent::UI::ViewListener, 168	OrganizationNames
OnPrintToPDFReady	Coherent::UI::CertificatePrincipal, 88
Coherent::UI::BrowserViewListener, 77	OrganizationUnitNames
Coherent::UI::ViewListener, 170	Coherent::UI::CertificatePrincipal, 88
OnReadyForBindings	Origin
Coherent::UI::BrowserViewListener, 78	Coherent::UI::HTTPHeader, 114
Coherent::UI::ViewListener, 170	
CoherentUIView, 99	Page
OnRequestMediaStream	CoherentUIView, 99
Coherent::UI::BrowserViewListener, 78	PeekFrameReady
Coherent::UI::ViewListener, 170	Coherent::UI::View, 148
OnScriptMessage	Pragma
Coherent::UI::BrowserViewListener, 78	Coherent::UI::HTTPHeader, 114
Coherent::UI::ViewListener, 170	Print
OnStartLoading	Coherent::UI::View, 148, 149
Coherent::UI::BrowserViewListener, 78	PrintToPDFReady
Coherent::UI::ViewListener, 170	Coherent::UI::BrowserViewListener, 82
OnStopLoading	Coherent::UI::ViewListener, 173
Coherent::UI::BrowserViewListener, 78	PropertyBindingFlags
Coherent::UI::ViewListener, 171	Coherent::UI::Binding, 63
OnSubscriptionCheckDone	ProxyAuthorization
Coherent::UI::ContextListener, 102	Coherent::UI::HTTPHeader, 114
OnTextInputTypeChanged	ProxyConnection
Coherent::UI::BrowserViewListener, 78	Coherent::UI::HTTPHeader, 114
Coherent::UI::ViewListener, 171	RadiusX
OnURLRequest	Coherent::UI::TouchEventData, 125
Coherent::UI::BrowserViewListener, 80	RadiusY
Coherent::UI::ViewListener, 171	Coherent::UI::TouchEventData, 125
OnViewCreated	Range
Coherent::UI::BrowserViewListener, 80	Coherent::UI::HTTPHeader, 114
Coherent::UI::ViewListener, 171	ReadFile
CoherentUIView, 99	Coherent::UI::FileHandler, 110
OnViewDestroyed	ReadyForBindings
CoherentUIView, 101	Coherent::UI::BrowserViewListener, 82
OnViewFocused	Coherent::UI::ViewListener, 173
CoherentUISystem, 94	ReceivesInput
operator bool	CoherentUIView, 99
Coherent::UI::Binding::Value, 134	Redraw
operator byte	Coherent::UI::View, 149
Coherent::UI::Binding::Value, 134	Referer
operator char	Coherent::UI::HTTPHeader, 114

RegisterForEvent	Coherent::UI::URLRequest, 127
Coherent::UI::View, 149	SetFocus
Release	Coherent::UI::View, 150
Coherent::UI::BrowserViewListener, 80	SetMasterVolume
Coherent::UI::ViewListener, 171	Coherent::UI::View, 150
Reload	SetMethod
Coherent::UI::View, 149	Coherent::UI::URLRequest, 127
CoherentUIView, 96	SetMousePosition
RemoveCrossOriginWhitelistEntry	CoherentUlView, 96
Coherent::UI::ViewContext, 155	SetReferrer
RemoveExtraHeader	Coherent::UI::URLRequest, 127
Coherent::UI::URLRequest, 127	•
RenderingDeviceType	SetResponseHeader
Coherent::UI, 61	Coherent::UI::ResourceResponse, 123
ReplyToJavaScriptMessage	SetScriptError
	Coherent::UI::View, 151
Coherent::UI::View, 149	SetStatus
RequestFrame	Coherent::UI::ResourceResponse, 123
Coherent::UI::View, 150	SetTargetFramerate
RequestMediaStream	Coherent::UI::View, 151
Coherent::UI::BrowserViewListener, 82	SetURL
Coherent::UI::ViewListener, 173	Coherent::UI::URLRequest, 127
Resize	SetZoomLevel
Coherent::UI::View, 150	Coherent::UI::View, 151
CoherentUIView, 96	ShowJavaScriptDialogs
Respond	CoherentUIView, 100
Coherent::UI::MediaStreamRequest, 119	Signal
	Coherent::UI::SurfaceResponse, 124
SByte	SignalFailure
Coherent::UI::Binding, 63	Coherent::UI::ResourceData, 122
SCE_ArgumentType	Coherent::UI::ResourceResponse, 123
Coherent::UI, 61	•
SCE_NoResult	SignalSuccess
Coherent::UI, 61	Coherent::UI::ResourceData, 122
SCE_NoSuchMethod	Coherent::UI::ResourceResponse, 123
Coherent::UI, 61	StartLoading
SCE_Success	Coherent::UI::BrowserViewListener, 82
Coherent::UI, 61	Coherent::UI::ViewListener, 173
SET_Error	StateOrProvinceName
Coherent::UI, 61	Coherent::UI::CertificatePrincipal, 89
SET OfflineGracePeriod	Static
Coherent::UI, 61	Coherent::UI::Binding, 63
SET_Success	StopLoading
Coherent::UI, 61	Coherent::UI::BrowserViewListener, 82
SET_SuccessNotify	Coherent::UI::ViewListener, 173
Coherent::UI, 61	StreetAddresses
SaveCookies	Coherent::UI::CertificatePrincipal, 89
Coherent::UI::ViewContext, 155	String
ScaleToFit	Coherent::UI::Binding, 63
	SubscriptionEmail
CoherentUIView, 100	Coherent::UI::ContextSettingsBase, 105
ScriptCallErrorType	SubscriptionErrorType
Coherent::UI, 61	Coherent::UI, 61
ScriptMessage	
Coherent::UI::BrowserViewListener, 82	SubscriptionKey
Coherent::UI::ViewListener, 173	Coherent::UI::ContextSettingsBase, 105
SetClickThroughAlphaThreshold	SupportClickThrough
Coherent::UI::View, 150	Coherent::UI::ViewInfo, 157
SetExtraHeader	CoherentUIView, 100
Coherent::UI::URLRequest, 127	SupportsClickThrough
SetExtraHeaders	Coherent::UI::View, 151

SystemListenerFactoryFunc CoherentUISystem, 93	Coherent::UI::ViewInfo, 157
,	VE_AbnormalTermination
Target	Coherent::UI, 62
Coherent::UI::ButtonHandler, 87	VE_ChildCompositionFailed
TargetFrameRate	Coherent::UI, 62
Coherent::UI::ViewInfo, 157	VE_ClickThroughFailed
TextInputControlType	Coherent::UI, 62
Coherent::UI, 61	VE FailedCreation
TextInputTypeChanged	Coherent::UI, 61
Coherent::UI::BrowserViewListener, 82	VE_FailedRenderingCreation
Coherent::UI::ViewListener, 174	Coherent::UI, 62
TouchEvent	VE_FrameAlreadyInFlight
Coherent::UI::View, 151	Coherent::UI, 62
TransferEncoding	VE_FrameNotReady
Coherent::UI::HTTPHeader, 114	Coherent::UI, 62
trigger	VE FrameNotRequeted
engine, 65	Coherent::UI, 62
TriggerEvent	VE InvalidCall
Coherent::UI::View, 151	Coherent::UI, 62
Type	VE InvalidPath
Coherent::UI::Binding::Value, 139	Coherent::UI, 62
Coherent::UI::KeyEventData, 117	
Coherent::UI::MediaStreamDevice, 118	VE_QueryNotReady
Coherent::UI::MouseEventData, 120	Coherent::UI, 62
	VE_Success
Coherent::UI::TouchEventData, 125	Coherent::UI, 61
UInteger	Value
Coherent::UI::Binding, 63	Coherent::UI::Binding::Value, 131, 132, 134
UISystem	ValueType
CoherentUISystem, 93	Coherent::UI::Binding, 63
URLRequest	View
Coherent::UI::BrowserViewListener, 82	CoherentUIView, 100
Coherent::UI::ViewListener, 174	ViewCreated
UnbindCall	Coherent::UI::BrowserViewListener, 82
	Coherent::UI::ViewListener, 174
Coherent::UI::View, 151	ViewDestroyedHandler
UnbindObject 450	CoherentUIView, 97
Coherent::UI::View, 153	ViewErrorType
Uninitialize	Coherent::UI, 61
Coherent::UI::ViewContext, 155	ViewType
UnregisterFromEvent	Coherent::UI, 62
Coherent::UI::View, 153	
Update	WheelX
Coherent::UI::ImageData, 116	Coherent::UI::MouseEventData, 121
Coherent::UI::ViewContext, 155	WheelY
UpdateView	Coherent::UI::MouseEventData, 121
MobileSurfaceView, 120	Width
UseCameraDimensions	Coherent::UI::ViewInfo, 158
CoherentUIView, 100	CoherentUIView, 100
UseURLCache	WriteFile
CoherentUISystem, 93	Coherent::UI::FileHandler, 111
UserAgent	WriteLog
Coherent::UI::HTTPHeader, 114	Coherent::UI::ILogHandler, 115
UserAgent	WriteMinidumps
Coherent::UI::ContextSettingsBase, 105	Coherent::UI::FactorySettingsBase, 110
UserAgentType	, , ,
Coherent::UI, 61	X
UsesSharedMemory	Coherent::UI::MouseEventData, 121
Coherent::UI::View, 153	Coherent::UI::TouchEventData, 125

```
XPos
CoherentUIView, 100

Y
Coherent::UI::MouseEventData, 121
Coherent::UI::TouchEventData, 125

YPos
CoherentUIView, 100
```