
# Introduction to Linux interfaces for virtual networking - Red Hat Developer

By Hangbin Liu October 22, 2018September 11, 2019

15-19 minutes



<u>Linux</u> has rich virtual networking capabilities that are used as basis for hosting VMs and <u>containers</u>, as well as cloud environments. In this post, I will give a brief introduction to all commonly used virtual network interface types. There is no code analysis, only a brief introduction to the interfaces and their usage on Linux. Anyone with a network background might be interested in this blog post. A list of interfaces can be obtained using the command ip link help.

This post covers the following frequently used interfaces and some interfaces that can be easily confused with one another:

- Bridge
- Bonded interface
- Team device
- VLAN (Virtual LAN)
- VXLAN (Virtual eXtensible Local Area Network)
- MACVLAN
- IPVLAN
- MACVTAP/IPVTAP
- MACsec (Media Access Control Security)
- VETH (Virtual Ethernet)
- VCAN (Virtual CAN)


- VXCAN (Virtual CAN tunnel)
- IPOIB (IP-over-InfiniBand)
- NLMON (NetLink MONitor)
- Dummy interface
- IFB (Intermediate Functional Block)
- netdevsim

After reading this article, you will know what these interfaces are, what's the difference between them, when to use them, and how to create them.

For other interfaces like tunnel, please see An introduction to Linux virtual interfaces: Tunnels

# **Bridge**

A Linux bridge behaves like a network switch. It forwards packets between interfaces that are connected to it. It's usually used for forwarding packets on routers, on gateways, or between VMs and network namespaces on a host. It also supports STP, VLAN filter, and multicast snooping.



Use a bridge when you want to establish communication channels between VMs, containers, and your hosts.


Here's how to create a bridge:


```
# ip link add br0 type bridge
# ip link set eth0 master br0
# ip link set tap1 master br0
# ip link set tap2 master br0
# ip link set veth1 master br0
```

This creates a bridge device named br0 and sets two TAP devices (tap1, tap2), a VETH device (veth1), and a physical device (eth0) as its slaves, as shown in the diagram above.

# **Bonded interface**

The Linux bonding driver provides a method for aggregating multiple network interfaces into a single logical "bonded" interface. The behavior of the bonded interface depends on the mode; generally speaking, modes provide either hot standby or load balancing services.





Use a bonded interface when you want to increase your link speed or do a failover on your server.


Here's how to create a bonded interface:

```
ip link add bond1 type bond miimon 100 mode active-backup
ip link set eth0 master bond1
ip link set eth1 master bond1
```

This creates a bonded interface named bond1 with mode active-backup. For other modes, please see the kernel documentation.

### Team device

Similar a bonded interface, the purpose of a team device is to provide a mechanism to group multiple NICs (ports) into one logical one (teamdev) at the L2 layer.



The main thing to realize is that a team device is not trying to replicate or mimic a bonded interface. What it does is to solve the same problem using a different approach, using, for example, a lockless (RCU) TX/RX path and modular design.

But there are also some functional differences between a bonded interface and a team. For example, a team supports LACP load-balancing, NS/NA (IPV6) link monitoring, D-Bus interface, etc., which are absent in bonding. For further details about the differences between bonding and team, see <a href="Bonding vs. Team">Bonding vs. Team</a> features


Use a team when you want to use some features that bonding doesn't provide.

Here's how to create a team:

```
# teamd -o -n -U -d -t team0 -c '{"runner": {"name":
"activebackup"},"link_watch": {"name": "ethtool"}}'
# ip link set eth0 down
# ip link set eth1 down
# teamdctl team0 port add eth0
# teamdctl team0 port add eth1
```

This creates a team interface named team0 with mode active-backup, and it adds eth0 and eth1 as team0's sub-interfaces.


A new driver called <u>net\_failover</u> has been added to Linux recently. It's another failover master net device for virtualization and manages a primary (<u>passthru/VF [Virtual Function]</u> device) slave net device and a standby (the original paravirtual interface) slave net device.



# **VLAN**

A VLAN, aka virtual LAN, separates broadcast domains by adding tags to network packets. VLANs allow network administrators to group hosts under the same switch or between different switches.

The VLAN header looks like:





Use a VLAN when you want to separate subnet in VMs, namespaces, or hosts.

Here's how to create a VLAN:

```
# ip link add link eth0 name eth0.2 type vlan id 2
# ip link add link eth0 name eth0.3 type vlan id 3
```

This adds VLAN 2 with name eth0.2 and VLAN 3 with name eth0.3. The topology looks like this:






**Note**: When configuring a VLAN, you need to make sure the switch connected to the host is able to handle VLAN tags, for example, by setting the switch port to trunk mode.

### **VXLAN**


VXLAN (Virtual eXtensible Local Area Network) is a tunneling protocol designed to solve the problem of limited VLAN IDs (4,096) in IEEE 802.1q. It is described by IETF RFC 7348.

With a 24-bit segment ID, aka VXLAN Network Identifier (VNI), VXLAN allows up to 2^24 (16,777,216) virtual LANs, which is 4,096 times the VLAN capacity.

VXLAN encapsulates Layer 2 frames with a VXLAN header into a UDP-IP packet, which looks like this:



VXLAN is typically deployed in data centers on virtualized hosts, which may be spread across multiple racks.



Here's how to use VXLAN:

# ip link add vx0 type vxlan id 100 local 1.1.1.1 remote 2.2.2.2 dev eth0
dstport 4789


For reference, you can read the <u>VXLAN kernel documentation</u> or <u>this VXLAN introduction</u>.

### **MACVLAN**


With VLAN, you can create multiple interfaces on top of a single one and filter packages based on a VLAN tag. With MACVLAN, you can create multiple interfaces with different Layer 2 (that is, Ethernet MAC) addresses on top of a single one.

Before MACVLAN, if you wanted to connect to physical network from a VM or namespace, you would have needed to create TAP/VETH devices and attach one side to a bridge and attach a physical interface to the bridge on the host at the same time, as shown below.







Now, with MACVLAN, you can bind a physical interface that is associated with a MACVLAN directly to namespaces, without the need for a bridge.




There are five MACVLAN types:

1. Private: doesn't allow communication between MACVLAN instances on the same physical interface, even if the external switch supports hairpin mode.







2. VEPA: data from one MACVLAN instance to the other on the same physical interface is transmitted over the physical interface. Either the attached switch needs to support hairpin mode or there must be a TCP/IP router forwarding the packets in order to allow communication.



3. Bridge: all endpoints are directly connected to each other with a simple bridge via the physical interface.



4. Passthru: allows a single VM to be connected directly to the physical interface.



5. Source: the source mode is used to filter traffic based on a list of allowed source MAC addresses to create MAC-based VLAN associations. Please see the commit message.

The type is chosen according to different needs. Bridge mode is the most commonly used.

Use a MACVLAN when you want to connect directly to a physical network from containers.


Here's how to set up a MACVLAN:

- # ip link add macvlan1 link eth0 type macvlan mode bridge
- # ip link add macvlan2 link eth0 type macvlan mode bridge
- # ip netns add net1
- # ip netns add net2
- # ip link set macvlan1 netns net1
- # ip link set macvlan2 netns net2


This creates two new MACVLAN devices in bridge mode and assigns these two devices to two different namespaces.


# **IPVLAN**

IPVLAN is similar to MACVLAN with the difference being that the endpoints have the same MAC address.




IPVLAN supports L2 and L3 mode. IPVLAN L2 mode acts like a MACVLAN in bridge mode. The parent interface looks like a bridge or switch.





In IPVLAN L3 mode, the parent interface acts like a router and packets are routed between endpoints, which gives better scalability.



Regarding when to use an IPVLAN, the <u>IPVLAN kernel documentation</u> says that MACVLAN and IPVLAN "are very similar in many regards and the specific use case could very well define which device to choose. if one of the following situations defines your use case then you can choose to use ipvlan – (a) The Linux host that is connected to the external switch / router has policy configured that allows only one mac per port.

- (b) No of virtual devices created on a master exceed the mac capacity and puts the NIC in promiscuous mode and degraded performance is a concern.
- (c) If the slave device is to be put into the hostile / untrusted network namespace where L2 on the slave could be changed / misused."

Here's how to set up an IPVLAN instance:

- # ip netns add ns0
- # ip link add name ipvl0 link eth0 type ipvlan mode 12
- # ip link set dev ipvl0 netns ns0


This creates an IPVLAN device named ipv10 with mode L2, assigned to namespace ns0.

# MACVTAP/IPVTAP

MACVTAP/IPVTAP is a new device driver meant to simplify virtualized bridged networking. When a MACVTAP/IPVTAP instance is created on top of a physical interface, the kernel also creates a character

device/dev/tapX to be used just like a TUN/TAP device, which can be directly used by KVM/QEMU.

With MACVTAP/IPVTAP, you can replace the combination of TUN/TAP and bridge drivers with a single module:



Typically, MACVLAN/IPVLAN is used to make both the guest and the host show up directly on the switch to which the host is connected. The difference between MACVTAP and IPVTAP is same as with MACVLAN/IPVLAN.

Here's how to create a MACVTAP instance:


# ip link add link eth0 name macvtap0 type macvtap

### **MACsec**

MACsec (Media Access Control Security) is an IEEE standard for security in wired Ethernet LANs. Similar to IPsec, as a layer 2 specification, MACsec can protect not only IP traffic but also ARP, neighbor discovery, and DHCP. The MACsec headers look like this:



The main use case for MACsec is to secure all messages on a standard LAN including ARP, NS, and DHCP messages.



# Switch

Here's how to set up a MACsec configuration:


# ip link add macsec0 link eth1 type macsec

**Note**: This only adds a MACsec device called macsec0 on interface eth1. For more detailed configurations, please see the "Configuration example" section in this <u>MACsec introduction by Sabrina Dubroca</u>.

### **VETH**

The VETH (virtual Ethernet) device is a local Ethernet tunnel. Devices are created in pairs, as shown in the diagram below.

Packets transmitted on one device in the pair are immediately received on the other device. When either device is down, the link state of the pair is down.



Use a VETH configuration when namespaces need to communicate to the main host namespace or between each other.

Here's how to set up a VETH configuration:

- # ip netns add net1
- # ip netns add net2
- # ip link add veth1 netns net1 type veth peer name veth2 netns net2

This creates two namespaces, net1 and net2, and a pair of VETH devices, and it assigns veth1 to namespace net1 and veth2 to namespace net2. These two namespaces are connected with this VETH pair. Assign a pair of IP addresses, and you can ping and communicate between the two namespaces.

### **VCAN**

Similar to the network loopback devices, the VCAN (virtual CAN) driver offers a virtual local CAN (Controller Area Network) interface, so users can send/receive CAN messages via a VCAN interface. CAN is mostly used in the automotive field nowadays.

For more CAN protocol information, please refer to the kernel CAN documentation.

Use a VCAN when you want to test a CAN protocol implementation on the local host.

Here's how to create a VCAN:

# ip link add dev vcan1 type vcan

### **VXCAN**

Similar to the VETH driver, a VXCAN (Virtual CAN tunnel) implements a local CAN traffic tunnel between two VCAN network devices. When you create a VXCAN instance, two VXCAN devices are created as a pair. When one end receives the packet, the packet appears on the device's pair and vice versa. VXCAN can be used for cross-namespace communication.

Use a VXCAN configuration when you want to send CAN message across namespaces.

Here's how to set up a VXCAN instance:

```
# ip netns add net1
# ip netns add net2
# ip link add vxcan1 netns net1 type vxcan peer name vxcan2 netns net2
```

Note: VXCAN is not yet supported in Red Hat Enterprise Linux.

### **IPOIB**

An IPOIB device supports the IP-over-InfiniBand protocol. This transports IP packets over InfiniBand (IB) so you can use your IB device as a fast NIC.

The IPoIB driver supports two modes of operation: datagram and connected. In datagram mode, the IB UD (Unreliable Datagram) transport is used. In connected mode, the IB RC (Reliable Connected) transport is used. The connected mode takes advantage of the connected nature of the IB transport and allows an MTU up to the maximal IP packet size of 64K.

For more details, please see the **IPOIB** kernel documentation.

Use an IPOIB device when you have an IB device and want to communicate with a remote host via IP.

Here's how to create an IPOIB device:

# ip link add ib0 name ipoib0 type ipoib pkey IB\_PKEY mode connected

### **NLMON**

NLMON is a Netlink monitor device.

Use an NLMON device when you want to monitor system Netlink messages.

Here's how to create an NLMON device:

```
# ip link add nlmon0 type nlmon
# ip link set nlmon0 up
# tcpdump -i nlmon0 -w nlmsq.pcap
```

This creates an NLMON device named nlmon0 and sets it up. Use a packet sniffer (for example, tcpdump) to capture Netlink messages. Recent versions of Wireshark feature decoding of Netlink messages.

# **Dummy interface**

A dummy interface is entirely virtual like, for example, the loopback interface. The purpose of a dummy interface is to provide a device to route packets through without actually transmitting them.

Use a dummy interface to make an inactive SLIP (Serial Line Internet Protocol) address look like a real address for local programs. Nowadays, a dummy interface is mostly used for testing and debugging.

Here's how to create a dummy interface:

```
# ip link add dummy1 type dummy
# ip addr add 1.1.1.1/24 dev dummy1
# ip link set dummy1 up
```

### **IFB**

The IFB (Intermediate Functional Block) driver supplies a device that allows the concentration of traffic from several sources and the shaping incoming traffic instead of dropping it.

Use an IFB interface when you want to gueue and shape incoming traffic.

Here's how to create an IFB interface:

```
# ip link add ifb0 type ifb
```

```
# ip link set ifb0 up
# tc qdisc add dev ifb0 root sfq
# tc qdisc add dev eth0 handle ffff: ingress
# tc filter add dev eth0 parent ffff: u32 match u32 0 0 action mirred egress
redirect dev ifb0
```

This creates an IFB device named ifb0 and replaces the root qdisc scheduler with SFQ (Stochastic Fairness Queueing), which is a classless queueing scheduler. Then it adds an ingress qdisc scheduler on eth0 and redirects all ingress traffic to ifb0.

For more IFB qdisc use cases, please refer to this Linux Foundation wiki on IFB.

# **Additional resources**

- Virtual networking articles on the Red Hat Developer blog
- Dynamic IP Address Management in Open Virtual Network (OVN)
- Non-root Open vSwitch in Red Hat Enterprise Linux
- Open vSwitch articles on the Red hat Developer Blog

### netdevsim interface

netdevsim is a simulated networking device which is used for testing various networking APIs. At this time it is particularly focused on testing hardware offloading, tc/XDP BPF and SR-IOV.

A netdevsim device can be created as follows

```
# ip link add dev sim0 type netdevsim
# ip link set dev sim0 up
```

To enable to offload:

```
# ethtool -K sim0 hw-tc-offload on
```

To load XDP BPF or tc BPF programs:

```
# ip link set dev sim0 xdpoffload obj prog.o
```

To add VFs for SR-IOV testing:

```
# echo 3 > /sys/class/net/sim0/device/sriov_numvfs
# ip link set sim0 vf 0 mac
```

To change the vf numbers, you need to disable them completely first:

```
# echo 0 > /sys/class/net/sim0/device/sriov_numvfs
# echo 5 > /sys/class/net/sim0/device/sriov_numvfs
```

Note: netdevsim is not compiled in RHEL by default