

Author: Donald Forbes

Document Date: 1 June 2006

Table of Contents

0. Document Control	3
Document Control O.1. Revision History	3
0.2. Document Distribution	3
0.3. Document References	3
0.4. Document Access Control	
1. Introduction	4
2. Solution Overview	4
2.1. Business Goals, Objectives & Purpose	4
3. Architecture Specification	4
3.1. Overview	4
3.2. Technical Architecture	4
3.2.1. Generic JMS Resource Adapter Configuration	
3.2.2. Application Server Configuration for Message Production	6
3.2.2.1. Connector Pool Properties	8
3.2.3. Deployment Descriptors for Message Driven Bean (Message Consumption)	8
3.2.3.1. MDB Deployment Descriptor Properties	9
3.3. Application Server Transaction Configuration	11
3.4. Overlap between GenericJMSRA config and JMS Client/Broker Configuration	
4. Appendix	15
4.1. Example Application Server Configuration Script Commands	
4.2. Example MDB Deployment Descriptors	16

0. Document References

Ref	Referenced Item
1	Generic JMS RA documentation – https://www.genericjmsra.dev.java.net
2	Sun Application Server 8.1 Admin guide
3	Sun Application Server 8.1 Reference Guide

Page 3 of 17 Author : Donald Forbes Issue Date : 1 June 2006

1. Introduction

In order to consume and produce messages from a JMS provider via a J2EE application server there are many steps required to setup the environment and many configuration options to be considered. These options make the environment very flexible but are very confusing to a novice, the cookbook is not a prescriptive recipe to setup the application server and JMS adapter but provides some guidance around the possible options and explains some potential pitfalls that must be considered.

2. Solution Overview

2.1. Business Goals, Objectives & Purpose

This document explains the configuration options that are available to a deployer when setting up J2EE applications that will consume from and produce to queues via the Generic JMS Resource Adapter.

3. Architecture Specification

3.1. Overview

The Sun Message Queue product enables asynchronous message delivery that conforms to the Java Messaging Specification (JMS) 1.1. Messages can be placed onto a queue from within an application server which does so by using a resource adapter that has been specifically developed to connect the Sun Application Server 8.x to any JMS compliant resource. The adapter is known as the GenericJMSRA. At a high level Figure 1 depicts the architecture used to communicate from a J2EE application to the queuing system.




Figure 1: Access Message Queue From J2EE application Via Generic JMS Resource Adapter

3.2. Technical Architecture

This document explains the mechanism used for both the production and consumption of messages from within a J2EE application running in the Sun application server 8.x. The flow of messages considered is depicted in Figure 2 where a J2EE application will consume messages from a queue and then subsequently produce messages onto another queue. Description of the configuration is fairly independent of this flow but applies, independently, to the configuration required to produce messages and consume these messages.




Figure 2: Application Architecture for message consumption and production

3.2.1. Generic JMS Resource Adapter Configuration

The Generic JMS Resource Adapter (genericjmsra) is a resource adapter that adheres to the connector architecture 1.5. The Connector Architecture provides a standard contract to allow bi-directional connectivity between J2EE applications and Enterprise Information Systems (EIS) which allows for enterprise application integration (EAI).

The genericjmsra is deployed into the application server so that its connectivity functionality to any JMS provider is available to the applications deployed in the same server. The genericjmsra is deployed in the standard manner for any J2EE resource archive. i.e. It is shipped as a "rar" file that is deployed into the application server. When it is deployed there are a number of configuration options that can define its behaviour. In this document it is assumed that all the JMS administered objects will be sourced from a directory server.

Prior to deploying the RA it is recommended to setup a thread pool for it to use. The thread pool protects the rest of the application server from becoming unresponsive should the adapter or EIS system it is connecting to behave incorrectly. This pool must be large enough to handle the expected demand while still small enough to not to demand unnecessary system resource.

Having setup the thread pool the RA can now be deployed and configured to use the thread pool. The GUI does this in a single step where all the configuration is specified and the asadmin command line first uses the "create-resource-adapter-config" command to define the parameters then the "deploy" command to actually deploy the RA into the application server.

The available parameters that are pertinent to the RA accessing JMS administered objects via LDAP are:-

Config Parameter	Description	Default Value	Example (To deploy using admin objects in a directory server)
ProviderIn tegrationM ode	Defines if the administered objects are beans with all configuration described in the AS configuration or if the objects are to be retrieved from an object store.		Jndi
JndiProper ties	Gives all the properties required to tell the RA where to look up the object store. Only required if the ProviderIntegrationMode is jndi.		java.naming.factory.initial=com.sun.j ndi.ldap.LdapCtxFactory,java.naming .provider.url=ldap://tannoch:389/ou=c onfigs%2cdc=uk%2cdc=sun%2cdc=c om,java.naming.security.principal=cn =Directory
SupportsXA	Defines if the resources that the genericjmsra connects to are to partake in an XA transaction.	False	True
UserName	Defines the username used to connect to the directory server		Admin
Password	Defines the password used to connect to the directory server.		Admin
LogLevel	Determines the level of logging that the genericra will output to the application server's log file. Valid values – FINEST, FINER, FINE, INFO, WARNING, SEVERE	INFO	INFO

Table 1: Generic JMS RA deployment parameters

Note:- Connecting to different parts of the LDAP tree via a single deployed Generic RA

When deploying the rar file properties are defined, these can be overridden either in the activation specification of a message driven bean (MDB) or in the properties of the connection resources. A bug (6418484) has been identified in Application Server 8.1 which results an overridden value for any of the properties in the pools is not being honoured. (According to the connector specification all javabean properties must be honoured.) As such if there are several connection pools being set up for multiple administered objects held in the directory server and these have different paths then multiple rar files would have to be deployed, each with a different URL specified or all the administered objects can be held in the same LDAP tree.

Alternatively, by explicitly specifying the JndiProperties in the resource adapter deployment descriptor (ra.xml) then the contract is honoured and different LDAP paths can be defined in different connection pools/MDB activation configurations.

i.e. Add the following xml snippet to the inbound and outbound configurations in the ra.xml.

3.2.2. Application Server Configuration for Message Production

When a J2EE application wishes to produce messages onto a message queue the code will perform a lookup in the application servers JNDI space to discover the QueueConnectionFactory, open the connection create any necessary sessions then close down the session and connection objects it used.

The application server must be configured to pool connections created by the GenericRA to the message queue broker, when the application requests a factory object the application server gives a handle to the pool and the creation of the connection will return a factory instance to the application from the pool. When the application closes the connection the factory instance is returned to the pool when any transaction that is in progress completes.

From a code perspective the create... method on the connection object will take an object from the pool and a close method returns the object but only once any transaction that is active has completed. Thus code could look like:-

The setup is depicted in Figure 3, this shows that the application server will maintain a pool of connections that are setup by the generic JMS resource adapter. A J2EE application can then make use of the pooled connections.




Figure 3: Pooling of connections for message production.

In order to configure this as a prerequisite the genericra must be deployed into the application server. The pool of QueueConnectionFactories can then be configured and the pool linked to the connector resource name that the application will lookup. i.e. Define the JNDI lookup name for locating the resource from a J2EE application.

Details on the configuration options for the application server pool settings are described in detail in the application server reference and administration guides. (Reference 2 & 3) However it is important to be aware of:-

Pool settings

 The pool settings define the maximum number of concurrent threads that can produce messages so the minimum pool size should be set to be about the number of concurrent threads that are expected.

- Each object in the pool results in two physical network connections being made to the broker (For Sun Message Queue) there is an overhead in stack memory for all the connections that are made which needs to be considered when setting the memory settings for the server.
- The Max wait time defines the amount of time before a timeout is returned. When an
 application requests an object from the pool if the pool has no objects available then the
 request will hang until either an object becomes available or the max wait time is exceeded.
 Once the wait time has expired then a timeout exception is returned to the application, the
 applications must be coded to handle this in an appropriate manner.
- Transaction support must be set to XATransaction if the resource is to participate in a two phase commit with other resources.

3. Close All Connections

A bug has been identified in AS8.1 (6411409) where with the close all connections being set
to true can result in duplicate messages being produced to a queue in the event of the
outbound queue being shutdown and restarted. This bug can be avoided by having Close
All Connections set to false. Releases of the application server higher than 8.1 SP10 will
not suffer from this issue.

3.2.2.1. Connector Pool Properties

Properties of the connector-connection-pool element are the names of setter methods of the managedconnectionfactory-class element in the ra.xml file. Properties of this element override the ManagedConnectionFactory JavaBean configuration settings. For the GenericJMSRA the properties that can be overridden are:-

Config Parameter	Description	Default Example Value	
ConnectionFac toryJndiName	This provides details of the actual entry of the managed object in LDAP. The connection factory. This can define the entire URL to the directory entry or can be relative to the URL defined in the deployment of the genericimsra.		cn=theQueueConnectionFa ctory
ClientId	The purpose of the client identifier is to associate a connection and its objects with a state maintained on behalf of the client by a provider. By definition, the client state identified by a client identifier can be in use by only one client at a time.		
ConnectionVal idationEnable d	This is a boolean that alters the behaviour of the GenericRA to confirm the connection is still valid before using it. It is mandatory to have the setting set to true if the connections are to reconnect to a broker that has failed for any reason.	False	true

Table 2: Generic RA configurable parameters for connector pool

3.2.3. Deployment Descriptors for Message Driven Bean (Message Consumption)

For message consumption through a Message Driven Bean the architecture used is depicted in Figure 4. When an MDB based application starts up the app will request a pool of message driven beans from the container, this request is passed on to the generic RA which will create a pool of JMS ServerSessions to consume messages. All these sessions are physically connected via a single connection to the broker. (two physical network connections)

When a Message Driven Bean is to consume messages from a queue via the GenericJMSRA it does so by specifying use of the connector resource that was named when deploying the GenericJMSRA in the sun-ejb-jar.xml deployment descriptor. This is done via the use of the resource-adapter-mid tag in the deployment descriptor. (DD) If this has been defined then the activation config specifies all the configuration necessary to connect the MDB to the queue and control the non-functional behaviour.

Because of the fact that there are two independent pools involved in the architecture of message consumption through the genericJMSRA care must be taken to ensure that the two pools remain in sync. The pools involved are:-

- MDB pool, defined by default in the AS configuration or overridden in the deployment descriptor for the MDB application.
- Generic RA pool of ServerSessions. This is defined in the activation config elements of the DD for the application.

The smaller of these two pools will define the maximum concurrency for message consumption. If the MDB pool is smaller than the RA pool then the RA will have created excess ServerSessions that never consume messages but simply use up some system resource. Conversly if the MDB pool is larger than the pool of ServerSessions then excess MDBs will not get connected to a ServerSession and hence never process messages.




Figure 4: Message Consumption by Message Driven Beans (MDB)

JMS resources accessed through the generic RA can be used in an XA transaction with other resource managers. As such there is the possibility that either a resource or the application server may fail during the XA transaction lifecycle, in this case the application server can be used to recover transaction, either committing or rolling back the transaction depending on the exact status at the point in time of the failure. On startup of the server the application server will connect to all XA resources and interrogate them to determine if any transactions need to be recovered. (rollback or commit) Message Driven Beans interact directly with the deployed resource adapter via the activation specification in their deployment descriptor. This means that the application server will not attempt to recover from the queue that a MDB is connected to. To work around this ensure that a connection pool is configured that points at the same broker/queue that the MDB consumes from.

3.2.3.1. MDB Deployment Descriptor Properties.

Config Parameter	arameter Description		g Parameter Description Default Value		Example	
MaxPoolSize	Maximum size of server session pool internally created by resource adapter for achieving concurrent message delivery. This should be equal to maximum pool size of MDB objects.		32			
MaxWaitTime	Resource Adapter will wait for the time in seconds specified by this property to obtain a server session from its internal pool. If this limit is exceeded message delivery will fail.	3				
MessageSelect or	A valid MessageSelector as specified by jms 1.1 specification.		<pre>MessageFormat = 'Version 3.4' or <![CDATA[</td></tr><tr><td>ClientID</td><td>ClientID as specified by jms 1.1 specification.</td><td></td><td>MdbConsumer</td></tr><tr><td>ConnectionFac toryJndiName</td><td>JNDI name of connection factory created in JMS provider. This connection factory will be used by resource adapter to create a connection to receive messages.</td><td></td><td>cn=myQueueConnectionFa ctory</td></tr><tr><td></td><td>Used only if ProviderIntegrationMode is configured as "jndi". The value points at the lookup name in the jndi store, thus if the administered objects are held in ldap then the value should be cn=</td><td></td><td></td></tr><tr><td>DestinationJn diName</td><td>JNDI name of destination created in JMS provider. This destination will be used by resource adapter to create a connection to receive messages from.</td><td></td><td>cn=myDestinationQueue</td></tr><tr><td></td><td>Used only if ProviderIntegrationMode is configured as "jndi". Syntax as per connection factory lookup.</td><td></td><td></td></tr><tr><td>DestinationTy pe</td><td>Type of the destination the MDB will listen to.</td><td></td><td>javax.jms.Queue or</td></tr><tr><td></td><td></td><td></td><td>javax.jms.Topic</td></tr></tbody></table>]]></pre>			

Config Parameter	Description	Default Value	Example
RedeliveryAtt empts	Number of times a message will be redelivered in case a message cause a runtime exception in the MDB.		0
	Note – Some JMS providers have this functionality built into their product. Unless the code want the poisoned messages to be handled by the dead message queue after a redelivery, it is better to keep the value set to zero. Otherwise, the re-delivery of rolled back messages and Redelivery of genericjmsra might confuse each other.		

Table 3: MDB Deployment Descriptor parameters

3.3. Application Server Transaction Configuration

There are a number of configuration options to control the behaviour of the transaction manager that is built into the application server. These options are configured in the specific configuration for the instance or cluster of instances that will be communicating with the JMS resources. The options for the transaction manager are described in Table 4.

Config Parameter		Description	Default	Example
GUI	Command Line		Value	
OnRestar t	config- name>.transaction- service.automatic- recovery	Determines if the application server will automatically attempt to recover transactions when it is started.	true	
Transact ion Timeout	config- name>.transaction- service.timeout-in- seconds	By default, the server does not timeout a transaction. That is, the server waits indefinitely for a transaction to complete. If you set a timeout value for transactions, if a transaction isn't completed within the configured time, the Application Server rolls back the transaction.	0	
Retry Timeout	config- name>.transaction- service.retry- timeout-in-seconds	Sets the amount of time (in seconds) the Application Server tries to connect to the unreachable server in the Retry Timeout field.	600	60
Transact ion Log Location	config- name>.transaction- service.tx-log-dir	The transaction log records the information about each transaction in order to maintain the data integrity of the resources involved and to recover from failures. Transaction logs are kept in the tx subdirectory of the directory specified by the Transaction Log Location. These logs are not human readable.	\${com.sun .aas.instan ceRoot}/lo gs	/some/other/directory/if/the/d efault/is/not/desired/log
Heuristi c Decision	config- name>.transaction- service.heuristic- decision	This can be set to rollback or commit. If a transaction is in an indeterminate state then the action specified here is the action that will be taken. i.e. By default it will rollback all operations.	rollback	
KeyPoint Interval	config- name>.transaction- service.keypoint- interval	Keypoint operations compress the transaction log file. The keypoint interval is the number of transactions between keypoint operations on the log. Keypoint operations can reduce the size of the transaction log files. A larger number of keypoint intervals (for example, 2048) results in larger transaction log files, but fewer keypoint operations, and potentially better performance. A smaller keypoint interval (for example, 256) results in smaller log files but slightly reduced performance due to the greater frequency of keypoint operations. Every transaction is written into the tx log file and every <i>n</i> transactions that occur the app server will clean out the transaction log file so that only currently active transactions are	2048	

Page 12 of 17 Author

Со	nfig Parameter	Description	Default	Example
GUI	Command Line		Value	
		held there. The value of <i>n</i> is the keypoint value. Thus a large value will give larger files but better performance as there are less clean out operations while a small value will give small files but the clear down has to happen more often. In either case transactions that are inflight will always be kept.		
		Set the keypoint interval to as large as possible a value if the disk space is of not a concern. At a key point, transaction log system logs a special record called "key point start" and then tries to rewrite all the active transactions. if they have been written earlier and puts "keypoint end" special record. Transaction log system considers the rewrite entries only if it finds a "key point start" as well as "keypoint end" records.		

Table 4: Application Server Transaction Manager configuration.

3.4. Overlap between GenericJMSRA config and JMS Client/Broker Configuration

A number of the configuration options that the genericjmsra can perform overlap with behaviour that can be configured either by the connection factories or by the broker it is connecting to. Only one object should take responsibility for this behaviour with the more centralised connection factories or broker taking control. The configuration options in particular are detailed in

Configuration	GenericRA	ConnectionFactory	Description
Redelivery	Value specified in the activationSpecification of an MDB. Key Properties:- RedeliveryAttempts RedeliveryInterval SendBadMessagesToDMD	N/A	Number of times a message will be redelivered in case a message causes a runtime exception in the MDB. If the number specified is exceeded then the message is placed on the dead message destination defined. Generally more control is desired and the client code determines what should be done with a message that cannot be processed. i.e. Set RedeliveryAttempts to 0
Reconnection	Activation specification properties for an MDB:- ReconnectAttempts ReconnectInterval Connection pool properties:- ConnectionValidationEnabled This must work in conjunction with the application servers pool. By specifying this option then any exception is	The connection factory is capable of performing a reconnect to the broker by setting the following properties:-Address List Number of address list iterations Enable autoreconnect Number of	Either option is viable to use however there are advantages to using the genericjmsra capabilities and app server config to control reconnect logic. For an MDB (inbound messages) reconnect there will be a controlled soft shutdown of current messages and cleanup of stale connections/sessions. This is not possible with the MQ reconnect logic. For outbound connections the configuration for the application server is preferred. If the

Configuration	GenericRA	ConnectionFactory	Description
	passed back to the application server which will destroy that pooled object and recreate the connection.	reconnect attempts per address Reconnect Interval These properties allow the connection to be re-established to all the possible brokers defined for a number of attempts. See MQ documentation for details.	connection validation fails then either a successful reconnect will occur and the client code continues or the reconnect fails and the client is immediately informed. If MQ does the reconnect then the pool will never become stale but if the broker is down for an extended period of time and the reconnect attempts is exceeded then the pool can become full of stale connections. Then the pool would have to be configured to have a steady state size of 0 and the resizer would have to size the pool down to 0 connections by the time that the reconnect attempts expires.

Page 14 of 17 Author : Donald Forbes Issue Date : 1 June 2006

4. Appendix

4.1. Example Application Server Configuration Script Commands

The following asadmin commands can be used to configure the application server to deploy the GenericJMSRA and configure the connection pools.

Asadmin Command (Not showing options of –host, port,user &passwordfile for clarity. Apply to all commands)	Description
asadmin create-threadpooltarget <configuration_name>maxthreadpoolsize <max_size>minthreadpoolsize <minimum size="">idletimeout <time_in_seconds_for_timeout>workqueues <number_of_work_queues> name_of_thread_pool</number_of_work_queues></time_in_seconds_for_timeout></minimum></max_size></configuration_name>	This command will create a thread pool in a configuration. The genericipmsra can then be allocated to utilise this threadpool. Ensure that the number of threads in the pool will be enough to cope with the number of connections that the generic JMSRA will be expected to setup. (i.e. Number of objects in the pools and number of server sessions/MDBs that it will be expected to handle.)
asadmin create-resource-adapter-configthreadpools \$THREAD_POOL_NAMEproperty SupportsXA=true:ProviderIntegrationMode=jndi:UserN ame= <user_name_for_jms>:Password=<jms_user_passwor d="">:JndiProperties=java.naming.factory.initial\\=co m.sun.jndi.ldap.LdapCtxFactory,java.naming.provide r.url\\="<url_for_direcory",java.naming.security.p rincipal\\="<username_for_directory">,java.naming.se curity.credentials\\=<userpassword_for_directory>: LogLevel=info name_of_resource_adapter_to_be_deployed</userpassword_for_directory></url_for_direcory",java.naming.security.p></jms_user_passwor></user_name_for_jms>	This command will setup the properties that will apply to the deployment of the generic JMS RA. The properties define the fact that it will: • Support XA transactions • provide a username and password for connecting to the JMS broker • Define the JNDI Properties that will be used to connect to the LDAP source. (URL, username/password etc.) • Output log level for the adapter. Other options link the adapter to the thread pool that was previously created. The name of the resource must match to the name that will be given to the deployed adapter. (next step)
asadmin deployname <name_of_resource_adapter_to_be_deployed>target <cluster_name_or_instance_name> /location/of/the/genericjmsra.rar_file</cluster_name_or_instance_name></name_of_resource_adapter_to_be_deployed>	This command will deploy the actual rar file to the server, using the configuration that was previously setup and defining the clusters/instances that it will be deployed to.
asadmin create-connector-connection-poolsteadypoolsize <expected_concurrency_value>maxpoolsize <max_concurrency_value>poolresize <number_pooled_objects_removed_when_resizing>idletimeout <how_often_pool_resizes>raname <resourse_adapter_to_use>connectiondefinition javax.jms.QueueConnectionFactorytransactionsupport XATransactionproperty ConnectionValidationEnabled=true:ConnectionFactory JndiName=<for_ldap_url_of_administered_object- cn=""> meaningful_name_for_connection_pool</for_ldap_url_of_administered_object-></resourse_adapter_to_use></how_often_pool_resizes></number_pooled_objects_removed_when_resizing></max_concurrency_value></expected_concurrency_value>	Creates the connection pool for all the connection factories that provide the access to the JMS resource. The usual pooling configuration options are required. The properties are extensions to the normal app server pooling mechanism that are specific to the GenericJMSRA. If the pool is to check the connection prior to usage then the property ConnectionValidationEnabled is required. The ConnectionFactoryJNDIName is used to specify the actual JMS administered object that is held in the directory server.
asadmin create-connector-resourcepoolname <link_to_pool_to_use>target <cluster_or_instancename> jndi_name_that_apps_will_lookup</cluster_or_instancename></link_to_pool_to_use>	This command will define the JNDI name that an application will lookup to get access to the resource. The name is then linked to the connector pool and all the clusters/instances that the resource is to be available on are defined.
asadmin create-admin-objectraname <name_of_resource_adapter_deployed>target <cluster_or_instancename>restype javax.jms.Queueproperty DestinationJndiName=<url_for_location_of_destination_in_directory> jndi_lookupname_for_destination</url_for_location_of_destination_in_directory></cluster_or_instancename></name_of_resource_adapter_deployed>	Defines the JNDI lookup name for an administered object. In the case of JMS this is the destination/queue name. The properties link the lookup to the resource adapter, type of the resource and the cluster/instances that will advertise the destination. The properties allow the URL for the lookup in Idap where the administered objects are stored.

There may be a requirement to add additional properties to the application server to add to the classpath or a need to modify the server policy file for the security manager.

4.2. Example MDB Deployment Descriptors

The following is an example of the sun-ejb.xml for an application that holds a message driven bean:-

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE sun-ejb-jar PUBLIC "-//Sun Microsystems, Inc.//DTD Application Server 8.1 EJB 2.1//EN"</pre>
                                                      "http://www.sun.com/software/appserver/dtds/sun-ejb-jar 2 1-1.dtd">
<sun-eib-iar>
     <enterprise-beans>
         <name>MessageQueueMDBProcessingModule
              <eib-name>OueueConsumerBean</eib-name>
              <jndi-name>jms/queue destination ra</jndi-name>
                   <ejb-ref-name>ejb/PersistenceFacadeBean</ejb-ref-name>
                   <jndi-name>ejb/PersistenceFacadeBean</jndi-name>
              </eib-ref>
              <mdb-connection-factory>
                   <jndi-name>jms/queue connection factory ra</jndi-name>
              </mdb-connection-factory>
              <mdb-resource-adapter>
                   <re>ource-adapter-mid>mq resource adapter</resource-adapter-mid>
                   <activation-config>
                       <activation-config-property>
                             <activation-config-property-name>DestinationType</activation-config-property-name>
                             <activation-config-property-value>javax.jms.Queue</activation-config-property-value>
                       </activation-config-property>
                        <activation-config-property>
                            \verb|\activation-config-property-name>| MaxPoolSize </activation-config-property-name>| MaxPoolSize </activation-config-propert
                             <activation-config-property-value>32</activation-config-property-value>
                       </activation-config-property>
                       <activation-config-property>
                             <activation-config-property-name>RedeliveryAttempts</activation-config-property-name>
                             <activation-config-property-value>0</activation-config-property-value>
                       </activation-config-property>
                       <activation-config-property>
                            \verb|\config-property-name|| Reconnect Attempts < / activation-config-property-name|| Activation-config-prope
                             <activation-config-property-value>4</activation-config-property-value>
                        </activation-config-property>
                       <activation-config-property>
                             <activation-config-property-name>ReconnectInterval</activation-config-property-name>
                             <activation-config-property-value>10</activation-config-property-value>
                       </activation-config-property>
                        <activation-config-property>
                            <activation-config-property-name>RedeliveryInterval</activation-config-property-name>
                             <activation-config-property-value>1</activation-config-property-value>
                        </activation-config-property>
                        <activation-config-property>
                             <activation-config-property-name>ConnectionFactoryJndiName</activation-config-property-name>
                            <activation-config-property-value>cn=queue connection factory</activation-config-property-value>
                          </activation-config-property>
                        <activation-config-property>
                            <activation-config-property-name>DestinationJndiName</activation-config-property-name>
                             <activation-config-property-value>cn=queue_dest</activation-config-property-value>
                       </activation-config-property>
                   </activation-config>
              </mdb-resource-adapter>
         </ejb>
         <cmp-resource>
              <default-resource-principal>
                   <name>QueueConsumer</name>
              </default-resource-principal>
         </cmp-resource>
         <message-destination>
              <message-destination-name>QueueConsumerDestination/message-destination-name>
              <jndi-name>jms/queue destination ra</jndi-name>
         </message-destination>
    </enterprise-beans>
</sun-ejb-jar>
```

