Package 'readr'

May 16, 2017

```
Version 1.1.1
```

Title Read Rectangular Text Data

Description The goal of 'readr' is to provide a fast and friendly way to read rectangular data (like 'csv', 'tsv', and 'fwf'). It is designed to flexibly parse many types of data found in the wild, while still cleanly failing when data unexpectedly changes.

```
Encoding UTF-8

Depends R (>= 3.0.2)
```

LinkingTo Rcpp, BH

Imports Rcpp (>= 0.12.0.5), tibble, hms, R6

Suggests curl, testthat, knitr, rmarkdown, stringi, covr

License GPL (>= 2) | file LICENSE

BugReports https://github.com/tidyverse/readr/issues

URL http://readr.tidyverse.org, https://github.com/tidyverse/readr

VignetteBuilder knitr

RoxygenNote 6.0.1

NeedsCompilation yes

Author Hadley Wickham [aut],

Jim Hester [aut, cre],

Romain Francois [aut],

R Core Team [ctb] (Date time code adapted from R),

RStudio [cph, fnd],

Jukka Jylänki [ctb, cph] (grisu3 implementation),

Mikkel Jørgensen [ctb, cph] (grisu3 implementation)

Maintainer Jim Hester < james.hester@rstudio.com>

Repository CRAN

Date/Publication 2017-05-16 19:03:57 UTC

2 cols

R topics documented:

cois	 	 	•	 •			 		•	 •	•		 •	•	•	•	
cols_condense	 	 					 										3
col_skip	 	 					 										4
count_fields	 	 					 										4
date_names	 	 					 										5
format_delim	 	 					 										5
guess_encoding .	 	 					 										6
locale	 	 					 										7
parse_atomic	 	 					 										8
parse_datetime .	 	 					 										9
parse_factor	 	 					 										12
parse_guess	 	 					 										13
parse_number	 	 					 										14
problems	 	 					 										15
read_delim	 	 					 										16
read_file	 	 					 										18
read_fwf	 	 					 										20
read_lines	 	 					 									•	22
read_log																•	23
read_table	 	 					 										25
spec_delim																	27
type_convert																	29
write_delim	 	 					 			 •							30
																	33
																	33

cols

Index

Create column specification

Description

Create column specification

Usage

```
cols(..., .default = col_guess())
cols_only(...)
```

column type.

Arguments

... Either column objects created by col_*(), or their abbreviated character names.

If you're only overriding a few columns, it's best to refer to columns by name.

If not named, the column types must match the column names exactly.

Any named columns not explicitly overridden in ... will be read with this

cols_condense 3

Examples

```
cols(a = col_integer())
cols_only(a = col_integer())

# You can also use the standard abreviations
cols(a = "i")
cols(a = "i", b = "d", c = "_")
```

cols_condense

Examine the column specifications for a data frame

Description

cols_condense() takes a spec object and condenses its definition by setting the default column type to the most frequent type and only listing columns with a different type.

spec() extracts the full column specification from a tibble created by readr.

Usage

```
cols_condense(x)
spec(x)
```

Arguments

Х

The data frame object to extract from

Value

A col_spec object.

```
df <- read_csv(readr_example("mtcars.csv"))
s <- spec(df)
s
cols_condense(s)</pre>
```

4 count_fields

7	- 1	
col	ski	n

Skip a column

Description

Use this function to ignore a column when reading in a file. To skip all columns not otherwise specified, use cols_only().

Usage

```
col_skip()
```

See Also

Other parsers: parse_datetime, parse_factor, parse_guess, parse_logical, parse_number

count_fields

Count the number of fields in each line of a file

Description

This is useful for diagnosing problems with functions that fail to parse correctly.

Usage

```
count_fields(file, tokenizer, skip = 0, n_max = -1L)
```

Arguments

file Either a path to a file, a connection, or literal data (either a single string or a raw

vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and

decompressed.

Literal data is most useful for examples and tests. It must contain at least one

new line to be recognised as data (instead of a path).

tokenizer A tokenizer that specifies how to break the file up into fields, e.g., tokenizer_csv(),

tokenizer_fwf()

skip Number of lines to skip before reading data.

n_max Optionally, maximum number of rows to count fields for.

```
count_fields(readr_example("mtcars.csv"), tokenizer_csv())
```

date_names 5

date_names

Create or retrieve date names

Description

When parsing dates, you often need to know how weekdays of the week and months are represented as text. This pair of functions allows you to either create your own, or retrieve from a standard list. The standard list is derived from ICU (http://site.icu-project.org) via the stringi package.

Usage

```
date_names(mon, mon_ab = mon, day, day_ab = day, am_pm = c("AM", "PM"))
date_names_lang(language)
date_names_langs()
```

Arguments

mon, mon_ab Full and abbreviated month names.

day, day_ab Full and abbreviated week day names. Starts with Sunday.

am_pm Names used for AM and PM.

language A BCP 47 locale, made up of a language and a region, e.g. "en_US" for American

English. See date_names_locales() for a complete list of available locales.

Examples

```
date_names_lang("en")
date_names_lang("ko")
date_names_lang("fr")
```

format_delim

Convert a data frame to a delimited string

Description

These functions are equivalent to write_csv() etc., but instead of writing to disk, they return a string.

Usage

```
format_delim(x, delim, na = "NA", append = FALSE, col_names = !append)
format_csv(x, na = "NA", append = FALSE, col_names = !append)
format_tsv(x, na = "NA", append = FALSE, col_names = !append)
```

6 guess_encoding

Arguments

X	A data frame to write to disk
delim	Delimiter used to separate values. Defaults to " ". Must be a single character.
na	String used for missing values. Defaults to NA. Missing values will never be quoted; strings with the same value as na will always be quoted.
append	If FALSE, will overwrite existing file. If TRUE, will append to existing file. In both cases, if file does not exist a new file is created.
col_names	Write columns names at the top of the file?

Value

A string.

Output

Factors are coerced to character. Doubles are formatted using the grisu3 algorithm. POSIXct's are formatted as ISO8601.

All columns are encoded as UTF-8. write_excel_csv() also includes a UTF-8 Byte order mark which indicates to Excel the csv is UTF-8 encoded.

Values are only quoted if needed: if they contain a comma, quote or newline.

References

Florian Loitsch, Printing Floating-Point Numbers Quickly and Accurately with Integers, PLDI '10, http://www.cs.tufts.edu/~nr/cs257/archive/florian-loitsch/printf.pdf

guess_encoding	Guess encoding of file

Description

Uses stringi::stri_enc_detect(): see the documentation there for caveats.

Usage

```
guess_encoding(file, n_max = 10000, threshold = 0.2)
```

Arguments

file	A character string specifying an input as specified in datasource(), a raw vector, or a list of raw vectors.
n_max	Number of lines to read. If n_max is -1, all lines in file will be read.
threshold	Only report guesses above this threshold of certainty.

locale 7

Value

A tibble

Examples

```
guess_encoding(readr_example("mtcars.csv"))
guess_encoding(read_lines_raw(readr_example("mtcars.csv")))
guess_encoding(read_file_raw(readr_example("mtcars.csv")))
guess_encoding("a\n\u00b5\u00b5")
```

locale

Create locales

Description

A locale object tries to capture all the defaults that can vary between countries. You set the locale in once, and the details are automatically passed on down to the columns parsers. The defaults have been chosen to match R (i.e. US English) as closely as possible. See vignette("locales") for more details.

Usage

```
locale(date_names = "en", date_format = "%AD", time_format = "%AT",
  decimal_mark = ".", grouping_mark = ",", tz = "UTC",
  encoding = "UTF-8", asciify = FALSE)

default_locale()
```

Arguments

date_names

Character representations of day and month names. Either the language code as string (passed on to date_names_lang()) or an object created by date_names().

date_format, time_format

Default date and time formats.

 ${\tt decimal_mark, grouping_mark}$

Symbols used to indicate the decimal place, and to chunk larger numbers. Decimal mark can only be , or ..

tz

Default tz. This is used both for input (if the time zone isn't present in individual strings), and for output (to control the default display). The default is to use "UTC", a time zone that does not use daylight savings time (DST) and hence is typically most useful for data. The absence of time zones makes it approximately 50x faster to generate UTC times than any other time zone.

Use "" to use the system default time zone, but beware that this will not be reproducible across systems.

For a complete list of possible time zones, see OlsonNames(). Americans, note that "EST" is a Canadian time zone that does not have DST. It is *not* Eastern Standard Time. It's better to use "US/Eastern", "US/Central" etc.

8 parse_atomic

encoding Default encoding. This only affects how the file is read - readr always converts

the output to UTF-8.

asciify Should diacritics be stripped from date names and converted to ASCII? This is

useful if you're dealing with ASCII data where the correct spellings have been

lost. Requires the **stringi** package.

Examples

```
locale()
locale("fr")

# South American locale
locale("es", decimal_mark = ",")
```

parse_atomic

Parse logicals, integers, and reals

Description

Use parse_*() if you have a character vector you want to parse. Use col_*() in conjunction with a read_*() function to parse the values as they're read in.

Usage

```
parse_logical(x, na = c("", "NA"), locale = default_locale())

parse_integer(x, na = c("", "NA"), locale = default_locale())

parse_double(x, na = c("", "NA"), locale = default_locale())

parse_character(x, na = c("", "NA"), locale = default_locale())

col_logical()

col_integer()

col_double()

col_character()
```

Arguments

x Character vector of values to parse.

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

parse_datetime 9

See Also

Other parsers: col_skip, parse_datetime, parse_factor, parse_guess, parse_number

Examples

```
parse_integer(c("1", "2", "3"))
parse_double(c("1", "2", "3.123"))
parse_number("$1,123,456.00")

# Use locale to override default decimal and grouping marks
es_MX <- locale("es", decimal_mark = ",")
parse_number("$1.123.456,00", locale = es_MX)

# Invalid values are replaced with missing values with a warning.
x <- c("1", "2", "3", "-")
parse_double(x)
# Or flag values as missing
parse_double(x, na = "-")</pre>
```

parse_datetime

Parse date/times

Description

Parse date/times

Usage

```
parse_datetime(x, format = "", na = c("", "NA"),
  locale = default_locale())

parse_date(x, format = "", na = c("", "NA"), locale = default_locale())

parse_time(x, format = "", na = c("", "NA"), locale = default_locale())

col_datetime(format = "")

col_date(format = "")
```

Arguments

Х

A character vector of dates to parse.

 $\quad \text{format} \quad$

A format specification, as described below. If set to "", date times are parsed as ISO8601, dates and times used the date and time formats specified in the locale().

Unlike strptime(), the format specification must match the complete string.

parse_datetime

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

Value

A POSIXct() vector with tzone attribute set to tz. Elements that could not be parsed (or did not generate valid dates) will be set to NA, and a warning message will inform you of the total number of failures.

Format specification

readr uses a format specification similar to strptime(). There are three types of element:

- 1. Date components are specified with "%" followed by a letter. For example "%Y" matches a 4 digit year, "%m", matches a 2 digit month and "%d" matches a 2 digit day. Month and day default to 1, (i.e. Jan 1st) if not present, for example if only a year is given.
- 2. Whitespace is any sequence of zero or more whitespace characters.
- 3. Any other character is matched exactly.

parse_datetime() recognises the following format specifications:

- Year: "%Y" (4 digits). "%y" (2 digits); 00-69 -> 2000-2069, 70-99 -> 1970-1999.
- Month: "%m" (2 digits), "%b" (abbreviated name in current locale), "%B" (full name in current locale).
- Day: "%d" (2 digits), "%e" (optional leading space)
- Hour: "%H" or "%I", use I (and not H) with AM/PM.
- Minutes: "%M"
- Seconds: "%S" (integer seconds), "%OS" (partial seconds)
- Time zone: "%Z" (as name, e.g. "America/Chicago"), "%z" (as offset from UTC, e.g. "+0800")
- AM/PM indicator: "%p".
- Non-digits: "%." skips one non-digit character, "%+" skips one or more non-digit characters, "%*" skips any number of non-digits characters.
- Automatic parsers: "%AD" parses with a flexible YMD parser, "%AT" parses with a flexible HMS parser.
- Shortcuts: "%D" = "%m/%d/%y", "%F" = "%Y-%m-%d", "%R" = "%H:%M", "%T" = "%H:%M:%S", "%x" = "%y/%m/%d".

parse_datetime 11

ISO8601 support

Currently, readr does not support all of ISO8601. Missing features:

- Week & weekday specifications, e.g. "2013-W05", "2013-W05-10"
- Ordinal dates, e.g. "2013-095".
- Using commas instead of a period for decimal separator

The parser is also a little laxer than ISO8601:

- Dates and times can be separated with a space, not just T.
- Mostly correct specifications like "2009-05-19 14:" and "200912-01" work.

See Also

Other parsers: col_skip, parse_factor, parse_guess, parse_logical, parse_number

```
parse_datetime("01/02/2010", "%d/%m/%Y")
parse_datetime("01/02/2010", "%m/%d/%Y")
# Handle any separator
parse_datetime("01/02/2010", "%m%.%d%.%Y")
# Dates look the same, but internally they use the number of days since
# 1970-01-01 instead of the number of seconds. This avoids a whole lot
# of troubles related to time zones, so use if you can.
parse_date("01/02/2010", "%d/%m/%Y")
parse_date("01/02/2010", "%m/%d/%Y")
# You can parse timezones from strings (as listed in OlsonNames())
parse_datetime("2010/01/01 12:00 US/Central", "%Y/%m/%d %H:%M %Z")
# Or from offsets
parse_datetime("2010/01/01 12:00 -0600", "%Y/%m/%d %H:%M %z")
# Use the locale parameter to control the default time zone
# (but note UTC is considerably faster than other options)
parse_datetime("2010/01/01 12:00", "%Y/%m/%d %H:%M",
 locale = locale(tz = "US/Central"))
parse_datetime("2010/01/01 12:00", "%Y/%m/%d %H:%M",
 locale = locale(tz = "US/Eastern"))
# Unlike strptime, the format specification must match the complete
# string (ignoring leading and trailing whitespace). This avoids common
# errors:
strptime("01/02/2010", "%d/%m/%y")
parse_datetime("01/02/2010", "%d/%m/%y")
# Failures ------
parse_datetime("01/01/2010", "%d/%m/%Y")
parse_datetime(c("01/ab/2010", "32/01/2010"), "%d/%m/%Y")
```

parse_factor

```
# By default, readr expects English date/times, but that's easy to change'
parse_datetime("1 janvier 2015", "%d %B %Y", locale = locale("fr"))
parse_datetime("1 enero 2015", "%d %B %Y", locale = locale("es"))
# ISO8601 -------
# With separators
parse_datetime("1979-10-14")
parse_datetime("1979-10-14T10")
parse_datetime("1979-10-14T10:11")
parse_datetime("1979-10-14T10:11:12")
parse_datetime("1979-10-14T10:11:12.12345")
# Without separators
parse_datetime("19791014")
parse_datetime("19791014T101112")
# Time zones
us_central <- locale(tz = "US/Central")</pre>
parse_datetime("1979-10-14T1010", locale = us_central)
parse_datetime("1979-10-14T1010-0500", locale = us_central)
parse_datetime("1979-10-14T1010Z", locale = us_central)
# Your current time zone
parse_datetime("1979-10-14T1010", locale = locale(tz = ""))
```

parse_factor

Parse factors

Description

parse_factor is similar to factor(), but will generate warnings if elements of x are not found in levels.

Usage

```
parse_factor(x, levels, ordered = FALSE, na = c("", "NA"),
  locale = default_locale(), include_na = TRUE)

col_factor(levels, ordered = FALSE, include_na = FALSE)
```

Arguments

X	Character vector of values to parse.
levels	Character vector providing set of allowed levels. if NULL, will generate levels

based on the unique values of x, ordered by order of appearance in x.

ordered Is it an ordered factor?

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

parse_guess 13

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

include_na If NA are present, include as an explicit factor to level?

See Also

Other parsers: col_skip, parse_datetime, parse_guess, parse_logical, parse_number

Examples

```
parse_factor(c("a", "b"), letters)

x <- c("cat", "dog", "caw")
levels <- c("cat", "dog", "cow")

# Base R factor() silently converts unknown levels to NA
x1 <- factor(x, levels)

# parse_factor generates a warning & problems
x2 <- parse_factor(x, levels)

# Using an argument of `NULL` will generate levels based on values of `x`
x2 <- parse_factor(x, levels = NULL)</pre>
```

parse_guess

Parse using the "best" type

Description

parse_guess() returns the parser vector; guess_parser() returns the name of the parser. These functions use a number of heuristics to determine which type of vector is "best". Generally they try to err of the side of safety, as it's straightforward to override the parsing choice if needed.

Usage

```
parse_guess(x, na = c("", "NA"), locale = default_locale())
col_guess()
guess_parser(x, locale = default_locale())
```

Arguments

x Character vector of values to parse.

na Character vector of strings to use for missing values. Set this option to character() to indicate no missing values.

parse_number

locale

The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use <code>locale()</code> to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark, and day/month names.

See Also

Other parsers: col_skip, parse_datetime, parse_factor, parse_logical, parse_number

Examples

```
# Logical vectors
parse_guess(c("FALSE", "TRUE", "F", "T"))

# Integers and doubles
parse_guess(c("1","2","3"))
parse_guess(c("1.6","2.6","3.4"))

# Numbers containing grouping mark
guess_parser("1,234,566")

parse_guess("1,234,566")

# ISO 8601 date times
guess_parser(c("2010-10-10"))
parse_guess(c("2010-10-10"))
```

parse_number

Parse numbers, flexibly

Description

This drops any non-numeric characters before or after the first number. The grouping mark specified by the locale is ignored inside the number.

Usage

```
parse_number(x, na = c("", "NA"), locale = default_locale())
col_number()
```

Arguments

x Character vector of values to parse.

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

problems 15

See Also

Other parsers: col_skip, parse_datetime, parse_factor, parse_guess, parse_logical

Examples

```
parse_number("$1000")
parse_number("1,234,567.78")
```

problems

Retrieve parsing problems

Description

Readr functions will only throw an error if parsing fails in an unrecoverable way. However, there are lots of potential problems that you might want to know about - these are stored in the problems attribute of the output, which you can easily access with this function. stop_for_problems() will throw an error if there are any parsing problems: this is useful for automated scripts where you want to throw an error as soon as you encounter a problem.

Usage

```
problems(x)
stop_for_problems(x)
```

Arguments

Х

An data frame (from read_*()) or a vector (from parse_*()).

Value

A data frame with one row for each problem and four columns:

row, col Row and column of problem expected What readr expected to find actual What it actually got

```
x <- parse_integer(c("1X", "blah", "3"))
problems(x)

y <- parse_integer(c("1", "2", "3"))
problems(y)</pre>
```

16 read_delim

read_delim

Read a delimited file (including csv & tsv) into a tibble

Description

read_csv() and read_tsv() are special cases of the general read_delim(). They're useful for reading the most common types of flat file data, comma separated values and tab separated values, respectively. read_csv2() uses; for separators, instead of, This is common in European countries which use, as the decimal separator.

Usage

```
read_delim(file, delim, quote = "\"", escape_backslash = FALSE,
 escape_double = TRUE, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 comment = "", trim_ws = FALSE, skip = 0, n_max = Inf,
 guess_max = min(1000, n_max), progress = show_progress())
read_csv(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = Inf,
 guess_max = min(1000, n_max), progress = show_progress())
read_csv2(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = Inf,
 guess_max = min(1000, n_max), progress = show_progress())
read_tsv(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = Inf,
 guess_max = min(1000, n_max), progress = show_progress())
```

Arguments

file Either a path to a file, a connection, or literal data (either a single string or a raw vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

delim Single character used to separate fields within a record.

quote Single character used to quote strings.

17 read_delim

escape_backslash

Does the file use backslashes to escape special characters? This is more general than escape_double as backslashes can be used to escape the delimiter character, the quote character, or to add special characters like \n.

escape_double

Does the file escape quotes by doubling them? i.e. If this option is TRUE, the value """" represents a single quote, \".

col_names

Either TRUE, FALSE or a character vector of column names.

If TRUE, the first row of the input will be used as the column names, and will not be included in the data frame. If FALSE, column names will be generated automatically: X1, X2, X3 etc.

If col_names is a character vector, the values will be used as the names of the columns, and the first row of the input will be read into the first row of the output data frame.

Missing (NA) column names will generate a warning, and be filled in with dummy names X1, X2 etc. Duplicate column names will generate a warning and be made unique with a numeric prefix.

col_types

One of NULL, a cols() specification, or a string. See vignette("column-types") for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Alternatively, you can use a compact string representation where each character represents one column: c = character, i = integer, n = number, d = double, l = logical, D = date, T = date time, t = time, t

locale

The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark, and day/month names.

na

Character vector of strings to use for missing values. Set this option to character() to indicate no missing values.

quoted_na

Should missing values inside quotes be treated as missing values (the default) or strings.

comment

A string used to identify comments. Any text after the comment characters will be silently ignored.

trim_ws

Should leading and trailing whitespace be trimmed from each field before pars-

skip

Number of lines to skip before reading data.

n_max

Maximum number of records to read.

guess_max

Maximum number of records to use for guessing column types.

progress

Display a progress bar? By default it will only display in an interactive session and not while knitting a document. The display is updated every 50,000 values

18 read_file

and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr. show_progress to FALSE.

Value

A data frame. If there are parsing problems, a warning tells you how many, and you can retrieve the details with problems().

Examples

```
# Input sources ------
# Read from a path
read_csv(readr_example("mtcars.csv"))
read_csv(readr_example("mtcars.csv.zip"))
read_csv(readr_example("mtcars.csv.bz2"))
read_csv("https://github.com/tidyverse/readr/raw/master/inst/extdata/mtcars.csv")
# Or directly from a string (must contain a newline)
read_csv("x,y\n1,2\n3,4")
# Column types ------
# By default, readr guesses the columns types, looking at the first 100 rows.
# You can override with a compact specification:
read_csv("x,y\n1,2\n3,4", col_types = "dc")
# Or with a list of column types:
read_csv("x,y\n1,2\n3,4", col_types = list(col_double(), col_character()))
# If there are parsing problems, you get a warning, and can extract
# more details with problems()
y \leftarrow read_csv("x\n1\n2\nb", col_types = list(col_double()))
problems(y)
read_csv("a,b\n1.0,2.0")
read_csv2("a;b\n1,0;2,0")
read_tsv("a\tb\n1.0\t2.0")
read_delim("a|b\n1.0|2.0", delim = "|")
```

read_file

Read/write a complete file

Description

read_file() reads a complete file into a single object: either a character vector of length one, or a raw vector. write_file() takes a single string, or a raw vector, and writes it exactly as is. Raw vectors are useful when dealing with binary data, or if you have text data with unknown encoding.

read_file 19

Usage

```
read_file(file, locale = default_locale())
read_file_raw(file)
write_file(x, path, append = FALSE)
```

Arguments

file Either a path to a file, a connection, or literal data (either a single string or a raw

vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and

decompressed.

Literal data is most useful for examples and tests. It must contain at least one

new line to be recognised as data (instead of a path).

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

x A data frame to write to disk

path Path or connection to write to.

append If FALSE, will overwrite existing file. If TRUE, will append to existing file. In

both cases, if file does not exist a new file is created.

Value

```
read_file: A length 1 character vector. read_lines_raw: A raw vector.
```

```
read_file(file.path(R.home("doc"), "AUTHORS"))
read_file_raw(file.path(R.home("doc"), "AUTHORS"))

tmp <- tempfile()

x <- format_csv(mtcars[1:6, ])
write_file(x, tmp)
identical(x, read_file(tmp))

read_lines(x)</pre>
```

20 read_fwf

read_fwf

Read a fixed width file into a tibble

Description

A fixed width file can be a very compact representation of numeric data. It's also very fast to parse, because every field is in the same place in every line. Unfortunately, it's painful to parse because you need to describe the length of every field. Readr aims to make it as easy as possible by providing a number of different ways to describe the field structure.

Usage

```
read_fwf(file, col_positions, col_types = NULL, locale = default_locale(),
  na = c("", "NA"), comment = "", skip = 0, n_max = Inf,
  guess_max = min(n_max, 1000), progress = show_progress())

fwf_empty(file, skip = 0, col_names = NULL, comment = "", n = 100L)

fwf_widths(widths, col_names = NULL)

fwf_positions(start, end = NULL, col_names = NULL)

fwf_cols(...)
```

Arguments

file

Either a path to a file, a connection, or literal data (either a single string or a raw vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

col_positions

Column positions, as created by fwf_empty(), fwf_widths() or fwf_positions(). To read in only selected fields, use fwf_positions(). If the width of the last column is variable (a ragged fwf file), supply the last end position as NA.

col_types

One of NULL, a cols() specification, or a string. See vignette("column-types") for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Osagi

read_fwf 21

Alternatively, you can use a compact string representation where each character represents one column: c = character, i = integer, n = number, d = double, l = logical, D = date, T = date time, t = time, tlocale The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark, and day/month names. Character vector of strings to use for missing values. Set this option to character() na to indicate no missing values. comment A string used to identify comments. Any text after the comment characters will be silently ignored. Number of lines to skip before reading data. skip Maximum number of records to read. n_max guess_max Maximum number of records to use for guessing column types. Display a progress bar? By default it will only display in an interactive session progress and not while knitting a document. The display is updated every 50,000 values and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr. show_progress to FALSE. col_names Either NULL, or a character vector column names. Number of lines the tokenizer will read to determine file structure. By default it is set to 100. widths Width of each field. Use NA as width of last field when reading a ragged fwf start, end Starting and ending (inclusive) positions of each field. Use NA as last end field when reading a ragged fwf file. If the first element is a data frame, then it must have all numeric columns and either one or two rows. The column names are the variable names, and the column values are the variable widths if a length one vector, and variable start and end positions. Otherwise, the elements of . . . are used to construct a data

See Also

read_table() to read fixed width files where each column is separated by whitespace.

frame with or or two rows as above.

```
fwf_sample <- readr_example("fwf-sample.txt")
cat(read_lines(fwf_sample))

# You can specify column positions in several ways:
# 1. Guess based on position of empty columns
read_fwf(fwf_sample, fwf_empty(fwf_sample, col_names = c("first", "last", "state", "ssn")))
# 2. A vector of field widths
read_fwf(fwf_sample, fwf_widths(c(20, 10, 12), c("name", "state", "ssn")))</pre>
```

22 read_lines

```
# 3. Paired vectors of start and end positions
read_fwf(fwf_sample, fwf_positions(c(1, 30), c(10, 42), c("name", "ssn")))
# 4. Named arguments with start and end positions
read_fwf(fwf_sample, fwf_cols(name = c(1, 10), ssn = c(30, 42)))
# 5. Named arguments with column widths
read_fwf(fwf_sample, fwf_cols(name = 20, state = 10, ssn = 12))
```

read_lines

Read/write lines to/from a file

Description

read_lines() reads up to n_max lines from a file. New lines are not included in the output. read_lines_raw() produces a list of raw vectors, and is useful for handling data with unknown encoding. write_lines() takes a character vector or list of raw vectors, appending a new line after each entry.

Usage

```
read_lines(file, skip = 0, n_max = -1L, locale = default_locale(),
    na = character(), progress = show_progress())

read_lines_raw(file, skip = 0, n_max = -1L, progress = show_progress())

write_lines(x, path, na = "NA", append = FALSE)
```

Arguments

na

file Either a path to a file, a connection, or literal data (either a single string or a raw

vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

skip Number of lines to skip before reading data.

n_max Number of lines to read. If n_max is -1, all lines in file will be read.

The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use locale() to create your own locale that

controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

read_log 23

progress Display a progress bar? By default it will only display in an interactive session

and not while knitting a document. The display is updated every 50,000 values and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr.show_progress to

FALSE.

x A data frame to write to disk

path Path or connection to write to.

append If FALSE, will overwrite existing file. If TRUE, will append to existing file. In

both cases, if file does not exist a new file is created.

Value

read_lines(): A character vector with one element for each line. read_lines_raw(): A list containing a raw vector for each line.

```
write_lines() returns x, invisibly.
```

Examples

```
read_lines(file.path(R.home("doc"), "AUTHORS"), n_max = 10)
read_lines_raw(file.path(R.home("doc"), "AUTHORS"), n_max = 10)

tmp <- tempfile()

write_lines(rownames(mtcars), tmp)
read_lines(tmp)
read_file(tmp) # note trailing \n

write_lines(airquality$0zone, tmp, na = "-1")
read_lines(tmp)</pre>
```

read_log

Read common/combined log file into a tibble

Description

This is a fairly standard format for log files - it uses both quotes and square brackets for quoting, and there may be literal quotes embedded in a quoted string. The dash, "-", is used for missing values.

Usage

```
read_log(file, col_names = FALSE, col_types = NULL, skip = 0,
  n_max = Inf, progress = show_progress())
```

24 read_log

Arguments

file

Either a path to a file, a connection, or literal data (either a single string or a raw vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

col names

Either TRUE, FALSE or a character vector of column names.

If TRUE, the first row of the input will be used as the column names, and will not be included in the data frame. If FALSE, column names will be generated automatically: X1, X2, X3 etc.

If col_names is a character vector, the values will be used as the names of the columns, and the first row of the input will be read into the first row of the output data frame.

Missing (NA) column names will generate a warning, and be filled in with dummy names X1, X2 etc. Duplicate column names will generate a warning and be made unique with a numeric prefix.

col_types

One of NULL, a cols() specification, or a string. See vignette("column-types") for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Alternatively, you can use a compact string representation where each character represents one column: c = character, i = integer, n = number, d = double, l = logical, D = date, T = date time, t = time, t

skip

Number of lines to skip before reading data.

n_max

Maximum number of records to read.

progress

Display a progress bar? By default it will only display in an interactive session and not while knitting a document. The display is updated every 50,000 values and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr. show_progress to FALSE.

Examples

read_log(readr_example("example.log"))

read_table 25

read_table

Read whitespace-separated columns into a tibble

Description

read_table() and read_table2() are designed to read the type of textual data where each column is #' separate by one (or more) columns of space.

read_table2() is like read.table(), it allows any number of whitespace characters between columns, and the lines can be of different lengths.

read_table() is more strict, each line must be the same length, and each field is in the same position in every line. It first finds empty columns and then parses like a fixed width file.

spec_table() and spec_table2() return the column specifications rather than a data frame.

Usage

```
read_table(file, col_names = TRUE, col_types = NULL,
  locale = default_locale(), na = "NA", skip = 0, n_max = Inf,
  guess_max = min(n_max, 1000), progress = show_progress(), comment = "")

read_table2(file, col_names = TRUE, col_types = NULL,
  locale = default_locale(), na = "NA", skip = 0, n_max = Inf,
  guess_max = min(n_max, 1000), progress = show_progress(), comment = "")
```

Arguments

file

Either a path to a file, a connection, or literal data (either a single string or a raw vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

col_names

Either TRUE, FALSE or a character vector of column names.

If TRUE, the first row of the input will be used as the column names, and will not be included in the data frame. If FALSE, column names will be generated automatically: X1, X2, X3 etc.

If col_names is a character vector, the values will be used as the names of the columns, and the first row of the input will be read into the first row of the output data frame.

Missing (NA) column names will generate a warning, and be filled in with dummy names X1, X2 etc. Duplicate column names will generate a warning and be made unique with a numeric prefix.

26 read_table

col_types One of NULL, a cols() specification, or a string. See vignette("column-types")

for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Alternatively, you can use a compact string representation where each character represents one column: c = character, i = integer, n = number, d = double, l = logical, D = date, T = date time, t = time, t

The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use locale() to create your own locale that

controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

skip Number of lines to skip before reading data.

n_max Maximum number of records to read.

guess_max Maximum number of records to use for guessing column types.

progress Display a progress bar? By default it will only display in an interactive session

and not while knitting a document. The display is updated every 50,000 values and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr.show_progress to

FALSE.

comment A string used to identify comments. Any text after the comment characters will

be silently ignored.

See Also

read_fwf() to read fixed width files where each column is not separated by whitespace. read_fwf()
is also useful for reading tabular data with non-standard formatting.

```
# One corner from http://www.masseyratings.com/cf/compare.htm
massey <- readr_example("massey-rating.txt")
cat(read_file(massey))
read_table(massey)

# Sample of 1978 fuel economy data from
# http://www.fueleconomy.gov/feg/epadata/78data.zip
epa <- readr_example("epa78.txt")
cat(read_file(epa))
read_table(epa, col_names = FALSE)</pre>
```

spec_delim 27

spec_delim

Generate a column specification

Description

When printed, only the first 20 columns are printed by default. To override, set options(readr.num_columns) can be used to modify this (a value of 0 turns off printing).

Usage

```
spec_delim(file, delim, quote = "\"", escape_backslash = FALSE,
 escape_double = TRUE, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 comment = "", trim_ws = FALSE, skip = 0, n_max = 0,
 guess_max = 1000, progress = show_progress())
spec_csv(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = 0,
 guess_max = 1000, progress = show_progress())
spec_csv2(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = 0,
 guess_max = 1000, progress = show_progress())
spec_tsv(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = c("", "NA"), quoted_na = TRUE,
 quote = "\"", comment = "", trim_ws = TRUE, skip = 0, n_max = 0,
 guess_max = 1000, progress = show_progress())
spec_table(file, col_names = TRUE, col_types = NULL,
 locale = default_locale(), na = "NA", skip = 0, n_max = 0,
 guess_max = 1000, progress = show_progress(), comment = "")
```

Arguments

file

Either a path to a file, a connection, or literal data (either a single string or a raw vector).

Files ending in .gz, .bz2, .xz, or .zip will be automatically uncompressed. Files starting with http://, https://, ftp://, or ftps:// will be automatically downloaded. Remote gz files can also be automatically downloaded and decompressed.

Literal data is most useful for examples and tests. It must contain at least one new line to be recognised as data (instead of a path).

delim

Single character used to separate fields within a record.

28 spec_delim

quote Single character used to quote strings.

escape_backslash

Does the file use backslashes to escape special characters? This is more general than escape_double as backslashes can be used to escape the delimiter character, the quote character, or to add special characters like \n.

Does the file escape quotes by doubling them? i.e. If this option is TRUE, the escape_double value """" represents a single quote, \".

col_names Either TRUE, FALSE or a character vector of column names.

> If TRUE, the first row of the input will be used as the column names, and will not be included in the data frame. If FALSE, column names will be generated automatically: X1, X2, X3 etc.

> If col_names is a character vector, the values will be used as the names of the columns, and the first row of the input will be read into the first row of the output data frame.

> Missing (NA) column names will generate a warning, and be filled in with dummy names X1, X2 etc. Duplicate column names will generate a warning and be made unique with a numeric prefix.

One of NULL, a cols() specification, or a string. See vignette("column-types") for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Alternatively, you can use a compact string representation where each character represents one column: c = character, i = integer, n = number, d = double, l = characterlogical, D = date, T = date time, t = time, t

The locale controls defaults that vary from place to place. The default locale is US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark, and day/month names.

Character vector of strings to use for missing values. Set this option to character() to indicate no missing values.

Should missing values inside quotes be treated as missing values (the default) or strings.

A string used to identify comments. Any text after the comment characters will be silently ignored.

Should leading and trailing whitespace be trimmed from each field before parsing it?

skip Number of lines to skip before reading data.

Maximum number of records to read. n_max

Maximum number of records to use for guessing column types. guess_max

col_types

locale

na

comment

quoted_na

trim_ws

type_convert 29

progress

Display a progress bar? By default it will only display in an interactive session and not while knitting a document. The display is updated every 50,000 values and will only display if estimated reading time is 5 seconds or more. The automatic progress bar can be disabled by setting option readr. show_progress to FALSE.

Value

The col_spec generated for the file.

Examples

type_convert

Re-convert character columns in existing data frame

Description

This is useful if you need to do some manual munging - you can read the columns in as character, clean it up with (e.g.) regular expressions and then let readr take another stab at parsing it. The name is a homage to the base type.convert().

Usage

```
type_convert(df, col_types = NULL, na = c("", "NA"), trim_ws = TRUE,
  locale = default_locale())
```

Arguments

df A data frame.

col_types One of NULL, a cols() specification, or a string. See vignette("column-types")

for more details.

If NULL, all column types will be imputed from the first 1000 rows on the input. This is convenient (and fast), but not robust. If the imputation fails, you'll need to supply the correct types yourself.

30 write_delim

If a column specification created by cols(), it must contain one column specification for each column. If you only want to read a subset of the columns, use cols_only().

Unlike other functions type_convert() does not allow character specifications of col_types.

na Character vector of strings to use for missing values. Set this option to character()

to indicate no missing values.

trim_ws Should leading and trailing whitespace be trimmed from each field before pars-

ing it?

locale The locale controls defaults that vary from place to place. The default locale is

US-centric (like R), but you can use locale() to create your own locale that controls things like the default time zone, encoding, decimal mark, big mark,

and day/month names.

Examples

write_delim

Write a data frame to a delimited file

Description

This is about twice as fast as write.csv(), and never writes row names. output_column() is a generic method used to coerce columns to suitable output.

Usage

```
write_delim(x, path, delim = " ", na = "NA", append = FALSE,
    col_names = !append)
write_csv(x, path, na = "NA", append = FALSE, col_names = !append)
```

write_delim 31

```
write_excel_csv(x, path, na = "NA", append = FALSE, col_names = !append)
write_tsv(x, path, na = "NA", append = FALSE, col_names = !append)
```

Arguments

X	A data frame to write to disk
path	Path or connection to write to.
delim	Delimiter used to separate values. Defaults to " ". Must be a single character.
na	String used for missing values. Defaults to NA. Missing values will never be quoted; strings with the same value as na will always be quoted.
append	If FALSE, will overwrite existing file. If TRUE, will append to existing file. In both cases, if file does not exist a new file is created.
col_names	Write columns names at the top of the file?

Value

write_*() returns the input x invisibly.

Output

Factors are coerced to character. Doubles are formatted using the grisu3 algorithm. POSIXct's are formatted as ISO8601.

All columns are encoded as UTF-8. write_excel_csv() also includes a UTF-8 Byte order mark which indicates to Excel the csv is UTF-8 encoded.

Values are only quoted if needed: if they contain a comma, quote or newline.

References

Florian Loitsch, Printing Floating-Point Numbers Quickly and Accurately with Integers, PLDI '10, http://www.cs.tufts.edu/~nr/cs257/archive/florian-loitsch/printf.pdf

```
tmp <- tempfile()
write_csv(mtcars, tmp)
head(read_csv(tmp))

# format_* is useful for testing and reprexes
cat(format_csv(head(mtcars)))
cat(format_tsv(head(mtcars)))
cat(format_delim(head(mtcars), ";"))

df <- data.frame(x = c(1, 2, NA))
format_csv(df, na = ".")

# Quotes are automatically as needed
df <- data.frame(x = c("a", '"', ",", "\n"))
cat(format_csv(df))</pre>
```

32 write_delim

```
# A output connection will be automatically created for output filenames
# with appropriate extensions.
dir <- tempdir()
write_tsv(mtcars, file.path(dir, "mtcars.tsv.gz"))
write_tsv(mtcars, file.path(dir, "mtcars.tsv.bz2"))
write_tsv(mtcars, file.path(dir, "mtcars.tsv.xz"))</pre>
```

Index

```
col_character(parse_atomic), 8
                                                 guess_parser (parse_guess), 13
col_date(parse_datetime), 9
                                                 locale, 7
col_datetime (parse_datetime), 9
                                                 locale(), 8–10, 13, 14, 17, 19, 21, 22, 26, 28,
col_double (parse_atomic), 8
col_factor (parse_factor), 12
col_guess (parse_guess), 13
                                                 OlsonNames, 7
col_integer (parse_atomic), 8
col_logical (parse_atomic), 8
                                                 parse_atomic, 8
col_number (parse_number), 14
                                                 parse_character(parse_atomic), 8
col_skip, 4, 9, 11, 13-15
                                                 parse_date (parse_datetime), 9
col_time (parse_datetime), 9
                                                 parse_datetime, 4, 9, 9, 13-15
cols, 2
                                                 parse_double (parse_atomic), 8
cols(), 17, 20, 24, 26, 28–30
                                                 parse_factor, 4, 9, 11, 12, 14, 15
cols_condense, 3
                                                  parse_guess, 4, 9, 11, 13, 13, 15
cols_only, 4
                                                 parse_integer (parse_atomic), 8
cols_only (cols), 2
                                                  parse_logical, 4, 11, 13-15
cols_only(), 17, 20, 24, 26, 28, 30
                                                 parse_logical (parse_atomic), 8
count_fields, 4
                                                 parse_number, 4, 9, 11, 13, 14, 14
                                                 parse_time (parse_datetime), 9
datasource(), 6
                                                 POSIXct(), 10
date_names, 5
                                                 problems, 15, 18
date_names(), 7
date_names_lang (date_names), 5
                                                  read.table(), 25
date_names_lang(), 7
                                                  read_csv (read_delim), 16
date_names_langs (date_names), 5
                                                  read_csv2 (read_delim), 16
default_locale (locale), 7
                                                  read_delim, 16
                                                  read_file, 18
factor(), 12
                                                  read_file_raw(read_file), 18
format_csv (format_delim), 5
                                                  read_fwf, 20
format_delim, 5
                                                  read_fwf(), 26
format_tsv (format_delim), 5
                                                 read_lines, 22
fwf_cols (read_fwf), 20
                                                  read_lines_raw (read_lines), 22
fwf_empty (read_fwf), 20
                                                  read_log, 23
fwf_empty(), 20
                                                 read_table, 25
fwf_positions (read_fwf), 20
                                                  read_table(), 21
fwf_positions(), 20
                                                  read_table2 (read_table), 25
fwf_widths (read_fwf), 20
                                                  read_tsv (read_delim), 16
fwf_widths(), 20
                                                  spec (cols_condense), 3
                                                 spec_csv (spec_delim), 27
guess_encoding, 6
```

INDEX

```
spec_csv2 (spec_delim), 27
spec_delim, 27
spec_table (spec_delim), 27
spec_tsv (spec_delim), 27
stop_for_problems (problems), 15
stringi::stri_enc_detect(),6
strptime(), 9, 10
tokenizer_csv(), 4
tokenizer_fwf(), 4
type.convert, 29
type_convert, 29
write.csv(), 30
{\tt write\_csv} \; ({\tt write\_delim}), \, 30
write_csv(), 5
write_delim, 30
write_excel_csv (write_delim), 30
write_file (read_file), 18
write_lines (read_lines), 22
write_tsv (write_delim), 30
```