

# OppNDA Tutorial

From Setup to Regression Analysis

Supplementary Material  
For Elsevier SIMPAT Submission

DHMAI Network Research Group  
<https://dhmairg.net>

January 2026

## Contents

<b>1</b>	<b>Introduction</b>	<b>2</b>
1.1	Workflow Overview . . . . .	2
1.2	Prerequisites . . . . .	2
<b>2</b>	<b>Installation and Setup</b>	<b>3</b>
2.1	Method 1: Automated Setup Scripts . . . . .	3
2.1.1	Windows . . . . .	3
2.1.2	Linux/macOS . . . . .	3
2.2	Method 2: Manual Installation . . . . .	4
2.3	Method 3: Docker Installation . . . . .	4
2.3.1	Using Docker Compose (Recommended) . . . . .	4
2.3.2	Manual Docker Build . . . . .	4
2.4	Accessing the Web Interface . . . . .	4
<b>3</b>	<b>Scenario Configuration</b>	<b>5</b>
3.1	Importing Existing Configuration Files . . . . .	5
3.2	Scenario Settings . . . . .	6
3.3	Network Interfaces . . . . .	6
3.4	Host Groups . . . . .	7
3.5	Message Events . . . . .	8
3.6	Report Selection . . . . .	8
3.7	Saving Configuration . . . . .	10
<b>4</b>	<b>Running the ONE Simulator</b>	<b>10</b>
4.1	Starting a Simulation . . . . .	10
4.2	Monitoring Progress . . . . .	10
4.3	Terminating a Simulation . . . . .	11
<b>5</b>	<b>Post-Processing: Report Averaging</b>	<b>11</b>
5.1	Understanding Filename Patterns . . . . .	11
5.2	Configuring the Averager . . . . .	12
5.3	Pattern Builder . . . . .	12
5.4	Running the Averager . . . . .	12
5.5	Understanding Averaged Output . . . . .	14
<b>6</b>	<b>Post-Processing: Visualization and Analysis</b>	<b>14</b>
6.1	Configuring Analysis . . . . .	14
6.2	Available Plot Types . . . . .	14
6.3	Plot Settings . . . . .	15
6.4	Running Analysis . . . . .	16
6.5	Viewing Generated Plots . . . . .	16
<b>7</b>	<b>Regression Analysis</b>	<b>16</b>
7.1	Preparing Input Data . . . . .	16
7.2	Configuring Regression . . . . .	18
7.3	Available ML Models . . . . .	18
7.4	Multi-Target Regression . . . . .	18
7.5	Running Regression . . . . .	19
7.6	Interpreting Results . . . . .	19

<b>8 Conclusion</b>	<b>19</b>
8.1 Tips for Advanced Usage	20
8.2 Further Resources	20

## 1 Introduction

OppNDA (Opportunistic Network Data Analyzer) is a comprehensive web-based toolkit designed to streamline the workflow of configuring, running, and analyzing simulations from the ONE (Opportunistic Network Environment) simulator. This tutorial provides step-by-step guidance for using OppNDA, from initial installation through advanced regression analysis.

### 1.1 Workflow Overview

The complete OppNDA workflow consists of the following stages:

1. **Setup:** Install dependencies and launch the application
2. **Configuration:** Define simulation scenarios using the web interface
3. **Simulation:** Execute the ONE simulator with configured parameters
4. **Averaging:** Aggregate results across multiple simulation seeds
5. **Analysis:** Generate publication-ready visualizations
6. **Regression:** Train machine learning models on simulation data




Figure 1: OppNDA workflow pipeline overview

### 1.2 Prerequisites

Before proceeding, ensure you have the following:

- Python 3.9 or higher
- ONE Simulator (for generating simulation reports)
- A modern web browser (Chrome, Firefox, Edge)
- Git (for cloning the repository)
- Docker (optional, for containerized deployment)

## 2 Installation and Setup

OppNDA provides multiple installation methods to accommodate different environments and preferences.

### 2.1 Method 1: Automated Setup Scripts

The simplest installation method uses the provided setup scripts.

#### 2.1.1 Windows

1. Download or clone the OppNDA repository:

```
git clone https://github.com/nafisshahriar/oppnda.git  
cd oppnda
```

2. Run the setup script:

```
scripts\setup.bat
```

3. Launch the application:

```
scripts\start.bat
```




Figure 2: Running setup.bat on Windows

#### 2.1.2 Linux/macOS

1. Clone and navigate to the repository:

```
git clone https://github.com/nafisshahriar/oppnda.git  
cd oppnda
```

2. Run the setup script:

```
bash scripts/setup.sh
```

3. Launch the application:

```
bash scripts/start.sh
```

## 2.2 Method 2: Manual Installation

For more control over the installation process:

```
# Create and activate virtual environment
python -m venv venv
source venv/bin/activate      # Linux/macOS
venv\Scripts\activate         # Windows

# Install dependencies
pip install -r requirements.txt

# Run the application
python OppNDA.py
```

## 2.3 Method 3: Docker Installation

For containerized deployment, OppNDA includes Docker support:

### 2.3.1 Using Docker Compose (Recommended)

```
# Build and run with Docker Compose
docker-compose up --build
```

### 2.3.2 Manual Docker Build

```
# Build the Docker image
docker build -t oppnda .

# Run the container
docker run -p 5000:5000 --name OppNDA oppnda
```

#### Tip

Docker is particularly useful for consistent deployment across different machines and for isolated testing environments. The containerized version includes all dependencies pre-configured.

## 2.4 Accessing the Web Interface

After launching OppNDA, open your web browser and navigate to:




Figure 3: OppNDA running in a Docker container

<http://localhost:5000/settings>




Figure 4: OppNDA web interface home page


### 3 Scenario Configuration

The Settings page provides a comprehensive interface for configuring ONE simulator scenarios. This section covers both creating new configurations and importing existing ones.

#### 3.1 Importing Existing Configuration Files

OppNDA supports importing existing ONE simulator configuration files (.txt format) directly into the GUI.

1. Click the **Import Config** button in the toolbar
2. Select your existing ONE configuration file
3. The GUI will parse and populate all settings automatically
4. Review and modify imported settings as needed



[Screenshot Placeholder]  
`import-config`  
*Importing an existing ONE configuration file*

Figure 5: Importing an existing ONE configuration file

### Note

When importing, OppNDA automatically recognizes standard ONE parameters and maps them to the corresponding GUI fields. Unknown parameters are preserved and can be viewed in the advanced settings section.

## 3.2 Scenario Settings

The basic scenario settings define the simulation environment:

1. **Scenario Name:** Enter a descriptive name for your simulation
2. **Simulation Time:** Set the duration in seconds
3. **Update Interval:** Configure the simulation tick rate
4. **World Size:** Define the simulation area dimensions (X, Y)

## 3.3 Network Interfaces

Configure the communication interfaces available to nodes:

1. Click **Add Interface** to create a new interface
2. Select the interface type (e.g., SimpleBroadcastInterface)




Figure 6: Basic scenario configuration panel

3. Configure parameters:

- Transmission speed
- Transmission range





Figure 7: Network interface configuration

### 3.4 Host Groups

Define different categories of mobile nodes:

1. Click **Add Group** to create a new host group
2. Configure group parameters:

- Group ID and number of hosts
- Movement model (RandomWaypoint, ShortestPathMapBasedMovement, etc.)
- Buffer size
- Message TTL (Time-To-Live)
- Router type (Epidemic, SprayAndWait, PRoPHET, etc.)



[Screenshot Placeholder]

group-config

*Host group configuration panel*

Figure 8: Host group configuration panel

### 3.5 Message Events

Configure message generation patterns:

1. Click **Add Event** to create a new event generator
2. Set event parameters:
  - Event class (MessageEventGenerator)
  - Message creation interval (min, max)
  - Message size range
  - Source and destination host ranges
  - Event timing (start, end)

### 3.6 Report Selection

Choose which reports the ONE simulator should generate:

1. Browse the available report types
2. Select desired reports (e.g., MessageStatsReport, DeliveredMessagesReport)
3. Configure report-specific parameters if needed
4. Set the report output directory




Figure 9: Message event generator configuration




Figure 10: Report type selection panel

### 3.7 Saving Configuration

After configuring all parameters:

1. Click **Save Config** to save the current configuration
2. The configuration is saved as a **.txt** file compatible with ONE
3. OppNDA also maintains JSON backups of all settings

## 4 Running the ONE Simulator

OppNDA provides integrated execution of the ONE simulator with real-time output monitoring.

### 4.1 Starting a Simulation

1. Ensure your configuration is saved
2. Click the **Run ONE** button
3. OppNDA will:
  - Save the current configuration
  - Launch the ONE simulator with appropriate parameters
  - Display real-time console output
  - Automatically trigger post-processing upon completion





Figure 11: The Run ONE button and configuration summary

### 4.2 Monitoring Progress

The console panel displays real-time output from the simulator:

- Simulation progress percentage

- Current simulation time
- Messages created and delivered
- Any warnings or errors



[Screenshot Placeholder]  
`console-output`  
*Real-time console output during simulation*

Figure 12: Real-time console output during simulation

### Tip

For batch simulations with multiple parameter combinations, you can configure seed ranges and parameter variations. OppNDA will execute simulations sequentially and aggregate results.

## 4.3 Terminating a Simulation

If needed, you can stop a running simulation:

1. Click the **Terminate** button next to the Run ONE button
2. Confirm the termination
3. Any partial results will be preserved

## 5 Post-Processing: Report Averaging

The averaging module aggregates results across multiple simulation runs (seeds) to produce statistically meaningful data.

### 5.1 Understanding Filename Patterns

OppNDA uses configurable filename patterns to group and average reports. A typical ONE report filename follows this structure:

```
RouterType_TTL_BufferSize_Seed_ReportType.txt
```

For example: `Epidemic_300_5M_1_MessageStatsReport.txt`

## 5.2 Configuring the Averager

1. Navigate to the **Post-Processing** section
2. Set the **Input Directory** containing raw report files
3. Configure the **Filename Pattern** using the drag-and-drop pattern builder
4. Set **Grouping Parameters** to define which parameters to group by (e.g., Router, TTL, Buffer)
5. Set the **Seed Position** to identify which part of the filename represents the seed number




Figure 13: Averager configuration panel with pattern builder

## 5.3 Pattern Builder

The interactive pattern builder helps define filename patterns:

1. Drag components (Router, TTL, Buffer, Seed, etc.) into position
2. Set delimiters between components (underscore, hyphen, etc.)
3. Preview how patterns match your actual files

## 5.4 Running the Averager

1. Click **Run Averager**
2. Monitor progress in the console panel
3. Averaged files are saved with **averaged\_** prefix in the output directory




Figure 14: Interactive pattern builder interface




Figure 15: Averager console output showing grouped files

## 5.5 Understanding Averaged Output

The averaged output files contain:

- Mean values across all seeds
- Standard deviation for each metric
- Count of samples averaged

# 6 Post-Processing: Visualization and Analysis

The analysis module generates publication-ready visualizations from averaged data.

## 6.1 Configuring Analysis

1. Select the **Input Directory** containing averaged reports
2. Choose **Report Types** to analyze
3. Configure axis parameters (X, Y, Z variables)
4. Set desired **Plot Types**




Figure 16: Analysis configuration panel

## 6.2 Available Plot Types

OppNDA supports multiple visualization types:

- **3D Surface Plots:** Visualize relationships between three variables
- **Line Plots:** Show trends across parameter values
- **Heatmaps:** Display intensity matrices
- **Violin Plots:** Show data distribution
- **Pair Plots:** Explore correlations between metrics




Figure 17: Plot type selection with preview

### 6.3 Plot Settings

Customize plot appearance:

1. **Figure Size:** Set dimensions in inches
2. **Font Sizes:** Configure title, label, and tick fonts
3. **Color Scheme:** Choose from available color palettes
4. **DPI:** Set resolution for saved images




Figure 18: Plot customization settings

## 6.4 Running Analysis

1. Click **Run Analysis**
2. Monitor progress as plots are generated
3. Generated plots are saved to the `plots/` directory




Figure 19: Analysis progress with real-time logging

## 6.5 Viewing Generated Plots

After analysis completes:

- View plots directly in the web interface
- Access high-resolution versions in the `plots/` directory
- Download plots in PNG or PDF format

## 7 Regression Analysis

The regression module trains machine learning models to understand and predict network performance metrics.

### 7.1 Preparing Input Data

Regression analysis uses CSV files generated during the analysis phase:

1. Ensure analysis has been run to generate CSV output
2. The CSV files contain structured data suitable for ML training




Figure 20: Example 3D surface plot showing delivery ratio




Figure 21: Example heatmap visualization

## 7.2 Configuring Regression

1. Navigate to the **Regression** section
2. Select the **Input CSV File**
3. Choose **Target Variable(s)** to predict (e.g., delivery\_ratio, latency)
4. Select **Predictor Variables** (e.g., TTL, buffer\_size, num\_hosts)
5. Choose **ML Models** to train




Figure 22: Regression configuration panel

## 7.3 Available ML Models

OppNDA supports multiple regression algorithms:

- **Linear Regression:** Simple interpretable model
- **Ridge Regression:** L2 regularized linear model
- **Lasso Regression:** L1 regularized for feature selection
- **Random Forest:** Ensemble tree-based method
- **Gradient Boosting:** Sequential ensemble method
- **Support Vector Regression:** Kernel-based method

## 7.4 Multi-Target Regression

OppNDA supports training models on multiple target variables simultaneously:

1. Select multiple target variables from the dropdown
2. Models are trained independently for each target
3. Results are aggregated for comparison

## 7.5 Running Regression

1. Click **Run Regression**
2. Monitor training progress
3. View model performance metrics ( $R^2$ , RMSE, MAE)




Figure 23: Regression training progress

## 7.6 Interpreting Results

The regression results panel displays:

- Model performance comparison table
- Feature importance rankings
- Actual vs. predicted scatter plots
- Cross-validation scores

### Tip

Use feature importance to identify which simulation parameters have the greatest impact on network performance metrics. This can guide future simulation parameter selection.

## 8 Conclusion

This tutorial has covered the complete OppNDA workflow from installation through regression analysis. Key takeaways:

1. **Flexible Installation:** Choose between scripts, manual setup, or Docker
2. **Intuitive Configuration:** Web-based GUI simplifies ONE simulator setup




Figure 24: Regression results and model comparison

3. **Config Import:** Easily import and modify existing configuration files
4. **Integrated Execution:** Run simulations and monitor in real-time
5. **Automated Post-Processing:** Seamless averaging and visualization
6. **Advanced Analytics:** ML-based regression for performance insights

## 8.1 Tips for Advanced Usage

- Use the performance optimization settings to handle large datasets
- Leverage the dynamic memory management for parallel processing
- Customize plot styles through the analysis configuration JSON
- Export configurations for reproducible experiments

## 8.2 Further Resources

- OppNDA Documentation: <https://oppnda.readthedocs.io>
- ONE Simulator: <https://github.com/akeranen/the-one>
- GitHub Repository: <https://github.com/nafisshahriar/oppnda>