



Network Fundamentals for Cloud

BITS Pilani
Pilani Campus

Nishit Narang WILPD-CSIS



CC ZG503: Network Fundamentals for Cloud Lecture No. 6: Transport Layer Fundamentals + SDN





BITS Pilani Pilani Campus


Fundamentals of Networking: Transport Layer Concepts

Slides Source: Computer Networking: A Top-Down Approach, 8th edition, Jim Kurose, Keith Ross, Pearson, 2020

All material copyright 1996-2020 J.F Kurose and K.W. Ross, All Rights Reserved


Transport services and protocols

- provide logical communication between application processes running on different hosts
- transport protocols actions in end systems:
 - sender: breaks application messages into segments, passes to network layer
 - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
 - TCP, UDP



Two principal Internet transport protocols

- TCP: Transmission Control Protocol
 - reliable, in-order delivery
 - congestion control
 - flow control
 - connection setup
- UDP: User Datagram Protocol
 - unreliable, unordered delivery
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees



UDP: User Datagram Protocol

- "no frills," "bare bones"
 Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others


Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
 - UDP can blast away as fast as desired!
 - can function in the face of congestion

UDP: User Datagram Protocol

- UDP use:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
 - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
 - add needed reliability at application layer
 - add congestion control at application layer

UDP: Transport Layer Actions



UDP: Transport Layer Actions


SNMP client

application
transport
(UDP)
network (IP)
link
physical

UDP sender actions:


- is passed an applicationlayer message
- determines UDP segment header fields values
- creates UDP segment
- passes segment to IP

SNMP server



UDP: Transport Layer Actions


SNMP client



UDP receiver actions:

- receives segment from IP
- checks UDP checksum header value
- extracts application-layer message
- demultiplexes message up to application via socket

SNMP server




TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size

- cumulative ACKs
- pipelining:
 - TCP congestion and flow control set window size
- connection-oriented:
 - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure



TCP sequence numbers, ACKs

Sequence numbers:


 byte stream "number" of first byte in segment's data

Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-oforder segments

 <u>A:</u> TCP spec doesn't say, - up to implementor



TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss


Q: how to estimate RTT?

- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT


TCP round trip time, timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT


- <u>exponential</u> <u>weighted</u> <u>moving</u> <u>average</u> (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125




TCP: retransmission scenarios



TCP: retransmission scenarios




Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack


Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?






Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers





flow control: # bytes receiver willing to accept

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?


-flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

application process Application removing data from TCP socket **buffers** TCP socket receiver buffers **TCP** code code from sender

receiver protocol stack

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow




TCP receiver-side buffering

TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
Socket clientSocket =
  newSocket("hostname", "port number");
```

```
application

connection state: ESTAB
connection Variables:
seq # client-to-server
server-to-client
rcvBuffer size
at server, client

network
```

```
Socket connectionSocket =
welcomeSocket.accept();
```

TCP 3-way handshake

Client state

serverSocket.listen(1) clientSocket = socket(AF_INET, SOCK_STREAM) connectionSocket, addr = serverSocket.accept() LISTEN LISTEN clientSocket.connect((serverName, serverPort) choose init seq num, x send TCP SYN msq **SYNSFNT** SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK SYN RCVD msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live

Server state


serverSocket = socket(AF INET, SOCK_STREAM)

serverSocket.bind(('', serverPort))

ESTAB

Transport Layer: 3-25

A human 3-way handshake protocol



Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver

Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols




TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

increase sending rate by 1 maximum segment size every RTT until loss detected

<u>Multiplicative Decrease</u> cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

Transport Layer: 3-30