



New to Gradio? Start here: Getting Started

See the Release History

← Label

LoginButton →

LinePlot

 $gradio.LinePlot(\cdots)$

Description

Create a line plot.

Behavior

As input: this component does *not* accept input.

As output: expects a pandas dataframe with the data to plot.

Initialization

Parameter	Description
value pd.DataFrame Callable None default: None	The pandas dataframe containing the data to display in a scatter plot.
x str None default: None	Column corresponding to the x axis.
y str None default: None	Column corresponding to the y axis.

imeter	Description
color	The column to determine the point color. If the column contains
str None	numeric data, gradio will interpolate the column data so that
default: None	small values correspond to light colors and large values
	correspond to dark values.
stroke_dash	The column to determine the symbol used to draw the line, e.g.
str None	dashed lines, dashed lines with points.
default: None	
overlay_point	Whether to draw a point on the line for each (x, y) coordinate
bool None	pair.
default: None	
title	The title to display on top of the chart.
str None	
default: None	
tooltip	The column (or list of columns) to display on the tooltip when a
list[str] str None	user hovers a point on the plot.
default: None	
x_title	The title given to the x axis. By default, uses the value of the x
str None	parameter.
default: None	
y_title	The title given to the y axis. By default, uses the value of the y
str None	parameter.
default: None	
x_label_angle	The angle for the x axis labels. Positive values are clockwise, and
float None	negative values are counter-clockwise.
default: None	

imeter	Description
y_label_angle float None default: None	The angle for the y axis labels. Positive values are clockwise, and negative values are counter-clockwise.
color_legend_title str None default: None	The title given to the color legend. By default, uses the value of color parameter.
<pre>stroke_dash_legend_title str None default: None</pre>	The title given to the stroke_dash legend. By default, uses the value of the stroke_dash parameter.
color_legend_position Literal[('left', 'right', 'top', 'bottom', 'top- left', 'top-right', 'bottom-left', 'bottom- right', 'none')] None default: None	The position of the color legend. If the string value 'none' is passed, this legend is omitted. For other valid position values see: https://vega.github.io/vega/docs/legends/#orientation.
stroke_dash_legend_position Literal[('left', 'right', 'top', 'bottom', 'top- left', 'top-right', 'bottom-left', 'bottom- right', 'none')] None default: None	The position of the stoke_dash legend. If the string value 'none' is passed, this legend is omitted. For other valid position values see: https://vega.github.io/vega/docs/legends/#orientation.
height int str None default: None	The height of the plot, specified in pixels if a number is passed, o in CSS units if a string is passed.
width int str None default: None	The width of the plot, specified in pixels if a number is passed, or in CSS units if a string is passed.

= imeter	Description
x_lim list[int] None default: None	A tuple or list containing the limits for the x-axis, specified as [x_min, x_max].
y_lim list[int] None default: None	A tuple of list containing the limits for the y-axis, specified as [y_min, y_max].
caption str None default: None	The (optional) caption to display below the plot.
interactive bool None default: True	Whether users should be able to interact with the plot by panning or zooming with their mouse or trackpad.
label str None default: None	The (optional) label to display on the top left corner of the plot.
show_label bool None default: None	Whether the label should be displayed.
container bool default: True	
scale int None default: None	

_ imeter	Description
min_width	
int	
default: 160	
every	If value is a callable, run the function 'every' number of seconds
float None	while the client connection is open. Has no effect otherwise.
default: None	Queue must be enabled. The event can be accessed (e.g. to
	cancel it) via this component's .load_event attribute.
visible	Whether the plot should be visible.
bool	
default: True	
elem_id	An optional string that is assigned as the id of this component in
str None	the HTML DOM. Can be used for targeting CSS styles.
default: None	
elem_classes	An optional list of strings that are assigned as the classes of this
list[str] str None	component in the HTML DOM. Can be used for targeting CSS
default: None	styles.
render	If False, component will not render be rendered in the Blocks
bool	context. Should be used if the intention is to assign event
default: True	listeners now but render the component later.
show_actions_button	Whether to show the actions button on the top right corner of
bool	the plot.
default: False	
hortcuts	
Class	Interface String Shortcut Initialization

"lineplot"

Uses default values

gradio.LinePlot

```
line_plot
    live_dashboard

import gradio as gr
from vega_datasets import data

stocks = data.stocks()
gapminder = data.gapminder()
gapminder = gapminder.loc[
    gapminder.country.isin(["Argentina", "Australia", "Afghanistan"])

climate = data.climate()
seattle_weather = data.seattle_weather()
```

Event Listeners

Description

Event listeners allow you to capture and respond to user interactions with the UI components you've defined in a Gradio Blocks app. When a user interacts with an element, such as changing a slider value or uploading an image, a function is called.

Supported Event Listeners

The LinePlot component supports the following event listeners. Each event listener takes the same parameters, which are listed in the Event Arguments table below.

Listener	Description
gradio.LinePlot.change(fn, ···)	Triggered when the value of the Plot changes either because of user input (e.g. a user types in a textbox) OR because of a function update (e.g. an image receives a value from the output of an event trigger). See .input() for a listener that is only triggered by user input.
gradio.LinePlot.clear(fn, ···)	This listener is triggered when the user clears the Plot using the X button for the component.

Parameter	Description
fn Callable None Literal['decorator'] default: "decorator"	the function to call when this event is triggered. Often a machine learning model's prediction function. Each parameter of the function corresponds to one input component, and the function should return a single value or a tuple of values, with each element in the tuple corresponding to one output component.
<pre>inputs Component list[Component] set[Component] None default: None</pre>	List of gradio.components to use as inputs. If the function takes no inputs, this should be an empty list.
outputs Component list[Component] None default: None	List of gradio.components to use as outputs. If the function returns no outputs, this should be an empty list.
api_name str None Literal[False] default: None	defines how the endpoint appears in the API docs. Can be a string, None, or False. If set to a string, the endpoint will be exposed in the API docs with the given name. If None (default), the name of the function will be used as the API endpoint. If False, the endpoint will not be exposed in the API docs and downstream apps (including those that gr.load this app) will not be able to use this event.
scroll_to_output bool default: False	If True, will scroll to output component on completion
show_progress	If True, will show progress animation while pending

Literal[('full', 'minimal', 'hidden')]

default: "full"

Parameter	Description
queue bool None default: None	If True, will place the request on the queue, if the queue has been enabled. If False, will not put this event on the queue, even if the queue has been enabled. If None, will use the queue setting of the gradio app.
batch bool default: False	If True, then the function should process a batch of inputs, meaning that it should accept a list of input values for each parameter. The lists should be of equal length (and be up to length <code>max_batch_size</code>). The function is then <i>required</i> to return a tuple of lists (even if there is only 1 output component), with each list in the tuple corresponding to one output component.
<pre>int default: 4</pre>	Maximum number of inputs to batch together if this is called from the queue (only relevant if batch=True)
preprocess bool default: True	If False, will not run preprocessing of component data before running 'fn' (e.g. leaving it as a base64 string if this method is called with the <code>Image</code> component).
postprocess bool default: True	If False, will not run postprocessing of component data before returning 'fn' output to the browser.
cancels dict[str, Any] list[dict[str, Any]] None default: None	A list of other events to cancel when this listener is triggered. For example, setting cancels=[click_event] will cancel the click_event, where click_event is the return value of another components .click method. Functions that have not yet run

(or generators that are iterating) will be cancelled, but

functions that are currently running will be allowed to finish.

Parameter	Description
every float None default: None	Run this event 'every' number of seconds while the client connection is open. Interpreted in seconds. Queue must be enabled.
<pre>trigger_mode Literal[('once', 'multiple', 'always_last')] None default: None</pre>	If "once" (default for all events except .change()) would not allow any submissions while an event is pending. If set to "multiple", unlimited submissions are allowed while pending, and "always_last" (default for .change() event) would allow a second submission after the pending event is complete.
js str None default: None	Optional frontend js method to run before running 'fn'. Input arguments for js method are values of 'inputs' and 'outputs', return should be a list of values for output components.
<pre>concurrency_limit int None Literal['default'] default: "default"</pre>	If set, this is the maximum number of this event that can be running simultaneously. Can be set to None to mean no concurrency_limit (any number of this event can be running simultaneously). Set to "default" to use the default concurrency limit (defined by the default_concurrency_limit parameter in Blocks.queue(), which itself is 1 by default).
concurrency_id str None default: None	If set, this is the id of the concurrency group. Events with the same concurrency_id will be limited by the lowest set concurrency_limit.
show_api bool	whether to show this event in the "view API" page of the Gradio app, or in the ".view_api()" method of the Gradio

clients. Unlike setting api_name to False, LoginButton →

to False will still allow downstream apps to use this event. If

fn is None, show_api will automatically be set to False.
Status



← Label ult: True