

New to Gradio? Start here: **Getting Started**See the **Release History**

← Plot ScatterPlot →

Radio

 $gradio.Radio(\cdots)$

Description

Creates a set of (string or numeric type) radio buttons of which only one can be selected.

Behavior


As input: passes the value of the selected radio button as a str or int or float or its index as an int into the function, depending on type.

As output: expects a str or int or float corresponding to the value of the radio button to be selected.

Initialization

Parameter	Description
choices list[str int float tuple[str, str int float]] None default: None	A list of string or numeric options to select from. An option can also be a tuple of the form (name, value), where name is the displayed name of the radio button and value is the value to be passed to the function, or returned by the function.
value str int float Callable None default: None	The option selected by default. If None, no option is selected by default. If callable, the function will be called whenever the app loads to set the initial value of the component.
type str default: "value"	Type of value to be returned by component. "value" returns the string of the choice selected, "index" returns the index of the choice selected.

= imeter	Description
label str None default: None	The label for this component. Appears above the component and is also used as the header if there are a table of examples for this component. If None and used in a <code>gr.Interface</code> , the label will be the name of the parameter this component is assigned to.
info str None default: None	Additional component description.
every float None default: None	If value is a callable, run the function 'every' number of seconds while the client connection is open. Has no effect otherwise. Queue must be enabled. The event can be accessed (e.g. to cancel it) via this component's .load_event attribute.
show_label bool None default: None	if True, will display label.
container bool default: True	If True, will place the component in a container - providing some extra padding around the border.
scale int None default: None	Relative width compared to adjacent Components in a Row. For example, if Component A has scale=2, and Component B has scale=1, A will be twice as wide as B. Should be an integer.
min_width int default: 160	Minimum pixel width, will wrap if not sufficient screen space to satisfy this value. If a certain scale value results in this Component being narrower than min_width, the min_width parameter will be respected first.
interactive bool None default: None	If True, choices in this radio group will be selectable; if False, selection will be disabled. If not provided, this is inferred based on whether the component is used as an input or output.



Shortcuts

Class	Interface String Shortcut	Initialization
gradio.Radio	"radio"	Uses default values

Demos

```
import gradio as gr

def sentence_builder(quantity, animal, countries, place, activity_list, morning):
    return f"""The {quantity} {animal}s from {" and ".join(countries)} went to the {place}
    where they {" and ".join(activity_list)} until the {"morning" if morning else "night"}"""

demo = gr.Interface(
    sentence_builder,
```

Event Listeners

Description

Event listeners allow you to capture and respond to user interactions with the UI components you've defined in a Gradio Blocks app. When a user interacts with an element, such as changing a slider value or uploading an image, a function is called.

Supported Event Listeners

The Radio component supports the following event listeners. Each event listener takes the same parameters, which are listed in the Event Arguments table below.

Listener	Description
gradio.Radio.select(fn, ···)	Event listener for when the user selects or deselects the Radio. Uses event data gradio. SelectData to carry value referring to the label of the Radio, and selected to refer to state of the Radio. See EventData documentation on how to use this event data
gradio.Radio.change(fn, ···)	Triggered when the value of the Radio changes either because of user input (e.g. a user types in a textbox) OR because of a function update (e.g. an image receives a value from the output of an event trigger). See .input() for a listener that is only triggered by user input.
gradio.Radio.input(fn, ···)	This listener is triggered when the user changes the value of the Radio.

Event Arguments

Parameter	Description
fn	the function to call when this event is triggered. Often a
Callable None Literal['decorator']	machine learning model's prediction function. Each
default: "decorator"	parameter of the function corresponds to one input
	component, and the function should return a single value or
	a tuple of values, with each element in the tuple
	corresponding to one output component.

Parameter	Description
<pre>inputs Component list[Component] set[Component] None default: None</pre>	List of gradio.components to use as inputs. If the function takes no inputs, this should be an empty list.
outputs Component list[Component] None default: None	List of gradio.components to use as outputs. If the function returns no outputs, this should be an empty list.
api_name str None Literal[False] default: None	defines how the endpoint appears in the API docs. Can be a string, None, or False. If set to a string, the endpoint will be exposed in the API docs with the given name. If None (default), the name of the function will be used as the API endpoint. If False, the endpoint will not be exposed in the API docs and downstream apps (including those that gr.load this app) will not be able to use this event.
scroll_to_output bool default: False	If True, will scroll to output component on completion
show_progress Literal[('full', 'minimal', 'hidden')] default: "full"	If True, will show progress animation while pending
queue bool None default: None	If True, will place the request on the queue, if the queue has been enabled. If False, will not put this event on the queue, even if the queue has been enabled. If None, will use the

queue setting of the gradio app.

Parameter	Description
batch bool default: False	If True, then the function should process a batch of inputs, meaning that it should accept a list of input values for each parameter. The lists should be of equal length (and be up to length max_batch_size). The function is then <i>required</i> to return a tuple of lists (even if there is only 1 output component), with each list in the tuple corresponding to one output component.
<pre>max_batch_size int default: 4</pre>	Maximum number of inputs to batch together if this is called from the queue (only relevant if batch=True)
preprocess bool default: True	If False, will not run preprocessing of component data before running 'fn' (e.g. leaving it as a base64 string if this method is called with the <code>Image</code> component).
postprocess bool default: True	If False, will not run postprocessing of component data before returning 'fn' output to the browser.
cancels dict[str, Any] list[dict[str, Any]] None default: None	A list of other events to cancel when this listener is triggered. For example, setting cancels=[click_event] will cancel the click_event, where click_event is the return value of another components .click method. Functions that have not yet run (or generators that are iterating) will be cancelled, but functions that are currently running will be allowed to finish.
every float None	Run this event 'every' number of seconds while the client connection is open. Interpreted in seconds. Queue must be

enabled.

default: None

If set, this is the maximum number of this event that can be running simultaneously. Can be set to None to mean no concurrency_limit (any number of this event can be running simultaneously). Set to "default" to use the default concurrency limit (defined by the default concurrency limit) parameter in Blocks.queue (), which itself is 1 by default).

concurrency_id If set, this is the id of the concurrency group. Events with the same concurrency_id will be limited by the lowest set str | None default: None concurrency_limit.

> whether to show this event in the "view API" page of the Gradio app, or in the ".view_api()" method of the Gradio clients. Unlike setting api_name to False, setting show_api to False will still allow downstream apps to use this event. If fn is None, show_api will automatically be set to False.

ScatterPlot → ← Plot



show_api

default: True

bool

