## ${\bf QConnectBase}$

v. 1.1.0

Nguyen Huynh Tri Cuong

05.07.2022

## Contents

1	Intr	roduction	1
2	Des	scription	2
	2.1	Getting Started	2
	2.2	Usage	2
		2.2.1 connect	2
		2.2.2 disconnect	3
		2.2.3 send command	3
		2.2.4 <b>verify</b>	4
	2.3	Example	4
	2.4	Contribution Guidelines	5
	2.5	Configure Git and correct EOL handling	5
	2.6	Sourcecode Documentation	6
	2.7	Feedback	6
	2.8	About	6
		2.8.1 Maintainers	6
		2.8.2 Contributors	6
	2.9	License	6
3	in	$_{ m it}_{}.{ m py}$	7
	3.1	Class: ConnectionManager	7
4	con	$\operatorname{nection\_base.py}$	8
	4.1	Class: BrokenConnError	8
	4.2	Class: ConnectionBase	8
		4.2.1 Method: is_supported_platform	8
		4.2.2 Method: is_precondition_pass	8
		4.2.3 Method: error_instruction	8
		4.2.4 Method: quit	9
		4.2.5 Method: connect	9
		4.2.6 Method: disconnect	9
		4.2.7 Method: send_obj	9
		4.2.8 Method: read_obj	10
		4.2.9 Method: wait_4_trace	10
		4.2.10 Method: wait_4_trace_continuously	11
		4.2.11 Method: create_and_activate_trace_queue	11
		4.2.12 Method: deactivate_and_delete_trace_queue	12
		4.2.13 Method: activate_trace_queue	12

		4.2.14 Method: deactivate_trace_queue	13
		4.2.15 Method: check_timeout	13
		4.2.16 Method: pre_msg_check	13
		4.2.17 Method: post_msg_check	13
5		ection_manager.py	14
	5.1	Class: InputParam	
		5.1.1 Method: get_attr_list	
	5.2	Class: ConnectParam	
	5.3	Class: SendCommandParam	
	5.4	Class: VerifyParam	
	5.5	Class: ConnectionManager	
		5.5.1 Method: quit	15
		5.5.2 Method: add_connection	15
		5.5.3 Method: remove_connection	
		5.5.4 Method: get_connection_by_name	
		5.5.5 Method: disconnect	16
		5.5.6 Method: connect	16
		5.5.7 Method: connect_named_args	16
		5.5.8 Method: connect_unnamed_args	16
		5.5.9 Method: send_command	17
		5.5.10 Method: send_command_named_args	17
		5.5.11 Method: send_command_unnamed_args	17
		5.5.12 Method: verify	18
		5.5.13 Method: verify_named_args	18
		$5.5.14$ Method: verify_unnamed_args	18
	5.6	Class: TestOption	19
c		eants.py	20
6	6.1	Class: SocketType	20
	6.2	Class: String	20
	0.2	Olass: String	20
7	qlog	ger.py	21
	7.1	Class: ColorFormatter	21
		7.1.1 Method: format	21
	7.2	Class: QFileHandler	21
		7.2.1 Method: get_log_path	21
		7.2.2 Method: get_config_supported	22
	7.3	Class: QDefaultFileHandler	22
		7.3.1 Method: get_log_path	22
		7.3.2 Method: get_config_supported	22
	7.4	Class: QConsoleHandler	22
		7.4.1 Method: get_config_supported	23
	7.5	Class: QLogger	23
		7.5.1 Method: get_logger	23
		7.5.2 Method: set_handler	

8	seria	al_base	e <b>.py</b>	<b>24</b>
	8.1	Class:	SerialConfig	24
	8.2	Class:	SerialSocket	24
		8.2.1	Method: connect	24
		8.2.2	Method: disconnect	24
		8.2.3	Method: quit	24
	8.3	Class:	SerialClient	25
		8.3.1	Method: connect	25
0		<b>.</b>		26
9		Class.	RawTCPBase	26 26
			RawTCPServer	
			RawTCPClient	26 26
	9.5	Class:	Raw I CP Cheft	20
<b>10</b>	$ssh_{-}$	client.	py	27
	10.1	Class:	AuthenticationType	27
	10.2	Class:	SSHConfig	27
	10.3	Class:	SSHClient	27
		10.3.1	Method: close	27
		10.3.2	Method: quit	27
	ı 1			20
11	_	base.p		28 28
			TCPConfig	28 28
	11.2		Method: close	28 28
			Method: quit	28 28
			Method: connect	28 28
			Method: disconnect	29
	11 9			
	11.3		TCPBaseServer	29
			Method: accept_connection	29 29
			Method: disconnect	
	11 /		TCPBaseClient	29 29
	11.4		Method: connect	29 29
			Method: disconnect	29
		11.4.2	Wethod: disconnect	29
<b>12</b>	utils	s.py		30
	12.1	Class:	Singleton	30
	12.2	Class:	DictToClass	30
		12.2.1	Method: validate	30
	12.3	Class:	Utils	30
		12.3.1	Method: get_all_descendant_classes	30
		12.3.2	Method: get_all_sub_classes	31
		12.3.3	Method: is_valid_host	31
		12.3.4	Method: execute_command	31
		12.3.5	Method: kill_process	31
		12.3.6	Method: caller_name	31

4 History	34
3 Appendix	33
12.6.3 Method: create_from_string	32
12.6.2 Method: get_data	32
12.6.1 Method: get_json	32
12.6 Class: ResponseMessage	32
12.5 Class: ResultType	32
12.4.2 Method: run	32
12.4.1 Method: stop	32
12.4 Class: Job	32
12.3.8 Method: is_ascii_or_unicode	32
12.3.7 Method: load_library	31

## Introduction

QConnectBaseLibrary is a connection testing library for RobotFramework. Library will be supported to downloaded from PyPI soon. It provides a mechanism to handle trace log continuously receiving from a connection (such as Raw TCP, SSH, Serial, etc.) besides sending data back to the other side. It's especially efficient for monitoring the overflood response trace log from an asynchronous trace systems. It is supporting Python 3.7+ and RobotFramework 3.2+.

## Description

QConnectBase

### 2.1 Getting Started

We have a plan to publish all the sourcecode as OSS in the near future so that you can downloaded from PyPI. For the current period, you can checkout

### **QConnectBaseLibrary**

After checking out the source completely, you can install by running below command inside **robotframework-quencet-base** directory.

python setup.py install

### 2.2 Usage

QConnectBase Library support following keywords for testing connection in RobotFramework.

### 2.2.1 connect

Use for establishing a connection.

### Syntax:

```
connect [conn_name] [conn_type] [conn_mode] [conn_conf] (All parame-
ters are required to be in order) or
connect conn_name=[conn_name] conn_type=[conn_type] conn_mode=[conn_mode]
conn_conf=[conn_conf] (All parameters are assigned by name)
```

### **Arguments**:

conn\_name: Name of the connection.

**conn\_type**: Type of the connection. QConnectBaseLibrary has supported below connection types:

- TCPIPClient: Create a Raw TCPIP connection to TCP Server.
- SSHClient: Create a client connection to a SSH server.
- SerialClient: Create a client connection via Serial Port.

conn\_mode: (unused) Mode of a connection type.

**conn\_conf**: Configurations for making a connection. Depend on **conn\_type** (Type of Connection), there is a suitable configuration in JSON format as below.

• TCPIPClient

#### • SSHClient

#### • SerialClient

```
"port" : [comport or null],
    "baudrate" : [Baud rate such as 9600 or 115200 etc.],
    "bytesize" : [Number of data bits. Possible values: 5, 6, 7, 8],
    "stopbits" : [Number of stop bits. Possible values: 1, 1.5, 2],
    "parity" : [Enable parity checking. Possible values: 'N', \( \to \) 'E', 'O', 'M', 'S'],
    "rtscts" : [Enable hardware (RTS/CTS) flow control.],
    "xonxoff" : [Enable software flow control.],
    "logfile": [Log file path. Possible values: 'nonlog', \( \to \) \( \to \) 'console', [user define path] ]
}
```

### 2.2.2 disconnect

Use for disconnect a connection by name.

Syntax:

disconnect conn\_name

**Arguments**:

conn\_name: Name of the connection.

#### 2.2.3 send command

Use for sending a command to the other side of connection.

Syntax:

```
send command [conn_name] [command] (All parameters are required to be in order) or
send command conn_name=[conn_name] command=[command] (All parameters are
assigned by name)
```

#### **Arguments**:

**conn\_name**: Name of the connection. **command**: Command to be sent.

### 2.2.4 verify

Use for verifying a response from the connection if it matched a pattern. Syntax:

```
verify [conn_name] [search_pattern] [timeout] [fetch_block] [eob_pattern]
[filter_pattern] [send_cmd] (All parameters are required to be in order) or
verify conn_name=[conn_name] search_pattern=[search_pattern] timeout=[timeout]
fetch_block=[fetch_block] eob_pattern=[eob_pattern] filter_pattern=[filter_pattern]
send_cmd=[send_cmd] (All parameters are assigned by name)
```

### **Arguments**:

**conn\_name**: Name of the connection.

search\_pattern: Regular expression for matching with the response.

timeout: Timeout for waiting response matching pattern.

**fetch\_block**: If this value is true, every response line will be put into a block untill a line match **eob\_pattern** pattern.

eob\_pattern: Regular expression for matching the endline when using fetch\_block.

filter\_pattern: Regular expression for filtering every line of block when using fetch\_block. send\_cmd: Command to be sent to the other side of connection and waiting for response.

#### Return value:

A corresponding match object if it is found. E.g.

- \${result}[0] will be "This is the 1st test command." which is the matched string.
- \${result}[1] will be "1st" which is the first captured string.
- \${result}[2] will be "command" which is the second captured string.

### 2.3 Example

```
*** Settings ***
Documentation Suite description
Library
        QConnectBase.ConnectionManager
*** Test Cases ***
Test SSH Connection
   # Create config for connection.
   ${config_string}= catenate
   ... {
        "address": "127.0.0.1",
   . . .
        "port": 8022,
   . . .
         "username": "root",
   . . .
         "password": "",
   . . .
         "authentication": "password",
   . . .
        "key_filename": null
   . . .
    . . .
   json.loads('''${config_string}''')
   ${config}=
                        evaluate
                                                                         json
   # Connect to the target with above configurations.
                    conn name=test ssh
   connect
                     conn_type=SSHClient
                     conn_conf=${config}
   # Send command 'cd ..' and 'ls' then wait for the response '.*' pattern.
   send command
                     conn_name=test_ssh
```

```
$\{\text{res}\}= \text{verify} & \text{conn_name=test_ssh} \\
\text{...} & \text{search_pattern=.*} \\
\text{log to console} & \{\text{res}\}

# Disconnect \\
\text{disconnect test_ssh}
```

Listing 2.1: Robot code example

### 2.4 Contribution Guidelines

QConnectBaseLibrary is designed for ease of making an extension library. By that way you can take advantage of the QConnectBaseLibrary's infrastructure for handling your own connection protocal. For creating an extension library for QConnectBaseLibrary, please following below steps.

- 1. Create a library package which have the prefix name is **robotframework-qconnect-**[your specific name].
- 2. Your hadling connection class should be derived from QConnectionLibrary.connection\_base.ConnectionBase class.
- 3. In your Connection Class, override below attributes and methods:
  - \_CONNECTION\_TYPE: name of your connection type. It will be the input of the conn\_type argument when using connect keyword. Depend on the type name, the library will determine the correct connection handling class.
  - \_\_init\_\_(self, \_mode, config): in this constructor method, you should:
    - Prepare resource for your connection.
    - Initialize receiver thread by calling self.\_init\_thread\_receiver(cls.\_socket\_instance, mode=""") method.
    - Configure and initialize the lowlevel receiver thread (if it's necessary) as below self.\_llrecv\_thrd\_obj = None self.\_llrecv\_thrd\_term = threading.Event() self.\_init\_thrd\_llrecv(cls.\_socket\_instance)
    - Incase you use the lowlevel receiver thread. You should implement the **thrd\_llrecv\_from\_connection\_interface** method. This method is a mediate layer which will receive the data from connection at the very beginning, do some process then put them in a queue for the **receiver thread** above getting later.
    - Create the queue for this connection (use Queue.Queue).
  - connect(): implement the way you use to make your own connection protocol.
  - \_read(): implement the way to receive data from connection.
  - \_write(): implement the way to send data via connection.
  - disconnect(): implement the way you use to disconnect your own connection protocol.
  - quit(): implement the way you use to quit connection and clean resource.

## 2.5 Configure Git and correct EOL handling

Here you can find the references for Dealing with line endings.

Every time you press return on your keyboard you're actually inserting an invisible character called a line ending. Historically, different operating systems have handled line endings differently. When you view changes in a file, Git handles line endings in its own way. Since you're collaborating on projects with Git and GitHub, Git might produce unexpected results if, for example, you're working on a Windows machine, and your collaborator has made a change in OS X.

To avoid problems in your diffs, you can configure Git to properly handle line endings. If you are storing the .gitattributes file directly inside of your repository, than you can asure that all EOL are manged by git correctly as defined.

### 2.6 Sourcecode Documentation

For investigating sourcecode, please refer to QConnectBase library documentation

### 2.7 Feedback

If you have any problem when using the library or think there is a better solution for any part of the library, I'd love to know it, as this will all help me to improve the library. Please don't hesitate to contact me.

Do share your valuable opinion, I appreciate your honest feedback!

### 2.8 About

### 2.8.1 Maintainers

Nguyen Huynh Tri Cuong

### 2.8.2 Contributors

Nguyen Huynh Tri Cuong Thomas Pollerspöck

### 2.9 License

Copyright 2020-2022 Robert Bosch GmbH

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

$$\_$$
init $\_$ .py

## 3.1 Class: ConnectionManager

QConnectBase.\_\_init\_\_

Class to manage all connections.

## connection\_base.py

### 4.1 Class: BrokenConnError

QConnectBase.connection\_base

### 4.2 Class: ConnectionBase

QConnectBase.connection\_base

Base class for all connection classes.

### 4.2.1 Method: is\_supported\_platform

Check if current platform is supported.

### Returns:

```
/ Type: bool /
True if platform is supported.
False if platform is not supported.
```

### 4.2.2 Method: is\_precondition\_pass

Check for precondition.

### Returns:

```
/ Type: bool / True if passing the precondition. False if failing the precondition.
```

### 4.2.3 Method: error\_instruction

Get the error instruction.

### Returns:

```
/ Type: str /
Error instruction string.
```

### 4.2.4 Method: quit

>> This method MUST be overridden in derived class << Abstract method for quiting the connection.

### Arguments:

```
• is_disconnect_all
/ Condition: optional / Type: bool /
Determine if it's necessary to disconnect all connections.
```

### Returns:

(no returns)

### 4.2.5 Method: connect

>> This method MUST be overridden in derived class << Abstract method for quiting the connection.

### **Arguments:**

```
• device
/ Condition: required / Type: str /
Device name.
```

• files

```
/ Condition: optional / Type: list / Trace file list if using dlt connection.
```

test\_connection
 / Condition: optional / Type: bool /
 Deternmine if it's necessary for testing the connection.

### Returns:

(no returns)

### 4.2.6 Method: disconnect

>> This method MUST be overridden in derived class << Abstract method for disconnecting connection.

### Arguments:

```
• n_thrd_id
/ Condition: required / Type: int /
Thread id.
```

### Returns:

(no returns)

### 4.2.7 Method: send\_obj

Wrapper method to send message to a tcp connection.

### Arguments:

```
obj
/ Condition: required / Type: str /
Data to be sent.
cr
/ Condition: optional / Type: str /
Determine if it's necessary to add newline character at the end of command.
```

#### Returns:

(no returns)

### 4.2.8 Method: read\_obj

Wrapper method to get the response from connection.

#### Returns:

```
msg/ Type: str /Responded message.
```

### 4.2.9 Method: wait\_4\_trace

Suspend the control flow until a Trace message is received which matches to a specified regular expression.

#### Arguments:

```
• search_obj

/ Condition: required / Type: str /

Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.
```

• use\_fetch\_block / Condition: optional / Type: bool / Default: False /

Determine if 'fetch block' feature is used.

• end\_of\_block\_pattern
/ Condition: optional / Type: str / Default: '.\*' /
The end of block pattern.

• filter\_pattern
/ Condition: optional / Type: str / Default: '.\*' /

/ Condition: optional / Type: int / Default: 0 /

Pattern to filter message line by line.

• timeout

Timeout parameter specified as a floating point number in the unit 'seconds'.

• fct\_args
/ Condition: optional / Type: Tuple / Default: None /
List of function arguments passed to be sent.

### Returns:

match/ Type: re.Match /

If no trace message matched to the specified regular expression and a timeout occurred, return None.

If a trace message has matched to the specified regular expression, a match object is returned as the result. The complete trace message can be accessed by the 'string' attribute of the match object. For access to groups within the regular expression, use the group() method. For more information, refer to Python documentation for module 're'.

### 4.2.10 Method: wait\_4\_trace\_continuously

Getting trace log continuously without creating a new trace queue.

### **Arguments:**

```
trace_queue
/ Condition: required / Type: Queue /
Queue to store the traces.
timeout
/ Condition: optional / Type: int / Default: 0 /
Timeout for waiting a matched log.
fct_args
/ Condition: optional / Type: Tuple / Default: None /
Arguments to be sent to connection.
```

#### Returns:

• None
/ Type: None /

If no trace message matched to the specified regular expression and a timeout occurred.

• match

```
/ Type: re.Match /
```

If a trace message has matched to the specified regular expression, a match object is returned as the result. The complete trace message can be accessed by the 'string' attribute of the match object. For access to groups within the regular expression, use the group() method. For more information, refer to Python documentation for module 're'.

### 4.2.11 Method: create\_and\_activate\_trace\_queue

Create Queue and assign it to \_trace\_queue object and activate the queue with the search element.

### Arguments:

• search\_element

```
/ Condition: required / Type: str /
```

Regular expression all received trace messages are compare to.

Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.#

• use\_fetch\_block

```
/ Condition: optional / Type: bool / Default: False /
```

Determine if 'fetch block' feature is used.

• end\_of\_block\_pattern

```
/ Condition: optional / Type: str / Default: '.*' /
```

The end of block pattern.

• regex\_line\_filter\_pattern

```
/ Condition: optional / Type: re.Pattern / Default: None /
```

Regular expression object to filter message line by line.

### Returns:

trq\_handle, trace\_queue
 / Type: tuple /
 The handle and search object

#### 4.2.12Method: deactivate\_and\_delete\_trace\_queue

Deactivate trace queue and delete.

### **Arguments:**

```
• trq_handle
  / Condition: required / Type: int /
  Trace queue handle.
• trace_queue
  / Condition: required / Type: Queue /
  Trace queue object.
```

### Returns:

(no returns)

#### Method: activate\_trace\_queue 4.2.13

Activates a trace message filter specified as a regular expression. All matching trace messages are put in the specified queue object.

### Arguments:

• search\_obj / Condition: required / Type: str /

Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.

• trace\_queue

```
/ Condition: required / Type: Queue /
```

A queue object all trace message which matches the regular expression are put in. The using application must assure, that the queue is emptied or deleted.

• use\_fetch\_block

```
/ Condition: optional / Type: bool / Default: False /
```

Determine if 'fetch block' feature is used.

• end\_of\_block\_pattern

```
/ Condition: optional / Type: str / Default: '.*' /
```

The end of block pattern.

• line\_filter\_pattern

```
/ Condition: optional / Type: re.Pattern / Default: None /
```

Regular expression object to filter message line by line.

### Returns:

• handle\_id / Type: int / Handle to deactivate the message filter.

### 4.2.14 Method: deactivate\_trace\_queue

Deactivates a trace message filter previously activated by ActivateTraceQ() method.

### **Arguments:**

handle
 / Condition: required / Type: int /
 Integer object returned by ActivateTraceQ() method.

### Returns:

```
* is_success

/ Type: bool / . False : No trace message filter active with the specified handle (i.e. handle is not in use).

True : Trace message filter successfully deleted.
```

### 4.2.15 Method: check\_timeout

>> This method will be override in derived class <<

Check if responded message come in cls.\_RESPOND\_TIMEOUT or we will raise a timeout event.

### Arguments:

```
• timeout
/ Condition: required / Type: int /
Timeout in seconds.
```

#### Returns:

(no returns)

### 4.2.16 Method: pre\_msg\_check

>> This method will be override in derived class <<

Pre-checking message when receiving it from connection.

### **Arguments:**

```
    msg
    / Condition: required / Type: str /
    Received message to be checked.
```

#### Returns:

```
(no returns)
```

### 4.2.17 Method: post\_msg\_check

>> This method will be override in derived class <<

Post-checking message when receiving it from connection.

### Arguments:

```
    msg
    / Condition: required / Type: str /
    Received message to be checked.
```

### Returns:

```
(no returns)
```

## connection\_manager.py

## 5.1 Class: InputParam

QConnectBase.connection\_manager

5.1.1 Method: get\_attr\_list

### 5.2 Class: ConnectParam

QConnectBase.connection\_manager

Class for storing parameters for connect action.

### 5.3 Class: SendCommandParam

QConnectBase.connection\_manager

Class for storing parameters for send command action.

## 5.4 Class: VerifyParam

QConnectBase.connection\_manager

Class for storing parameters for verify action.

## 5.5 Class: ConnectionManager

QConnectBase.connection\_manager

Class to manage all connections.

### 5.5.1 Method: quit

Quit connection manager.

### Returns:

(no returns)

### 5.5.2 Method: add\_connection

Add a connection to managed dictionary.

### **Arguments:**

```
name
/ Condition: required / Type: str /
Connection's name.
conn
/ Condition: required / Type: socket.socket /
Connection object.
```

### Returns:

(no returns)

### 5.5.3 Method: remove\_connection

Remove a connection by name.

### Arguments:

```
• connection_name
/ Condition: required / Type: str /
Connection's name.
```

### Returns:

(no returns)

### 5.5.4 Method: get\_connection\_by\_name

Get an exist connection by name.

#### **Arguments:**

```
    connection_name
    / Condition: required / Type: str /
    Connection's name.
```

### Returns:

• conn
/ Type: socket.socket /
Connection object.

### 5.5.5 Method: disconnect

Keyword for disconnecting a connection by name.

### **Arguments:**

```
    connection_name
    / Condition: required / Type: str /
    Connection's name.
```

### Returns:

(no returns)

### 5.5.6 Method: connect

Keyword for making a connection.

Keyword Arguments.

### Arguments:

• args

(refer to connect\_unnamed\_args method for details)

```
/ Condition: required / Type: tuple /
Non-Keyword Arguments.
• kwargs
/ Condition: required / Type: dict /
```

#### Returns:

(no returns)

### 5.5.7 Method: connect\_named\_args

Making a connection with name arguments.

### Arguments:

```
(refer to connect_unnamed_args method for details)
```

```
• kwargs
/ Condition: required / Type: dict /
Keyword Arguments.
```

### Returns:

(no returns)

### 5.5.8 Method: connect\_unnamed\_args

Making a connection.

### **Arguments:**

```
• connection_name
/ Condition: required / Type: str /
Name of connection.
```

```
connection_type/ Condition: required / Type: str /Type of connection.
```

```
mode
/ Condition: required / Type: str /
Connection mode.
config
/ Condition: required / Type: json /
Configuration for connection.
```

#### Returns:

(no returns)

#### 5.5.9 Method: send\_command

Keyword for sending command to a connection.

### Arguments:

(refer to send\_unnamed\_args method for details)

```
args
/ Condition: require / Type: tuple /
Non-Keyword Arguments.
kwargs
/ Condition: require / Type: dict /
```

Keyword Arguments.

### Returns:

(no returns)

### 5.5.10 Method: send\_command\_named\_args

Send command to a connection with name arguments.

### Arguments:

```
(refer to send_unnamed_args method for details)
```

```
• kwargs
/ Condition: required / Type: dict /
Keyword Arguments.
```

#### Returns:

(no returns)

### 5.5.11 Method: send\_command\_unnamed\_args

Send command to a connection.

### Arguments:

```
    connection_name
        / Condition: required / Type: str /
        Name of connection.
    command
        / Condition: required / Type: str /
        Command to be sent.
```

### Returns:

(no returns)

### 5.5.12 Method: verify

Keyword uses to verify a pattern from connection response after sending a command.

### **Arguments:**

(refer to verify\_unnamed\_args method for details)

```
args
/ Condition: required / Type: tuple /
Non-Keyword Arguments.
kwargs
/ Condition: required / Type: dict /
Keyword Arguments.
```

#### Returns:

```
match_res/ Type: str /Matched string.
```

### 5.5.13 Method: verify\_named\_args

Verify a pattern from connection response after sending a command with named arguments.

#### **Arguments:**

(refer to verify\_unnamed\_args method for details)

```
• kwargs
/ Condition: required / Type: dict /
Keyword Arguments.
```

### Returns:

```
match_res/ Type: str /Matched string.
```

### 5.5.14 Method: verify\_unnamed\_args

Verify a pattern from connection response after sending a command.

### Arguments:

```
    connection_name
        / Condition: required / Type: str /
        Name of connection.
    search_obj
        / Condition: required / Type: str /
        Description of the provided forms of the pr
```

Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.

```
    fetch_block
    / Condition: optional / Type: bool / Default: False /
    Determine if 'fetch block' feature is used.
```

```
    eob_pattern
        / Condition: optional / Type: str / Default: '.*' /
        The end of block pattern.
    filter_pattern
        / Condition: optional / Type: str / Default: '.*' /
        Pattern to filter message line by line.
    timeout
        / Condition: optional / Type: float / Default: 0 /
        Timeout parameter specified as a floating point number in the unit 'seconds'.
    fct_args
        / Condition: optional / Type: Tuple / Default: None /
        List of function arguments passed to be sent.
```

### Returns:

match\_res/ Type: str /Matched string.

## 5.6 Class: TestOption

QConnectBase.connection\_manager

## constants.py

## 6.1 Class: SocketType

QConnectBase.constants

## 6.2 Class: String

QConnectBase.constants

## qlogger.py

### 7.1 Class: ColorFormatter

```
QConnectBase.qlogger
```

Custom formatter class for setting log color.

### 7.1.1 Method: format

Set the color format for the log.

### Arguments:

```
• record / Condition: required / Type: str / Log record.
```

### Returns:

```
/ Type: logging.Formatter / Log with color formatter.
```

## 7.2 Class: QFileHandler

```
QConnectBase.qlogger
```

Handler class for user defined file in config.

### 7.2.1 Method: get\_log\_path

Get the log file path for this handler.

### **Arguments:**

```
• config
/ Condition: required / Type: DictToClass /
Connection configurations.
```

### Returns:

```
/ Type: str / Log file path.
```

### 7.2.2 Method: get\_config\_supported

Check if the connection config is supported by this handler.

### Arguments:

```
    config
        / Condition: required / Type: DictToClass /
        Connection configurations.
```

### Returns:

```
/ Type: bool /
True if the config is supported.
False if the config is not supported.
```

### 7.3 Class: QDefaultFileHandler

```
QConnectBase.qlogger
```

Handler class for default log file path.

### 7.3.1 Method: get\_log\_path

Get the log file path for this handler.

### Arguments:

```
• logger_name
/ Condition: required / Type: str /
Name of the logger.
```

### Returns:

```
/ Type: str / Log file path.
```

### 7.3.2 Method: get\_config\_supported

Check if the connection config is supported by this handler.

### Arguments:

```
• config / Condition: required / Type: DictToClass / Connection configurations.
```

### Returns:

```
/ Type: bool /
True if the config is supported.
False if the config is not supported.
```

## 7.4 Class: QConsoleHandler

```
QConnectBase.qlogger
```

Handler class for console log.

### 7.4.1 Method: get\_config\_supported

Check if the connection config is supported by this handler.

### Arguments:

```
    config
        / Condition: required / Type: DictToClass /
        Connection configurations.
```

### Returns:

```
/ Type: bool /
True if the config is supported.
False if the config is not supported.
```

### 7.5 Class: QLogger

```
QConnectBase.qlogger
```

Logger class for QConnect Libraries.

### 7.5.1 Method: get\_logger

Get the logger object.

### **Arguments:**

```
• logger_name
/ Condition: required / Type: str /
Name of the logger.
```

#### Returns:

```
• logger
/ Type: Logger /
Logger object. .
```

### 7.5.2 Method: set\_handler

Set handler for logger.

### Arguments:

```
    config
        / Condition: required / Type: DictToClass /
        Connection configurations.
```

### Returns:

handler\_ins
 / Type: logging.handler /
 None if no handler is set.
 Handler object.

# serial\_base.py

## 8.1 Class: SerialConfig

```
QConnectBase.serialclient.serial_base
```

Class to store the configuration for Serial connection.

### 8.2 Class: SerialSocket

```
QConnectBase.serialclient.serial_base
```

Class for handling serial connection.

### 8.2.1 Method: connect

Connect to serial port.

### Returns:

 $(no\ returns)$ 

### 8.2.2 Method: disconnect

Disconnect serial port.

### **Arguments:**

```
_device/ Condition: required / Type: str /Unused
```

### Returns:

(no returns)

### 8.2.3 Method: quit

Quit serial connection.

### Returns:

(no returns)

## 8.3 Class: SerialClient

QConnectBase.serialclient.serial\_base

Serial client class.

### 8.3.1 Method: connect

Connect to the Serial port.

### Returns:

 $(no\ returns)$ 

## raw\_tcp.py

### 9.1 Class: RawTCPBase

QConnectBase.tcp/raw.raw\_tcp

Base class for a raw tcp connection.

### 9.2 Class: RawTCPServer

QConnectBase.tcp/raw.raw\_tcp

Class for a raw tcp connection server.

### 9.3 Class: RawTCPClient

QConnectBase.tcp/raw.raw\_tcp

Class for a raw tcp connection client.

## ssh\_client.py

## 10.1 Class: AuthenticationType

QConnectBase.tcp/ssh.ssh\_client

## 10.2 Class: SSHConfig

QConnectBase.tcp/ssh.ssh\_client

Class to store the configuration for SSH connection.

### 10.3 Class: SSHClient

QConnectBase.tcp/ssh.ssh\_client

SSH client connection class. Method: connect -----

Implementation for creating a SSH connection.

Returns:

(no returns)

### 10.3.1 Method: close

Close SSH connection.

Returns:

(no returns)

### 10.3.2 Method: quit

Quit and stop receiver thread.

Returns:

(no returns)

## tcp\_base.py

## 11.1 Class: TCPConfig

```
QConnectBase.tcp.tcp_base
```

Class to store configurations for TCP connection.

### 11.2 Class: TCPBase

QConnectBase.tcp.tcp\_base

Base class for a tcp connection.

### 11.2.1 Method: close

Close connection.

### Returns:

(no returns)

### 11.2.2 Method: quit

Quit connection.

### **Arguments:**

• is\_disconnect\_all / Condition: required / Type: bool /

Determine if it's necessary for disconnect all connection.

### Returns:

(no returns)

### 11.2.3 Method: connect

>> Should be override in derived class.

Establish the connection.

#### Returns:

(no returns)

### 11.2.4 Method: disconnect

>> Should be override in derived class.

Disconnect the connection.

### Returns:

(no returns)

### 11.3 Class: TCPBaseServer

QConnectBase.tcp.tcp\_base

Base class for TCP server.

### 11.3.1 Method: accept\_connection

Wrapper method for handling accept action of TCP Server.

### Returns:

 $(no\ returns)$ 

11.3.2 Method: connect

11.3.3 Method: disconnect

### 11.4 Class: TCPBaseClient

QConnectBase.tcp.tcp\_base

Base class for TCP client.

### 11.4.1 Method: connect

### 11.4.2 Method: disconnect

## utils.py

## 12.1 Class: Singleton

QConnectBase.utils

Class to implement Singleton Design Pattern. This class is used to derive the TTFisClientReal as only a single instance of this class is allowed.

Disabled pyLint Messages: R0903: Too few public methods (%s/%s) Used when class has too few public methods, so be sure it's really worth it.

This base class implements the Singleton Design Pattern required for the TTFisClientReal. Adding further methods does not make sense.

### 12.2 Class: DictToClass

QConnectBase.utils

Class for converting dictionary to class object.

### 12.2.1 Method: validate

### 12.3 Class: Utils

QConnectBase.utils

Class to implement utilities for supporting development.

### 12.3.1 Method: get\_all\_descendant\_classes

Get all descendant classes of a class

**Arguments:** cls: Input class for finding descendants.

#### Returns:

/ Type: list /

Array of descendant classes.

### 12.3.2 Method: get\_all\_sub\_classes

Get all children classes of a class

### **Arguments:**

```
• cls
/ Condition: required / Type: class /
Input class for finding children.
```

#### Returns:

```
/ Type: list /
Array of children classes.
```

- 12.3.3 Method: is\_valid\_host
- 12.3.4 Method: execute\_command
- 12.3.5 Method: kill\_process
- 12.3.6 Method: caller\_name

Get a name of a caller in the format module.class.method

### Arguments:

```
• skip / Condition: required / Type: int /
```

Specifies how many levels of stack to skip while getting caller name. skip=1 means "who calls me", skip=2 "who calls my caller" etc.

#### Returns:

```
/ Type: str / An empty string is returned if skipped levels exceed stack height
```

### 12.3.7 Method: load\_library

Load native library depend on the calling convention.

### Arguments:

```
• path
/ Condition: required / Type: str /
Library path.
```

• is\_stdcall

```
/ Condition: optional / Type: bool / Default: True /
```

Determine if the library's calling convention is stdcall or cdecl.

### Returns:

Loaded library object.

### 12.3.8 Method: is\_ascii\_or\_unicode

Check if the string is ascii or unicode

Arguments: str\_check: string for checking codecs: encoding type list

#### Returns:

/ Type: bool /

True : if checked string is ascii or unicode False : if checked string is not ascii or unicode

### 12.4 Class: Job

QConnectBase.utils

12.4.1 Method: stop

12.4.2 Method: run

### 12.5 Class: ResultType

QConnectBase.utils

Result Types.

## 12.6 Class: ResponseMessage

QConnectBase.utils

Response message class

### 12.6.1 Method: get\_json

Convert response message to json

Returns:

Response message in json format

### 12.6.2 Method: get\_data

Get string data result

Returns:

 $String\ result$ 

### 12.6.3 Method: create\_from\_string

# Appendix

### About this package:

Table 13.1: Package setup

Setup parameter	Value
Name	QConnectBase
Version	1.1.0
Date	05.07.2022
Description	Robot Framework test library for TCP, SSH, serial connection
Package URL	robotframework-qconnect-base
Author	Nguyen Huynh Tri Cuong
Email	cuong.nguyenhuynhtri@vn.bosch.com
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

# History

1.1.0	07/2022
Initial version	

 ${\bf QConnectBase.pdf}$ 

Created at 31.08.2022 - 16:03:50 by GenPackageDoc v. 0.28.0