

# Εθνικό Μετσόβιο Πολυτεχνείο

Σχολή Ηλεκτρολόγων Μηχανικών και Μηχανικών Υπολογιστών Τομέας Τεχνολογίας Πληροφορικής και Υπολογιστών

# Formally Verified Tag-Based Enforcement of Control Flow Integrity

Διπλωματική Εργασία

του

Νίκου Γιανναράκη

Επιβλέπων: Κωστής Σαγώνας

Αν. Καθηγητής Ε.Μ.Π.

Εργαστήριο Τεχνολογίας Λογισμικού Αθήνα, Σεπτέμβριος 2014



Εθνικό Μετσόβιο Πολυτεχνείο Σχολή Ηλεκτρολόγων Μηχανικών και Μηχανικών Υπολογιστών Τομέας Τεχνολογίας Πληροφορικής και Υπολογιστών Εργαστήριο Τεχνολογίας Λογισμικού

# Formally Verified Tag-Based Enforcement of Control Flow Integrity

# Διπλωματική Εργασία

TOI

Νίκου Γιανναράκη

Επιβλέπων: Κωστής Σαγώνας

Αν. Καθηγητής Ε.Μ.Π.

Εγκρίθηκε από την τριμελή εξεταστική επιτροπή την  $11^{\eta}$  Σεπτεμβρίου, 2014.

Κωστής Σαγώνας Νικόλαος Παπασπύρου Ιώαννης Σμαραγδάκης

Αν. Καθηγητής Ε.Μ.Π. Αν. Καθηγητής Ε.Μ.Π. Αν. Καθηγητής Ε.Μ.Π.

Copyright © – All rights reserved Nick Giannarakis, 2014. Με επιφύλαξη παντός δικαιώματος.

Απαγορεύεται η αντιγραφή, αποθήκευση και διανομή της παρούσας εργασίας, εξ ολοκλήρου ή τμήματος αυτής, για εμπορικό σκοπό. Επιτρέπεται η ανατύπωση, αποθήκευση και διανομή για σκοπό μη κερδοσκοπικό, εκπαιδευτικής ή ερευνητικής φύσης, υπό την προϋπόθεση να αναφέρεται η πηγή προέλευσης και να διατηρείται το παρόν μήνυμα. Ερωτήματα που αφορούν τη χρήση της εργασίας για κερδοσκοπικό σκοπό πρέπει να απευθύνονται προς τον συγγραφέα.

Οι απόψεις και τα συμπεράσματα που περιέχονται σε αυτό το έγγραφο εκφράζουν τον συγγραφέα και δεν πρέπει να ερμηνευθεί ότι αντιπροσωπεύουν τις επίσημες θέσεις του Εθνικού Μετσόβιου Πολυτεχνείου.

The purpose of this diploma thesis is to present a novel, hardware-assisted, formally verified implementation of low-level security policies, such as Control-Flow Integrity and Call Stack Protection. Contrary to existing

## Keywords

concolic testing, Erlang, software testing, dynamic symbolic execution, SMT solving

# Ευχαριστίες

Θα ήθελα να ευχαριστήσω τον Κωστή Σαγώνα για την καθοδήγησή του, την υπομονή του και την πίστη του σε εμένα. Σε μια περίεργη περίοδο της ακαδημαϊκής μου πορείας, η εμπιστοσύνη που μου έδειξε αποτέλεσε το σημαντικότερο κίνητρό μου.

Επίσης θα ήθελα να ευχαριστήσω τον Νίκο Παπασπύρου, καταρχάς για την πολύτιμη βοήθεια του, αλλά πολύ περισσότερο για το ότι αποτελεί τον βασικό λόγο για τον οποίο ασχολήθηκα με την Πληροφορική. Η διδασκαλία του και το ήθος του ήταν και συνεχίζουν να είναι έμπνευση για εμένα.

Ευχαριστώ την οικογένειά μου που με έκανε τον άνθρωπο που είμαι σήμερα.

Τέλος, ευχαριστώ την Μαιρούλα μου για την στήριξη της όλα αυτά τα χρόνια. Σε ευχαριστώ που είσαι εσύ και που με κάνεις καλύτερο!

Άγγελος Γιάντσιος

# Contents

				5
Eυ	χαρι	στίες		7
Co	onten	ıts		10
Lis	st of	Figure	es	11
1	Intr	oducti	on	13
	1.1	Motiva	ation	13
	1.2	Thesis	Outline	14
2	Mic	ro-poli	cies: Verified, Hardware-Assisted Monitors	15
	2.1	Micro-	Policies	15
	2.2	Examp	ole: Non-Writable Code & Non-Executable Data	16
	2.3	Generi	c Verification Framework for Micro-Policies	17
		2.3.1	Correctness of micro-policies	17
		2.3.2	Symbolic Machine	18
	2.4	A Prog	grammable Unit for Metadata Processing	20
		2.4.1	Hardware Architecture	20
		2.4.2	Concrete Machine Modeling PUMP Architecture	21
		2.4.3	Concrete Policy Monitor	22
3	Con	trol-Fl	low Integrity	23
	3.1	Relate	d Work	23
		3.1.1	Balancing between performance and security	23
		3.1.2	Coarse-grained CFI Micro-Policy	24

		3.1.3	Formal verification of Control-Flow Integrity	25
	3.2	Fine-G	Frained Control-Flow Integrity Micro-Policy	25
4	Form	nally \	Verified Control-Flow Integrity Micro-Policy	27
	4.1	Repres	senting control-flow graphs	27
	4.2	Contro	ol-Flow Integrity Property	28
	4.3	The A	bstract Machine	30
		4.3.1	Operational semantics	30
		4.3.2	Attacker model	31
		4.3.3	Allowed control-flows for the abstract machine	31
		4.3.4	Stopping predicate for the abstract machine	32
		4.3.5	CFI proof for the Abstract Machine	32
	4.4	The Sy	ymbolic Machine	33
		4.4.1	Transfer Function	34
		4.4.2	Attacker model	35
		4.4.3	Allowed control-flows for the Symbolic Machine	35
		4.4.4	Initial states of the Symbolic Machine	35
		4.4.5	Stopping predicate for the Symbolic Machine	37
	4.5	Conclu	asion	38
	4.6	Future	Work	38
		4.6.1	Call-Stack Protection/ XFI	38
Bi	bliog	graphy		39
A	Stu	ff		41
	A.1	Contro	ol-Flow Integrity Micro-Policy	42

# List of Figures

2.1	Rules enforcing NWC and NXD	16
2.2	Stepping relation for the symbolic machine	19
2.3	Concrete step rules for Store instruction	21
3.1	Rules enforcing fine-grained CFI, NXD and NWC	24
3.2	Rules enforcing fine-grained CFI, NXD and NWC	26
4.1	Interface of node identifiers	28
4.2	Function on ids representing the set of allowed jumps	28
4.3	Function on words representing the set of allowed jumps	28
4.4	Step relation definition	29
4.5	Interface of a cfi_machine	29
4.8	Step rule for Store instruction of abstract machine	30
4.9	Step rule for Jump and Jal instruction of abstract machine	31
4.10	Step rule for monitor services of abstract machine	31
4.11	Attacker model for the abstract machine	31
4.12	Allowed control-flows for instructions of the abstract machine	32
4.15	Coq definition of Symbolic tags	34
4.16	Transfer function for symbolic machine in Gallina	34
4.17	Attacker capabilities	35
4.18	Attacker model for the Symbolic machine	35
4.19	Allowed control-flows for instructions of the symbolic machine	36
4.23	Initial symbolic states predicate	37
4 24	Symbolic invariants preservation	37

## Chapter 1

# Introduction

#### 1.1 Motivation

Computer hardware and software continuously grow in size and complexity and as a result ensuring the absence of exploitable behaviors is becoming increasingly difficult. In the era when (Feedback: where?) computer systems are used extensively to carry important information (e.g. credit card numbers, national security documents), it has been widely accepted that security of these systems is a priority. Researchers have identified a number of potential vulnerabilities which arise from the violation of known but in-practice unenforceable safety and security policies.

So far, computer security has been delegated mostly to software, while the hardware is being almost completely controlled by the software. High-level languages are becoming more widely used, due to features such as strong type systems with type inference and automatic memory management, making programming less error prone and reducing the number of exploitable bugs. Furthermore, in order to strengthen the security of computing systems a variety of low-level mitigation techniques (TODO: reference some? stack canaries, ASLR,  $W \oplus X$ ) have been proposed, however these are mostly ad-hoc solutions designed to prevent specific known attacks, rather than enforcing a security policy by preventing a well-defined class of attacks, thus making it hard to reason about their effectiveness. In fact most of these mitigation techniques can be circumvented by attackers, (TODO: reference; Overcoming CFI; Eternal War in Memory) which has lead to a continuous "chase" between attackers and security researchers.

One common attack technique is to exploit some low-level vulnerability such as a buffer overflow to redirect the control flow to attacker injected code. This attack can be stopped by a simple protection scheme known as  $W \oplus X$ , which enforces that a memory page is either executable or writable but not both. Unfortunately, clever attack techniques can bypass  $W \oplus X$ . In particular, attackers have been using code-reuse attacks (e.g. return/jump - oriented programming) that allows them to chain together existing pieces of code to achieve malicious behavior without directly introducing new code. Abadi et al. [1] introduced a property called Control Flow Integrity (CFI), which provides effective protection against control-flow hijacking attacks. CFI enforces that any execution of a program will respect a statically computed control flow graph (CFG). (Feedback: missing references throughout)

The main contribution of this thesis is the formalization and verification of a dynamic monitor for CFI, based on a generic hardware-software security mechanism. We provide a precise attacker model and prove in Coq that the monitor enforces a variant of the CFI

property proposed by Abadi *et al.* [1]. To obtain this result we prove refinement between a concrete machine running a monitor satisfying our Coq specification and an abstract machine having CFI by construction. We conclude the proof using a novel generic result stating that under certain assumptions CFI is preserved by refinement. (Feedback: Is there anything missing here?)

#### 1.2 Thesis Outline

Map 1. Intro 2a. Safety and Security Policies 2b. Micropolicies 3. CFI description 4. CFI formalization 5. Conclusions and Future work 6. Related work

Chapter 2 of this thesis briefly describes the basic requirements a security policy must satisfy and puts into context the framework we utilize in order to formalize and enforce a Control-Flow Integrity (CFI) policy. Chapter 3 discusses the current state of research on Control-Flow Integrity and clarifies our goals and contributions to it. Chapter 4 describes in detail the design of a fine-grained CFI policy and how we used the framework from Chapter 2 in order to enforce the policy and formally reason about it's security properties. Chapter 5.. conclusions, future work? Chapter 6.. related work and bibliography? Appendix with code and/or step relations etc.?

## Chapter 2

# Micro-policies: Verified, Hardware-Assisted Monitors

Currently the hardware provides very limited security mechanisms (TODO: name some; 4 protection rings, page-level memory protection via virtual memory), leaving most of the work to the software. This requires that the software performs various sanity-checks during an execution and that it carefully maintains various safety and security invariants, a tedious and error-prone task that results in high runtime performance overheads.

Many potentially effective mitigation techniques are not deployed because of the performance overhead they incur. Another requirement for deployment of a protection mechanism is the compatibility with existing executables and the degree of intervention required by a human. Usually even making slight changes to a code and redistributing has high cost and the protection mechanism is likely to see very low adoption.

The lack of efficient and effective generic ways to enforce security policies, forces programmers to protect their own code, a task which is not trivial even for the small and simply programs. As a result most, if not all, software carries weaknesses which can be exploited by an attacker. "Safe" languages, automate some of the checks required and eases the work of the programmer, for example by implementing array bounds checking or by disallowing pointer-arithmetic. However these solutions only reduce the chance of introducing exploitable bugs in a program and do not enforce stricter, more effective policies such as Control Flow Integrity or complete Memory Safety (spatial/temporal protection for heap and stack). In addition, we still need effective and efficient protection mechanisms for a plethora of software written in unsafe languages such as C.

#### 2.1 Micro-Policies

(Feedback: More text introducing micro-policies: instruction-level security monitoring mechanisms based on fine-grained metadata tags (PUMP is just a way of implementing this efficiently))

(Feedback: Can the main idea of the CFI micro-policy be introduced here already? See grant proposal.)

A wide range of security policies can be enforced by associating metadata to the data being processed (e.g., this is an instruction, this is from the network, this is private, etc.), propagating the metadata as instructions are executed and using a set of rules on the metadata to check whether a policy is violated and how the tags should be propagated.

Abstractly, these rules form a partial function from a set of input tags to a set of output

tags

$$(opcode, tag_{pc}, tag_{instr}, tag_{arg1}, tag_{arg2}, tag_{arg3}) \rightarrow (tag_{pc'}, tag_{result})$$

informally read as, "if the next instruction to be executed is opcode, the current tag of the program counter is  $pc_{tag}$ , the current tag on the instruction location is  $tag_{instr}$  and the tags on the operands of the instruction are  $tag_{arg1}, tag_{arg2}$  and  $tag_{arg3}$  then if execution of the instruction is allowed the tag on the program counter should be set to  $tag_{pc'}$  and any new data created by the instruction should be tagged  $tag_{result}$ ".

More specific, a micro-policy is made up of the following elements:

- 1. a set of *metadata tags* used to tag the contents of the memory and all the registers as well as the pc.
- 2. a transfer function that implements the checks on the tags and the tag propagation as described above.
- 3. a tagging scheme for the initial state of the machine.
- 4. for some micro-policies, a set of *monitor services* (i.e., privileged code) that can be invoked by user code.

Furthermore, as we will see in 2.4, a software-hardware mechanism that allows for implementation of micro-policies without sacrificing flexibility (in terms of the policies that can be enforced) has already been designed. Simulations and benchmarks show that the runtime overhead is very low compared to dedicated software solutions thus making it a realistic and appealing way to deploy a wide range of security policies in future computing systems.

### 2.2 Example: Non-Writable Code & Non-Executable Data

(CH: Make it clearer that this is informal and you will return to the formalization later on)

(CH: Symbolic vs concrete rules ... should introduce symbolic rules first, although this is a quite trivial example; ALT: write these as pseudo-Coq functions?)

(CH: Rename Instr to Code?)

Consider the set of tags  $\mathcal{T} = \{Data, Instr\}$ . If we initially tag all executable regions in memory as Instr and all non-executable as Data then we can enforce NWC by two rules of the form

$$\frac{Store: \{CI=Instr, MR=Data\} \rightarrow \{PC'=-, RES=Data\}}{opcode \not \in \{Store\}}$$
 (Rest) 
$$\frac{opcode \not \in \{Store\}}{opcode: \{CI=Instr\} \rightarrow \{PC'=-, RES=-\}}$$

Figure 2.1: Rules enforcing NWC and NXD

The dashes in the result vector, represent don't care values, meaning we will not use their values for anything, so any tag (usually a default tag set by the policy designer) can be used. Furthermore, we are omitting from the input vector the fields that are unused

by the transfer function. For this simply policy, the transfer function only uses the tag on the current instruction (CI) and in the case of a Store instruction the tag on the memory (MR), i.e., the tag on the memory location we are trying to write. Additionally, if no rule applies, execution of the instruction is disallowed. Informally the above rules can be read as "If the tag on the current instruction is Instr, then if the opcode of the instruction is Store, execution should be allowed only if the tag of the third operand is Data. In that case the tag on the new data on the memory should remain Data. If the opcode of the instruction is not Store, then it's allowed and the result tags are indifferent for the enforced policy."

#### 2.3 Generic Verification Framework for Micro-Policies

Unsurprisingly, designing a security policy, reasoning about it's effectiveness against potential attackers and encoding it as a micro-policy can become a complex task. Azevedo et al. [8] built a generic framework for defining micro-policies on top of a simple machine modeling a RISC processor augmented with the PUMP hardware (referred to as concrete machine), formalized this framework in Coq and used it to define and formally verify micro-policies for dynamic sealing, control-flow integrity, memory safety, compartmentalization and protecting the enforcement mechanism (monitor) itself.

The framework offers a high-level machine, called the symbolic machine, that abstracts away from unnecessary low-level implementation details and can be used as an interface to a concrete machine, simplifying the work of the micro-policy designer and allowing him to define and reason about a micro-policy using structured mathematical objects than low-level machine words.

In order to implement the micro-policy at the concrete machine level, one needs to additionally provide machine code that implements the transfer function, an encoding of tags to words and machine code for any monitor services that the micro-policy may use. The relation between the symbolic and the concrete machine is formally defined as a two-way refinement (forward and backward). This is a generic refinement proof, parameterized by the encoding of the symbolic tags to words and a proof of correctness of the monitor code for a micro-policy. The designer of a micro-policy can use this two-way refinement simply by providing these two parameters.

#### 2.3.1 Correctness of micro-policies

For each micro-policy an abstract machine which serves as a specification to the invariants the policy designer wants to enforce is defined. The abstract machine is "correct" by construction, meaning that it's designed to respect those invariants. Using the symbolic machine as an intermediate step to simplify the proofs, by proving a refinement between the symbolic and the abstract machine and by utilizing the the generic refinement between the symbolic and the concrete machine, we can prove a refinement between the abstract and the concrete machine, thus showing that every valid step for the concrete machine is also a valid step for the abstract machine.

All the machines introduced in the original paper by Azevedo et al. [8], as well as this thesis, have a similar structure. In particular, they share a common RISC-based instruction set (with a few - uninteresting for the scope of this thesis - exceptions) and they have a fixed number of general-purpose registers, along with a pc register. Of course the abstract machine defined by the policy designer can differ in various ways, but more similarities with the symbolic machine implies easier proofs of correctness.

(Feedback: Introduce the (names of the) various machines and how they relate to each-other. Nice diagram?)

(TODO: Write instruction set)

#### 2.3.2 Symbolic Machine

As mentioned above, the symbolic machine enables us to abstract away from various low-level details of the concrete machine. We can express and reason about policies in terms of mathematical objects written in Gallina rather than machine code and the corresponding proofs for the concrete machine comes for free under some assumptions. In essence, the symbolic machine is parameterized by a micro-policy as it was defined in 2.1, with the addition of an internal state that can be used by monitor services.

The states of the symbolic machine consists of the memory, the registers, the pc register and the internal state. The memory and register contents, as well as the pc, are all tagged with a symbolic tag t. We name their contents  $symbolic \ atoms$  referred to with the notation w@t, where w is the value (word) and t is the tag.

At each step, a record named mvector is formed. It consists of the current opcode, the tag on the pc, the tag on the current instruction and optionally up to three tags depending on the opcode of the instruction. The mvector is passed to the transfer function which decides whether the step violated the policy enforced by the transfer function and in this case halts the machine, or if no violation occurred returns a tag for the new pc and a tag for any results the instruction execution produced.

We give, in form of inference rules, the stepping relation for the Symbolic machine, demonstrating how the transfer function and the tag propagation works at each step.

$$\begin{split} &mem[pc] = (\emptyset l_t) \quad decode \ i = Nop \\ &Nop : \{PC = l_{pc}, CI = l_t\} \rightarrow \{PC' = l'_{pc}, RES = -\} \\ &(mem, reg, pc@l_{pc}, int) \rightarrow (mem, reg, pc + 1@l'_{pc}, int) \\ &mem[pc] = i@l_t \quad decode \ i = Const \ n \quad reg[r] = w_ol_d@l_{cld} \\ &Const : \{PC = l_{pc}, CI = l_t, OP1 = l_{old}) \rightarrow \{PC' = l'_{pc}, RES = l_{res}\} \\ ®[ - reg[l' - n@l' res] \\ &(mem, reg, pc@l_{pc}, int) \rightarrow (mem, reg', pc + 1@l'_{pc}, int) \\ &mem[pc] = i@l_t \quad decode \ i = Mov \ r_p \ r_s \\ ®[r_p] = w_ol_p \\ ®[r_p] \\ ®[r_p] = w_ol_p \\ ®[r_p] = w_ol_p \\ ®[r_p] \\ ®[r_p] = w_ol_p \\ ®[r_p] = w_ol_p \\ ®[r_p] \\ ®[r_p] = w_ol_p \\ ®[r_p] \\ ®[r_p] = w_ol_p \\ ®[r_p] \\ &re$$

Figure 2.2: Stepping relation for the symbolic machine

Notice for example, that when a store instruction executed, the tag on the memory location to be overwritten is fetched, allowing the *transfer* function to know what kind of data we are trying to overwrite. Returning to the example micro-policy in 2.2 we can define the transfer function that is used by the symbolic machine as a Coq function.

(TODO: Actually define it - but wait for beautified coq code to kick in)

#### 2.4 A Programmable Unit for Metadata Processing

(CH: Could consider moving this one level up (turn it into chapter))

#### 2.4.1 Hardware Architecture

The Programmable Unit for Metadata Processing (PUMP) architecture [11] allows us to efficiently implement a wide range of micro-policies [10], using software to define the rules enforcing the policy, while the hardware provides efficiency by undertaking the propagation of the tags and a rules cache.

On the hardware level, the PUMP is an extension to a conventional RISC architecture. Every word of data in the machine - whether in memory or a register, is extended with a word-sized metadata tag. These tags are not interpreted by hardware, instead the interpretation of the tags is left to the software, thus making it easy to implement new policies on the metadata. Since tags are word-sized, they can be pointers to complex data-structures of tags, such as tuples of tags, allowing for complex policies to be expressed and multiple orthogonal policies to be enforced in parallel.

The hardware undertakes the correct propagation of tags from operands to results according to the rules defined by the software. A hardware rule cache mapping sets of input tags to sets of output tags is used for common case efficiency. On each instruction dispatch, in parallel with the usual behavior of an instruction (e.g., execution of an addition in the ALU), the hardware forms the set of input tags and a lookup is performed on the rule cache. If the lookup is successful a set of output tags is returned and combined with the results of the normal execution of the instruction a new state is produced. On the other hand, if the lookup failed, the hardware invokes a trusted piece of system software - the fault handler - which checks the input tags and decides whether the execution should be allowed or not. In the first case, the fault handler returns a set of result tags, a pair of set of input and output tags is formed and inserted into the rules cache, while the faulting instruction is restarted and will now hit the cache. Otherwise, execution of this instruction violated some rules of the enforced policy and execution should not continue normally (e.g., should be halted).

As described in the original PUMP paper by Dehon et al. [11] and in [10] a rich set of effective security policies can be efficiently implemented using the architecture mentioned above. In particular, implementations of dynamic typing, memory safety for heap-based data, control flow integrity and taint tracking are described, evaluated against a specific threat model and benchmarked. The benchmarks are done using a simulation of the described hardware and the two papers claim low overhead (3% on average) for each of the policies named above.

Compared to other software solutions for enforcing security policies, the PUMP offers significantly lower overhead, thanks to dedicated hardware assistance, while the fact that interpretation of the metadata is done by software offers flexibility with regard to the policies that can be implemented, compared to hardware solutions implementing a specific

policy.

While the PUMP offers flexibility at a low runtime performance overhead, there are more overheads associated to such a mechanism. For example adding metadata to all the data in the machine, would result in a 100% memory overhead. In addition, the extra hardware and the rule cache along with potentially larger memories could result into a 400% overhead on energy usage. [10] The authors claim that a careful and well-optimized implementation can reduce these numbers, resulting in a 50% energy overhead. (Feedback: use optimized numbers)

#### 2.4.2 Concrete Machine Modeling PUMP Architecture

The concrete machine is a model of the PUMP architecture, modeling a RISC machine with a rules *cache* and the software *miss handler*. The instruction set has been extended with four additional instructions that are meant to be used by monitor code only, a restriction that is enforced by the monitor self-protection micro-policy.

The state of the concrete machine consists of the memory, the registers, the pc register, the epcregister a special purpose register that holds the address of the faulting instruction after a cache miss and a rules cache. The cache works as a key-value store where a key is an input vector that contains an instruction opcode, the tag of the current instruction, the tag of the pc and up to three operand tags, and a value is an output vector which contain a tag for the new pc and a tag for any results from the execution of the instruction. In the context of the concrete machine a tag is the encoding into a word of a symbolic tag. Lifting this encoding relation to vectors, we get that a concrete vector is the encoding of a symbolic vector (mvector). Similar to the symbolic machine the contents of the memory, the registers, the pc and the epc are concrete atoms w@t where w is a word and t is the encoding of a tag into a word.

The stepping relation for the concrete machine is a bit more complicated than the one for the symbolic machine. In particular, on each step the machine forms the *input vector* and looks it up in the cache. If the lookup succeeds then the instruction is allowed, an *output vector* is returned by the cache and the next state is tagged according to it. If the lookup fails, then the *input vector* is saved in memory, the current pc is stored in epc and the machine traps to the *miss handler*. The above are demonstrated in the two example rules below:

```
\begin{split} mem[pc] &= i@t_i & decode \ i = Store \ r_p \ r_s \\ reg[r_p] &= w_p@t_p \quad reg[r_s] = w_s@t_s \quad mem[w_p] = w_{old}@t_{old} \\ cache \vdash (Store, t_{pc}, t_i, t_p, t_s, t_{old}) \mapsto (t'_{pc}, t'_d) \\ & \underline{mem' = mem[w_p \leftarrow w_s@t'_d]} \\ \hline (mem, reg, pc@t_{pc}, epc, cache) \rightarrow (mem', reg, (pc+1)@t'_{pc}, epc, cache)} \end{split} \tag{Store})
\frac{mem[pc] = i@t_i \quad decode \ i = Store \ r_p \ r_s}{reg[r_p] = w_p@t_p \quad reg[r_s] = w_s@t_s \quad mem[w_p] = w_{old}@t_{old}} \\ cache \vdash (Store, t_{pc}, t_i, t_p, t_s, t_{old}) \not\mapsto \\ mem' = mem[0..5 \leftarrow (Store, t_{pc}, t_i, t_p, t_s, t_{old})] \\ \hline (mem, reg, pc@t_{pc}, epc, cache) \rightarrow (mem', reg, trapaddr@Monitor, pc@t_{pc}, cache) \\ (Store-Miss) \end{split}
```

Figure 2.3: Concrete step rules for Store instruction

Addresses 0 to 5 are used to store the *input vector* and 6 to 7 are used by the miss handler to store the *output vector*. As a side-note, cache eviction is not modeled (an infinite cache is assumed).

#### 2.4.3 Concrete Policy Monitor

Unlike the symbolic machine, where the user cannot cannot change the *transfer* function, enforcing a micro-policy on the concrete machine requires that we are able to protect the memory of the policy monitor and that privileged instructions are not executed by user code. This self-protection policy can be easily composed with another micro-policy and enforced by the infrastructure described above.

Using tags of the form, *User st*, *Entry st*, *Monitor* we can distinguish between user memory, monitor memory and monitor services. In particular *User st* is used to tag a user-level atom, where *st* is the word-encoding of a symbolic tag. *Monitor* is used to tag the monitor memory and a few reserved registers. The *pc* is tagged with *Monitor* when a monitor execution takes place and *User st* when user-code is executed. The tag *Entry st* is used to tag the first instruction of a monitor service and serves as an indication that execution will continue under the privileged *Monitor* mode.

The miss handler is a composed policy monitor that protects itself from *User* code and that enforces a desired micro-policy. One important thing to note is that the miss handler for the concrete machine can take an arbitrary number of steps before deciding that no violation occurred and returning to *User* mode, unlike the symbolic *transfer* function that does not need to take any steps.

## Chapter 3

# Control-Flow Integrity

Restricting the control-flow of a program in some way is a technique widely spread among security researchers. For example non-executable data (NXD) can be considered as a form of (very) coarse-grained CFI where control-flow is not allowed to reach any memory region that holds non-executable data. Other mitigation techniques such as protecting return addresses on the stack enforce a form of coarse-grained CFI.

Moreover it is common that security properties are enforced dynamically by code that is statically injected to the program (e.g., Inlined Reference Monitors (IRM) [12] follow that approach), thus some form of *CFI* is required in order to ensure that these checks are not circumvented.

(TODO: Think about title)

#### 3.1 Related Work

#### 3.1.1 Balancing between performance and security

Abadi et al. first proposed a technique to enforce CFI based on IRMs. In particular, they proposed to mark all valid targets of *indirect* control transfers with a unique identifier and inject checks before all indirect jumps (including return instructions). However they assume that any two destinations are equivalent, in the sense that they share the same identifier, if the CFG contains edges from the same set of sources, which may significantly reduce the precision of the CFG. The authors also note that a 2-ID approach where one identifier is used for calls and another for returns could provide adequate security in many cases.

The work of Abadi *et al.* sparked interest of researchers who tried to improve some of the weaknesses of the initial implementation, usually by choosing between performance against precision and vice-versa.

Bletsch et al. [4] followed the work of Abadi et al., but changed their checking mechanism to perform the check after the control flow transfer has occurred which, as the authors claim, reduced the cache pressure and resulted in better performance. Precision remains the same with the implementation of Abadi et al..

Zhang et al. [21] proposed Compact Control Flow Integrity and Randomization (CC-FIR), a new efficient way to enforce coarse-grained CFI. CCFIR collects all valid targets of indirect control-transfers and stores them in a random order, in a protected section called "Springboard section". Indirect control-transfers are only allowed to addresses that are in the Springboard. Their implementation uses a 3-ID approach where one identifier is used

for calls and the two other identifiers are for returns, separating them between returns to sensitive and non-sensitive functions. Their implementation also supports interaction between protected and un-protected modules, which makes it an attractive solution to coarse-grained CFI.

The above techniques are evaluated in [13] where the authors demonstrate code-reuse attacks against binaries protected by coarse-grained CFI. These attacks illustrate the need for fine-grained CFI which however incurs a high runtime-overhead penalty making deployment of such a mechanism unlikely.

Standard assumptions for effective CFI Most -if not all- CFI implementations also come with a set of assumptions under which CFI holds. Two standard assumptions for all mechanisms that attempt to enforce CFI are:

- Non-Executable Data (NXD), a security mechanism that disallows execution of data.
- Non-Writable Code (*NWC*). Changing the code of a program would allow an attacker to circumvent dynamic checks.

Both assumptions are fairly standard for modern computers and are enforced through hardware or software. In some cases NXD can be lifted, but additional security risks and complexity is not worth the minor advantages offered by such an action.

Many implementations that attempt to do fine-grained *CFI* also require that identifiers used to mark nodes in the CFG are unique.

#### 3.1.2 Coarse-grained CFI Micro-Policy

#### (CH: consider moving to appendix, or related work section)

We can use the PUMP to implement the coarse-grained CFI mechanisms described earlier. Suppose we want to implement 1-ID CFI, we tag all indirect flow destinations and sources with a tag Marked and the rest of the instructions as Unmarked. Executing instructions that are sources of indirect flows, propagates their instruction tag to the pc. We then have to check that the tag on the destination matches the tag on the tag on the pc.

$$egin{aligned} op \in \{ \mathit{Jump}, \mathit{Jal} \} \ op : \{ \mathit{CI=Marked} \} &
ightarrow \{ \mathit{PC'=Marked}, \mathit{RES=-} \} \end{aligned}$$

$$\frac{op \not\in \{\textit{Jump}, \textit{Jal}\}}{op: \{\textit{PC=Marked}, \textit{CI=Marked}\} \rightarrow \{\textit{PC'=Unmarked}, \textit{RES=-}\}} \quad \text{(Check)}$$

$$\frac{\textit{op} \not\in \{\textit{Jump}, \textit{Jal}\}}{\textit{op}: \{\textit{PC} = \textit{Unmarked}, \textit{CI} = \textit{Unmarked}\} \rightarrow \{\textit{PC'} = \textit{Unmarked}, \textit{RES} = -\}} \text{ (NoCheck)}$$

Figure 3.1: Rules enforcing fine-grained CFI, NXD and NWC

Rule *Mark* is used in the case the opcode is Jump or Jal (the only indirect jumps in the RISC machine we examine) and propagates the *Marked* tag on the tag of the new *pc*. Rule *Check* applies when the tag on the *pc* is set to *Marked* and corresponds to a legal destination and rule *NoCheck* corresponds to any instruction that is not a jump source or target.

We do not further study this coarse-grained approach as we consider it ineffective since attacks against it has already been demonstrated in [13]. Instead we are going to focus on implementing and formalizing a fine-grained *CFI* micro-policy.

#### 3.1.3 Formal verification of Control-Flow Integrity

In [2] Abadi et al. extended their original paper, with -among other things- a more detailed formal study of CFI. Their formalization regarded a much simpler machine than the x86 omitting all the complexity in modern systems. The machine has a few instructions, a separate data memory and instruction memory which by the operational semantics of the machine are non-executable and non-writable (enforcing NXD and NWC by construction), and a small set of registers. Moreover, their attacker model permits arbitrary changes to the data memory, arbitrary changes to all the registers but a few distinguished ones that are used during the dynamic checks and no changes to the instruction memory. The authors proof that under some assumptions CFI is preserved for every step even in the presence of an attacker as powerful as the one described above. Their formal study served as a guideline for the implementation, but as it is done on paper their proofs cannot be machine checked. Furthermore, their formalization omits less interesting but important details such as instruction encoding and decoding which as shown in [15] are far from trivial for the x86.

Machine-checked formal verification efforts include [22], which is a SFI formalization for the ARM architecture that also enforces CFI. Their formalization was developed using the HOL theorem prover and a program logic framework they created. However their benchmarks report a 240% runtime overhead. The authors of [7] claim partial proofs for a CFI enforcement mechanism focused on the kernel of an operating system. Their runtime overhead can also reach 100%.

#### 3.2 Fine-Grained Control-Flow Integrity Micro-Policy

The PUMP hardware allows us to avoid taking the difficult decision between performance and security. As shown in [10], we can enforce a *fine-grained CFI* policy with an average runtime overhead of less than 3% (maximum overhead of less than 10%), on the SPEC2006 benchmarks

(CH: Shrink and polish this) In our design, we take the standard approach and claim CFI under NXD and NWC(CH: make it clear that we ENFORCE NXD and NWC). We considered designs that lifted these assumptions but we rejected them, for the time being, as there did not seem to be any considerable advantage i.e., compatibility with self-modifying programs, JIT compilers, etc. Allowing the code of the program to change, would in practice require for the CFG to change as well, which unless done in a controlled, "safe" way, would invalidate the enforcement of CFI. However, we do not have to rely on special hardware or software to enforce NXD and NWC. We can achieve this easily and efficiently by creating a separate (CH: could be separate, but we include it into the CFI one) micro-policy.

The micro-policy we implemented and studied is a composition of a fine-grained *CFI* micro-policy and the *NWC*, *NXD* micro-policies explained above.

Our approach uses unique identifiers to tag the contents of the memory that correspond to sources and potential destinations of indirect flows according to a binary relation (on the identifiers)  $\mathcal{CFG}$ .

Consider the set of tags  $\mathcal{T} = \{Data, Instr\ id, Instr\ id, Instr\ id\$ is a unique identifier (i.e., used to tag the contents of only one location in the memory). (CH: maybe add more intuition: for instance, we can choose identifiers to be the addresses at which the instructions are stored + example (POPL)) Adapting the rules from 2.2, we shall use Data to tag all contents in memory that are considered non-executable data,  $Instr\ id$  to tag all contents in memory that are considered executable instructions and are sources or targets of indirect control flows and  $Instr\ \bot$  to tag all other instructions. The rules to enforce NWC and NXD are intuitively the same and only change to account for the splitting of the Instr tag.

We follow the same idea as with coarse-grained CFI, propagating the instruction tag of instructions that are sources of indirect flows to the tag on the pc of the next state and upon execution of the next instruction, checking that the tag on the pc and on the instruction are in some relation. In the case of coarse-grained CFI we required that they match but for fine-grained CFI we require that they are in the CFG relation.

$$\begin{array}{c} op \in \{Jump, Jal\} & (src, dst) \in \mathcal{CFG} \\ \hline op : \{PC = Instr \ src, CI = Instr \ dst\} \rightarrow \{PC' = Instr \ dst, RES = -\} \end{array} (\mathsf{FLow/Check}) \\ \hline \\ op \in \{Jump, Jal\} \\ \hline op : \{PC = Data, CI = Instr \ dst\} \rightarrow \{PC' = Instr \ dst, RES = -\} \end{array} (\mathsf{FLow/NoCheck}) \\ \hline \\ \frac{(src, dst) \in \mathcal{CFG}}{Store : \{PC = Instr \ src, CI = Instr \ dst, MR = Data\} \rightarrow \{PC' = Data, RES = Data\} \\ (STORE/CHECK) \\ \hline \\ \frac{ti \in \{Instr \ dst, Instr \ \bot\}}{Store : \{PC = Data, CI = ti, MR = Data\} \rightarrow \{PC' = Data, RES = Data\} \\ (STORE/NoCheck) \\ \hline \\ \frac{opcode \not\in \{Jump, Jal, Store\} \quad (src, dst) \in \mathcal{CFG}}{opcode : \{PC = Instr \ src, CI = Instr \ dst\} \rightarrow \{PC' = Data, RES = -\}} \end{aligned} (\mathsf{REST/Check}) \\ \\ \frac{opcode \not\in \{Jump, Jal, Store\} \quad ti \in \{Instr \ dst, Instr \ \bot\}}{opcode : \{PC = Data, CI = ti\} \rightarrow \{PC' = Data, RES = -\}} \end{aligned} (\mathsf{REST/NoCheck})$$

Figure 3.2: Rules enforcing fine-grained CFI, NXD and NWC

We note in the above rules that the tag on the pc is Data when no check for a control-flow violation is required and Instr src where src is some id, when an indirect flow instruction was executed and a check for a control-flow violation is required. An important observation is that the rules above allow for one control-flow violation to occur, but disallow the next step and therefore the machine will certainly halt after a violation.

If the PUMP hardware fetched the tag on the memory address the machine is jumping to and passed it as an argument to input vector, as it does in the case of a Store instruction, we would be able to enforce *CFI* with no violations at all. (TODO: It can't do that for efficiency reasons?)

## Chapter 4

# Formally Verified Control-Flow Integrity Micro-Policy

Using the micro-policies framework described in 2.3 we proved that the concrete machine instantiated with a CFI micro-policy like the one described in 3.2 simulates an abstract machine that has CFI by construction. We do this proof by using the symbolic machine as an intermediate step, to prove backwards simulation between the symbolic and the abstract machine and afterwards by leveraging the framework of section 2.3 we obtain a backwards refinement between the concrete and the abstract machine.

In addition, we provide an attacker model for all the machines used and we prove that a property capturing the notion of *CFI* holds even when the attacker tampers with the machine, similarly to what is proposed in [2], but adapted to the setting of our machines. We do this by first proving this property for the abstract machine and then by using a generic preservation theorem we developed we prove that this property is *preserved* by backwards refinement and thus transferring the property to the symbolic and consequently to the concrete machine.

## 4.1 Representing control-flow graphs

Our approach for enforcing CFI, as explained in 3.2, requires that we encode the nodes in the control-flow graph in terms of identifiers, which in turn are used to tag all sources and targets of indirect control-flows.

At this point we take a detour, to point out an important design point of the micropolicies framework and our *CFI* micro-policy. Throughout both developments, a heavily parametric and modular approach was taken. This parametric design is enabled by the use of the *Section* and *Type Classes* mechanisms of Coq. As an example, the node identifiers, along with a number of properties we require of them are expressed by the following interface (defined in terms of a type class):

The Context command on the top of the code above, allows us to assume that there exists an instance of this interface. In fact, the machine\_types argument is just another type class, serving as a specification of the various types of the machine (e.g., the word size). This approach allowed us to abstract away from various details and structure our proofs in a clean way. In addition, we can easily instantiate a different machine with minimal changes in our proofs and definitions (e.g., instantiate the machine with a different word size).

However, one drawback is that one wrong specification in a type class would disallow

```
Context {t : machine_types}.

Class cfi_id := {
  id : eqType;

  word_to_id : word t → option id;
  id_to_word : id → word t;

  id_to_wordK : ∀ x, word_to_id (id_to_word x) = Some x;
  word_to_idK : ∀ w x, word_to_id w = Some x → id_to_word x = w
}.
```

Figure 4.1: Interface of node identifiers

us to instantiate it and would require that we go back and change all parts that used this wrong specification (e.g., in our case, the *machine\_types* class was widely used). Therefore one should be careful when doing heavy use of such mechanisms.

Returning to the identifiers, looking at the definition in ??, we require that the type of the identifiers id is an Eqtype (has decidable boolean equality) and that there exists conversion functions between elements of type word and id, satisfying some constraints.

(Question: Should I give some intuition, as to why word\_to\_id is partial? Is it obvious?)

As mentioned in 3.2, we check for violations of the control-flow with respect to a binary relation (on the identifiers)  $\mathcal{CFG}$  which represents the set of allowed (indirect) jumps. We can extend this relation to precisely describe the control-flow of a program, by lifting  $\mathcal{CFG}$  to a relation  $\mathcal{SUCC}_{\mathcal{CFG}}$  on machine states, that includes the set of allowed targets for the rest of the instructions. Throughout this thesis we use  $\mathcal{CFG}$  to refer to the set of allowed jumps. In our Coq development we assumed a translation of the allowed jumps in form of a function on two identifiers.

```
Variable cfg : id \rightarrow id \rightarrow bool.
```

Figure 4.2: Function on ids representing the set of allowed jumps

In addition we defined a function valid\_jmp (referred to with the notation  $\mathcal{J}$ ) that expresses the set of allowed jumps between words, by using the word to id function.

```
Definition valid_jmp w1 w2 :=

match word_to_id w1, word_to_id w2 with

| Some id1, Some id2 ⇒ cfg id1 id2

| _, _ ⇒ false
end.
```

Figure 4.3: Function on words representing the set of allowed jumps

## 4.2 Control-Flow Integrity Property

Our formalization includes a definition of CFI, similar to the one found in [2], which we prove to be true of all our machines. The need for a new definition arises from

fundamental differences between our enforcement mechanism on the concrete mechanism and the one used by Abadi *et al.*. In particular, our enforcement-mechanism does not prevent a violation, instead it can detect it after it has occurred by taking an arbitrary number of "protected" (monitor mode) steps before eventually bringing the machine to a halt. This does not have any impact on the security effectiveness of our mechanism, it does however lead to a more complex definition and therefore more complex proofs.

The definition of CFI is further parameterized by an attacker model. We model the attacker as a step relation  $(\rightarrow_a)$ . Intuitively the attacker is allowed to change any user-level data but not the code of the program and the pc, as well as the tags in the case of a tagged machine. This limitations ensures that an attacker cannot directly circumvent the monitor protection mechanism and our user-level policies (NWC, NXD and CFI). To account for attacker steps, the stepping relation is extended as the union of the normal step relation  $(\rightarrow_a)$ , as defined by the machine semantics, and the attacker step relation  $(\rightarrow_a)$ , as defined by the attacker model.

$$\frac{s \to_n s'}{s \to s'} \qquad \frac{s \to_a s'}{s \to s'}$$

Figure 4.4: Step relation definition

We define a predicate *initial s*, where s is a machine state, that states that s is an initial state. We use this predicate to express some invariants that are preserved through execution (e.g., the initial tagging scheme for the memory). Finally we define a stopping predicate on an execution trace that states that the machine is coming to a halt with respect to normal steps.

Since we want to instantiate the above parameters in a different way for each of our machines, it makes sense to wrap them in a type class which we will instantiate for each machine to get the corresponding definition of *CFI*.

```
Class cfi_machine := {
    state : Type;
    initial : state → Prop;

    step_n : state → state → Prop;
    step_a : state → state → Prop;

    succ : state → state → bool;
    stopping : list state → Prop
}.
```

Figure 4.5: Interface of a cfi machine

For a machine of type cfi machine we give the following definitions:

```
Definition 4.6. We say that an execution trace s_0 \to s_1 \to \ldots \to s_n has CFI if for all i \in [0, \ldots, n) if s_i \to_n s_{i+1} then (s_i, s_{i+1}) \in \mathcal{SUCC}_{CFG}
```

(Question: The word relation for succ and cfg is strange since they are booleans, is it ok, or does it confuse you, making you believe they are Props?)

The above definition corresponds to the one found in [1], however it is stronger in the sense that it requires that steps that are in the intersection of normal and attacker steps

respect the control-flow. If we did not allow for any violations then the above definition would be enough, but since our enforcement mechanism allows for one violation we have to resort to a weaker definition.

Definition 4.7 (CFI). We say that the machine (State, initial,  $\rightarrow_n$ ,  $\rightarrow_a$ ,  $SUCC_{CFG}$ , stopping) has CFI with respect to the set of allowed indirect jumps CFG if, for any execution starting from initial state  $s_0$  and producing a trace  $s_0 \rightarrow \ldots \rightarrow s_n$ , either

- 1. The whole trace has CFI according to 4.6, or else
- 2. There is some i such that  $s_i \to_n s_{i+1}$ , and  $(s_i, s_{i+1}) \notin \mathcal{SUCC}_{\mathcal{CFG}}$ , where the sub-traces  $s_0 \to \ldots \to s_i$  and  $s_{i+1} \to \ldots \to s_n$  both have CFI and the sub-trace  $s_{i+1} \to \ldots \to s_n$  is stopping.

#### 4.3 The Abstract Machine

The abstract machine has CFI, NXD and NWC by construction and will serve as a specification for the symbolic and eventually the concrete machine that implement CFI through the tag-based system explained in the previous chapter.

Unlike the symbolic and the concrete machine, this abstract machine splits the memory into two disjoint memories, an instruction memory and a data memory. The instruction memory is fixed (non-writable) and the machine uses this memory to fetch instructions to execute, so *NWC* and *NXD* are enforced by construction.

In addition the state of the machine includes an ok bit, indicating whether a control-flow violation has occurred or not. The rest of the machine state is completed by a set of registers and a pc register. We use a 5-tuple notation for the state (im, dm, reg, pc, ok), where the first field is the instruction memory, the second the data memory, the third the registers, the fourth is the pc register and the fifth is the pc bit.

#### 4.3.1 Operational semantics

Below is the step rule for the Store instruction, illustrating both *NWC* and *NXD*. Notice that the instruction is fetched by the instruction memory and the store is done on the data memory.

$$\begin{split} &im[pc] = i \quad decode \ i = Store \ r_p \ r_s \quad reg[r_p] = p \\ &\frac{reg[r_s] = w \quad dm' = dm[p \leftarrow w]}{(im, dm, reg, pc, true) \rightarrow (im, dm', reg', pc + 1, true)} \end{split} \tag{Store}$$

Figure 4.8: Step rule for Store instruction of abstract machine

In the above rule, the ok bit is true for both the starting and the resulting state. In fact, the machine can take a step only when the ok bit is set to true. In the above rule, the ok bit is set to true in the resulting state, indicating that no control-flow violation has happened, as expected by the execution of a Store instruction. Control-flow violations in the NWC setting our machine is executing, can only occur from indirect jump instructions, in our case the Jump and Jal instructions. Upon execution of a Jump or Jal instruction, we consult  $\mathcal{J}$  (see 4.3) to check whether the change of control-flow is legal. If the jump is not allowed according to  $\mathcal{J}$  then the jump is taken but the ok bit is set to false, which will

$$\begin{array}{ll} im[pc] = i & decode \ i = Jal \ r & reg[r] = pc' \\ \frac{reg' = reg[ra \leftarrow pc + 1] & ok = (pc, pc') \in \mathcal{J}}{(im, dm, reg, pc, true) \rightarrow (im, dm, reg', pc', ok)} \end{array} \tag{JAL}$$

$$\frac{\mathit{im}[\mathit{pc}] = \mathit{i} \quad \mathit{decode} \; \mathit{i} = \mathit{Jump} \; \mathit{r} \quad \mathit{reg}[\mathit{r}] = \mathit{pc'} \quad \mathit{ok} = (\mathit{pc}, \mathit{pc'}) \in \mathcal{J}}{(\mathit{im}, \mathit{dm}, \mathit{reg}, \mathit{pc}, \mathit{true}) \rightarrow (\mathit{im}, \mathit{dm}, \mathit{reg'}, \mathit{pc'}, \mathit{ok})} \; (\texttt{Jump})$$

Figure 4.9: Step rule for Jump and Jal instruction of abstract machine

halt the machine in the next step, as it is only allowed to step when the ok bit is set to true. Otherwise the ok bit will remain true.

As the abstract machine serves as a specification to a machine with CFI, a more intuitive definition of it would not include the ok bit and would only allow the Jump and Jal instructions to step if they do not violate the control-flow graph. However, this abstract machine would not allow for any violations to occur unlike our enforcement mechanism for the symbolic and the concrete machine and would lead to more complex simulation proofs, therefore we do not favor it.

The abstract machine also allows for monitor services to be included, although the CFI enforcement mechanism does not require any. We assume that a monitor service is a privileged action and that it's execution does not violate the control-flow of the program. Execution of a monitor service is done simply by jumping to it's address, there is no separate instruction. As with all other instructions, execution of the monitor service is only allowed if the ok bit is set to true.

Figure 4.10: Step rule for monitor services of abstract machine

(TODO: Put all rules in appendix?)

#### 4.3.2 Attacker model

The attacker for the abstract machine is allowed to change the contents of the data memory and the registers but not the rest of the state.

$$rac{dom \; dm = dom \; dm'}{(im, dm, reg, pc, ok) 
ightarrow _a^A \; (im, dm', reg', pc, ok)}$$

Figure 4.11: Attacker model for the abstract machine

#### 4.3.3 Allowed control-flows for the abstract machine

We can construct a function  $\mathcal{SUCC}^{\mathcal{A}}_{\mathcal{CFG}}$  for the abstract machine that represents the set of allowed control-flows for all instructions, by extending the set of allowed jumps  $\mathcal{CFG}$  we introduced earlier.

Below we give a specification of the  $SUCC_{CFG}^A$  function for the abstract machine, in form of inference rules. A function is defined in the actual Coq development.

$$\begin{split} & \underline{im[pc] = i \quad decode \ i \in \{Jal \ r, Jump \ r\} \quad (pc, pc') \in \mathcal{J}}{((im, dm, reg, pc, ok), (im, dm', reg', pc', ok)) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}} \text{(Indirectflows)} \\ & \underline{im[pc] = i \quad decode \ i = Bnz \ r \ imm} \\ & \underline{(pc' = pc + 1) \lor (pc' = pc + imm)} \\ & \underline{((im, dm, reg, pc, ok), (im, dm', reg', pc', ok)) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}} \text{(Conditionalflows)} \\ & \underline{im[pc] = i \quad decode \ i \not\in \{Jal \ r, Jump \ r, Bnz \ r \ imm, \varnothing\}} \\ & \underline{pc' = pc + 1} \\ & \underline{((im, dm, reg, pc, ok), (im, dm', reg', pc', ok)) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}} \text{(Normalflows)} \\ & \underline{im[pc] = \varnothing \quad dm[pc] = \varnothing} \\ & \underline{get\_service \ pc = (addr, f)} \\ & \underline{((im, dm, reg, pc, ok), (im, dm', reg', pc', ok)) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}} \text{(Serviceflows)} \end{split}$$

Figure 4.12: Allowed control-flows for instructions of the abstract machine

Notice that a monitor service is allowed to return anywhere. As we mentioned before, monitor services, execute in a protected by the monitor environment where we assume that an attacker who can only tamper the machine at the user level cannot interfere.

#### 4.3.4 Stopping predicate for the abstract machine

Finally, we define what it means for the abstract machine to be "stopping" by defining a predicate on execution traces:

- 1. All states in the trace are stuck with respect to normal steps  $(\rightarrow_n)$
- 2. All steps in the trace are attacker steps  $(\rightarrow_a)$

#### 4.3.5 CFI proof for the Abstract Machine

Regarding initial states, we only require that the ok bit is set to true. We can now instantiate the class of the machines defined in 4.5, with the abstract machine and that the abstract machine has CFI according to definition 4.7. We first prove a helpful lemma.

Lemma 4.13 (Step Intersection). For all states st st' such that  $st \to_a^A st'$  and  $st \to_n st'$ ,  $(st, st') \in \mathcal{SUCC}_{CFG}^A$ .

Proof.

- By the relation  $st \to_n st'$  we know that the ok bit of st is set to true.
- The relation  $st \to_a^A st'$  retains the ok bit of st, therefore st' has the ok bit set to true.
- It trivially follows from the definition of  $\mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  that  $(st, st') \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$ .

**Theorem 4.14** (Abstract CFI). The abstract machine has the *CFI* property defined by 4.7.

*Proof.* The proof proceeds by induction on the execution trace.

- Base Case In this case the execution trace is made up of a single step  $st \to st'$ . We proceed with case analysis on the step.
  - Attacker Step By lemma 4.13 we note that an attacker step cannot be a normal step outside the  $\mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  relation. Thus in this case the whole trace has CFI according to 4.6.
  - Normal Step By case analysis, if  $(st, st') \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  then trivially the whole trace has CFI. Otherwise  $(st, st') \notin \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  and the sub-traces st and st' vacuously have CFI. In addition the sub-trace st' is stopping, as the ok bit of st' is set to false and the state is stuck with respect to normal steps.
- Inductive Case In this case the execution trace is extended by an additional step at it's beginning  $s_0 \to s_1 \to s_2 \to \ldots \to s_n$ . By the induction hypothesis either:
  - The trace  $s_1 \to s_2 \to \ldots \to s_n$  has CFI, by case analysis if  $(s_0, s_1) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  the whole trace has CFI. Otherwise  $(s_0, s_1) \notin \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$ , the sub-trace  $s_0$  vacuously has CFI and the sub-trace  $s_1 \to \ldots \to s_n$  has CFI by the induction hypothesis. Additionally, the sub-trace  $s_1 \to \ldots \to s_n$  is stopping because:
    - \* The whole trace is made up of attacker steps. Since  $(s_0, s_1) \notin SUCC_{CFG}^A$  the ok bit of  $s_1$  will be set to false and a normal step is not allowed by the operational semantics, while attacker steps retain the ok bit.
    - \* The whole trace is stuck with respect to normal steps. Trivial from the above.
  - There exists a step  $s_{v1} \to_n s_{v2}$  such that  $(s_{v1}, s_{v2}) \notin SUCC_{CFG}^A$  and the subtraces  $s_1 \to \ldots \to s_{v1}$  and  $s_{v2} \to \ldots \to s_n$  both have CFI and the later is also a stopping trace.
    - \* If  $(s_0, s_1) \in \mathcal{SUCC}_{\mathcal{CFG}}^{\mathcal{A}}$  then 4.7 still holds and the sub-trace  $s_1 \to \ldots \to s_{v1}$  is extended by one step to  $s_0 \to \ldots \to s_{v1}$ .
    - \* Otherwise the ok bit for  $s_1$  is set to false and the rest of the trace is stuck with respect to normal steps. However from the induction hypothesis we know that  $s_{v1} \rightarrow_n s_{v2}$ , which is a contradiction.

### 4.4 The Symbolic Machine

The symbolic machine was described in 2.3.2. Unlike the abstract machine, the symbolic machine has one memory and the distinction between data and executable instructions is made through tags, in a fashion similar to what was shown in 2.2 and 3.2. We instantiate the symbolic machine, according to the aforementioned sections, with a set of tags  $\mathcal{T} = \{Data, Instrid, Instr \bot\}$  where id is drawn from the class of identifiers 4.1.

Although enforcement of CFI does not require any monitor services we expose the monitor services mechanism and we check whether calls to each monitor service are allowed or not according to the control-flow graph. This is done by assuming a lookup-table of

```
Context {ids : @cfi_id t}.
Inductive cfi_tag : Type :=
| INSTR : option id → cfi_tag
| DATA : cfi_tag.
```

Figure 4.15: Coq definition of Symbolic tags

monitor services where each entry has a tag that is used to check for control-flow violations and a semantic function from symbolic state to symbolic state which produces the new machine state after execution of the system call, as shown in 2.2.

We do not need any internal state for this micro-policy therefore, only the transfer function is left to implement.

#### 4.4.1 Transfer Function

We implement the *transfer* function based on the rules found in 3.2, using Gallina to define a function mapping input vectors (mvector) to output vectors (rvector).

```
Definition cfi handler umvec :=
  match umvec with
  | mkMVec JUMP (INSTR (Some n)) (INSTR (Some m))
  \mid mkMVec JAL (INSTR (Some n)) (INSTR (Some m)) \Rightarrow
    if cfg n m then Some (mkRVec (INSTR (Some m)) DATA)
    else None
  | mkMVec JUMP DATA (INSTR (Some n))
  \mid mkMVec JAL DATA (INSTR (Some n)) \Rightarrow
    Some (mkRVec (INSTR (Some n)) DATA)
  | mkMVec JUMP DATA (INSTR None)
  \mid mkMVec JAL DATA (INSTR None) \Rightarrow
    None
  | mkMVec STORE (INSTR (Some n)) (INSTR (Some m)) [ ; ; DATA] ⇒
    if cfg n m then Some (mkRVec DATA DATA) else None
  \mid mkMVec STORE DATA (INSTR ) \mid ; ; DATA\mid \Rightarrow
    Some (mkRVec DATA DATA)
  \mid mkMVec STORE \Rightarrow None
  \mid mkMVec (INSTR (Some n)) (INSTR (Some m)) \Rightarrow
    if cfg n m then Some (mkRVec DATA DATA) else None
  \mid mkMVec DATA (INSTR _) _ \Rightarrow
    Some (mkRVec DATA DATA)
  \mid mkMVec \Rightarrow None
  end.
```

Figure 4.16: Transfer function for symbolic machine in Gallina

(TODO: Should I remove the aggressive capitalization above? It may make it less painful on the eye...)

Although, the rules in 3.2 were fairly simply, expressing them using Gallina's pattern matching increased their size. We also experimented, with different ways of writing the transfer function but we decided to stick with the definition above as it's the most straightforward. It's worth to note that bugs in the above definition were easily made apparent

when proving theorems involving the transfer function. In fact, an "interesting" experiment was to re-define the above function in a different way and prove the two equivalent. It took two iterations before getting both functions to agree and although for small definitions like the one above, testing or manually reviewing the code will reveal most if not all bugs, the importance of formal verification in software engineering and critical software is made obvious even for definitions that may seem trivial at first. The correctness of the transfer function will come from simulation proofs between the abstract and the symbolic machine.

#### 4.4.2 Attacker model

Similar to the abstract attacker, the symbolic attacker can change all words tagged as *Data* but not the ones tagged as *Instr*. This is expressed by the following relations:

$$\frac{1}{w_1@Data \to_a^S w_2@Data} \qquad \qquad \text{(AttackData)}$$
 
$$\frac{1}{w_1@Instr\ id \to_a^S w_1@Instr\ id} \qquad \qquad \text{(AttackInstr)}$$

Figure 4.17: Attacker capabilities

These attacker capabilities on symbolic atoms are lifted to the memory and registers by a pointwise extension. (TODO: be more specific about pointwise?)

$$\frac{\textit{mem} \rightarrow_a^S \textit{mem'} \quad \textit{reg} \rightarrow_a^S \textit{reg'}}{(\textit{mem}, \textit{reg}, \textit{pc}@t_{\textit{pc}}, \textit{int}) \rightarrow_a^S (\textit{mem'}, \textit{reg'}, \textit{pc}@t_{\textit{pc}}, \textit{int})}$$

Figure 4.18: Attacker model for the Symbolic machine

#### 4.4.3 Allowed control-flows for the Symbolic Machine

Similar to the abstract machine 4.3.3, we construct  $SUCC_{CFG}^{S}$  for the symbolic machine (figure 4.19) by extending the set of allowed jumps CFG.

#### 4.4.4 Initial states of the Symbolic Machine

For the symbolic machine, we do require that certain tagging conventions are respected initially. Additionally we prove that these initial conditions are invariants of the machine and they are preserved at every (normal or attacker) step.

These invariants are required for backward simulation between the symbolic and the abstract machine. More invariants may be required for forward simulation.

(TODO: hopefully try to get to forward simulation and see what's the situation there.)

Definition 4.20 (Instructions Tagged). For all addresses addr in the memory such that

$$mem[addr] = i@Instrid$$

addr is in the domain of word to id and additionally

$$word\_to\_id$$
  $addr = id$ 

Figure 4.19: Allowed control-flows for instructions of the symbolic machine

Definition 4.21 (Entry Points Tagged). For all addresses addr such that

$$mem[addr] = \varnothing$$
  
 $get\_service \ addr = (it, f)$   
 $it = Instrid$ 

addr is in the domain of word to id and additionally

$$word\_to\_id$$
  $addr = id$ 

Definition 4.22 (Valid Jumps Tagged). For all addresses saddr, taddr such that

$$(saddr, taddr) \in \mathcal{J}$$

it holds that

$$\exists \textit{i}, \textit{mem}[\textit{saddr}] = \textit{i}@\textit{Instr} (word\_to\_id \ \textit{saddr})$$

and either

$$\exists i', mem[taddr] = i'@Instrword to id taddr$$

or

$$mem[taddr] = \varnothing$$
  
 $\exists (it, f), get\_service \ addr = (it, f)$   
 $it = Instr \ (word\_to\_id \ taddr)$ 

We define a predicate *initial* on symbolic states as the conjunction of the above invariants and the proposition that the tag on the pc is set to Data.

```
Definition invariants st :=
    instructions_tagged (Symbolic.mem st) ∧
    valid_jmp_tagged (Symbolic.mem st) ∧
    entry_points_tagged (Symbolic.mem st).

Definition initial (s : Symbolic.state t) :=
    (common.tag (Symbolic.pc s)) = DATA ∧
    invariants s.
```

Figure 4.23: Initial symbolic states predicate

It's straightforward by the semantics of the step relations to prove that both normal and attacker steps preserve each of the invariants. We only need to assume that this holds for monitor services (i.e., if we were to provide some monitor services they would have to preserve these invariants).

```
Lemma invariants _ preserved _ by _ step st st' :
    invariants st →
    step _n st st' →
    invariants st'.

Lemma invariants _ preserved _ by _ step _a st st' :
    invariants st →
    step _a st st' →
    invariants st'.
```

Figure 4.24: Symbolic invariants preservation

#### 4.4.5 Stopping predicate for the Symbolic Machine

Similar to the abstract machine, we say that an execution trace of the symbolic machine is stopping if:

- 1. All states in the trace are stuck with respect to normal steps  $(\rightarrow_n)$
- 2. All steps in the trace are attacker steps  $(\rightarrow_a)$

- 4.5 Conclusion
- 4.6 Future Work
- 4.6.1 Call-Stack Protection/ XFI

# Bibliography

- M. Abadi, M. Budiu, Ú. Erlingsson, and J. Ligatti. Control-flow integrity. In 12th ACM Conference on Computer and Communications Security, pages 340-353. ACM, 2005.
- [2] M. Abadi, M. Budiu, U. Erlingsson, and J. Ligatti. Control-flow integrity principles, implementations, and applications. *ACM Transactions on Information System Security*, 13(1), 2009.
- [3] Aleph One. Smashing the Stack for Fun and Profit. Phrack, 7(49), November 1996.
- [4] T. Bletsch, X. Jiang, and V. Freeh. Mitigating code-reuse attacks with control-flow locking. In *Proceedings of the 27th Annual Computer Security Applications Conference*, ACSAC '11, pages 353–362, New York, NY, USA, 2011. ACM.
- [5] E. Buchanan, R. Roemer, H. Shacham, and S. Savage. When Good Instructions Go Bad: Generalizing Return-Oriented Programming to RISC. In *Proc. ACM CCS*, pages 27–38, Oct. 2008.
- [6] S. Checkoway, L. Davi, A. Dmitrienko, A.-R. Sadeghi, H. Shacham, and M. Winandy. Return-Oriented Programming without Returns. In A. Keromytis and V. Shmatikov, editors, *Proceedings of CCS 2010*, pages 559–72. ACM Press, Oct. 2010.
- [7] J. Criswell, N. Dautenhahn, and V. Adve. KCoFI: Complete control-flow integrity for commodity operating system kernels. 2014.
- [8] A. A. de Amorim, M. Dénès, N. Giannarakis, C. Hriţcu, B. C. Pierce, A. Spector-Zabusky, and A. Tolmach. Micro-policies: A framework for verified, hardware-assisted security monitors. Under Review, July, July 2014.
- [9] A. A. de Amorim, M. Dénès, N. Giannarakis, C. Hriţcu, B. C. Pierce, A. Spector-Zabusky, and A. Tolmach. Micro-policies: A framework for verified, hardware-assisted security monitors. Under Review, July, July 2014.
- [10] U. Dhawan, C. Hriţcu, N. Vasilakis, S. Chiricescu, J. M. Smith, B. C. Pierce, and A. DeHon. Architectural support for software-defined metadata processing. Under Review, August, Aug. 2014.
- [11] U. Dhawan, N. Vasilakis, R. Rubin, S. Chiricescu, J. M. Smith, T. F. Knight, B. C. Pierce, and A. DeHon. PUMP A Programmable Unit for Metadata Processing. In Proceedings of the 3rd International Workshop on Hardware and Architectural Support for Security and Privacy, HASP '14, New York, NY, USA, June 2014. ACM.

- [12] Ú. Erlingsson. The inlined reference monitor approach to security policy enforcement. PhD thesis, Cornell University, Jan. 2004.
- [13] E. Göktaş, E. Athanasopoulos, H. Bos, and G. Portokalidis. Out of control: Overcoming control-flow integrity. In *IEEE Symposium on Security and Privacy*, 2014.
- [14] J. McDonald. Bugtraq: Defeating Solaris/SPARC Non-Executable Stack Protection, Mar. 1999.
- [15] G. Morrisett, G. Tan, J. Tassarotti, J.-B. Tristan, and E. Gan. RockSalt: better, faster, stronger SFI for the x86. In ACM SIGPLAN Conference on Programming Language Design and Implementation (PLDI), pages 395-404. ACM, 2012.
- [16] T. Newsham. Bugtraq: Re: Smashing the Stack: prevention?, Apr. 1997.
- [17] B. Niu and G. Tan. Modular control-flow integrity. In ACM SIGPLAN Conference on Programming Language Design and Implementation, page 58. ACM, 2014.
- [18] H. Shacham. The geometry of innocent flesh on the bone: return-into-libc without function calls (on the x86). In ACM Conference on Computer and Communications Security, pages 552-561. ACM, 2007.
- [19] Solar Designer. Bugtraq: Getting around non-executable stack (and fix), Aug. 1997.
- [20] L. Szekeres, M. Payer, T. Wei, and D. Song. SoK: Eternal war in memory. In *IEEE Symposium on Security and Privacy*, pages 48–62. IEEE Computer Society, 2013.
- [21] C. Zhang, T. Wei, Z. Chen, L. Duan, L. Szekeres, S. McCamant, D. Song, and W. Zou. Practical Control Flow Integrity & Randomization for Binary Executables. In *IEEE Symposium on Security and Privacy*, 2013.
- [22] L. Zhao, G. Li, B. D. Sutter, and J. Regehr. ARMor: fully verified software fault isolation. In 11th International Conference on Embedded Software, pages 289–298. ACM, 2011.

# Appendix A

# Stuff

#### A.1 Control-Flow Integrity Micro-Policy

We begin with a micro-policy targeting control-flow hijacking attacks, in which an attacker exploits a low-level vulnerability (e.g. a buffer or integer overflow) to gain full control of a target program [?, 20, 3, ?, ?, ?, ?, ?]. As a first line of defense, we can use tags to make code non-writable (NWC) and data non-executable (NXD), preventing the injection and execution of an attacker payload. This useful defense appears in various forms in existing systems. However, it does not prevent code-reuse attacks [16, 19, 14, 18, 6, 5, ?, 13] such as return- or jump-oriented programming [18, 6], where the attacker chains together existing code snippets ("gadgets") to induce arbitrary malicious behavior. We therefore use tags to enforce fine-grained control-flow integrity (CFI) [2, 22, 21, 7, 17, 22, 7] on top of basic NWC and NXD protection. This ensures that all indirect control flows (computed jumps) adhere to a fixed control flow graph (CFG).

We use tags to distinguish between code and data. Tags on memory and the PC are drawn from the set  $Data \mid Code \ addr \mid Code \ \bot$  (registers are always tagged Data). To simplify the CFG conformance checks, instructions that are the source or target of indirect control flows are tagged with  $Code \ addr$ , where addr is the address of that instruction in memory. For example, a Jump instruction stored at address 500 is tagged  $Code \ 500$ . All other instructions are tagged  $Code \ \bot$ .  $(AAA: Actually, we \ can't \ use \ the instruction's address on the tag if we are to have the same number of bits on words and tags. Maybe change to "id"?)$ 

We write transfer functions as a collection of symbolic rules [9, 11]. (The PUMP hardware uses a lower-level concrete rule format, described in ??.) Each symbolic rule has the form "opcode:  $(PC, CI, OP_1, OP_2, OP_3) \rightarrow (PC', R')$ ," which says that the rule matches on the given opcode together with the metadata tags on the program counter (PC), the current instruction (CI), and on up to three operands  $(OP_1 \text{ to } OP_3)$ . If the rule applies, the right-hand side determines how to update the tags on the PC (PC') and on the result of the operation (R'). We write "—" to indicate input or output fields that are ignored ("wildcard"). All instructions that are not explicitly allowed by the symbolic rules are disallowed.  $(AAA: We should choose only one of - or _ for our wildcard and use it consistently (cf. the "Store" rule below))$ 

The CFI transfer function enforces that only memory locations tagged *Data* can be modified (NWC) and only instructions fetched from locations tagged *Code* can be executed (NXD). The symbolic rule for the *Store* instruction illustrates both these points:

$$Store: (Data, Code\_, -, -, Data) \rightarrow (Data, -)$$

It requires the fetched *Store* instruction to be tagged *Code* and the written location to be tagged *Data*. This rule only applies when the PC is also tagged *Data*, which is the case when the *Store* instruction was reached by direct control flow (not a computed jump). The rule preserves the *Data* tag on the PC, since *Store* is not a computed jump. Performing a computed jump (e.g., using *Jal*, a jump-and-link instruction) requires that the current instruction be tagged *Code src* for some address *src*.

$$Jal: (Data, Code \ src, -, -, -) \rightarrow (Code \ src, -)$$

This rule copies *Code src* to the PC tag to indicate that a jump from *src* has just occurred. Only on the next instruction do we have enough information about the destination in the tags to check that the jump is indeed allowed by the CFG. For this we add a second rule for *Store*, dealing with the case where it is the target of a jump and thus the PC is tagged *Code src*.

$$\frac{(\textit{src}, \textit{tgt}) \in \textit{CFG}}{\textit{Store} : (\textit{Code src}, \textit{Code tgt}, -, -, \textit{Data}) \rightarrow (\textit{Data}, -)}$$

(AAA: Maybe we could discuss here a little bit why we verify the jump on the next instruction, as opposed to when the jump is performed. This might get some people confused, since this is not very natural and fundamentally driven by our current design of the PUMP. Even Nick wanted to know if we couldn't do it differently.) The premise of this rule ensures that the source and target of the just-performed jump are allowed by the CFG. We add a similar rule for each instruction, including jumps (since the target of a computed jump can itself be another computed jump):

$$\frac{(\textit{src}, \textit{tgt-src}) \in \textit{CFG}}{\textit{Jal} : (\textit{Code src}, \textit{Code tgt-src}, -, -, -) \rightarrow (\textit{Code tgt-src}, -)}$$

This micro-policy enforces fine-grained CFI [17, 13, 7], not coarse-grained approximations [2, 21] that are potentially vulnerable to attack [13]. Indeed, we recently proved [9] that this micro-policy enforces a variant of the CFI property introduced by Abadi *et al.* [2], ensuring that all indirect control flows adhere to a fixed CFG. Recent simulations of an optimized PUMP architecture [10] show that the CFI policy can be enforced with around 3% average runtime overhead.