## SPIRou Data Reduction Software

# User Guide

0.0.1

# For DRS SPIRou0.0.1

N. Cook, F. Bouchy, E. Artigau, I. Boisse, M. Hobson, C. Moutou 2017-11-27



#### Abstract

This is the guide to installing, running, and using the SPIRou DRS.

# Contents

1	Intr	roduction 1	Ĺ
	1.1	Code blocks	Ĺ
2	Inst	tallation 3	3
	2.1	Introduction	3
	2.2	Download	3
	2.3	Prerequisites	
		2.3.1 Anaconda python distribution	
		2.3.2 Separate python installation	
	2.4	Installation Linux and macOS	
	2.4		
		2.111 Entraction	
		2.4.2 Modify environmental settings	
		2.4.3 Make recipes executable	
	2.5	Installation Windows	
		2.5.1 How to modify environmental settings in windows	j
	2.6	Setting up the DRS	7
	2.7	Validating Installation on Linux and macOS	3
	2.8	Validating Installation on Windows	
		0	
3	Dat	a Architecture 10	)
	3.1	Installed file structure	)
	3.2	The Installation root directory	
	0.2	3.2.1 The bin directory	
	3.3		
	5.5	V.	
	0.4	3.3.1 The raw and reduced data directories	
	3.4	The calibration database directory	•
4	Heir	ng the DRS	1
4		Running the DRS recipes directly	
	4.1		
	4.2	Running the DRS recipes from a python script	
	4.3	Working example of the code for SPIRou	
		4.3.1 Overview	
		4.3.2 Run through from command line/python shell (Linux and macOS) 15	)
		4.3.3 Run through python script	3
5	<b>T</b> Iao	er modifiable variables	1
Э			
	5.1	Global variables	
	5.2	Directory variables	)
6	The	e Recipes	2
	6.1	The cal DARK spirou recipe	
	6.2	The cal loc RAW spirou recipe	
	6.3	The cal_SLIT_spirou recipe	
	6.4	The cal_SEIT_spirou recipe	
	6.5	The cal_extract_RAW_spirou recipes	
	6.6	The cal DRIFT RAW spirou recipe	1

# Introduction

### 1.1 Code blocks

Certain sections will be written in code blocks, these imply text that is written into a text editor, the command shell console, or a python terminal/script. Below explains how one can distinguish these in this document.

The following denotes a line of text (or lines of text) that are to be edited in a text editor.

```
text

# A variable name that can be changes to a specific value

VARIABLE_NAME = "Variable Value"
```

These can also be shell scripts in a certain language:

```
#!/usr/bin/bash
# Find out which console you are using
echo $0
# Set environment Hello
export Hello="Hello"
```

```
#!/usr/bin/tcsh
# Find out which console you are using
echo $0
# Set environment Hello
setenv Hello "Hello"
```

The following denotes a command to run in the command shell console

```
CMD input

>>> cd ~/Downloads
```

The following denotes a command line print out

```
Command line output

This is a print out in the command line produced by using the echo command
```

The following denotes a python terminal or python script

#### ${\bf 2} \qquad {\rm Chapter} \ 1 \quad {\rm Introduction}$

```
Python/Ipython

import numpy as np
print("Hello world")
print("{0} seconds".format(np.sqrt(25)))
```

# Installation

### 2.1 Introduction

Once finalized the installation should just be a download, run setup.py and configure the DRS directories, however, during development the following stages are required.

**Note:** Currently the download repository on git-hub is private and requires a git-hub account, and the user to be added to the list of collaborators. To be added to the collaborators please email neil.james.cook@gmail.com with your git-hub username.

### 2.2 Download

Get the latest version of the DRS (for SPIRouversion 0.0.1). Use any of the following ways:

- manually download from here: https://github.com/njcuk9999/spirou\_py3
- use Git:

```
CMD input

>>> git checkout https://github.com/njcuk9999/spirou_py3.git
```

• use SVN:

```
CMD input

>>> svn checkout https://github.com/njcuk9999/spirou_py3.git
```

• use ssh:

```
CMD input

>>> scp -r git@github.com:njcuk9999/spirou_py3.git
```

## 2.3 Prerequisites

It is recommended to install the latest version of Anaconda python distribution, available for Windows, macOS and Linux (here: https://www.anaconda.com/download/). However one can run the DRS on a native python installation.

We recommend python 3 over python 2 for long term continued support (however the latest version of the DRS supports the newest versions of python 2.7).

Note: Before installing the DRS you must have one of the following:

- Latest version of Anaconda (for python 2 or python 3) RECOMMENDED
- An Up-to-date version of python (python 2 or python 3)

#### 2.3.1 Anaconda python distribution

A valid version of the Anaconda python distribution (for python2 or python 3) Currently tested version of python are:

- Python 2.7.13 and Anaconda 4.4.0
- Python 3.6.3 and Anaconda 5.0.1 RECOMMENDED

#### 2.3.2 Separate python installation

An up-to-date version of python (either python 2 or python 3) and the following python modules (with version of python they were tested with).

- Python 3.6
  - ASTROPY (tested with version 2.0.2)
  - MATPLOTLIB (tested with version 2.1.0)
  - NUMPY (tested with version 1.13.3)
  - and the following built-in modules (comes with python): DATETIME, FILECMP, GLOB, OS,
     PKG RESOURCES, SHUTIL, SYS, TIME, WARNINGS
- Python 2.7
  - astropy (tested with version 1.3.2)
  - matplotlib (tested with version 2.0.2)
  - numpy (tested with version 1.12.1)
  - and the following built-in modules (comes with python): \_\_\_FUTURE\_\_\_, COLLECTIONS, DATETIME, FILECMP, GLOB, OS, PKG RESOURCES, SHUTIL, SYS, TIME, WARNINGS

### 2.4 Installation Linux and macOS

Currently the DRS has to be installed manually. This involves the following steps:

- 1. Extraction (Section 2.4.1)
- 2. Modify environmental settings (Section 2.4.2)
- 3. Make recipes executable (Section 2.4.3)

#### 2.4.1 Extraction

The first step is to extract the DRS into a folder (the {INSTALL\_DIR}). Do this by using the following commands:

```
CMD input

>> cd {INSTALL_DIR}

>> unzip DRS.zip
```

#### 2.4.2 Modify environmental settings

The next step is to modify your PATH and PYTHONPATH environmental variables (to include the {INSTALL DIR}. This depends which shell you are using (type 'echo \$0' to find out which).

• In bash open the '.bashrc' text file in your home (~) directory (or create it if it doesn't exist)

```
bash
export PATH={INSTALL_DIR}/bin/:$PATH
export PYTHONPATH={INSTALL_DIR}:{INSTALL_DIR}/bin/:$PYTHONPATH
```

• In csh /tcsh open the '.cshrc' or '.tcshrc' text file in your home ( $\sim$ ) directory (or create it if it doesn't exist)

```
tcsh/csh
setenv PATH {INSTALL_DIR}/bin/:${PATH}
setenv PYTHONPATH {INSTALL_DIR}:{INSTALL_DIR}/bin/:${PYTHONPATH}
```

#### 2.4.3 Make recipes executable

To run the recipes from the command line (without starting python) one must make them executable. Do this by using the following command:

```
CMD input

>>> chmod +x {INSTALL_DIR}/bin/*.py
```

### 2.5 Installation Windows

This is very similar currently to the Linux/macOS installation (in the future a '.exe' file will be given).

- 1. Extract to {INSTALL DIR} with your favourite unzipping softwear.
- 2. Add {INSTALL DIR}to your PYTHONPATH (Section 2.5.1)

#### 2.5.1 How to modify environmental settings in windows

This process is a little more convoluted than on Linux or macOS system.

- 1. Go to 'My computer > Properties > Advanced System Settings > Environmental Variables'.
- 2. if under system variable 'PythonPath' exists click edit and add '{INSTALL\_DIR};' to the end. i.e.

```
text
C:\Python27;{INSTALL_DIR};
```

3. if under system variables 'PythonPath' does not exist create a new variable called 'PythonPath' and add:

```
text
%PYTHONPATH%;{INSTALL_DIR};{INSTALL_DIR}\bin\;
```

For problems/troubleshooting see here: https://stackoverflow.com/questions/3701646.

## 2.6 Setting up the DRS

Before running the DRS one must set the data paths.

```
The 'config.txt' file is located in the {INSTALL_DIR} in the config folder. i.e. at {INSTALL_DIR}/config/config.txt
```

The following keywords **must** be changed (and must be a valid path):

```
{TDATA}
                        = /drs/data/
                                            / Define the DATA directory
{DRS ROOT}
                        = /drs/INTROOT/ / Define the installation direc-
                                               tory ({INSTALL DIR})
                        = /drs/data/raw
{DRS_DATA_RAW}
                                            / Define the folder with the raw
                                               data files in
{DRS_DATA_REDUC}
                        = /drs/data/reduced /
                                              Define the directory that the
                                               reduced data should be saved
                                               to/read from
{DRS CALIB DB}
                        = /drs/data/calibDB/
                                              Define the directory that the
                                               calibration files should be
                                               saved to/read from
{DRS DATA MSG}
                        = /drs/data/msg
                                              Define the directory that the
                                               log messages are stored in
{DRS DATA WORKING} = /drs/data/tmp/
                                              Define the working directory
```

The directories here are for linux and macOS systems another example would be '/home/user/IN-TROOT' for the {INSTALL\_DIR} directory.

On Windows machines this would be equivalent to 'C:\Users\<username>\INTROOT' in Windows Vista, 7, 8 and 10 or 'C:\Documents and Settings\<username>\INTROOT' on early versions of Windows.

The following keywords can be changed:

```
{DRS_PLOT} = 1 / Whether to show plots
{PRINT_LEVEL} = "all" / Level at which to print
{LOG_LEVEL} = "all" / Level at which to log in log file
```

For the '{PRINT LEVEL} and {LOG LEVEL} keywords the values are set as follows:

- "all" prints all events
- "info" prints info, warning and error events
- "warning" prints warning and error events
- "error" print only error events

## 2.7 Validating Installation on Linux and macOS

**Note:** One must install the DRS (Section 2.4) AND set up the DRS (Section 2.6) before validation will be successful.

There are four ways to run the DRS in Linux and macOS (thus four ways to verify installation was correct).

• To validate running from command line type:

```
CMD input

>>> cal_validate_spirou.py
```

• To validate running from python/ipython from the command line type:

```
CMD input

>>> python cal_validate_spirou.py
>>> ipython cal_validate_spirou.py
```

• To validate running from ipython, open ipython and type:

```
Python/Ipython

run cal_validate_spirou.py
```

• To validate running from import from python/ipython, open python/ipython and type:

```
Python/Ipython

import cal_validate_spirou
cal_validate_spirou.main()
```

If validation is successful the following should appear:

```
Command line output
HH:MM:SS.S -
              || *********************
HH:MM:SS.S -
             || * SPIROU @(#) Geneva Observatory (0.0.1)
             HH:MM:SS.S -
HH:MM:SS.S -
             ||(dir_data_raw)
                                DRS_DATA_RAW=/scratch/Projects/spirou_py3/data/raw
             ||(dir_data_reduc)
HH:MM:SS.S -
                                 DRS_DATA_REDUC=/scratch/Projects/spirou_py3/data/reduced
             ||(dir_calib_db)
||(dir_data_msg)
||(print_level)
HH:MM:SS.S -
                                 DRS_CALIB_DB=/scratch/Projects/spirou_py3/data/calibDB
HH:MM:SS.S -
                                 DRS_DATA_MSG=/scratch/Projects/spirou_py3/data/msg
HH:MM:SS.S -
                                  PRINT_LEVEL=all
                                                        %(error/warning/info/all)
HH:MM:SS.S -
             ||(log_level)
                                  LOG_LEVEL=all
                                                       %(error/warning/info/all)
HH:MM:SS.S -
             ||(plot_graph)
                                  DRS_PLOT=1
                                                       %(def/undef/trigger)
HH:MM:SS.S -
             ||(used_date)
                                  DRS_USED_DATE=undefined
HH:MM:SS.S -
             ||(working_dir)
                                  DRS_DATA_WORKING=/scratch/Projects/spirou_py3/data/tmp/
HH:MM:SS.S -
                                  DRS_INTERACTIVE is not set, running on-line mode
HH:MM:SS.S -
HH:MM:SS.S -
             ||Validation successful. DRS installed corrected.
```

## 2.8 Validating Installation on Windows

**Note:** One must install the DRS (Section 2.5) AND set up the DRS (Section 2.6) before validation will be successful.

In windows there are currently 3 ways to run the RS (running in python/ipython).

• To validate running from python/ipython from the command line type:

```
CMD input

>>> python cal_validate_spirou.py

>>> ipython cal_validate_spirou.py
```

• To validate running from ipython, open ipython and type:

```
Python/Ipython

rum cal_validate_spirou.py
```

• To validate running from import from python/ipython, open python/ipython and type:

```
Python/Ipython

import cal_validate_spirou
cal_validate_spirou.main()
```

If validation is successful the following should appear:

```
Command line output
HH:MM:SS.S -
             || ***********************
HH:MM:SS.S -
             || * SPIROU @(#) Geneva Observatory (0.0.1)
             || ***********************
HH:MM:SS.S -
HH:MM:SS.S -
             ||(dir_data_raw) DRS_DATA_RAW=/scratch/Projects/spirou_py3/data/raw
             ||(dir_data_reduc)
HH:MM:SS.S -
                                  DRS_DATA_REDUC=/scratch/Projects/spirou_py3/data/reduced
             ||(dir_calib_db)
HH:MM:SS.S -
                                 DRS_CALIB_DB=/scratch/Projects/spirou_py3/data/calibDB
HH:MM:SS.S -
             ||(dir_data_msg)
                                  DRS_DATA_MSG=/scratch/Projects/spirou_py3/data/msg
HH:MM:SS.S -
             ||(print_level)
                                  PRINT_LEVEL=all
                                                        %(error/warning/info/all)
HH:MM:SS.S -
             ||(log_level)
                                  LOG_LEVEL=all
                                                       %(error/warning/info/all)
HH:MM:SS.S -
                                 DRS_PLOT=1
             ||(plot_graph)
                                                      %(def/undef/trigger)
HH:MM:SS.S -
             ||(used_date)
                                  DRS_USED_DATE=undefined
HH:MM:SS.S -
             ||(working_dir)
                                  DRS_DATA_WORKING=/scratch/Projects/spirou_py3/data/tmp/
HH:MM:SS.S -
                                  DRS_INTERACTIVE is not set, running on-line mode
HH:MM:SS.S -
HH:MM:SS.S - | | Validation successful. DRS installed corrected.
```

# Data Architecture

Described below is the file structure, after correct installation (Chapter 2).

### 3.1 Installed file structure

The file structure should look as follows:

```
{dir}
 __{DRS_ROOT}
   _bin
    _ ..... Recipes
    config
    documentation
    SpirouDRS
    _ ...... The DRS Module
 {DATA_ROOT}*
  _calibDB
  msg
  raw
  reduced
  _{\rm L} tmp
* This is the recommended file structure and raw, reduced, calibDB, msg and tmp can be changed
using the {DATA_ROOT_RAW}, {DATA_ROOT_REDUCED}, {DATA_ROOT_CALIB},
{DATA ROOT MSG}, and {DATA ROOT TMP} variables in Section 2.6.
```

i.e. for the paths given in Section 2.6 this would be:

```
drs
__INTROOT
__bin
__config
__documentation
__SpirouDRS
__data
__calibDB
__msg
__raw
__YYYYMMDD
__reduced
__tmp
```

## 3.2 The Installation root directory

The {INSTALL\_ROOT} contains all the installed recipes, modules functions, documentation and configuration files needed to run the DRS. The file structure is set up as below:

```
{dir}

DRS_ROOT}

bin

config

documentation

SpirouDRS

Recipes

Configuration files

Documentation files

The DRS Module
```

#### 3.2.1 The bin directory

The bin directory is located in the {INSTALL\_ROOT} directory. This contains all the recipes that can be used. A detailed description of all recipes can be found in Chapter 6 but are listed here for completeness.

- cal DARK spirou.py
- $\bullet$  cal\_DRIFT\_RAW\_spirou.py
- cal\_extract\_RAW\_spirou.py
- $\bullet$  cal\_extract\_RAW\_spirouAB.py
- cal\_extract\_RAW\_spirouC.py
- cal\_FF\_RAW\_spirou.py
- cal loc RAW spirou.py
- $\bullet$  cal\_SLIT\_spirou.py
- $\bullet$  cal\_validate\_spirou.py

## 3.3 The data root directory

This is the directory where all the data should be stored. The default and recommended design is to have {DATA\_ROOT\_RAW}, {DATA\_ROOT\_REDUCED}, {DATA\_ROOT\_CALIB}, {DATA\_ROOT\_MSG}, and {DATA\_ROOT\_TMP} as sub-directories of {DATA\_ROOT}. However as in Section 2.6. these sub-directories can be defined elsewhere.

#### 3.3.1 The raw and reduced data directories

The raw observed data is stored under the {DATA\_ROOT\_RAW} path, the files are stored by night in the form YYYYMMDD.

The file structure can be seen below:

## 3.4 The calibration database directory

The calibDB contains all the calibration files that pass the quality tests and a test file 'master\_calib\_SPIROU.txt '. It is located at {DATA\_ROOT\_CALIB} or if this is not defined is located by default at the {DATA\_ROOT} directory.

Each line in this file is a unique calibration file and lines are formatted in the following manner:

```
text
{key} {night_repository} {filename} {human readable date} {unix time}
```

#### where

- {key} is a code assigned for each type of calibration file. Currently accepted keys are:
  - DARK Created from cal DARK spirou.py
  - ORDER PROFIL {fiber} Created in cal loc RAW spirou.py
  - LOC C Created in cal loc RAW spirou.py
  - TILT Created in cal\_SLIT\_spirou.py
  - FLAT {fiber} Created in cal FF RAW spirou.py
  - WAVE Currently manually added
- {night\_repository} is the raw data observation directory (in {DATA\_ROOT\_RAW}) normally in the form YYYYMMDD.
- {filename} is the filename of the calibration file (located in the calibDB).
- {human readable date} is the date in DD/MM/YY/HH:MM:SS.ss format taken from the header keyword 'ACQTIME1' of the file that created the calibration file.
- {unix time} is the time (as in {human readable date}) but in unix time (in seconds).

An example working master\_calib\_SPIROU.txt is shown below (assuming the listed files are present in {DATA\_ROOT\_CALIB})

```
DARK 20170710 dark_dark02d406.fits 07/10/17/16:37:48 1499704668.0

ORDER_PROFIL_C 20170710 dark_flat02f10_order_profil_C.fits 07/10/17/17:03:50 1499706230.0

LOC_C 20170710 dark_flat02f10_loco_C.fits 07/10/17/17:03:50 1499706230.0

ORDER_PROFIL_AB 20170710 flat_dark02f10_order_profil_AB.fits 07/10/17/17:07:08 1499706428.0

LOC_AB 20170710 flat_dark02f10_loco_AB.fits 07/10/17/17:07:08 1499706428.0

TILT 20170710 fp_fp02a203_tilt.fits 07/10/17/17:25:15 1499705515.0

FLAT_C 20170710 dark_flat02f10_flat_C.fits 07/10/17/17:03:50 1499706230.0

WAVE 20170710 spirou_wave_ini3.fits 07/10/17/17:03:50 1499706230.0
```

# Using the DRS

There are two ways to run the DRS recipes. The first (described in Section 4.1) directly calls the code and inputs arguments (either from the command line or from python), the second way is to import the recipes in a python script and define arguments in a call to a function (see Section 4.2).

## 4.1 Running the DRS recipes directly

As in Chapter 2, using Linux or macOS one can run DRS recipes from the command line or from python, in windows one is required to be in python before running the scipts. Below we use cal\_DARK\_spirou.pyas an example:

• To run from command line type:

```
CMD input

>>> cal_DARK_spirou.py {YYMMDD} {Filenames})
```

• To run from python/ipython from the command line type:

```
CMD input

>>> python cal_DARK_spirou.py {YYMMDD} {Filenames})ipython
    (*cal_DARK_spirou.py {YYMMDD} {Filenames})
```

• To run from ipython, open ipython and type:

```
Python/Ipython

run cal_DARK_spirou.py {YYMMDD} {Filenames})
```

## 4.2 Running the DRS recipes from a python script

In any operating system one can also import a recipe and call a function to run the code. This is useful in batch operations, timing tests and unit tests for example. Below we use cal\_DARK\_spirou.pyas an example:

```
# import the recipe
import cal_DARK_spirou
# define the night folder name
night_name = "20170710"
# define the file(s) to run through the code
files = ['dark_dark02d406.fits']
# run code
cal_validate_spirou.main(night_name=night_name, files=files)
```

## 4.3 Working example of the code for SPIRou

#### 4.3.1 Overview

For this example all files are from:

```
CMD input

>> spirou@10.102.14.81:/data/RawImages/H2RG-AT4/AT4-04/2017-07-10_15-36-18/ramps/
```

following our example data architecture (from Section 2.6 and shown explicity in Section 3.1) all files should be places in the {DATA\_RAW\_ROOT} (/drs/data/raw in our case). and we will also need the current WAVE file from here:

```
CMD input

>>> spirou@10.102.14.81:/data/reduced/DATA-CALIB/spirou_wave_ini3.fits
```

which needs to be placed in the {DRS\_CALIB\_DB} directory (/drs/data/calibDB in our case). Starting with RAMP files and ending with extracted orders and calculated drifts we need to run six codes:

```
1. cal DARK spirou.py (See Section 6.1)
```

2. cal loc RAW spirou.py( $\times$ 2) (See Section 6.2)

4. cal FF RAW spirou.py(
$$\times$$
2) (See Section 6.4)

5. (add spirou wave ini3.fits to calibDB)

6. cal\_extract\_RAW\_spirouAB.pyand cal\_extract\_RAW\_spirouC.py(many times) (See Section 6.5)

```
7. cal DRIFT RAW spirou.py (See Section 6.6)
```

#### 4.3.2 Run through from command line/python shell (Linux and macOS)

As long as all codes are excutable (see Section 2.4.3) one can run all codes from the command line or if not excutable or one has a preference for python one can run the following with 'python {command}', 'ipython {command}' or indeed through an interactive ipython session using 'run {command}'.

1. run the dark extraction on the 'dark dark' file:

```
CMD input

>>> cal_DARK_spirou.py 20170710 dark_dark02d406.fits
```

2. run the order localisation on the 'dark flat' files:

```
CMD input

>>> cal_loc_RAW_spirou.py 20170710 dark_flat02f10.fits dark_flat03f10.fits dark_flat04f10.fits
    dark_flat05f10.fits dark_flat06f10.fits
```

3. run the order localisation on the 'flat dark' files:

```
CMD input

>>> cal_loc_RAW_spirou.py 20170710 flat_dark02f10.fits flat_dark03f10.fits flat_dark04f10.fits flat_dark05f10.fits flat_dark06f10.fits
```

4. run the slit calibration on the 'fp fp' files.

```
CMD input

>>> cal_SLIT_spirou.py 20170710 fp_fp02a203.fits fp_fp03a203.fits fp_fp04a203.fits
```

5. run the flat field creation on the 'dark flat' files:

Note: if using same files as above you will get an error message when running the file. To solve this open the 'master\_calib\_SPIROU.txt' file located in {DATA\_ROOT\_CALIB}. Edit the unix date in the line that begins 'TILT' so that it is less than or equal to the unix date on rows 'ORDER\_PROFIL\_AB' (i.e. easiest to change it to the date on the 'ORDER\_PROFIL\_AB')

The human date format must match the unix date thus both must be changed if one is modified.

i.e. the 'master\_calib\_SPIROU.txt' file should look go from

```
DARK 20170710 dark_dark02d406.fits 07/10/17/16:37:48 1499704668.0

ORDER_PROFIL_C 20170710 dark_flat02f10_order_profil_C.fits 07/10/17/17:03:50 1499706230.0

LOC_C 20170710 dark_flat02f10_loco_C.fits 07/10/17/17:03:50 1499706230.0

ORDER_PROFIL_AB 20170710 flat_dark02f10_order_profil_AB.fits 07/10/17/17:07:08

1499706428.0

LOC_AB 20170710 flat_dark02f10_loco_AB.fits 07/10/17/17:07:08 1499706428.0

TILT 20170710 fp_fp02a203_tilt.fits 07/10/17/17:25:15 1499707515.0
```

#### to this:

```
DARK 20170710 dark_dark02d406.fits 07/10/17/16:37:48 1499704668.0

ORDER_PROFIL_C 20170710 dark_flat02f10_order_profil_C.fits 07/10/17/17:03:50 1499706230.0

LOC_C 20170710 dark_flat02f10_loco_C.fits 07/10/17/17:03:50 1499706230.0

ORDER_PROFIL_AB 20170710 flat_dark02f10_order_profil_AB.fits 07/10/17/17:07:08

1499706428.0

LOC_AB 20170710 flat_dark02f10_loco_AB.fits 07/10/17/17:07:08 1499706428.0

TILT 20170710 fp_fp02a203_tilt.fits 07/10/17/17:07:08 1499706428.0
```

#### CMD input

cal\_FF\_RAW\_spirou.py 20170710 dark\_flat02f10.fits dark\_flat03f10.fits dark\_flat04f10.fits
dark\_flat05f10.fits dark\_flat06f10.fits

6. Currently we do not create a new wavelength calibration file for this run. Therefore we need one (as stated in the above section). We use the one from here:

```
CMD input

>>> spirou@10.102.14.81:/data/reduced/DATA-CALIB/spirou_wave_ini3.fits
```

then place it in the {DATA\_ROOT\_CALIB} folder. You will also need to edit the 'master\_calib\_SPIROU.txt' file located in {DATA\_ROOT\_CALIB}.

Add the folloing line to 'master calib SPIROU.txt'

```
text
WAVE 20170710 spirou_wave_ini3.fits 07/10/17/17:03:50 1499706230.0
```

and the 'master\_calib\_SPIROU.txt' should look like this:

```
DARK 20170710 dark_dark02d406.fits 07/10/17/16:37:48 1499704668.0

ORDER_PROFIL_C 20170710 dark_flat02f10_order_profil_C.fits 07/10/17/17:03:50 1499706230.0

LOC_C 20170710 dark_flat02f10_loco_C.fits 07/10/17/17:03:50 1499706230.0

ORDER_PROFIL_AB 20170710 flat_dark02f10_order_profil_AB.fits 07/10/17/17:07:08 1499706428.0

LOC_AB 20170710 flat_dark02f10_loco_AB.fits 07/10/17/17:07:08 1499706428.0

TILT 20170710 fp_fp02a203_tilt.fits 07/10/17/17:07:08 1499706428.0

WAVE 20170710 spirou_wave_ini3.fits 07/10/17/17:03:50 1499706230.0
```

7. run the extraction files on the 'hcone\_dark', 'dark\_hcone', 'hcone\_hcone', 'dark\_dark\_AHC1', 'hctwo\_dark', 'dark\_hctwo', 'hctwo-hctwo', 'dark\_dark\_AHC2' and 'fp\_fp' files. For example for the 'fp\_fp' files:

```
CMD input

>>> cal_extract_RAW_spirouAB.py 20170710 fp_fp02a203.fits fp_fp03a203.fits fp_fp04a203.fits
>>> cal_extract_RAW_spirouC.py 20170710 fp_fp02a203.fits fp_fp03a203.fits fp_fp04a203.fits
```

8. run the drift calculation on the 'fp fp' files:

```
CMD input

CMD input

CMD input

CMD input

CMD input
```

#### 4.3.3 Run through python script

The process is in the same order as Section 4.3.2, including changing the date on the 'TILT' keyword and adding the 'WAVE' line, and adding the wave file to the calibDB folder).

```
import cal_DARK_spirou, cal_loc_RAW_spirou
import cal_SLIT_spirou, cal_FF_RAW_spirou
import cal_extract_RAW_spirou, cal_DRIFT_RAW_spirou
import matplotlib.pyplot as plt
# define constants
NIGHT_NAME = '20170710'
# cal_dark_spirou
files = ['dark_dark02d406.fits']
                                          # set up files
cal_DARK_spirou.main(NIGHT_NAME, files) # run cal_dark_spirou
plt.close('all')
                                          # close graphs
# cal_loc_RAW_spirou - flat_dark
files = ['flat_dark02f10.fits', 'flat_dark03f10.fits', 'flat_dark04f10.fits',
         'flat_dark05f10.fits','flat_dark06f10.fits']
cal_loc_RAW_spirou.main(NIGHT_NAME, files)
plt.close('all')
# cal_loc_RAW_spirou - dark_flat
files = ['dark_flat02f10.fits', 'dark_flat03f10.fits', 'dark_flat04f10.fits',
         'dark_flat05f10.fits', 'dark_flat06f10.fits']
cal_loc_RAW_spirou.main(NIGHT_NAME, files)
plt.close('all')
# cal_SLIT_spirou
files = ['fp_fp02a203.fits', 'fp_fp03a203.fits', 'fp_fp04a203.fits']
cal_SLIT_spirou.main(NIGHT_NAME, files)
plt.close('all')
# cal_FF_RAW_spirou - flat_dark
files = ['flat_dark02f10.fits', 'flat_dark03f10.fits','flat_dark04f10.fits',
         'flat_dark05f10.fits', 'flat_dark06f10.fits']
cal_FF_RAW_spirou.main(NIGHT_NAME, files)
plt.close('all')
# cal_FF_RAW_spirou - dark_flat
files = ['dark_flat02f10.fits', 'dark_flat03f10.fits', 'dark_flat04f10.fits',
         'dark_flat05f10.fits', 'dark_flat06f10.fits']
cal_FF_RAW_spirou.main(NIGHT_NAME, files)
plt.close('all')
# cal_extract_RAW_spirou - fp_fp AB
files = ['fp_fp02a203.fits', 'fp_fp03a203.fits', 'fp_fp04a203.fits']
cal_extract_RAW_spirou.main(NIGHT_NAME, files, 'AB')
plt.close('all')
# cal_extract_RAW_spirou - fp_fp C
files = ['fp_fp02a203.fits', 'fp_fp03a203.fits', 'fp_fp04a203.fits']
cal_extract_RAW_spirou.main(NIGHT_NAME, files, 'C')
plt.close('all')
# test cal_DRIFT_RAW_spirou
files = ['fp_fp02a203.fits', 'fp_fp03a203.fits', 'fp_fp04a203.fits']
cal_DRIFT_RAW_spirou.main(NIGHT_NAME, files)
plt.close('all')
```

# User modifiable variables

To better understand the variables in the DRS we have laid out each variable in the following way:

#### • Variable title

Description of the variable

VARIABLE NAME = Default Value

Used in: The code used a variable is used in

Defined in: The place where the variable can be found

## 5.1 Global variables

#### • DRS Name

Defines the data reduction software name

DRS\_NAME = SPIROU
Used in: All Recipes
Defined in: config.txt

#### • Plotting switch

Defines whether to show plots (A value of 1 to show plots, a value of 0 to not show plots)

DRS\_PLOT = 1 Used in: All Recipes Defined in: config.txt

#### • Print message level

The level of messages to print, values can be as follows:

- "all" prints all events
- "info" prints info, warning and error events
- "warning" prints warning and error events
- "error" print only error events

PRINT\_LEVEL = all
Used in: All Recipes
Defined in: config.txt

#### • Log message level

```
The level of messages to print, values can be as follows:

- "all" - prints all events

- "info" - prints info, warning and error events

- "warning" - prints warning and error events

- "error" - print only error events

LOG_LEVEL = all
Used in: All Recipes
Defined in: config.txt
```

## 5.2 Directory variables

These were mentioned in Section 2.6 and are located in teh 'config.txt' file. The 'config.txt' file is located in the {INSTALL DIR} in the config folder (i.e. at {INSTALL DIR}/config/config.txt).

Currently the directory variables are:

• The data directory

```
Defines the path to the data directory

TDATA = /drs/data/
Used in: All Recipes
Defined in: config.txt
```

• The installation directory

```
Defines the instllation directory ({INSTALL_DIR})

DRS_ROOT = /drs/INTROOT/
Used in: All Recipes
Defined in: config.txt
```

• The raw data directory

```
Defines the directory that the reduced data should be saved to/read from

DRS_DATA_RAW = /drs/data/raw
Used in: All Recipes
Defined in: config.txt
```

• The reduced data directory

```
Defines the directory that the reduced data should be saved to/read from

DRS_DATA_REDUC = /drs/data/reduced
Used in: All Recipes
Defined in: config.txt
```

#### • The calibration database and calibration file directory

Defines the directory that the calibration files and database should be saved to/read from

 $\frac{DRS\_CALIB\_DB}{} = \frac{\sqrt{drs}}{data} = \frac{\sqrt{drs}}{data}$ 

Used in: All Recipes
Defined in: config.txt

#### • The log directory

Defines the directory that the log messages are stored in

 $\frac{DRS\_DATA\_MSG}{} = \frac{/drs/data/msg}{}$ 

Used in: All Recipes
Defined in: config.txt

#### • The working directory

Defines the working directory

Used in:

Defined in:

All Recipes config.txt

# The Recipes

- 6.1 The cal\_DARK\_spirou recipe
- 6.2 The cal loc RAW spirou recipe
- 6.3 The cal\_SLIT\_spirou recipe
- 6.4 The cal FF RAW spirou recipe
- 6.5 The cal extract RAW spirou recipes
- 6.6 The cal\_DRIFT\_RAW\_spirou recipe