

## INDUCED PROBABILITY DISTRIBUTIONS

## Why

We can interpret the codomain of a random variable as a new sample space, since the underlying probability distribution induces a new probability distribution.

## **Definition**

Let  $p:\Omega\to \mathbf{R}$  be a probability distribution and  $x:\Omega\to V$  an outcome variable. Define  $q:V\to \mathbf{R}$  by

$$q(a) = \mathbf{P}[x = a].$$

Since events  $x^{-1}(a)$  for  $a \in V$  partition  $\Omega$ ,  $\sum_{a \in A} q(a) = 1$ . We call q the induced distribution (or induced probability mass function) of the random variable x. Thus we can think of V as a set of outcomes, which we call the outcomes induced by x.

## Notation

It is common to denote it by  $p_x$ .

If  $x:\Omega\to V$  is a random variable and  $f:V\to U$ , then if we define  $y:\Omega\to V$  so that  $y\equiv f(x),\ y$  is a random variable with induced distribution  $p_y:\Omega\to \mathbf{R}$  satisfying

$$p_y(b) = \sum_{a \in V | y(a) = b} p_x(a).$$

As a matter of practical computation, we can evaluate probabilities having to do with the outcome variable x using  $p_x$  instead of p. For example with x as in the example above,  $\mathbf{P}(x=4 \text{ or } x=5) = p_x(4) + p_x(5)$ , rather than  $\sum_{\omega \in \Omega \mid x(\omega)=4 \text{ or } x(\omega)=5} p(\omega)$ .

