

Why

There is a natural predictor corresponding to a normal linear model.

Definition

Let $(x : \Omega \to \mathbf{R}^d, A \in \mathbf{R}^{n \times d}, e : \Omega \to \mathbf{R}^n)$ be a normal linear model over the probability space $(\Omega, \mathcal{A}, \mathbf{P})$.

Predictive density

We are modeling $h_{\omega}: \mathbf{R}^d \to \mathbf{R}$ by $h_w(a) = x(\omega)^{\top} a$. The *predictive* density for a dataset $c^1, \ldots, c^m \in \mathbf{R}^d$ is the conditional density of the random vector $(h_{(\cdot)}(c^1), \ldots, h_{(\cdot)}(c^m))$ given y.

Proposition 1. The predictive density for $c^1, \ldots, c^m \in \mathbb{R}^d$ (with data matrix $C \in \mathbb{R}^{m \times d}$) is normal with mean

$$g(a) = (C\Sigma_x A^{\top})(A\Sigma_x A^{\top} + \Sigma_e)^{-1} \gamma.$$

and covariance

$$C\Sigma_x C^{\top} - C\Sigma_x A^{\top} (A\Sigma_x A^{\top} + \Sigma_e)^{-1} A\Sigma_x C^{\top}.$$

Proof. Define (as usual) $y:\Omega\to \mathbf{R}^n$ and $z:\Omega\to \mathbf{R}^m$ by

$$y = Ax + e$$
$$z = Cx.$$

Recognize (x, y, z) as jointly normal, and use Normal Conditionals). \square

Predictor

The normal linear model predictor or normal linear model regressor for the normal linear model (x, A, e) is the predictor which assigns to a new point $a \in \mathbf{R}^d$ the mean of the predictive density at a. That is, the predictor $g: \mathbf{R}^d \to \mathbf{R}$ defined by

$$g(a) = a^{\top} \Sigma_x A^{\top} (A \Sigma_x A^{\top} + \Sigma_e)^{-1} \gamma.$$

In the above we have substituted a^{\top} for C. In the case of normal random vectors this corresponds with the MAP estimate and the MMSE estimate.¹ Notice that g is *linear* in its argument, a.

The use of a normal linear model predictor is often called Bayesian linear regression. The word Bayesian is used in reference to treating the parameters of the function, x, as a random variable.

¹Future editions will have discussed this and include a reference to the sheet.

