

REAL HYPERPLANES

Why

We generalize the notion of a point in \mathbf{R} , a line in \mathbf{R}^2 and a plane in \mathbf{R}^3 .

Definition

A hyperplane is a (n-1)-dimensional affine set in \mathbb{R}^n .

Discussion

Since the n-1-dimensional subspaces are the orthogonal complements of the one-dimensional subspaces, they are the sets which can be specified by

$$\{x \in \mathbf{R}^n \mid x \perp b\} + a$$

for $a, b \in \mathbb{R}^n$. The hyperplanes are translates of these,

$$\{x \in \mathbf{R}^n \mid x \perp b\} + a = \{x + a \mid \langle x, b \rangle = 0\}$$

$$= \{y \mid \langle y - a, b \rangle = 0\} = \{y \mid \langle y, b \rangle = \beta\},$$

where $\beta = \langle a, b \rangle$.

Characterization

Proposition 1. $H \subset \mathbb{R}^n$ is a hyperplane if and only if there exists $\beta \in \mathbb{R}$ and nonzero $b \in \mathbb{R}^n$ so that

$$H = \{ x \in \mathbf{R}^n \mid \langle x, b \rangle = \beta \}.$$

Remark 1. b and β are unique up to a common nonzero multiple. For example, b, β and 2b, 2β give the same hyperplane.

Remark 2. Any such vector b is called a normal (or normal vector) to the hyperplane.

Remark 3. If H is a hyperplane not containing the origin, then there is a unique unit vecor u and $\alpha > 0$ so that

$$H = \{ x \in \mathbf{R}^n \mid \langle x, u \rangle = \alpha \}$$

