


3-Dimensional Matrices



Structured Data Types



Matrices

- Declaration in C:

```
type name[NumRows][NumColumns];      // indexed starting at (0,0)
```

- Storage by rows in consecutive memory locations

- Access element A[i][j]: **@start A + (i*NumColumns + j) * size**

(size: size of the elements of A)



Structured Data Types

Matrices

- Examples:

Declaration in C	Size of Element	Size of Matrix	@element (i, j)
char A[80][25];	1B	2000B	@start A + i*25 + j
char *B[80][10];	4B	3200B	@start B + (i*10+j)*4
double C[1024][100];	8B	800KB	@start C + (i*100+j)*8
int *D[5][90];	4B	1800B	@start D + (i*90+j)*4
int E[100][30];	4B	12000B	@start E + (i*30+j)*4



Structured Data Types

Matrices 3-Dimensions


- Example, 3-dimensional integer array:

```
int M3D[10][64][48]      // each int occupies 4 bytes
```

- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- M3D[**face**][**row**][**column**]



3-Dimensional Matrix





Structured Data Types

Matrices 3-Dimensions

- Example, 3-dimensional integer array:

```
int M3D[10][64][48]      // each int occupies 4 bytes
```

- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- Access to element M3D[**face**][**row**][**column**]:
 - $\text{@start} + (\text{face} \cdot 64 \cdot 48 + \text{row} \cdot 48 + \text{column}) \cdot 4$



Structured Data Types

Matrices 3-Dimensions

- Example, 3-dimensional integer array:

```
int M3D[10][64][48]      // each int occupies 4 bytes
```

- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- Access to element M3D[**face**][**row**][**column**]:
 - $\text{@start} + (\text{face} \cdot 64 \cdot 48 + \text{row} \cdot 48 + \text{column}) \cdot 4$

Structured Data Types



Matrices 3-Dimensions

- So, given a 3-dimensional matrix:
type M3D[**NumFaces**][**NumRows**][**NumCols**]
- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- Access to element M3D[**face**][**row**][**column**]:
 - $\text{@start} + (\text{face} \cdot \text{NumRows} \cdot \text{NumCols} + \text{row} \cdot \text{NumCols} + \text{column}) \cdot \text{size}$



Structured Data Types

Matrices 3-Dimensions

- Example, 3-dimensional integer array:
`int M3D[10][64][48] // each int occupies 4 bytes`
- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- Access to element `M3D[face][row][column]`:
 - `@start M3D + (face·64·48 + row·48 + column)·4`
- It is simple to figure out how N-dimensional matrices are stored/accessed.

Structured Data Types



Matrices 4-Dimensions

- So, given a 4-dimensional matrix:
type M3D[**NumFaces**][**NumRows**][**NumCols**][**NumSets**]
- The matrix is stored in consecutive memory locations: face to face and in each face by rows.
- Access to element M3D[**face**][**row**][**column**][**set**]:

```
@start M3D + (face·NumRows·NumCols·NumSets + row·NumCols·NumSets +  
                 column·NumSets + set)·size
```