Physics 7701 Introduction

Maxwell Equations

For reference in Jackson, see section i or Zangwill chapter 2.

$$\vec{\nabla} \cdot \vec{D} = \rho \rightarrow \vec{\nabla} \cdot \vec{E} = \rho/\epsilon_0$$

$$\vec{\nabla} \times \vec{H} - \frac{\partial \vec{D}}{\partial t} = \vec{J} \rightarrow \vec{\nabla} \cdot \vec{B} - \frac{1}{c^2} \frac{\partial \vec{E}}{\partial t} = \mu_0 \vec{J}$$

$$\vec{\nabla} \times \vec{E} - \frac{\partial \vec{B}}{\partial t} = 0$$

$$\vec{\nabla} \cdot \vec{B} = 0$$

These maxwell equations all functions of \vec{x}, t , and are local equations, which means the maxwell equations are evaluated at a small neighborhood around a point \vec{x}_1 .

Additionally, we have the Lorentz force equation:

$$\vec{F} = q(\vec{E} + \vec{v} \times \vec{B})$$

To comfortably solve those equations, we note that the knowledge of **vector** calculus and differential equations are going to be needed.

Note: because differential operator are linear, superposition could be imposed for Maxwell equations.

Application 1

What is the basic physics principle underlying a ground fault circuit interrupter?

- 1. Charge conservation if there is current leakage, charge conservation would be broken.
- 2. Two current carrying wire with opposite current would have zero effect if the current on the two wires is exact.
- 3. induced current in a coil around the loop of the wires if the current conservation is broken, which triggers the GFCI.

Kronecker Delta and Levi Epsilon

Definitions

Below is the definition for Kronecker Delta

$$\delta_{ij} = 1 \text{ if } i = j$$

 $\delta_{ij} = 0 \text{ if } i \neq j$

Below is the definition for Levi Epsilon

$$\epsilon_{ijk} = 1$$
 if i, j, k are cyclic $\epsilon_{ijk} = -1$ if i, j, k are anti-cyclic $\epsilon_{ijk} = 0$ if i, j, k for other cases

Using Enistine's sum convention, we can write vector operators such as dot products and cross products using this convention:

1.
$$\vec{A} \cdot \vec{B} = A_1 B_1 + A_2 B_2 + A_3 B_3 = \sum_i A_i B_i = \sum_i \sum_j A_i \delta_{ij} B_j$$

$$2. \left(\vec{A} \times \vec{B} \right)_i = \epsilon_{ijk} A_j B_k$$

Additionally, we can derive some properties of these two special functions:

1.
$$\epsilon_{ijk}\epsilon_{ilm} = \delta_{jl}\delta_{km} - \delta_{jm}\delta_{kl}$$

2.
$$\delta_{ii} = 3$$

With such notation in mind, we can simplify $\vec{\nabla} \times (\vec{\nabla} \times \vec{A}) = \vec{\nabla} (\vec{\nabla} \cdot \vec{A}) - \nabla^2 \vec{A}$:

Current Conservation

Does the principle of the current consevation (or charge conservation) is apparent in the maxwell's equation?

Note that the concept of current conservation is the same as if the following equality is true:

$$\frac{\partial \rho}{\partial t} + \vec{\nabla} \cdot \vec{J} = 0$$

Which indicates that the change in charge density over time has to be explained by a divergence of current.

Prove

From Maxwell's equations, we have:

$$\vec{\nabla} \cdot E = \frac{\rho}{\epsilon_0}$$