```
DECLARE (N, R) FIXED BINARY(31);
DECLARE YES BIT(1) INITIAL ('1'B), NO BIT(1) INITIAL ('0'B);
DECLARE PRIME BIT(1);
DO WHILE (YES);
  GET LIST(N);
   IF N <= 1 THEN
     FUT EDIT ('ILLEGAL INPUT N =', N, ' <= 1')
            (SKIP, X(10), A, F(5), A);
  ELSE DO:
     PRIME = YES;
      IF N > 2 & MOD(N, 2) = 0 THEN
        PRIME = NO;
      DO R = 3 TO SQRT(N) BY 2 WHILE (PRIME = YES);
         IF MOD(N, R) = 0 THEN
           PRIME = NO;
      END;
      IF PRIME THEN
        PUT EDIT (N, ' IS A PRIME NUMBER') (SKIP, F(15), A);
        PUT EDIT (N, ' IS NOT A PRIME NUMBER') (SKIP, F(15), A);
  END;
END:
```

This version is slightly longer, but markedly easier to understand. And it has no duplicated PUT statement either.

Don't strain to re-use code; reorganize instead.

A faster-running program is often the by-product of clear, straightforward code. As an example, this program computes n! for n = 3, 5, ..., 49.

```
C FACTORIAL PROGRAM

DOUBLE PRECISION FACTOR, X

NAMELIST /OUT/I, FACTOR

DO 100 I =3,50,2

FACTOR = I

J =I-1

DO 200 K=1,J

X=K

200 FACTOR = FACTOR*X

100 WRITE (6,OUT)

STOP

END
```

Admittedly one does not compute a table of odd factorials very often, but this program is needlessly complicated and wasteful, because it recomputes n! from scratch for each n, instead of just multiplying the previous value by  $n \times (n-1)$ . Here's the simpler version: