OpenCore Install Guide

Why OpenCore over Clover and others

USB Creation

Creating the USB <

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

config.plist Setup

Configs

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist >

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot Process

System Debugging: In-depth

Post Install

Post-Install ☐

Universal >

Laptop Specifics

Cosmetics

Multiboot

Miscellaneous

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

Desktop Haswell and Broadwell

Support	Version
Initial macOS Support	OS X 10.8, Mountain Lion
Note 1	Haswell iGPUs are only supported up-to macOS 12

Starting Point

So making a config.plist may seem hard, it's not. It just takes some time but this guide will tell you how to configure everything, you won't be left in the cold. This also means if you have issues, review your config settings to make sure they're correct. Main things to note with OpenCore:

GitHub □

Switch theme

Dortania Guides 🔻

- All properties must be defined, there are no default OpenCore will fall back on so do not delete sections unless told **explicitly so**. If the guide doesn't mention the option, leave it at default.
- The Sample.plist cannot be used As-Is, you must configure it to your system
- DO NOT USE CONFIGURATORS, these rarely respect OpenCore's configuration and even some like Mackie's will add Clover properties and corrupt plists!


Now with all that, a quick reminder of the tools we need

- ProperTree □
 - Universal plist editor
- GenSMBIOS ☑
 - For generating our SMBIOS data
- Sample/config.plist ☐
 - See previous section on how to obtain: config.plist Setup

WARNING

Read this guide more than once before setting up OpenCore and make sure you have it set up correctly. Do note that images will not always be the most up-to-date so please read the text below them, if nothing's mentioned then leave as default.

ACPI



Add

Info

This is where you'll add SSDTs for your system, these are very important to booting macOS and have many uses like USB maps ☐, disabling unsupported GPUs and such. And with our system, it's even required to boot. Guide on making them found here: Getting started with ACPI

For us we'll need a couple of SSDTs to bring back functionality that Clover provided:

Required SSDTs	Description
SSDT-PLUG ☑	Allows for native CPU power management on Haswell and newer, see Getting Started With ACPI Guide for more details.
SSDT-EC □	Fixes the embedded controller, see Getting Started With ACPI Guide ☐ for more details.

Note that you **should not** add your generated DSDT.aml here, it is already in your firmware. So if present, remove the entry for it in your config.plist and under EFI/OC/ACPI.

€ © OpenCore Install GuideSwitch theme GitHub ☑

Why OpenCore over Clover and others

USB Creation

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo UEFI

Cleaning up

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues
Userspace Issues

Post-Install Issues

Post-Install Issues

OpenCore Debugging

Miscellaneous Issues

Lie de cata a dia a the access

Understanding the macOS Boot Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal

Laptop Specifics >

Cosmetics

Multiboot

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

EFI/OC/ACPI folder and must be specified in your config under ACPI -> Add as well.

Delete

This blocks certain ACPI tables from loading, for us we can ignore this.


Patch

This section allows us to dynamically modify parts of the ACPI (DSDT, SSDT, etc.) via OpenCore. For us, our patches are handled by our SSDTs. This is a much cleaner solution as this will allow us to boot Windows and other OSes with OpenCore

Quirks

Settings relating to ACPI, leave everything here as default as we have no use for these quirks.

Booter



This section is dedicated to quirks relating to boot.efi patching with OpenRuntime, the replacement for AptioMemoryFix.efi

MmioWhitelist

This section is allowing spaces to be passthrough to macOS that are generally ignored, useful when paired with DevirtualiseMmio

Quirks

Info

Settings relating to boot.efi patching and firmware fixes, for us, we leave it as default

► More in-depth Info

DeviceProperties

€ OpenCore Install Guide
Switch theme

Why OpenCore over Clover and others

USB Creation

Creating the USB 🔻

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo UEFI

Cleaning up

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues
Userspace Issues

Post-Install Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal

Laptop Specifics >

Cosmetics

Multiboot >

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU


macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits



GitHub ☐

Add

Sets device properties from a map.

PciRoot(0x0)/Pci(0x2,0x0)

This section is set up via WhateverGreen's **Framebuffer Patching Guide** ☑ and is used for setting important iGPU properties.

The config.plist doesn't already have a section for this so you will have to create it manually.

AAPL, ig-platform-id is what macOS uses to determine how the iGPU drivers interact with our system, and the two values choose between are as follows:

AAPL,ig-platform- id	Comment
0300220D	Used when the Desktop Haswell iGPU is used to drive a display
04001204	Used when the Desktop Haswell iGPU is only used for computing tasks and doesn't drive a display
07002216	Used when the Desktop Broadwell iGPU is used to drive a display

I added another portion as well that shows a device-id fake in case you have an HD 4400 which is unsupported in macOS.

The device-id fake is set up like so:

• 12040000 - this is the device id for HD 4600 which does have support in macOS

We also add 3 more properties, framebuffer-patch-enable, framebuffer-stolenmem and framebuffer-fbmem. The first enables patching via WhateverGreen.kext, the second sets the min stolen memory to 19MB and third sets the framebuffer memory to 9MB. This is usually unnecessary, as this can be configured in BIOS(64MB recommended) but required when not available.

• Note: Headless framebuffers(where the dGPU is the display out) do not need framebuffer-patch-enable , framebuffer-stolenmem and framebuffer-fbmem

Key	Туре	Value
AAPL,ig-platform-id	Data	0300220D
framebuffer-patch-enable	Data	01000000
framebuffer-stolenmem	Data	00003001
framebuffer-fbmem	Data	00009000
device-id	Data	12040000

(This is an example for a desktop HD 4400 without a dGPU and no BIOS options for iGPU memory)

Key	Туре	Value
AAPL,ig-platform-id	Data	07002216
framebuffer-patch-enable	Data	01000000
framebuffer-stolenmem	Data	00003001
framebuffer-fbmem	Data	00009000

(This is an example for a desktop Iris Pro 6200 and no BIOS options for iGPU memory)

PciRoot(0x0)/Pci(0x1b,0x0)

Why OpenCore over Clover and others

USB Creation

Creating the USB <

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal >

Laptop Specifics >

Cosmetics Multiboot

Miscellaneous

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Clover Conversion ☐

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

• You can delete this property outright as it's unused for us at this time

For us, we'll be using the boot-arg alcid=xxx instead to accomplish this. alcid will override all other layout-IDs present. More info on this is covered in the Post-Install Page

Delete

Removes device properties from the map, for us we can ignore this

Kernel



Add

Here's where we specify which kexts to load, in what specific order to load, and what architectures each kext is meant for. By default we recommend leaving what ProperTree has done, however for 32-bit CPUs please see below:

► More in-depth Info

Emulate

Needed for spoofing unsupported CPUs like Pentiums and Celerons

- Cpuid1Mask: Leave this blank
- Cpuid1Data: Leave this blank

Force

Used for loading kexts off system volume, only relevant for older operating systems where certain kexts are not present in the cache(ie. IONetworkingFamily in 10.6).

For us, we can ignore.

Block

Blocks certain kexts from loading. Not relevant for us.

Patch

Patches both the kernel and kexts.

Why OpenCore over Clover and others

USB Creation

Creating the USB 🔻

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI☐

config.plist Setup

Configs

Intel Desktop config.plist 🔻

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

Cleaning up

UEFI

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist ►

AMD Desktop config.plist ►

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues
Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ☐

Universal >

Cosmetics

Multiboot >

Miscellaneous >

Laptop Specifics >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

Quirks

Info

Settings relating to the kernel, for us we'll be enabling the following:

Quirk	Enabled	Comment
AppleCpuPmCfgLock	NO	Need if running 10.10 or older and cannot disable CFG-Lock in the BIOS
AppleXcpmCfgLock	YES	Not needed if CFG-Lock is disabled in the BIOS
DisableloMapper	YES	Not needed if VT-D is disabled in the BIOS
LapicKernelPanic	NO	HP Machines will require this quirk
PanicNoKextDump	YES	
PowerTimeoutKernelPanic	YES	
XhciPortLimit	YES	Disable if running macOS 11.3+

► More in-depth Info

Scheme

Settings related to legacy booting(ie. 10.4-10.6), for majority you can skip however for those planning to boot legacy OSes you can see below:

► More in-depth Info

Misc

• • •	Volumes/INSTALL MAC/EFI/OC/	config.plist - Edited
Key	Туре	Value
Root	Dictionary	8 key/value pairs
> ACPI	Dictionary	4 key/value pairs
> Booter	Dictionary	3 key/value pairs
> DeviceProperties	Dictionary	2 key/value pairs
> Kernel	Dictionary	7 key/value pairs
∨ Misc	Dictionary	7 key/value pairs 7 key/value pairs
BlessOverride	Array	0 children
∨ Boot	Dictionary	13 key/value pairs
ConsoleAttributes	* Number	0
HibernateMode	* String	None
HideAuxiliary	# String # Boolean	True
LauncherOption	* String	Disabled
Launcher Option Launcher Path		Default
PickerAttributes	String	Default 17
	* Number	
PickerAudioAssist	Boolean	False
PickerMode	String	Builtin
PickerVariant	String	Auto
PollAppleHotKeys		False
ShowPicker		True
TakeoffDelay	* Number	0
Timeout	* Number	5
∨ Debug	Dictionary	8 key/value pairs
AppleDebug	Boolean	True
ApplePanic	≉ Boolean	True
DisableWatchDog	Boolean	False
DisplayDelay	≉ Number	0
DisplayLevel	* Number	2147483650
LogModules	\$ String	•
SvsReport	Boolean	False
Target	Number	67
∨ Entries	* Array	1 child
v 0	Dictionary	8 key/value pairs
Arguments	\$ String	
Auxiliary	≉ Boolean	False
Comment	String	Not signed for security reasons
Enabled	≇ Boolean	False
Flavour	String	Auto
Name	String	CustomOS
Path	String	PciRoot(0x0)/Pci(0x1,0x1)/Pci(0x0,0x0)/NVMe(0x1,11-22
TextMode	Boolean	False
∨ Security	Dictionary	13 key/value pairs
AllowSetDefault		True
ApECID	Number ■	0
AuthRestart	≇ Boolean	False
BlacklistAppleUpdate	print Boolean	True
DmgLoading	# String	Signed
EnablePassword		False
ExposeSensitiveData	* Number	6
HaltLevel	* Number	2147483648
PasswordHash	≉ Data	♦
PasswordSalt	* Data	•
ScanPolicy	* Number	^
SecureBootModel	* String	Set SecureBootModel to Disabled If
Vault	s String	Optional you require NVIDIA's web Driver
> Serial	Dictionary	2 key/value pairs

Boot

Why OpenCore over Clover and others

USB Creation

Creating the USB v

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI☐

config.plist Setup

Configs

Intel Desktop config.plist ▼

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

Cleaning up

UEFI

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Understanding the m Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal **•**

Laptop Specifics >

Cosmetics

Multiboot >

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

HideAuxiliary YES Press space to show macOS recovery and other auxiliary entries

GitHub □

► More in-depth Info

Debug

Info

Helpful for debugging OpenCore boot issues(We'll be changing everything but DisplayDelay):

Quirk	Enabled
AppleDebug	YES
ApplePanic	YES
DisableWatchDog	YES
Target	67

► More in-depth Info

Security

Info

Security is pretty self-explanatory, do not skip. We'll be changing the following:

Quirk	Enabled	Comment
AllowSetDefault	YES	
BlacklistAppleUpdate	YES	
ScanPolicy	0	
SecureBootModel	Default	Leave this as Default for OpenCore to automatically set the correct value corresponding to your SMBIOS. The next page goes into more detail about this setting.
Vault	Optional	This is a word, it is not optional to omit this setting. You will regret it if you don't set it to Optional, note that it is case-sensitive

► More in-depth Info

Serial

Used for serial debugging (Leave everything as default).

Tools

Used for running OC debugging tools like the shell, ProperTree's snapshot function will add these for you.

Entries

Used for specifying irregular boot paths that can't be found naturally with OpenCore.

Won't be covered here, see 8.6 of Configuration.pdf ☐ for more info

NVRAM

Why OpenCore over Clover and others

USB Creation

Creating the USB v

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist 🔻

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up
Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist 🕨

Intel HEDT config.plist

AMD Desktop config.plist >

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot Process

System Debugging: In-depth

Post Install

Post-Install ☐

Universal

Laptop Specifics >

Cosmetics

Multiboot

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

Key	Туре	Value
Root	Dictionary	8 key/value pairs
> ACPI	Dictionary	4 key/value pairs
> Booter	Dictionary	3 key/value pairs
> DeviceProperties	Dictionary	2 key/value pairs
> Kernel	Dictionary	7 key/value pairs
> Misc	Dictionary	7 key/value pairs
∨ NVRAM	* Dictionary	5 key/value pairs
∨ Add	Dictionary	3 key/value pairs
✓ 4D1EDE05-38C7-4A6A-9CC6-4BCCA8B38	BC' a Dictionary	1 key/value pair
DefaultBackgroundColor	₽ Data	<00000000>
∨4D1FDA02-38C7-4A6A-9CC6-4BCCA8B30	01(a Dictionary	1 key/value pair
rtc-blacklist	₽ Data	• ************************************
∨7C436110-AB2A-4BBB-A880-FE41995C9F	82 a Dictionary	7 key/value pairs
#INFO (prev-lang:kbd)	s String	en:252 (ABC), set 656e3a323532
ForceDisplayRotationInEFI	* Number	0
SystemAudioVolume	₽ Data	<46>
boot-args	String	-v keepsyms=1 debug=0x100 alcid=1
csr-active-config	property Data property Data	<00000000>
prev-lang:kbd	₽ Data	•
run-eti-upgater	\$ String	NO
∨ Delete	Dictionary	3 key/value pairs
✓ 4D1EDE05-38C7-4A6A-9CC6-4BCCA8B38	BC' : Array	1 child
0	String	DefaultBackgroundColor
∨4D1FDA02-38C7-4A6A-9CC6-4BCCA8B30	01(a Array	1 child
0	* String	rtc-blacklist
∨7C436110-AB2A-4BBB-A880-FE41995C9F	82 a Array	2 children
0	* String	boot-args
1	s String	ForceDisplayRotationInEFI
LegacyOverwrite		False
> LegacySchema	Dictionary	2 key/value pairs
WriteFlash		True
> PlatformInfo	Dictionary	8 key/value pairs
> UEFI	Dictionary	10 key/value pairs

Add

4D1EDE05-38C7-4A6A-9CC6-4BCCA8B38C14

Used for OpenCore's UI scaling, default will work for us. See in-depth section for more info

► More in-depth Info

4D1FDA02-38C7-4A6A-9CC6-4BCCA8B30102

OpenCore's NVRAM GUID, mainly relevant for RTCMemoryFixup users

► More in-depth Info

7C436110-AB2A-4BBB-A880-FE41995C9F82

System Integrity Protection bitmask

• General Purpose boot-args:

boot-args	Description
-v	This enables verbose mode, which shows all the behind-the-scenes text that scrolls by as you're booting instead of the Apple logo and progress bar. It's invaluable to any Hackintosher, as it gives you an inside look at the boot process, and can help you identify issues, problem kexts, etc.
debug=0x100	This disables macOS's watchdog which helps prevents a reboot on a kernel panic. That way you can <i>hopefully</i> glean some useful info and follow the breadcrumbs to get past the issues.
keepsyms=1	This is a companion setting to debug=0x100 that tells the OS to also print the symbols on a kernel panic. That can give some more helpful insight as to what's causing the panic itself.
alcid=1	Used for setting layout-id for AppleALC, see supported codecs to figure out which layout to use for your specific system. More info on this is covered in the Post-Install Page

• GPU-Specific boot-args:

boot-args	Description
agdpmod=pikera	Used for disabling board ID checks on some Navi GPUs (RX 5000 & 6000 series), without this you'll get a black screen. Don't use if you don't have Navi (ie. Polaris and Vega cards shouldn't use this)
-radcodec	Used for allowing officially unsupported AMD GPUs (spoofed) to use the Hardware Video Encoder
radpg=15	Used for disabling some power-gating modes, helpful for properly initializing AMD Cape Verde based GPUs
unfairgva=1	Used for fixing hardware DRM support on supported AMD GPUs
nvda_drv_vrl=1	Used for enabling NVIDIA's Web Drivers on Maxwell and Pascal cards in macOS Sierra and High Sierra

OpenCore Install Guide GitHub □ Switch theme

Why OpenCore over Clover and others

USB Creation

Creating the USB <

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

config.plist Setup

Configs

Intel Desktop config.plist 🔻

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Intel BIOS settings

Cleaning up

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist >

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues Userspace Issues

Post-Install Issues

Miscellaneous Issues OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ☐

Universal >

Cosmetics >

Multiboot

Miscellaneous

Laptop Specifics >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

-wegnoegpu

Used for disabling all other GPUs than the integrated Intel iGPU, useful for those wanting to run newer versions of macOS where their dGPU isn't supported

• csr-active-config: 00000000

- Settings for 'System Integrity Protection' (SIP). It is generally recommended to change this with csrutil via the recovery partition.
- o csr-active-config by default is set to 00000000 which enables System Integrity Protection. You can choose a number of different values but overall we recommend keeping this enabled for best security practices. More info can be found in our troubleshooting page: Disabling SIP
- run-efi-updater: No
 - o This is used to prevent Apple's firmware update packages from installing and breaking boot order; this is important as these firmware updates (meant for Macs) will not work.
- prev-lang:kbd: <>
 - Needed for non-latin keyboards in the format of lang-COUNTRY: keyboard, recommended to keep blank though you can specify it(**Default in Sample config is Russian**):
 - American: en-US:0 (656e2d55533a30 in HEX)
 - Full list can be found in AppleKeyboardLayouts.txt☆
 - Hint: prev-lang:kbd can be changed into a String so you can input en-US:0 directly instead of converting to HEX
 - Hint 2: prev-lang:kbd can be set to a blank variable (eg. <>) which will force the Language Picker to appear instead at first boot up.

Key	Туре	Value
prev-lang:kbd	String	en-US:0

Delete


Info

Forcibly rewrites NVRAM variables, do note that Add will not overwrite values already present in NVRAM so values like boot-args should be left alone. For us, we'll be changing the following:

Quirk	Enabled
WriteFlash	YES

► More in-depth Info

PlatformInfo



Info

For setting up the SMBIOS info, we'll use CorpNewt's GenSMBIOS ☐ application.

For this Haswell example, we chose the iMac15,1 SMBIOS. The typical breakdown is as follows:

SMBIOS	Hardware
iMac14,4	Haswell with only iGPU

Switch theme

Why OpenCore over Clover and others

USB Creation

Creating the USB ▼

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist v

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake
Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ☐

Universal >

Cosmetics

Multiboot >

Miscellaneous >

Laptop Specifics >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

iMac15,1	Haswell with dGPU
iMac16,2	Broadwell

Note: The following SMBIOS are only supported up-to macOS 11, Big Sur. For cases where you must boot Monterey, see below:

GitHub □

► Monterey SMBIOS table

Note 2: All of these SMBIOSes were dropped in macOS Ventura. If running macOS Ventura, use a Kaby Lake SMBIOS.

Run GenSMBIOS, pick option 1 for downloading MacSerial and Option 3 for selecting out SMBIOS. This will give us an output similar to the following:

Type: iMac15,1
Serial: C02M9SYJFY10
Board Serial: C02408101J9G2Y7A8

SmUUID: 7B227BEC-660D-405F-8E60-411B3E4EF055

The Type part gets copied to Generic -> SystemProductName.

The Serial part gets copied to Generic -> SystemSerialNumber.

The Board Serial part gets copied to Generic -> MLB.

The Smuuid part gets copied to Generic -> SystemUUID.

We set Generic -> ROM to either an Apple ROM (dumped from a real Mac), your NIC MAC address, or any random MAC address (could be just 6 random bytes, for this guide we'll use 11223300 0000. After install follow the Fixing iServices page on how to find your real MAC Address)

Reminder that you need an invalid serial! When inputting your serial number in Apple's Check Coverage Page ?, you should get a message such as "Unable to check coverage for this serial number."

Automatic: YES

• Generates PlatformInfo based on Generic section instead of DataHub, NVRAM, and SMBIOS sections

:::

Generic

► More in-depth Info

UEFI

Why OpenCore over Clover and others

USB Creation

Creating the USB •

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

UEFI

Cleaning up

PlatformInfo

Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues
Userspace Issues

Post-Install Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal **•**

Laptop Specifics >

Multiboot

MUITIDOOT

Cosmetics >

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU


macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits



ConnectDrivers: YES

• Forces .efi drivers, change to NO will automatically connect added UEFI drivers. This can make booting slightly faster, but not all drivers connect themselves. E.g. certain file system drivers may not load.

Drivers

Add your .efi drivers here.

Only drivers present here should be:

- HfsPlus.efi
- OpenRuntime.efi
 - ► More in-depth Info

APFS

By default, OpenCore only loads APFS drivers from macOS Big Sur and newer. If you are booting macOS Catalina or earlier, you may need to set a new minimum version/date. Not setting this can result in OpenCore not finding your macOS partition!

macOS Sierra and earlier use HFS instead of APFS. You can skip this section if booting older versions of macOS.

APFS Versions

Both MinVersion and MinDate need to be set if changing the minimum version.

macOS Version	Min Version	Min Date
High Sierra (10.13.6)	748077008000000	20180621
Mojave (10.14.6)	945275007000000	20190820
Catalina (10.15.4)	1412101001000000	20200306
No restriction	-1	-1

Audio

Related to AudioDxe settings, for us we'll be ignoring(leave as default). This is unrelated to audio support in macOS.

• For further use of AudioDxe and the Audio section, please see the Post Install page: Add GUI and Boot-chime

Why OpenCore over Clover and others

USB Creation

Creating the USB 🔻

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI ☐

config.plist Setup

Configs

Intel Desktop config.plist

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up
Intel BIOS settings

Skylake

Kaby Lake

Coffee Lake

Comet Lake

Intel Laptop config.plist

Intel HEDT config.plist

AMD Desktop config.plist

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues

Userspace Issues

Post-Install Issues

Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal **•**

Laptop Specifics >

Cosmetics

Multiboot

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

Output

Relating to OpenCore's visual output, leave everything here as default as we have no use for these quirks.

► More in-depth Info

ProtocolOverrides

Mainly relevant for Virtual machines, legacy macs and FileVault users. See here for more details: Security and FileVault

GitHub □

Quirks

Info

Relating to quirks with the UEFI environment, for us we'll be changing the following:

Quirk	Enabled	Comment
IgnoreInvalidFlexRatio	YES	
UnblockFsConnect	NO	Needed mainly by HP motherboards

► More in-depth Info

ReservedMemory

Used for exempting certain memory regions from OSes to use, mainly relevant for Sandy Bridge iGPUs or systems with faulty memory. Use of this quirk is not covered in this guide

Cleaning up

And now you're ready to save and place it into your EFI under EFI/OC.

For those having booting issues, please make sure to read the **Troubleshooting section** first and if your questions are still unanswered we have plenty of resources at your disposal:

Intel BIOS settings

• Note: Most of these options may not be present in your firmware, we recommend matching up as closely as possible but don't be too concerned if many of these options are not available in your BIOS

Disable

- Fast Boot
- Secure Boot
- Serial/COM Port
- Parallel Port
- VT-d (can be enabled if you set DisableIoMapper to YES)
- Compatibility Support Module (CSM) (Must be off in most cases, GPU errors/stalls like gIO are common when this option is enabled)
- Thunderbolt (For initial install, as Thunderbolt can cause issues if not setup correctly)
- Intel SGX
- Intel Platform Trust
- CFG Lock (MSR 0xE2 write protection)(This must be off, if you can't find the option then enable AppleXcpmCfgLock under Kernel -> Quirks. Your hack will not boot with CFG-Lock enabled)
 - For 10.10 and older, you'll need to enable AppleCpuPmCfgLock as well

Enable

- VT-x
- Above 4G Decoding
- Hyper-Threading
- Execute Disable Bit

EHCI/XHCI Hand-off

- OS type: Windows 8.1/10 UEFI Mode (some motherboards may require "Other OS" instead)
- DVMT Pre-Allocated(iGPU Memory): 64MB or higher
- SATA Mode: AHCI

Once done here, we need to edit a couple extra values. Head to the Apple Secure Boot Page

Skylake →

GitHub ☐

USB Creation

Creating the USB ▼

Making the installer in macOS

Making the installer in Windows

Making the installer in Linux

Adding The Base OpenCore Files

Gathering files

Getting started with ACPI☐

config.plist Setup

Configs

Intel Desktop config.plist ▼

Penryn

Clarkdale

Sandy Bridge

Ivy Bridge

Haswell

Starting Point

ACPI

Booter

DeviceProperties

Kernel

Misc

NVRAM

PlatformInfo

UEFI

Cleaning up
Intel BIOS settings

......

Skylake

Kaby Lake

Coffee Lake
Comet Lake

Intel Laptop config.plist >

Intel HEDT config.plist

AMD Desktop config.plist >

Apple Secure Boot

Installation

Installation Process

Troubleshooting

General Troubleshooting

OpenCore Boot Issues

Kernel Issues
Userspace Issues

Post-Install Issues
Miscellaneous Issues

OpenCore Debugging

Understanding the macOS Boot

Process

System Debugging: In-depth

Post Install

Post-Install ⊡

Universal >

Laptop Specifics
Cosmetics

Multiboot

Miscellaneous >

Extras

Fixing KASLR slide values

Disabling GPU

macOS 13: Ventura

Clover Conversion ☐

Choosing the right SMBIOS

Misc

Supporting the guides

Credits

← Ivy Bridge