Termite2 - Installation

Software Requisites:

- · Java SE Development Kit 8;
- Apache Tomcat Server v9; *
- Localhost network ports available for Termite2-Cli: 8081; *
- Local network ports available for Termite2Server: 7000, (8085 and 8095); **
- Emulator instances must be provided by Android SKD;
- Most up to date Android SDK command line tools.
- * This is only needed if the user intends on using the Termite2 GUI.
- ** These ports can be user configured by accessing the file config/communicationports.txt on the Termite2Server folder.

Introduction

Termite2 is a testbed for developing mobile applications that use Encounter Networks as communication technology.

Termite2 system is composed by 3 main components:

- **Termite2-API** used on the application similar to the old Termite-API version (see https://nuno-santos.github.io/termite/index.html);
- Termite2-Cli responsible for creating and manipulating the emulated network;
- Termite2Server responsible for managing the Android emulators used on the emulated network.

Termite 2 supports a distributed system architecture; this means that the emulated network provided by Termite2-Cli can run on an independent machine while all the Android emulators can run on other machines. To achieve this the Termite2Server must first be installed and run on the machine(s) that the user intends on running the emulators. Figure depicts a simplified view of Termite2's distributed architecture.

To install each component on the desired machine(s) just follow the steps below.




Figure 1 - Termite2 distributed system architecture.

Termite2 Server

- 1. Set the following environmental variables:
 - TERMITE2_SERVER_PATH="path to Termite2Server folder"
 - ANDROID_SDK_PATH="path to android studio sdk"
- 2. Run the Termite2Server:
 - In Linux or Mac OS run the script termite2server.sh
 - In Windows run the batch file termite2server.bat
- 3. If everything goes well the following output is expected:

Termite2 Server ONLINE on network 192.168.1.X: Working Directory = .../Termite2 Server TERMITE2_PLATFORM = mac ANDROID_SDK_PATH = .../Library/Android/sdk Type "help" or "h" for the full command list

Termite2Server is now up and ready; now let's install Termite2-Cli.

IMPORTANT (Android auth_token ERRORS):

For Termite2Server to be able to properly create, delete and manage emulator instances, make sure that the authentication token necessary to execute such operations is changed to null. To do this you need to access the following file ".emulator_console_auth_token" (its location varies from user to user), delete its contents and let it blank. DO NOT DELETE THE FILE.

Termite2 Client

- 1. Set the following environmental variables:
 - TERMITE2_CLI_PATH="path to Termite2-Cli folder"
 - TOMCAT_PATH=".../apache-tomcat-9.0.34" (This variable is optional and its only needed if the user intends on using Termite2 GUI; see next section)
- 2. Set the Termite2Server(s) network(s):

For Termite2-Cli to connect with the Termite2Server(s) with first need to indicate to Termite2-Cli where each Termite2Server is running. To do this we need to provide the network ip of each machine running Termite2Server.

Open the text file at ~/Termite2-Cli/config/networks.txt Here you must type each Termite2Server network and the clientport you wish the Termite2-cli to connect to, ex:

192.168.1.1:8085 192.168.1.2:8085 192.168.1.3:8085

. . .

- 3. Run the Termite2-Cli:
 - In Linux or Mac OS run the script termite2cli.sh
 - In Windows run the batch file termite2cli.bat
- 4. If everything goes well the following output is expected:

Connection/s to Termite2Server/s established without errors.

Termite UI Options:

Type '1' to use the default console UI.

Type '2' to use the Webpage GUI.

>

Termite2 Client is now up and ready; the user can now choose the desired user interface. Option 1 for the default console UI or option 2 to use the Termite2's graphical user interface (Termite2 GUI) that runs on Tomcat and is accessed through the url: localhost:8080/Termite2UI/index.html; to set up this new user interface please see the next section.

Termite2 GUI *

The new Termite2 user interface uses the Google maps API in order to better display the virtual nodes created on the emulated network and their interactions. Because of this it is necessary to first set the required Google Maps API key with a set of active APIs. This is done as follows:

- 1. To get the Api key with the APIs; Roads API, Directions API and Maps Javascript API, please follow the oficial google documentation at https://developers.google.com/maps/documentation/javascript/get-api-key.
- 2. After generating your key and activating the APIs place your api key (ONLY THE KEY) inside the text file at ".../Termite2-Cli/ui/Termite2UI/apikey.txt".

Everything is set and you can now use the new Termite2 GUI by selecting option 2 when starting Termite2-Cli.

* This section is optional and it is only needed if the user intends on using Termite2 GUI.