

# IRC Library for Python 3 https://github.com/nutjob-laboratories/erkle

## Version 0.015





Summary	
Philosophy	
Low Level	
Why not use Twisted or irclib?	
Requirements	3
Python libraries	
Erkle Object	
Creation	
Methods	
Attributes	_
Hook decorator and events	
Events	
Event sets	
erkle.events.dump	
erkle.events.messages	
Examples	10
Greeter Bot	
Auto-Op Bot	
License	11

### **Summary**

*Erkle* is a low level, event-driven IRC library for Python 3, designed for both quick and dirty IRC bots or for full blown IRC clients.

#### **Philosophy**

*Erkle* was designed with the following in mind:

- **Little or no boilerplate code.** To write a IRC bot or client, the programmer should only have to write the functionality he or she wants to employ.
- Modular code. Most IRC bots or clients will require some common functionality. The
  programmer shouldn't have to <u>reinvent the wheel</u> every time they create a new bot or
  client. Code should be able to be isolated into <u>modules</u> for repeated use.
- **Standalone code.** Functionality should stand on its own, and not be implemented by subclass or object inheritance.
- **Little or no library requirements.** The library should use the Python standard library over third party libraries whenever possible.

#### Low Level

To use *Erkle*, understanding IRC and the IRC protocol is a necessity. *Erkle* is designed to be low level, meaning its interface is influenced by the protocol itself. Since there's no syntactic sugar to hide the difficult or complex parts of the protocol, *Erkle* code should be easy to understand if you understand the underlying protocol.

The IRC protocol is defined in a series of RFC documents:

- RFC 1459
- RFC 2812

#### Why not use **Twisted** or **irclib**?

TODO: write this section

## Requirements

*Erkle* uses, for the most part, only modules in the Python standard library. To use <u>SSL/TLS</u> to connect to IRC servers, however, the <u>pyOpenSSL</u> library must be installed. To install this library via the Python package installer, <u>pip</u>, execute this command:

pip install pyOpenSSL

## **Python libraries**

Erkle uses the following modules from the standard library:

- sys
- socket
- collections
- string
- threading
- ssl (only if it is available)

# **Erkle Object**

## Creation

Erkle is an object that creates and manages an IRC connection. Erkle() can take eight arguments (see below). Once the Erkle object is created, use the connect() or spawn() methods to cause the object to connect to the IRC server.

Argument	Туре	Description	
nickname	string	Sets the nickname the IRC client connection will use.	
username	string	Sets the username the IRC client connection will use.	
realname	string	Sets the realname the IRC client connection will use.	
server	string	Sets the IP/hostname of the IRC server to connect to.	
port	integer	Sets the port on the IRC server to connect to. Default: 6667	
password string Sets the password the IRC client connection will send to the server if requirements to be password to be passw			
SSL	boolean	Sets whether to use SSL to connect to the IRC server; set to True to use SSL. Default: False	
encoding	string	What string encoding type the server connection uses. Default: utf-8	

#### **Methods**

Method	Arguments	Description
connect	None.	Connects to the IRC server.
spawn	None.	Spawns a new thread, and connects to IRC using that thread. A reference to the created thread is stored in the <i>Erkle</i> object. The <i>Thread</i> object's "name" attribute will be set to <b>server:port</b> . For example, if the thread's <i>Erkle</i> object is connected to an IRC server at "irc.efnet.org" on port 7000, the thread's "name" will be irc.efnet.org:7000.
thread	None.	If <i>Erkle</i> 's connection was started with the spawn() method, the object's <i>Thread</i> object (see the Python documentation for the <i>Threading</i> library) will be returned; otherwise, <b>None</b> is returned.
send	• data (string)	Sends a "raw" message to the IRC server; the message will not be processed in any way before being sent.
privmsg	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a chat message to a channel or user. This can also be called via an alias: msg ()
action	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a CTCP action message to a channel or user. This can also be called via an alias: me ()
notice	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a notice to a user or channel.
join	<ul><li>channel (string)</li><li>key (string)</li></ul>	Joins a channel.

part	<ul><li>channel (string)</li><li>reason (string)</li></ul>	Leaves a channel.
kick	<ul><li>target (string)</li><li>channel (string)</li><li>reason (string)</li></ul>	Kicks a user from a channel (the client must be a channel operator in the channel).
ban	• channel (string) • mask (string)	Bans any user who's nick/host/username matches a mask from a channel (the client must be a channel operator in the channel). See <a href="RFC 1459"><u>RFC 1459</u></a> for more information on masks.
unban	<ul><li>channel (string)</li><li>mask (string)</li></ul>	Removes a channel ban from a channel (the client must be a channel operator in the channel).
lock	<ul><li>channel (string)</li><li>key (string)</li></ul>	Sets a channel key on a channel (the client must be a channel operator in the channel).
unlock	<ul><li>channel (string)</li><li>key (string)</li></ul>	Removes a channel key from a channel (the client must be a channel operator in the channel).
mode	<ul><li>target (string)</li><li>mode (string)</li></ul>	Sets a mode on a channel or user. See <u>RFC 1459</u> for more information on modes.
invite	<ul><li>user (string)</li><li>channel (string)</li></ul>	Sends a channel invitation to a user.
away	• message (string)	Sets the client to "away" on the IRC server.
back	None.	Sets the client to "back" on the IRC server.
whois	• user (string)	Requests WHOIS data on a user from the server. When the WHOIS data is received, the whois event will be triggered.
list	None.	Requests a list of channels from the server. When the channel list is received, the list event will be triggered.
quit	• reason (string)	Disconnects from the IRC server.

#### **Attributes**

An *Erkle* also has a number of attributes that store information about the server and client. Not all of these values will be available immediately; the values are populated as the server sends the appropriate data to the client. Most of these values should be available by the time the **welcome** event is triggered.

Attribute	Туре	Description
nickname	string	The client's nickname.
username	string	The client's username.
realname	string	The client's realname.
server	string	The server's address.
port	integer	The server's port.
password	string	The password used to connect to the server, if there is one.
usessl	boolean	Whether SSL is being used for this connection or not.
hostname	string	The server's hostname.
software	string	The server's software.

options	list	A list of the options the server supports.
network	string	The network the server belongs to.
commands	list	A list of commands supported by the server.
maxchannels	integer	The maximum number of channels a client can join on the server.
maxnicklen	integer	The maximum number of characters allowed for a nickname on the server.
channellen	integer	The maximum number of characters allowed for a channel name on the server.
topiclen	integer	The maximum number of characters allowed for a channel topic on the server.
kicklen	integer	The maximum number of characters allowed for a kick message on the server.
awaylen	integer	The maximum number of characters allowed for an away message on the server.
maxtargets	integer	The maximum number of targets a message can be sent to on a server.
modes	integer	The maximum number of channel modes that can be set on the server.
chantypes	list	What channel types the server uses.
prefix	list of lists	What channel status prefixes the server uses; each entry contains a list with the first value being the status type, and the second value being the prefix used for that type.
chanmodes	list	What channel modes the server uses.
casemapping	string	The casemapping the server uses.
spoofed	string	If the client's host is spoofed by the server, then the spoofed host name will be stored here.
users	dictionary of lists	An in-memory database of channel users. The dictionary uses channel names for keys, and each dictionary entry is a list of the named channel's users.
topic	dictionary	An in-memory database of channel topics. The dictionary uses channel names for keys, and each dictionary entry is a string containing the named channel's topic (or <i>None</i> if the topic is blank or unknown).

#### Hook decorator and events

Included with the *Erkle* object is the *hook* decorator. The *hook* decorator is used to decorate<sup>1</sup> functions that should be executed when specific events occur; this is called "hooking" an event. *hook* exposes one method: **event**. To hook an event, pass the name of the event (as a string) as the only argument to the **event** method. For example, to hook an event named "connect", the decorator required would look like:

@hook.event("connect")

<sup>1 &</sup>lt;a href="https://www.python.org/dev/peps/pep-0318/">https://www.python.org/dev/peps/pep-0318/</a>

Events can be hooked to an unlimited number of functions. Function hooks will be executed in the order in which they were hooked.

There are 23 IRC events that can be hooked. The hooked function can take a number of different arguments, depending on the event. The first (and sometimes only) argument passed to every hooked function is **connection**, which is the *Erkle* object running the IRC connection.

#### **Events**

Event	Arguments	Description
connect	Erkle object	Triggered when the Erkle object connects to IRC.
motd	<ul><li>Erkle object</li><li>message (string)</li></ul>	Triggered when the server's message of the day (MOTD) is received.
welcome	Erkle object	Triggered when registration with the IRC server is complete.
nick-taken	<ul><li>Erkle object</li><li>nickname (string)</li></ul>	Triggered when <i>Erkle</i> 's nickname is already taken during registration; <b>nickname</b> contains the new nickname.
ping	Erkle object	Triggered when the IRC server sends <i>Erkle</i> a PING command.
join	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> </ul>	Triggered whenever a user joins a channel <i>Erkle</i> is in. <b>nickname</b> contains the user's nickname, <b>host</b> contains the user's host, and <b>channel</b> contains the name of the channel joined. This event will trigger when the <i>Erkle</i> object joins a channel as well.
part	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>reason (string)</li> </ul>	Triggered whenever a user leaves a channel <i>Erkle</i> is in. <b>nickname</b> contains the nickname of the user, <b>host</b> contains the user's host, <b>channel</b> contains the name of the channel, and <b>reason</b> contains the reason why the user quit. If no reason has been provided, <b>reason</b> will be set to <b>None</b> .
quit	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>reason (string)</li> </ul>	Triggered when a user quits the IRC server. <b>nickname</b> contains the user's nickname, <b>host</b> contains the user's host, and <b>reason</b> contains the reason why the user quit. If no reason has been provided, <b>reason</b> will be set to <b>None</b> .
nick	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>new_nickname (string)</li> </ul>	Triggered when a user changes their nickname. <b>nickname</b> contains the user's original nickname, <b>host</b> contains the user's host, and <b>new_nickname</b> contains the user's new nickname.
names	<ul> <li>Erkle object</li> <li>channel (string)</li> <li>users (list)</li> </ul>	Triggered when <i>Erkle</i> generates a list of users in a specific channel. This list will be regenerated every time a user changes their nick, quits IRC, or leaves a channel. <b>channel</b> contains the name of the channel, and <b>users</b> contains a list of users in that channel. If the server is configured for it, each user entry will contain the user's nickname and host, in the form <i>nickname!</i> <b>username@hostname</b> ; otherwise, the entry will only contain the user's nickname. Channel status symbols ('@' for channel operators, '+' for voiced users, etc.) are prefixed to each user's nickname.  Generated user lists are stored in the <i>Erkle</i> object, accessible in the <b>users</b> attribute.

public	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>message (string)</li> </ul>	Triggered when <i>Erkle</i> receives a public message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, <b>channel</b> contains the name of the channel the message was sent to, and <b>message</b> contains the message contents.
private	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>message (string)</li> </ul>	Triggered when <i>Erkle</i> receives a private message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, and <b>message</b> contains the message contents.
notice	<ul><li>Erkle object</li><li>sender (string)</li><li>message (string)</li></ul>	Triggered when <i>Erkle</i> receives a notice message. <b>sender</b> contains the nickname of the sender, and <b>message</b> contains the message contents.
action	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>target (string)</li> <li>message (string)</li> </ul>	Triggered when <i>Erkle</i> receives a CTCP action message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, <b>target</b> contains the name of the channel or username the message was sent to, and <b>message</b> contains the message contents.
away	<ul><li>Erkle object</li><li>nickname (string)</li><li>reason (string)</li></ul>	Triggered when <i>Erkle</i> receives an "away" notification.
back	Erkle object	Triggered when <i>Erkle</i> unsets itself as "away".
topic	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>topic (string)</li> </ul>	Triggered when <i>Erkle</i> receives a channel topic update. <b>nickname</b> contains the topic setter's nickname, <b>host</b> contains the setter's host, <b>channel</b> contains channel name, and <b>topic</b> contains the channel's topic. If the topic is set to an empty string, <b>topic</b> is set to <i>None</i> .
mode	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>target (string)</li> <li>mode (string)</li> </ul>	Triggered when <i>Erkle</i> receives a channel or user mode change notification. <b>nickname</b> contains the mode setter's nickname, <b>host</b> contains the setter's host, <b>target</b> contains the user or channel the mode applies to, and <b>mode</b> contains the modes (and mode parameters) being set. If the mode is being set by the server, <b>nickname</b> and <b>host</b> will be set to the server's hostname.
kick	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>target (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>Erkle</i> receives a kick notification. <b>nickname</b> contains the kicker's nickname, <b>host</b> contains the kicker's host, <b>channel</b> contains the channel being kicked from, <b>target</b> contains the nickname of the user being kicked, and <b>reason</b> contains the reason given for the kick. If no reason is provided, <b>reason</b> will be set to <i>None</i> .
kicked	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>Erkle</i> is kicked from a channel. <b>nickname</b> contains the kicker's nickname, <b>host</b> contains the kicker's host, <b>channel</b> contains the channel being kicked from, and <b>reason</b> contains the reason given for the kick. If no reason is provided, <b>reason</b> will be set to <i>None</i> .
invite	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> </ul>	Triggered whenever <i>Erkle</i> receives a channel invitation. <b>nickname</b> contains the inviter's nickname, <b>host</b> contains the inviter's host, and <b>channel</b> contains the channel <i>Erkle</i> is being invited to.

whois	<ul> <li>Erkle object</li> <li>nickname (string)</li> <li>username (string)</li> <li>host (string)</li> <li>realname (string)</li> <li>server (string)</li> <li>idle (integer)</li> <li>signon (string)</li> <li>channels (list)</li> <li>privileges (string)</li> </ul>	Triggered whenever <i>Erkle</i> receives WHOIS data from the server. <b>nickname</b> contains the user's nickname, <b>username</b> contains the user's username, <b>host</b> contains the user's host, <b>realname</b> contains the user's realname, <b>server</b> contains the server the user is connected to, <b>idle</b> contains the number of seconds the user has been idle, <b>signon</b> contains the timestamp of when the user signed on to the server, <b>channels</b> contains a list of channels (with status) the user is in, and <b>privileges</b> contains any special privileges the user has (or <i>None</i> if the user has none).
list	<ul><li>Erkle object</li><li>channels (list of lists)</li></ul>	Triggered whenever <i>Erkle</i> receives a channel list from the server. Each entry in <b>channels</b> is a list that contains, in this order:  0. channel name (string)  1. number of users in the channel (integer)  2. channel topic (string) ( <i>None</i> if there's no topic)
line	<ul><li>Erkle object</li><li>line (string)</li></ul>	Triggered whenever <i>Erkle</i> receives a line of data from the server.
error	<ul> <li>Erkle object</li> <li>code (string)</li> <li>subject (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>Erkle</i> receives an error message from the server. <b>code</b> is the error's code (from the IRC RFC documents), <b>subject</b> is the "subject" of the error (if there is no "target", <b>subject</b> will be set to <i>None</i> ), and <b>reason</b> contains a short description of the error.

*Erkle*'s **connect()** is a blocking function, so hooked functions should be declared *before* **connect()** is called.

#### **Event sets**

*Erkle* contains a few sets of pre-written event handlers; they reside in the **erkle.events** package. To use an event set, simply import it.

Package	erkle.events.dump
Hooks	action, away, back, connect, join, kick, kicked, mode, motd, names, nick, nick-taken, notice, part, ping, private, public, quit, topic, welcome
Description	Prints event-specific data from every <b>Erkle</b> event to the console.

Package	erkle.events.messages
Hooks	notice, private, public
Description	Prints incoming messages to the console.

## **Examples**

#### **Greeter Bot**

Here's an example bot that connect to an IRC server, join a channel, and greets everyone who joins that channel by name:

```
from erkle import *

SERVER = "irc.efnet.org"
PORT = 6667
CHANNEL = "#erklebot"

@hook.event("welcome")
def welcomed(connection):
    connection.join(CHANNEL)

@hook.event("join")
def joined(connection, nickname, host, channel):
    connection.msg("Welcome to "+CHANNEL+", "+nickname+"!")

bot = Erkle("greetbot", "greetbot", "Erkle Bot", SERVER, PORT)
bot.connect()
```

#### **Auto-Op Bot**

This bot will automatically grant channel operator status to any user in a list of nicknames contained in the script. The bot will have to be granted channel operator status by another channel operator, however.

```
from erkle import *
SERVER = "irc.efnet.org"
PORT = 6667
CHANNELS = [ "#erklebot", "#erklesupport", "#pythonfans" ]
OPERATORS = [ "alice", "bob", "carol", "dave" ]
@hook.event("welcome")
def welcomed(connection):
  for channel in CHANNELS:
    connection.join(channel)
@hook.event("join")
def joined(connection, nickname, host, channel):
  if nickname in OPERATORS:
    connection.mode(channel, "+o "+nickname)
    connection.privmsq(nickname, "Welcome back, "+nickname)
bot = Erkle("greetbot", "greetbot", "Erkle Bot", SERVER, PORT)
bot.connect()
```

. . .

## License

#### **MIT License**

Copyright (c) 2019 Dan Hetrick

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.