

**Erkle** is an event-driven IRC library for Python 3. Functions can be "hooked" to a specific event by using a function decorator named **hook**.

# Requirements

**Erkle** uses, for the most part, only modules that are included by default with Python. To use SSL to connect to IRC servers, however, the *pyOpenSSL*<sup>1</sup> library must be installed. To install this library via pip, execute this command:

pip install pyOpenSSL

Requirements	1
ErkleClient	
Arguments to ErkleClient()	
Methods	
Hook Decorator	
Events	5
Event sets	7
erkle.events.dump	
erkle.events.messages	7
Examples	8
Greeter Bot	8
License	

```
from erkle import *

@hook.event("welcome")
def welcome(connection):
    connection.join("#erklelib")

@hook.event("join")
def cjoin(connection, nickname, host, channel):
    connection.msg(channel, "Hello world!")
    connection.quit()

bot = ErkleClient("mybot", "mybot", "Erkle Bot", "irc.efnet.org", 6667)
bot.connect()
```

Example Erkle usage

<sup>1 &</sup>lt;a href="https://www.pyopenssl.org">https://www.pyopenssl.org</a>

# **ErkleClient**

ErkleClient is an object that creates and manages an IRC connection. ErkleClient() can take eight arguments (see below). Once the ErkleClient object is created, use the connect() or spawn() function to cause the object to connect to the IRC server.

Table 1: Arguments to ErkleClient()

Argument	Туре	Description
nickname	string	Sets the nickname the IRC client connection will use.
username	string	Sets the username the IRC client connection will use.
realname	string	Sets the realname the IRC client connection will use.
server	string	Sets the IP/hostname of the IRC server to connect to.
port	integer	Sets the port on the IRC server to connect to. Default: 6667
password	string	Sets the password the IRC client connection will send to the server if required. <i>Default: None</i>
SSL	boolean	Sets whether to use SSL to connect to the IRC server; set to True to use SSL. <i>Default: False</i>
encoding	string	What string encoding type the server connection users. Default: utf-8

Table 2: ErkleClient methods

Method	Arguments	Description
connect	None.	Connects to the IRC server.
spawn	None.	Spawns a new thread, and connects to IRC using that thread.
send	• data (string)	Sends a "raw" message to the IRC server; the message will not be processed in any way before being sent.
msg	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a chat message to a channel or user.
action	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a CTCP action message to a channel or user.
notice	<ul><li>target (string)</li><li>message (string)</li></ul>	Sends a notice to a user or channel.
join	<ul><li>channel (string)</li><li>key (string)</li></ul>	Joins a channel.
part	<ul><li>channel (string)</li><li>reason (string)</li></ul>	Leaves a channel.
kick	<ul><li>target (string)</li><li>channel (string)</li><li>reason (string)</li></ul>	Kicks a user from a channel (the client must be a channel operator in the channel).
invite	<ul><li>user (string)</li><li>channel (string)</li></ul>	Sends a channel invitation to a user.
whois	• user (string)	Requests WHOIS data on a user from the server. When the WHOIS data is received, the whois event will be triggered.
channels	None	Requests a list of channels from the server. When the channel list is received, the list event will be triggered.
quit	• reason (string)	Disconnects from the IRC server.

*ErkleClient* also has a number of attributes that store information about the server and client. Not all of these values will be available immediately; the values are populated as the server sends the appropriate data to the client. Most of these values should be available by the time the welcome event is triggered.

Table 3: ErkleClient attributes

Attribute	Туре	Description
nickname	string	The client's nickname.
username	string	The client's username.
realname	string	The client's realname.
server	string	The server's address.
port	integer	The server's port.
password	string	The password used to connect to the server, if there is one.
usessl	boolean	Whether SSL is being used for this connection or not.

hostname	string	The server's hostname.
software	string	The server's software.
options	list	A list of the options the server supports.
network	string	The network the server belongs to.
commands	list	A list of commands supported by the server.
maxchannels	integer	The maximum number of channels a client can join on the server.
maxnicklen	integer	The maximum number of characters allowed for a nickname on the server.
channellen	integer	The maximum number of characters allowed for a channel name on the server.
topiclen	integer	The maximum number of characters allowed for a channel topic on the server.
kicklen	integer	The maximum number of characters allowed for a kick message on the server.
awaylen	integer	The maximum number of characters allowed for an away message on the server.
maxtargets	integer	The maximum number of targets a message can be sent to on a server.
modes	integer	The maximum number of channel modes that can be set on the server.
chantypes	list	What channel types the server uses.
prefix	list of lists	What channel status prefixes the server uses; each entry contains a list with the first value being the status type, and the second value being the prefix used for that type.
chanmodes	list	What channel modes the server uses.
casemapping	string	The casemapping the server uses.
spoofed	string	If the client's host is spoofed by the server, then the spoofed host name will be stored here.
users	dictionary of lists	An in-memory database of channel users. The dictionary uses channel names for keys, and each dictionary entry is a list of the named channel's users.
topic	dictionary	An in-memory database of channel topics. The dictionary uses channel names for keys, and each dictionary entry is a string containing the named channel's topic (or <i>None</i> if the topic is blank or unknown).

## **Hook Decorator**

Included with the *ErkleClient* object is the *hook* object. The *hook* object is used to decorate<sup>2</sup> functions that should be executed when specific events occur; this is called "hooking" an event. *hook* exposes one method: **event**. To hook an event, pass the name of the event (as a

<sup>2</sup> https://www.python.org/dev/peps/pep-0318/

string) as the only argument to **event** method. For example, to hook an event named "connect", the decorator required would look like:

#### @hook.event("connect")

Events can be hooked to an unlimited number of functions. Function hooks will be executed in the order in which they were hooked.

There are 23 IRC events that can be hooked. The hooked function can take a number of different arguments, depending on the event. The first (and sometimes only) argument passed to every hooked function is **connection**, which is the *ErkleClient* object running the IRC connection.

Table 4: Events

Event	Arguments	Description
connect	ErkleClient object	Triggered when the <i>ErkleClient</i> object connects to IRC.
motd	<ul><li>ErkleClient object</li><li>message (string)</li></ul>	Triggered when the server's message of the day (MOTD) is received.
welcome	ErkleClient object	Triggered when registration with the IRC server is complete.
nick-taken	<ul><li>ErkleClient object</li><li>nickname (string)</li></ul>	Triggered when the client's nickname is already taken during registration; <b>nickname</b> contains the new nickname.
ping	ErkleClient object	Triggered when the IRC server sends <i>ErkleClient</i> a PING command.
join	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> </ul>	Triggered whenever a user joins a channel the client is in. <b>nickname</b> contains the user's nickname, <b>host</b> contains the user's host, and <b>channel</b> contains the name of the channel joined. This event will trigger when the <i>ErkleClient</i> object joins a channel as well.
part	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>reason (string)</li> </ul>	Triggered whenever a user leaves a channel the client is in. <b>nickname</b> contains the nickname of the user, <b>host</b> contains the user's host, <b>channel</b> contains the name of the channel, and <b>reason</b> contains the reason why the user quit. If no reason has been provided, <b>reason</b> will be set to <b>None</b> .
quit	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>reason (string)</li> </ul>	Triggered when a user quits the IRC server. <b>nickname</b> contains the user's nickname, <b>host</b> contains the user's host, and <b>reason</b> contains the reason why the user quit. If no reason has been provided, <b>reason</b> will be set to <b>None</b> .
nick	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>new_nickname (string)</li> </ul>	Triggered when a user changes their nickname. <b>nickname</b> contains the user's original nickname, <b>host</b> contains the user's host, and <b>new_nickname</b> contains the user's new nickname.

names	<ul> <li>ErkleClient object</li> <li>channel (string)</li> <li>users (list)</li> </ul>	Triggered when <i>ErkleClient</i> generates a list of users in a specific channel. This list will be regenerated every time a user changes their nick, quits IRC, or leaves a channel. <b>channel</b> contains the name of the channel, and <b>users</b> contains a list of users in that channel. If the server is configured for it, each user entry will contain the user's nickname and host, in the form <i>nickname</i> ! <i>username@hostname</i> ; otherwise, the entry will only contain the user's nickname. Channel status symbols ('@' for channel operators, '+' for voiced users, etc.) are prefixed to each user's nickname.
public	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>message (string)</li> </ul>	Triggered when <i>ErkleClient</i> receives a public message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, <b>channel</b> contains the name of the channel the message was sent to, and <b>message</b> contains the message contents.
private	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>message (string)</li> </ul>	Triggered when <i>ErkleClient</i> receives a private message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, and <b>message</b> contains the message contents.
notice	<ul><li>ErkleClient object</li><li>sender (string)</li><li>message (string)</li></ul>	Triggered when <i>ErkleClient</i> receives a notice message. <b>sender</b> contains the nickname of the sender, and <b>message</b> contains the message contents.
action	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>target (string)</li> <li>message (string)</li> </ul>	Triggered when <i>ErkleClient</i> receives a CTCP action message. <b>nickname</b> contains the sender's nickname, <b>host</b> contains the sender's host, <b>target</b> contains the name of the channel or username the message was sent to, and <b>message</b> contains the message contents.
away	<ul><li>ErkleClient object</li><li>nickname (string)</li><li>reason (string)</li></ul>	Triggered when <i>ErkleClient</i> receives an "away" notification.
back	ErkleClient object	Triggered when ErkleClient unsets itself as "away".
topic	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>topic (string)</li> </ul>	Triggered when <i>ErkleClient</i> receives a channel topic update. <b>nickname</b> contains the topic setter's nickname, <b>host</b> contains the setter's host, <b>channel</b> contains channel name, and <b>topic</b> contains the channel's topic. If the topic is set to an empty string, <b>topic</b> is set to <i>None</i> .
mode	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>target (string)</li> <li>mode (string)</li> </ul>	Triggered when <i>ErkleClient</i> receives a channel or user mode change notification. <b>nickname</b> contains the mode setter's nickname, <b>host</b> contains the setter's host, <b>target</b> contains the user or channel the mode applies to, and <b>mode</b> contains the modes (and mode parameters) being set. If the mode is being set by the server, <b>nickname</b> and <b>host</b> will be set to the server's hostname.
kick	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>target (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>ErkleClient</i> receives a kick notification. <b>nickname</b> contains the kicker's nickname, <b>host</b> contains the kicker's host, <b>channel</b> contains the channel being kicked from, <b>target</b> contains the nickname of the user being kicked, and <b>reason</b> contains the reason given for the kick. If no reason is provided, <b>reason</b> will be set to <i>None</i> .

kicked	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>ErkleClient</i> is kicked from a channel. <b>nickname</b> contains the kicker's nickname, <b>host</b> contains the kicker's host, <b>channel</b> contains the channel being kicked from, and <b>reason</b> contains the reason given for the kick. If no reason is provided, <b>reason</b> will be set to <i>None</i> .
invite	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>host (string)</li> <li>channel (string)</li> </ul>	Triggered whenever <i>ErkleClient</i> receives a channel invitation. <b>nickname</b> contains the inviter's nickname, <b>host</b> contains the inviter's host, and <b>channel</b> contains the channel <i>ErkleClient</i> is being invited to.
whois	<ul> <li>ErkleClient object</li> <li>nickname (string)</li> <li>username (string)</li> <li>host (string)</li> <li>realname (string)</li> <li>server (string)</li> <li>idle (integer)</li> <li>signon (string)</li> <li>channels (list)</li> <li>privileges (string)</li> </ul>	Triggered whenever <i>ErkleClient</i> receives WHOIS data from the server. <b>nickname</b> contains the user's nickname, <b>username</b> contains the user's username, <b>host</b> contains the user's host, <b>realname</b> contains the user's realname, <b>server</b> contains the server the user is connected to, <b>idle</b> contains the number of seconds the user has been idle, <b>signon</b> contains the timestamp of when the user signed on to the server, <b>channels</b> contains a list of channels (with status) the user is in, and <b>privileges</b> contains any special privileges the user has (or <i>None</i> if the user has none).
list	<ul> <li>ErkleClient object</li> <li>channels (list of lists)</li> </ul>	Triggered whenever <i>ErkleClient</i> receives a channel list from the server. Each entry in <b>channels</b> is a list that contains, in this order:  0. channel name (string) 1. number of users in the channel (integer) 2. channel topic (string) ( <i>None</i> if there's no topic)
line	<ul><li> ErkleClient object</li><li> line (string)</li></ul>	Triggered whenever <i>ErkleClient</i> receives a line of data from the server.
error	<ul> <li>ErkleClient object</li> <li>code (string)</li> <li>subject (string)</li> <li>reason (string)</li> </ul>	Triggered whenever <i>ErkleClient</i> receives an error message from the server. <b>code</b> is the error's code (from the IRC RFC documents), <b>subject</b> is the "subject" of the error (if there is no "target", <b>subject</b> will be set to <i>None</i> ), and <b>reason</b> contains a short description of the error.

*ErkleClient*'s **connect()** is a blocking function, so hooked functions should be declared *before* **connect()** is called.

# **Event sets**

**Erkle** contains a few sets of pre-written event handlers; they reside in the **erkle.events** package. To use an event set, simply import it.

Pac	kage	erkle.events.dump
Но	100C	action, away, back, connect, join, kick, kicked, mode, motd, names, nick, nick-taken, notice, part, ping, private, public, quit, topic, welcome
Desc	ription	Prints event-specific data from every <b>Erkle</b> event to the console.

Package	erkle.events.messages
Hooks	notice, private, public

# **Examples**

### **Greeter Bot**

Here's an example bot that connect to an IRC server, join a channel, and greet everyone who joins that channel by name:

```
from erkle import *

SERVER = "irc.efnet.org"
PORT = 6667
CHANNEL = "#erklebot"

@hook.event("welcome")
def welcomed(connection):
    connection.join(CHANNEL)

@hook.event("join")
def joined(connection, nickname, host, channel):
    connection.msg("Welcome to "+CHANNEL+", "+nickname+"!")

bot = ErkleClient("greetbot", "greetbot", "Erkle Bot", SERVER, PORT)
bot.connect()
```

. . .

## License

#### **MIT License**

Copyright (c) 2019 Dan Hetrick

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.