[DRAFT]: Best Practices for Thermodynamic Property Prediction from Molecular Simulations

Bryce C. Manubay,^{1,*} John D. Chodera,^{2,†} and Michael R. Shirts^{1,‡}

¹University of Colorado Boulder, Boulder, CO 80309

²Computational Biology Program, Sloan Kettering Institute,

Memorial Sloan Kettering Cancer Center, New York, NY 10065, United States

(Dated: January 6, 2018)

This document describes a collected set of best practices for computing various physical properties from molecular simulations of liquid mixtures.

Keywords: best practices; molecular dynamics simulation; physical property computation

Todo list

I. Preliminaries

Definitions

10

11

12

13

14

- V: Volume
- *U*: Total internal energy (including potential and kinetic, excluding external energy such as due to gravity, etc)
- S: Entropy
- N: Number of particles
- T: Temperature
- P: Pressure
- k_B: Boltzmann constant
- β : $(k_B T)^{-1}$
- M: Molar mass
- ρ : Density (M/V)
- H: Enthalpy
- G: Gibbs Free Energy (free enthalpy)
- A: Helmholtz Free Energy
 - μ: Chemical potential
- D: Total dipole moment
- u: reduced energy
- f: reduced free energy

Macroscopically, the quantities V,U,N are constants (assuming the system is not perturbed in any way), as we assume that the fluctuations are essentially zero, and any uncertainty comes from our inability to measure that constant value precisely. For a mole of compound (about 18 mL for water), the relative uncertainty in any of these quantities is about 10^{-12} , far lower than any thermodynamics experiment can actually measure.

However, in a molecular simulation, these quantities are not necessarily constant. For example, in an NVT equilib- rium simulation, U is allowed to vary. For a long enough simulation (assuming ergodicity, which can pretty much always be assumed with correctly implemented simulations and simple fluids), then the ensemble average value of U is U will converge to a constant value, and in the limit of large simulations/long time will converge to the macroscopic value U; at least, the macroscopic value of that given model, though perhaps not the U for the real system. In an V is a variable, and we must estimate what the macroscopic value would be using the ensemble average V.

The quantities T, P, and μ are typically set as constant during the equilibrium simulations and experiments of interest here. More precisely, the system is in contact with a thermal bath with a fixed T (or in the case of NPT simulations, in contact with a thermal and mechanical bath), and we sample from the systems in equilibrium with this bath. There are a number of quantities that can be used to ESTIMATE constants such as T and P. For example, $\frac{1}{3Nk_B}\sum_i m_i |v_i|^2\rangle$, where m is the mass of each particle and $|v_i|$ is the magnitude of the velocity of each particle, is an estimate of T (the temperature of the bath), and it's average will be equal to the T. But it is not the temperature. This quantity fluctuates, but T remains constant; otherwise the simulation could not be at constant temperature.

Ensemble averages of some quantity X ($\langle X \rangle$) are assumed to be averages over the appropriate Boltzmann weighting, i.e. in the NVT ensemble with classical statistical mechanics, they would be $\int X(\vec{x},\vec{p})e^{-\beta U(\vec{x},\vec{p})}d\vec{x}d\vec{p}$. We note that in the limit of very large systems, $\langle X \rangle_{NPT}=\sqrt{\langle X \rangle_{NVT}}=\langle X \rangle_{uVT}$.

Ensemble averages can be computed by one of two ways. First, they can be computed directly, by running a simulation that produces samples with the desired Boltzmann distribution. In that case ensemble averages can be computed as

^{*} bryce.manubay@colorado.edu

[†] john.chodera@choderalab.org

[‡] Corresponding author; michael.shirts@colorado.edu

 $_{75}$ simple averages, $\langle V \rangle = rac{1}{N} \sum_i V_i$, where the sum is over all $_{111}$ from the mixture distribution becomes. observations. Uncertainties can be estimated in a number of 77 different ways, but usually require estimating the number of uncorrelated samples. Secondly, they can be calculated as reweighted estimates from several different simulations, as $\langle V \rangle = \frac{1}{\sum_i w_i} V_i w_i$ where w_i is a reweighting factor that can 81 be derived from importance sampling theory.

To simplify our discussion of reweighting, we use some additional notation. We define the reduced potential $u\,=\,$ $\beta U(\vec{x})$ in the canonical (NVT) ensemble, $u = \beta U + \beta PV$ ₈₅ in the isobaric-isothermal (NPT) ensemble, and $u=\beta U-$ ₈₆ $\beta N\mu$ in the grand canonical ensemble (similar potentials $_{87}$ can be defined in other ensembles). We then define $f \, = \,$ ₈₈ $\int e^{-u} dx$, where the integral is over all of the DOF of the system (x for NVT, x,V for NPT, and x,N for μVT). For $_{90}$ NPT, we then have f=eta G, and for NVT we have f=₉₁ βA , while for μVT we have $f = -\beta \langle P \rangle V$.

Observables by reweighting

To calculate expectations at one set of parameters generated with parameters that give rise to a different set of probability distributions, we start with the definition of an ensemble average given a probability distribution $p_i(x)$.

$$\langle X \rangle_i = \int X(x) p_i(x) dx$$
 (1)

97 We then multiply and divide by $p_i(x)$, to get

92

$$\langle X \rangle_i = \int X(x) p_i(x) \frac{p_j(x)}{p_j(x)} dx = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx$$
(2)

98 We then note that this last integral can be estimated by the 99 Monte Carlo estimate

$$\langle X \rangle_i = \int X(x) p_j(x) \frac{p_i(x)}{p_j(x)} dx = \frac{1}{N} \sum_{n=1}^N X(x_n) \frac{p_i(x_n)}{p_j(x_n)}$$
(3)

 $_{ ext{\tiny 100}}$ Where the x_k are sampled from probability distribution

We now define the mixture distribution of K other distributions as: $p_m(x)=\frac{1}{N}\sum_{i=1}^N N_k p_k(x)$, where $N=\sum_k N_k$. We can construct a sample from the mixture distribution $_{
m 105}$ by simply pooling all the samples from k individual simulations. The formula for calculating ensemble averages in a distribution $p_i(x)$ from samples from the mixture distribu-108 tion is:

$$\langle X \rangle_i = \sum_{n=1}^N X(x_n) \frac{p_i(x_n)}{\sum_{k=1}^{N_k} p_k(x_n)} \tag{4}$$

109 In the case of Boltzmann averages, then $p_i(x) = e^{f_i - u_i(x)}$, 145 where the reduced free energy f is unknown. Reweighting 146 mechanical observables by both direct methods pulled from

$$\langle X \rangle_i = \sum_{n=1}^{N} X(x_n) \frac{e^{f_i - u_i(x_n)}}{\sum_{k=1}^{N_k} e^{f_k - u_k(x)}}$$
 (5)

which can be seen to be the same formula as the MBAR formula for expectations. The free energies can be obtained by setting X = 1, and looking at the K equations obtained by reweighting to the K different distributions.

Observables by derivatives

Finite differences at different temperatures and pressures 118 can be calculated by including states with different reduced potentials. For example, $u_i(x) = \beta_i U(x) + \beta_i (P_i + \Delta P) V$, or $u_j=\frac{1}{k_B(T_i+\Delta T)}U(x)+\frac{1}{k_B(T_i+\Delta T)}P_iV$. However, the relationship between f and G can be problematic when looking at differences in free energy with respect to temperature, because $G_2 - G_1 = \beta_2 f_2 - \beta_1 f_1$. We can in general write

$$\Delta G_{ij}(T) = k_B T \left(\Delta f_{ij}(T) - \Delta f_{ij}(T_{ref}) \right) + \frac{T}{T_{ref}} \Delta G_{ij}(T_{ref})$$

, where $\Delta G_{ij}(T_{ref})$ is known at some temperature.

Since with MBAR, one can make the differences as small as one would like (you don't have to actually carry out a simulation at those points), we can use the simplest formulas: 128 central difference for first derivatives:

$$\frac{\partial A}{\partial x} \approx \frac{1}{2\Delta x} \left(A(x + \Delta x) - A(x - \Delta x) \right)$$

129 And for 2nd derivatives:

$$\frac{\partial^2 A}{\partial x^2} \approx \frac{1}{\Delta x^2} \left(A(x + \Delta x) - 2A(x) + A(x - \Delta x) \right)$$

Thus, only properties at two additional points need to be evaluated to calculate both first and 2nd derivatives.

For mixed partial derivatives, we can write (in the central 133 difference approximation).

$$\frac{\partial^2 A}{\partial x \partial y} \approx \frac{A(x + \Delta x, y + \Delta y) - A(x + \Delta x, y - \Delta y) - A(x - \Delta x, y + \Delta y)}{4 \Delta x \Delta y}$$

It may first appear that these finite difference calculations will propagate significant error as they subtract similar num-136 bers. However, MBAR calculates the covariance matrix between $\langle A \rangle$, $\langle A(x+\Delta x) \rangle$, and $\langle A(x-\Delta x) \rangle$, meaning in prac-138 tice the uncertainty is far lower than would be expected by standard error propagation of uncorrelated observables.

Note that if the finite differences are re-evaluated using 141 reweighting approaches, it is important that the simulation (4) 142 used generates the correct Boltzmann distribution. If not, 143 reweighted observables will be incorrect, and the results of 144 the finite difference approach will have significant error.

The following document details calculation of various

Corrections in certain observables are also summarized 176 sired by simply substituting: where suggested by previous authors.

 $_{147}$ literature sources and the use of reweighting techniques. $_{175}$ This can be calculated from the reduced free energy f if de-

$$\rho \approx \frac{\beta M}{\frac{f(P + \Delta P) - f(P - \Delta P)}{2\Delta P}} \tag{12}$$

Intuitively, one would imagine that equation 12 would be 178 a worse estimate of density given that the calculations in-179 volved have more room for error than direct simulations. That being said, this method should prove invaluable when estimating densities of unsampled states using MBAR.

Single Phase Properties

150

151

152

Pure Solvent Properties

Molar volume / Density

We suggest, that molar volume is usually a better quantity to use than density. Molar volume contains the same information as density, since we assume the molar masses are invariant under parameterization. The molar volume is simply the volume divided by the number of moles, and in an 158 NPT simulation, the volume is what one directly calculates. 159 Any additional error propagation is complicated by putting the density in the denominator. Starting with the equation used to calculate the density experimentally:

$$\rho = \frac{M}{V} \tag{6}$$

with the ensemble estimate (calculated either directly, or 165 with reweighting) to obtain:

$$\rho = \frac{M}{\langle V \rangle} \tag{7}$$

b. Derivative Estimate From the differential definition of the Gibbs free energy $dG = VdP - SdT + \sum_i \mu_i dN_i$ that 168 V can be calculated from the Gibbs free energy as:

$$\langle V \rangle = \left(\frac{\partial G}{\partial P}\right)_{T.N}$$
 (8)

The density can therefore be estimated from the Gibbs free ing these values into the enthalpy equation gives: 170 energy.

$$\rho = \frac{M}{\left(\frac{\partial G}{\partial P}\right)_{T,N}} \tag{9}$$

196

198

171 The derivative can be estimated using a central difference 172 numerical method utilizing Gibbs free energies reweighted 173 to different pressures.

$$\left(\frac{\partial G}{\partial P}\right)_{TN} \approx \frac{G_{P+\Delta P} - G_{P-\Delta P}}{2\Delta p}$$
 (10)

174 The density can then finally be estimated.

$$\rho \approx \frac{M}{\frac{G(P + \Delta P) - G(P - \Delta P)}{2\Delta P}} \tag{11}$$

2. Molar Enthalpy

This section is on the relation of enthalpy to Gibbs free energy (should we need it). This is not an experimental quan-185 tity, but will be helpful in calculating related properties of interest. The enthalpy, H, can be found from the Gibbs free energy, G, by the Gibbs-Helmholtz relation:

a. Direct simulation estimate H can be calculated as di-189 rectly as:

$$H = \langle U \rangle + P \langle V \rangle$$

₁₉₀, where U is the total internal energy (including both kinetic 191 and potential energy).

b. Derivative estimate

$$H = -T^2 \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \right)_{P,N} \tag{13}$$

Transforming the derivative in the Gibbs-Helmholtz rela- $_{193}$ tion to be in terms of eta instead of T yields:

$$H = -T^{2} \frac{\beta^{2}}{\beta^{2}} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial T} \frac{\partial T}{\partial \beta} \frac{\partial \beta}{\partial T} \right)_{P,N} \tag{14}$$

Recall that $\beta=\frac{1}{k_BT}$, therefore $\frac{\partial \beta}{\partial T}=-\frac{1}{k_BT^2}$. Substitut-

$$H = \frac{1}{k_B^3 T^2 \beta^2} \left(\frac{\partial \left(\frac{G}{T} \right)}{\partial \beta} \right)_{P,N}$$

$$= \frac{1}{k_B} \left(\frac{\partial \left(\frac{G}{T} \right)}{\beta} \right)_{P,N} = \frac{\partial f}{\partial \beta_{P,N}} \quad (15)$$

3. Heat Capacity

(11) There are two different heat capacities: the isochoric heat capacity $C_V=\frac{\partial U}{\partial T_V}$, and isobaric heat capacity $C_P=\frac{\partial U}{\partial T_V}$

 $\frac{\partial H}{\partial T}_{P}$. The are calculated

205

206

209

212

213

221

202 a. Direct simulation estimate There is no direct way to 2 203 estimate either heat capacity.

b. T he definition of the isobaric heat capacity is:

$$C_P = \left(\frac{\partial H}{\partial T}\right)_{P,N} \tag{16}$$

$$C_{P} = \frac{\partial \left(\frac{\partial f}{\partial \beta}\right)}{\partial T}_{PN} \tag{17}$$

$$C_P = k_B \beta^2 \frac{\partial^2 f}{\partial \beta^2} \tag{18}$$

This could be computed by finite differences approach or 230 analytical derivation using MBAR 231

 $_{
m 210}$ c. Fluctuation estimate The enthalpy fluctuation for- $_{
m 211}$ mula can also be used to calculate $C_P[1]$.

$$C_P = \frac{\langle H^2 \rangle - \langle H \rangle^2}{N k_B \langle T \rangle^2} \tag{19}$$

The form is equivalent for isochoric heat capacity, but with derivatives at constant volume rather than pressure.

4. Isothermal Compressibility

The definition of isothermal compressibility is:

$$\kappa_T = -\frac{1}{V} \left(\frac{\partial V}{\partial P} \right)_T \tag{20}$$

 $_{^{218}}$ a. First Derivative Thus, it can be estimated by the fi- $_{^{219}}$ nite difference of $\langle V \rangle$

$$\kappa_T = -\frac{1}{2V(T,P)^2} \left(\langle V(P+\Delta P,T) \rangle - \langle V(P-\Delta P,T) \rangle \right)$$

²²⁰ Or by the finite differences evaluation of:

$$\kappa_T = -\frac{\left(\frac{\partial^2 G}{\partial P^2}\right)_{T,N}}{\left(\frac{\partial G}{\partial P}\right)_{T,N}} = -\frac{\left(\frac{\partial^2 f}{\partial P^2}\right)_{T,N}}{\left(\frac{\partial f}{\partial P}\right)_{T,N}} \tag{22}$$

 κ_T can also be estimated from the ensemble average 248 and fluctuation of volume (in the NPT ensemble) or particle 249 number (in the μ VT ensemble)[2]: 250

$$\kappa_T = \beta \frac{\langle \Delta V^2 \rangle_{NTP}}{\langle V \rangle_{NTP}} = V \beta \frac{\langle \Delta N^2 \rangle_{VT}}{\langle N \rangle_{\mu VT}}$$
 (23)

5. Speed of Sound

The definition of the speed of sound is[3]:

$$c^2 = \left(\frac{\partial P}{\partial \rho}\right)_S = -\frac{V^2}{M} \left(\frac{\partial P}{\partial V}\right)_S \tag{24}$$

$$c^{2} = \frac{V^{2}}{\beta M} \left[\frac{\left(\frac{\gamma_{V}}{k_{B}}\right)^{2}}{\frac{C_{V}}{k_{B}}} + \frac{\beta}{V \kappa_{T}} \right]$$
 (25)

Where:

228

$$\gamma_V = \left(\frac{\partial P}{\partial T}\right)_V \tag{26}$$

 γ_V is known as the isochoric pressure coefficient. κ_T is the same isothermal compressibility from equation 20

²³⁹ An alternate derivation, applying the triple product rule to $\left(\frac{\partial P}{\partial V}\right)_S$ yields the following.

$$\left(\frac{\partial P}{\partial V}\right)_{S} = \frac{\left(\frac{\partial S}{\partial V}\right)_{P}}{\left(\frac{\partial S}{\partial P}\right)_{V}} \tag{27}$$

$$\left(\frac{\partial S}{\partial V}\right)_{P} = \left(\frac{\partial S}{\partial T}\right)_{P} \left(\frac{\partial T}{\partial V}\right)_{P} = \frac{C_{P}}{T} \left(\frac{\partial T}{\partial V}\right)_{P} = \frac{C_{P}}{TV\alpha} \tag{28}$$

Where $\alpha=\frac{1}{V}\left(\frac{\partial V}{\partial T}\right)_P=\left(\frac{\partial \ln V}{\partial T}\right)_P$ is the coefficient of thermal expansion. The second term in our triple product rule expansion, $\left(\frac{\partial S}{\partial P}\right)_V$, can be expressed as follows:

$$\left(\frac{\partial S}{\partial P}\right)_{V} = \left(\frac{\partial S}{\partial T}\right)_{V} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T} \left(\frac{\partial T}{\partial P}\right)_{V} = \frac{C_{V}}{T\gamma_{V}} \tag{29}$$

Thus our derivation yields:

$$\left(\frac{\partial P}{\partial V}\right)_{S} = \frac{C_{P}\gamma_{V}}{C_{V}V\alpha} \tag{30}$$

Horn et al set out several ways for calculating $\alpha[1]$:

251

252

253

254

256

260

261

262

268

269

a. Analytical derivative of density with respect to temperature

$$\alpha = -\frac{d\ln\langle\rho\rangle}{dT} \tag{31}$$

272

290

b. Numerical derivative of density over range of T of in- 276 Then the definition of terest. The same finite differences approach as shown for 277 pound i in a mixture is: isothermal compressibility can be applied here, thus:

$$\alpha = -\frac{d \ln \langle \rho \rangle}{dT} = -\frac{1}{2\rho(T, P)} \left(\ln \langle \rho(P, T + \Delta T) \rangle - \ln \langle V(P, T - \Delta T) \rangle \right)$$

c. Using the enthalpy-volume fluctuation formula

$$\alpha = \frac{\langle VH \rangle - \langle V \rangle \langle H \rangle}{k_B \langle T \rangle^2 \langle V \rangle} \tag{33}$$

Finite differences approximations and/or analytical $_{287}$ derivation can also be used to calculate γ_V or by note of the $_{288}$ zsp relation: $_{289}$

$$\gamma_V = -\frac{\alpha}{\kappa_T} \tag{34}$$

6. Dielectric Constant

This equation was provided by a literature reference authored by CJ Fennell[4] and is the standard for calculating the dielectric constant. Below, $\epsilon(0)$ is the zero frequency dielectric constant, V is the system volume and D is the total system dipole moment.

$$\epsilon(0) = 1 + \frac{4\pi}{3k_B T \langle V \rangle} (\langle D^2 \rangle - \langle D \rangle^2) \tag{35}$$

B. Binary Mixture Properties

1. Mass Density, Speed of Sound and Dielectric Constant

The methods for these calculations are the same for a multicomponent system.

2. Activity Coefficient

The definition of chemical potential in a pure substance

$$\mu(T,P) = \left(\frac{\partial G}{\partial N}\right)_{T,P} \tag{36}$$

which is a function of only temperature and pressure.

Then the definition of the chemical potential μ_i of compound i in a mixture is:

$$\mu_i(T, P, \vec{N}) = \left(\frac{\partial G}{\partial N_i}\right)_{T, P, N_i \neq i} \tag{37}$$

 $_{^{279}}$ N_i refers to a molecule of component i and $N_{j \neq i}$ refers to $_{^{280}}$ all molecules other than component i, with \vec{N} the vector of all component numbers. Since μ_i is intensive, this is equivalently a function of the vector of mole fractions \vec{x}_i instead of simply of N_i .

For an ideal solution, the chemical potential μ_i can be related to the pure chemical potential by

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln \left(\gamma_i\right) \tag{38}$$

By analogy to this form, we can say

$$\mu_i(T, P, \vec{x}_i) = \mu(T, P) + k_B T \ln(x_i \gamma_i) \tag{39}$$

Where γ_i is the activity coefficient of component i, and is a function of T,P,and \vec{x}_i . Rearrangement of the previous equation yields:

$$\gamma_i = \frac{e^{\left(\frac{\mu_i(T,P,\vec{x}_i) - \mu(T,P)}{k_B T}\right)}}{x_i} \tag{40}$$

Although chemical potentials cannot be directly calculated from simulation, chemical potential residuals can. We can calculate the difference $\mu_i(T,P,\vec{x}_i)-\mu(T,P)$ by calculating $\Delta\mu(T,P)_{liquid}-\Delta\mu(T,P)_{gas}$ using a standard alchemical simulation of the pure substance, followed by the calculation of $\mu_i(T,P,\vec{x}_i)_{liquid}-\Delta\mu(T,P,\vec{x}_i)_{gas}$, and assuming that $\Delta\mu(T,P,\vec{x}_i)_{gas}=\Delta\mu(T,P)_{gas}$. Note: there are a few subtleties here relating to the $\ln x_i$ factor, but it appears that with alchemical simulations with only one particle that is allowed to change, this will cancel out (need to follow up).

Several of these alchemical simulation methods for calculating activity coefficients have been pioneered by Andrew Paluch [5]. A method detailing the calculation of infinite dilution activity coefficients γ_i^{inf} for binary a mixture follows

312 directly:

313 314

315

321

322

323

338

341 342

$$\begin{split} \ln \gamma_{2}^{\infty}\left(T,P,x_{2}=0\right) &= \beta \mu_{2}^{res,\infty}\left(T,P,N_{1},N_{2}=1\right) \\ &+ \ln \left[\frac{RT}{V_{1}\left(T,P\right)}\right] - \ln f_{2}^{0}\left(T,P\right) \end{aligned} \tag{41} \quad \text{356}$$

Where $\beta\mu_2^{res,\infty}$ is the dimensionless residual chemical $^{_{358}}$ potential of component 2 at infinite dilution. The residual is defined here as the difference between the liquid and ideal gas state. $V_1(T, P)$ is the molar volume of component 1 at T and P. $\ln f_2^0(T, P)$ is the natural logarithm of the pure $_{320}$ liquid fugacity of component 2 and is defined as:

$$\ln f_2^0(T, P) = \beta \mu_2^{res}(T, P) + \ln \left[\frac{RT}{V_2(T, P)} \right]$$
 (42)

approach utilizing MBAR in order to calculate the residual chemical potentials (recall that the chemical potential is the partial molar Gibbs free energy and dimensionless Gibbs free energy differences between multiple states are readily computed with MBAR). The idea is to connect two states of interest. In the case of a pure liquid, connecting a system of pure liquid molecules with N-1 interacting molecules and one fully decoupled molecule to a system of N fully interacting molecules. The coupling/decoupling process is detailed 371 ₃₃₅ turned on for the decoupled molecule until they are fully on. ₃₇₄ following terms were added as a correction. The free energy of this coupling is calculated by sampling 337 summing the free energy changes along this path.

Excess Molar Properties

The general definition of an excess molar property can be 340 stated as follows:

$$y^E = y^M - \sum_i x_i y_i \tag{43}$$

Where y^E is the excess molar quantity, y^M is the mixture quantity, x_i is the mole fraction of component i in the mixture and y_i is the pure solvent quantity. In general, the simplest methods for calculating excess molar properties for binary mixtures will require three simulations. One simulation is run for each pure component and a third will be run for the 349 specific mixture of interest. We note that only one set of pure 350 simulations are needed to calculate excess properties at all 380 351 compositions.

Excess Molar Heat Capacity and Volume

Excess molar heat capacities and volume will be calcu- $_{
m 354}$ lated using the methods for the pure quantities in section Iin combination with the general method for excess property calculation above.

5. Excess Molar Enthalpy

Excess molar enthalpy can be calculated using the general relation of molar enthalpy as it relates to Gibbs Free En- $_{361}$ ergy from section I and the general method of excess molar property calculation above or by the following[7]:

$$H^{E} = \langle E^{M} \rangle + PV^{E} - \sum_{i} x_{i} \langle E_{i} \rangle \tag{44}$$

Where $\langle E \rangle$ denotes an ensemble average of total energy Paluch et al. use a multistage free energy perturbation 366 and V^E is calculated using the general method of excess molar properties.

Suggested Corrections

1. Heat Capacity

Horn et al suggest a number of vibrational corrections be by Paluch et al [6], but involves a linear alchemical switch- $_{372}$ applied to the calculation of C_P due to a number of approxing function where LJ and electronic interactions are slowly 373 imations made during the simulation of the liquid [1]. The

$$\left(\frac{\partial E_{vib,l}}{\partial T}\right)_{P} = \left(\frac{\partial E_{vib,l,intra}^{QM}}{\partial T}\right)_{P} + \left(\frac{\partial E_{vib,l,inter}^{QM}}{\partial T}\right)_{P} - \left(\frac{\partial E_{vib,l,inter}^{CM}}{\partial T}\right)_{P} \tag{45}$$

Where:

$$\left(\frac{\partial E_{vib}^{CM}}{\partial T}\right)_{P} = k_{B} n_{vib} \tag{46}$$

$$\left(\frac{\partial E_{vib}^{QM}}{\partial T}\right)_{P} = \sum_{i=1}^{n_{vib}} \left(\frac{h^{2} v_{i}^{2} e^{\frac{h v_{i}}{k_{B} T}}}{k_{B} T^{2} \left(e^{\frac{h v_{i}}{k_{B} T}} - 1\right)^{2}}\right)$$
(47)

Above, n_{vib} is the number of vibrational modes, h is $_{ t 408}$ phase. Planck's constant and v_i is the vibrational frequency of $_{ t 84}$ mode i.

III. Properties Involving Change of Phase

385

386

387

388

389

391

392

394

398

399

400

404 405

A. Pure Solvent Properties

1. Enthalpy of Vaporization

The definition of the enthalpy of vaporization is[8]:

$$\Delta H_{vap} = H_{gas} - H_{liq} = U_{gas} - U_{liq} + P(V_{gas} - V_{liq}) \ \ \mbox{(48)} \label{eq:delta_transform}$$

If we assume that $V_{qas} >> V_{liq}$ and that the gas is ideal:

$$\Delta H_{vap} = U_{gas,potential} - U_{liq,potential} + RT \tag{49}$$

B. Suggested Corrections

1. Enthalpy of Vaporization

An alternate, but similar, method for calculating the enthalpy of vaporization is recommended by Horn et al [1].

$$\Delta H_{vap} = -\frac{E_{liq,potential}}{N} + RT - PV_{liq} + C$$
 (50)

In the above equation ${\cal C}$ is a correction factor for vibrational energies, polarizability, non-ideality of the gas and pressure. It can be calculated as follows.

$$C_{vib} = C_{vib,intra} + C_{vib,inter}$$

$$= (E_{vib,QM,gas,intra} - E_{vib,QM,liq,intra})$$

$$+ (E_{vib,QM,liq,inter} - E_{vib,CM,liq,inter})$$
(51)

 $_{\rm 402}$ $\,$ The QM and CM subscripts stand for quantum and classical mechanics, respectively.

$$C_{pol} = \frac{N}{2} \frac{\left(d_{gas} - d_{liq}\right)^2}{\alpha_{p,gas}} \tag{52}$$

Where d_i is the dipole moment of a molecule in phase i 447 and $lpha_{p,qas}$ is the mean polarizability of a molecule in the gas 448

$$C_{ni} = P_{vap} \left(B - T \frac{dB}{dT} \right) \tag{53}$$

Where B is the second virial coefficient.

410

$$C_{x} = \int_{P_{ext}}^{P_{vap}} \left[V\left(P_{ext}\right) \left[1 - \left(P - P_{ext}\right) \kappa_{T} \right] - TV\alpha \right] dP \tag{54}$$

Where P_{ext} is the external pressure and $V\left(P_{ext}\right)$ is the volume at P_{ext} .

This is frequently done as a single simulation calculation by assuming the average intramolecular energy remains constant during the phase change, which is rigorously correct for something like a rigid water molecule (intramolecular energies are zero), but less true for something with structural rearrangement between gas and liquid phases.

As discussed by myself and MRS, we have decided to not initially begin the parameterization process using enthalpy of vaporization data. While force field parameterization is commonly done using said property we have ample reason to not follow classical practice. First of all, the enthalpy data is usually not collected at standard temperature and pressure, but at the saturation conditions of the liquid being vasorized [9]. This would require corrections to be made to get the property at STP (the process will be explained besides) low) using fitted equations for heat capacity. Not only is this inconvenient, but it adds an unknown complexity when adibration. Often times the uncertainties due to the added correctant tion. Often times the uncertainties of these "experimental" enthalpies are unrecorded because they are estimated from fitted Antoine equation coefficients [9].

An additional issue is the necessity of having to use gas
phase simulation data in order to validate a parameterization process meant for small organic liquids and their mixtures. Following an example of Wang et al. [10] we plan to
instead use enthalpy of vaporization calculations as an unbiased means of testing the success of the parameterization. If
the parameterization procedure is expanded to use enthalpy
of vaporization, corrections can be made to the experimental data in order to get a value at STP using the following
equation.

$$\Delta H_{vap}(T) = \Delta H_{vap}^{ref} + \int_{T_{ref}}^{T} \left(C_{P,gas} - C_{P,liq} \right) dT \quad (55)$$

- [1] H. et al., "Development of an improved four-site water model 467 449 for biomolecular simulations: Tip4p-ew," Journal of Chemical 450 Physics, vol. 120, no. 20, pp. 9665-9678, 5 2004. 451
- [2] D. et al., "Insights into protein compressibility from molecu- 470 452 lar dynamics simulations," The Journal of Physical Chemistry 453 B, vol. 105, no. 3, pp. 715–724, 12 2000.

454

- 455 [3] R. Lustig, "Direct molecular nvt simulation of the isobaric 473 heat capacity, speed of sound and joule-thomson coefficient," Molecular Simulation, vol. 37, no. 6, pp. 457–465, 5 2011. 457
- [4] C. Fennell, "Simple liquid models with corrected dielectric 476 constants," The Journal of Physical Chemistry B, vol. 116, no. 23, 459 pp. 6936-6944, 3 2012. 460
- [5] P. et al., "Developing a predictive form of mosced for nonelec- 479 461 trolyte solids using molecular simulation: Application to ac- 480 462 etanilide, acetaminophen, and phenacetin," Industrial and En- 481 [10] W. et al., "Development of polarizable models for molecular 463 gineering Chemistry Research, vol. 55, no. 18, pp. 5415-5430, 4 482 464 465
- [6] —, "Calculating the fugacity of pure, low volatile liquids 484 466

- via molecular simulation with application to acetanilide, acetaminophen, and phenacetin," Industrial and Engineering Chemistry Research, vol. 54, no. 36, pp. 9027–9037, 9 2015.
- D. et al., "Enthalpies of mixing predicted using molecular dynamics simulations and opls force field," Fluid Phase Equilibria, vol. 289, no. 2, pp. 156–165, 3 2010.
- W. et al., "Application of molecular dynamincs simulations in molecular property prediction. 1. density and heat of vaporization," Journal of Chemical Theory and Computation, vol. 7, no. 7, pp. 2151-2165, 5 2011.

474

477

- [9] C. et al., "Enthalpies of vaporization of organic and organometallic compounds, 1880âĂŞ2002," Journal of Physical and Chemical Reference Data, vol. 32, no. 2, pp. 519-878, 4 2003.
- mechanical calculations iv: van der waals parameterization," Journal of Physical Chemistry B, vol. 116, no. 24, pp. 7088–7101, 6 2012.