Virtual Memory (1)

Dr. Jun Zheng
CSE325 Principles of Operating
Systems
11/4/2019




Background

• Code needs to be in memory to execute, but entire program rarely used Error code, unusual routines, large data structures ☐ Entire program code not needed at same time ☐ Consider ability to execute partially-loaded program Program no longer constrained by limits of physical memory □ Each program takes less memory while running -> more programs run at the same time ☐ Increased CPU utilization and throughput with no increase in response time or turnaround time ☐ Less I/O needed to load or swap programs into memory -> each user program runs faster


Background (Cont.)

- □ Virtual memory separation of user logical memory from physical memory
 - □Only part of the program needs to be in memory for execution
 - □ Logical address space can therefore be much larger than physical address space
 - □Allows address spaces to be shared by several processes
 - □Allows for more efficient process creation
 - ☐ More programs running concurrently
 - □ Less I/O needed to load or swap processes





Background (Cont.)

- □ **Virtual address space** logical view of how process is stored in memory
 - ☐ Usually start at address o, contiguous addresses until end of space
 - ☐ Meanwhile, physical memory organized in page frames
 - ☐ MMU must map logical to physical
- ☐ Virtual memory can be implemented via demand paging: only bring in pages actually used




Virtual Memory That is Larger Than Physical Memory






Demand Paging


- ☐ Bring a page into memory only when it is needed
 - ☐ Less I/O needed, no unnecessary I/O
 - ☐ Less memory needed
 - ☐ Faster response
 - ☐ More users
- □ Lazy swapper never swaps a page into memory unless page will be needed
 - ☐ Swapper that deals with pages is a **pager**






Basic Concepts

☐ With swapping, pager guesses which pages will be used before the process is swapped out again ☐ Instead of swapping in a whole process, pager brings in only those pages into memory ☐ How to determine that set of pages? □ Need new MMU functionality to implement demand paging ☐ If pages needed are already memory resident ☐ No difference from non demand-paging ☐ If page needed and not memory resident ☐ Need to detect and load the page into memory from storage ☐ Without changing program behavior ☐ Without programmer needing to change code




Valid-Invalid Bit


- With each page table entry a valid−invalid bit is associated
 (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- ☐ Initially valid—invalid bit is set to i on all entries
- ☐ Example of a page table snapshot:



 \square During MMU address translation, if valid—invalid bit in page table entry is $\mathbf{i} \Rightarrow \mathbf{page}$ fault



Steps in Handling a Page Fault



Aspects of Demand Paging

☐ Extreme case – start process with *no* pages in memory □ OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault ☐ And for every other process pages on first access **□** Pure demand paging ☐ Actually, a given instruction could access multiple pages -> multiple page faults ☐ Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory ☐ Pain decreased because of **locality of reference** ☐ Hardware support needed for demand paging ☐ Page table with valid / invalid bit Secondary memory (swap device with swap space) Instruction restart