2-Dimensional flow cytometry

Omid Gholamalamdari

8/19/2020

Materials Needed

- Propidium Iodide 1mg/ml
- RNase A 1mg/ml
- EdU and Click-iT reaction materials

Procedure

Cell harvest

- 1. Pulse the cells with media containing 10uM of EdU for 15-30 minutes in CO₂ incubator.
- 2. Harvest cells 3×10^6 in media (scrape 6cm plate or cell suspension) and transfer to 1.5 ml tube.
- 3. Centrifuge cells in a 1.5 ml tube for 5 min, 1000 rpm, RT.
- 4. Aspirate supernatant completely with P200 (will be effective if spun down ~3 sec once again to discard residual supernatant − same for all aspiration procedures below)
- 5. Aspirate the media and resuspend the cells with 1ml of PBS. Centrifuge.
- 6. Aspirate and resuspend the cells in 100μ l PBS+ 1%NGS.

Cell fixation

- 1. Take chilled 100% EtOH to cold room.
- 2. place the centrifuge tube on the vortex and add 900μ l of 100% EtOH dropwise to tube.
- 3. Mix well and keep the tube at 4°C overnight.

Click-iT reaction

- 1. Centrifuge 5 min, 1000 rpm, RT, then aspirate supernatant completely.
- 2. Add 1ml of 0.5% Triton X-100/PBS, resuspend by tapping.
- 3. Add 0.5 ml of 1% BSA/PBS and incubate for 30 minutes at RT (blocking)
- 4. Meanwhile prepare click chemistry cocktail <15 minutes before use.
 - Mix the ingredients in the **following order**.

Component	For $1000\mu l$
1X Click-iT reaction Buffer	$860\mu l$
$CuSO_4$	$40\mu l$
Alexa-488 azide (1mM)	$4\mu\mathrm{l}$
Reaction buffer additive (1X)	$100\mu l$

- 6. Aspirate and resuspend the cells in 500µl of the cocktail and incubate for 30 minutes at RT in dark.
- 7. Wash twice with 1ml of PBS.

PI staining

- 1. Discard supernatant and resuspend cell pellet in 1ml PBS containing 10 $\mu g/ml$ RNase A and 20 $\mu g/ml$ PI stock solution, transfer to FACS tubes and incubate at room temperature (RT) in the dark for 30 min. (For "EdU-only", just add PBS).
- 2. Transfer to a 5 ml Falcon 2054 FACS tube for FACS/LSRII analysis.
- 3. Adjust concentration to 2 x 106 /ml by adding 5 μ g/ml PI in PBS.