

1 The User's Manual		
2 Basic mode of operation.	3	
-		
3 Using the compiler		
3.1 Compiler command line format		
3.2 Runtime options		
3.3 Examples		
3.3.1 A simple example (with one source file)		
3.3.2 An example with multiple files		
3.4 Extending the compiler.		
3.5 Distributing compiled C files	13	
4 Using the interpreter.	15	
4.1 Interpreter command line format.		
4.2 Writing Scheme scripts.		
4.3 Toplevel commands.		
4.4 toplevel-command.		
4.5 History access.		
4.6 set-describer!		
4.7 Auto-completion and edition.		
4.8 Accessing documentation.		
no . recoming documentation		
5 Supported language	21	
6 Deviations from the standard	22	
7 Extensions to the standard	23	
	20	
8 Non-standard read syntax		
8.1 Multiline Block Comment.		
8.2 Expression Comment		
8.3 External Representation		
8.4 Syntax Expression.		
8.5 Location Expression		
8.6 Keyword		
8.7 Multiline String Constant		
8.9 Foreign Declare		
8.10 Sharp Prefixed Symbol.		
8.11 Bang		
8.11.1 Line Comment.		
8.11.2 Eof Object		
8.11.3 DSSSL Formal Parameter List Annotation		
8.11.4 Read Mark Invocation		
8.12 Case Sensitive Expression.		
8.13 Case Insensitive Expression.		
8.14 Conditional Expansion		
0.17 Conditional Dapansion		
9 Non-standard macros and special forms	30	
9.1 Making extra libraries and extensions availablee.		
9.1.1 require-extension.		
9.1.2 define-extension		

9 Non-standard macros and special forms	
9.2 Binding forms for optional arguments	32
9.2.1 optional	
9.2.2 case-lambda	
9.2.3 let-optionals.	
9.2.4 let-optionals*	33
9.3 Other binding forms	3
9.3.1 and-let*	33
9.3.2 rec	3
9.3.3 cut	3
9.3.4 define-values	34
9.3.5 fluid-let	3
9.3.6 let-values	34
9.3.7 let*-values	
9.3.8 letrec-values	
9.3.9 parameterize	
9.3.10 receive	
9.3.11 set!-values.	
9.4 Substitution forms and macros.	
9.4.1 define-constant	
9.4.2 define-inline.	
9.4.3 define-macro.	
9.4.4 define-for-syntax	
9.5 Conditional forms.	
9.5.1 select	
9.5.2 unless.	
9.5.3 when	
9.6 Record structures.	
9.6.1 define-record	
9.6.2 define-record-printer	
9.6.3 define-record-type	
9.7 Other forms.	
9.7.1 assert	
9.7.2 cond-expand	
9.7.3 ensure.	
9.7.4 eval-when	
9.7.5 include	
9.7.6 nth-value.	
9.7.7 time	
<u>9.7.7 time</u>	4\
10 Dattern metaline	4
10.1 Pattern Matching Expressions.	
10.2 Patterns	
10.4 R 15: P 1	
10.4 Record Structures Pattern.	
10.5 Code Generation.	40
11 Deslamations	
11 Declarations.	
11.1 declare	
11.2 always-bound	
11.3 block	
11.4 block-global	
11.5 hide	4′

11.6 bound-to-procedure	48
* * * * * * * * * * * * * * * * * * *	
11.0.1.1	48
11.8 check-c-syntax.	48
11.9 compress-literals.	48
11.10 constant	48
11.11 export	
11.12 emit-exports.	
11.13 emit-external-prototypes-first	
11.14 disable-interrupts.	
11.15 disable-warning.	
11.16 import	
11.17 inline	
11.18 inline-limit.	
11.19 interrupts-enabled	
11.20 keep-shadowed-macros	
11.21 lambda-lift	
11.22 link-options.	
11.23 no-argc-checks.	
11.24 no-bound-checks.	
11.25 no-procedure-checks	
11.26 post-process.	
11.27 number-type.	52
11.28 fixnum-arithmetic.	52
11.29 run-time-macros	52
11.30 standard-bindings	52
11.31 extended-bindings	52
11.32 usual-integrations	52
11.33 unit	53
11.34 unsafe.	53
11.35 unused.	
11.36 uses	
12 Parameters	54
12.1 make-parameter.	
12.2 case-sensitive.	
12.3 dynamic-load-libraries	
12.4 command-line-arguments.	
12.5 current-read-table.	
12.6 exit-handler.	
12.7 eval-handler	
12.8 force-finalizers.	
12.9 implicit-exit-handler	
12.10 keyword-style	
12.11 load-verbose	
12.12 program-name.	
12.13 repl-prompt.	
12.14 reset-handler.	56
<u>-2-12 - 2556- 2342-565</u>	
13 Unit library	
13 Unit library	57
13 Unit library	57

<u>13 Unit library</u>	
<u>13.1.3 bit-set?</u>	57
<u>13.1.4 fixnum?</u>	57
13.1.5 Arithmetic fixnum operations	58
13.1.6 Arithmetic floating-point operations	58
<u>13.1.7 signum</u>	59
<u>13.1.8 finite?</u>	59
13.2 File Input/Output	
13.2.1 current-output-port	
13.2.2 current-error-port	
13.2.3 flush-output	59
<u>13.2.4 port-name</u>	
13.2.5 port-position	
13.2.6 set-port-name!	60
<u>13.3 Files</u>	
13.3.1 delete-file	
<u>13.3.2 file-exists?</u>	
13.3.3 rename-file	
13.4 String ports.	
13.4.1 get-output-string.	
13.4.2 open-input-string	
13.4.3 open-output-string.	
13.5 Feature identifiers	
<u>13.5.1 features</u>	
<u>13.5.2 feature?</u>	
13.5.3 register-feature!	
13.5.4 unregister-feature!	
13.6 Keywords.	
13.6.1 get-keyword	
13.6.2 keyword?	
13.6.3 keywordstring	
13.6.4 stringkeyword	
13.7 Exceptions	
13.7.1 condition-case.	
13.7.2 breakpoint	
13.8 Environment information and system interface	
13.8.1 argv	
13.8.2 exit	
13.8.3 build-platform.	
13.8.4 chicken-version	
13.8.5 errno.	
13.8.6 geteny.	
13.8.7 machine-byte-order.	
13.8.8 machine-type	
13.8.9 on-exit	
13.8.10 software-type	
13.8.11 software-version.	
13.8.12 c-runtime.	
13.8.13 system	
13.9 Execution time	
13.9.1 cpu-time	
13.9.2 current-milliseconds	
13.9.3 current-seconds	65

13 Unit library	
13.9.4 current-gc-milliseconds	69
13.10 Interrupts and error-handling.	69
13.10.1 enable-warnings.	69
<u>13.10.2 error</u>	69
13.10.3 get-call-chain.	69
13.10.4 print-call-chain	70
13.10.5 print-error-message	70
13.10.6 procedure-information.	
13.10.7 reset.	70
13.10.8 warning.	70
13.10.9 singlestep	
13.11 Garbage collection.	
13.11.1 gc	
13.11.2 memory-statistics.	
13.11.3 set-finalizer!	
13.11.4 set-gc-report!	
13.12 Other control structures.	
13.12.1 andmap.	
13.12.2 ormap	
13.12.3 promise?	
13.13 String utilities.	
13.13.1 reverse-liststring.	
13.14 Generating uninterned symbols.	
13.14.1 gensym	
13.14.2 stringuninterned-symbol.	
13.15 Standard Input/Output	
13.15.1 port?	
13.15.2 print.	
13.15.3 print*	
13.16 User-defined named characters.	
<u>13.16.1 char-name</u>	
<u>13.17 Blobs</u>	
<u>13.17.1 make-blob</u>	
<u>13.17.2 blob?</u>	
<u>13.17.3 blob-size</u>	
13.17.4 blobstring.	75
<u>13.17.5 stringblob</u>	75
13.18 Vectors	75
13.18.1 vector-copy!	75
13.18.2 vector-resize.	75
13.19 The unspecified value.	75
<u>13.19.1 void</u>	75
13.20 Continuations.	76
<u>13.20.1 call/cc</u>	76
13.20.2 continuation-capture	76
13.20.3 continuation?	
13.20.4 continuation-graft	
13.20.5 continuation-return	
13.21 Setters	
13.21.1 setter	
13.21.2 getter-with-setter	
13.22 Reader extensions.	

13 Unit library	
13.22.1 define-reader-ctor.	77
13.22.2 set-read-syntax!	77
13.22.3 set-sharp-read-syntax!	
13.22.4 set-parameterized-read-syntax!	78
13.22.5 copy-read-table	
14 Unit eval	80
14.1 Loading code	80
14.1.1 load	80
14.1.2 load-relative.	80
14.1.3 load-noisily	81
14.1.4 load-library	81
14.1.5 set-dynamic-load-mode!	81
14.2 Read-eval-print loop.	82
<u>14.2.1 repl</u>	82
14.3 Macros	82
14.3.1 get-line-number	82
14.3.2 macro?	82
14.3.3 macroexpand	82
14.3.4 macroexpand-1	83
14.3.5 undefine-macro!	83
14.3.6 syntax-error.	83
14.4 Loading extension libraries	
14.4.1 repository-path	83
14.4.2 extension-information	
14.4.3 provide	82
14.4.4 provided?	82
14.4.5 require	82
14.4.6 set-extension-specifier!	82
14.5 System information.	85
14.5.1 chicken-home	85
14.6 Eval	85
14.6.1 eval	85
15 Unit extras	80
15.1 Lists	86
15.1.1 alist-ref	86
15.1.2 alist-update!	86
15.1.3 atom?	86
15.1.4 rassoc	86
15.1.5 butlast	
15.1.6 chop	
15.1.7 compress	
15.1.8 flatten	
15.1.9 intersperse	
15.1.10 join	
15.1.11 shuffle	
15.1.12 tail?	
15.2 String-port extensions.	
15.2.1 call-with-input-string.	
15.2.2 call-with-output-string.	
15.2.3 with-input-from-string.	

15 Unit extras	
15.2.4 with-output-to-string.	89
15.3 Formatted output	89
15.3.1 printf	89
15.3.2 fprintf	89
15.3.3 sprintf	
15.3.4 format	
15.4 Hash tables.	
15.4.1 hash-table-remove!	
15.5 Queues	
15.5.1 listqueue.	
15.5.2 make-queue	
15.5.3 queue?	
15.5.4 queuelist	
15.5.5 queue-add!	
15.5.6 queue-empty?	
15.5.7 queue-first	
15.5.8 queue-last	
15.5.9 queue-remove!	
15.5.10 queue-push-back!	
15.5.11 queue-push-back-list!	
15.6 Sorting	
15.6.1 merge	
15.6.2 sort	
15.6.3 sorted?	
15.7 Random numbers	
15.7 Random numbers	
15.7.2 randomize	
15.8 Input/Output extensions.	
15.8.1 make-input-port.	
15.8.2 make-output-port	
15.8.3 pretty-print.	
15.8.4 pretty-print-width	
15.8.5 read-byte	
15.8.6 write-byte	
15.8.7 read-file	
15.8.8 read-line	
15.8.9 write-line	
15.8.10 read-lines	
15.8.11 read-string.	
15.8.12 read-string!	
15.8.13 write-string	
15.8.14 read-token	
15.8.15 with-error-output-to-port	
15.8.16 with-input-from-port.	
15.8.17 with-output-to-port	
15.9 Strings	
<u>15.9.1 conc.</u>	
15.9.2 string	
15.9.3 string-chop.	
15.9.4 string-chomp.	98
15.9.5 string-compare3	98
15.9.6 string-intersperse.	98

	15 Unit extras	
	15.9.7 string-split.	98
	15.9.8 string-translate.	99
	15.9.9 string-translate*	99
	<u>15.9.10 substring=?</u>	99
	15.9.11 substring-index	99
15.10	<u>0 Combinators</u>	100
	<u>15.10.1 any?</u>	100
	15.10.2 constantly.	100
	15.10.3 complement	100
	<u>15.10.4 compose</u>	100
	<u>15.10.5 conjoin</u>	101
	15.10.6 disjoin	101
	15.10.7 each	101
	15.10.8 flip	101
	15.10.9 identity	102
	15.10.10 project	102
	15.10.11 list-of	102
	15.10.12 noop.	102
	15.10.13 o.	
15.1	1 Binary searching.	
	15.11.1 binary-search	
16 U	Jnit srfi-1.	104
1 <b>7</b> U	Unit srfi-4	105
	17.1 make-XXXvector	
	17.2 u8vectorblob.	
	17.3 s8vectorblob	
	17.4 u16vectorblob.	
	17.5 s16vectorblob	
	17.6 u32vectorblob.	
	17.7 s32vectorblob	
	17.8 f32vectorblob.	
	17.9 f64vectorblob.	
	17.10 u8vectorblob/shared	
	17.11 s8vectorblob/shared	
	17.12 u16vectorblob/shared	
	17.13 s16vectorblob/shared	
	17.14 u32vectorblob/shared	
	17.15 s32vectorblob/shared	
	17.16 f32vectorblob/shared	
	17.17 f64vectorblob/shared	
	17.18 blobu8vector.	
	17.19 blobs8vector	
	17.20 blobu16vector.	
	17.20 blobs16vector	
	17.22 blobu32vector.	
	17.22 blobs32vector	
	17.24 blobf32vector.	
	17.25 blobf64vector.	
	17.25 blobu8vector/shared	
	17.26 blobs8vector/shared	
	1 / . 2 / DIOUSO VECTOI/SHATEU	108

	<u>17 Unit srfi-4</u>	
	17.28 blobu16vector/shared	108
	17.29 blobs16vector/shared.	108
	17.30 blobu32vector/shared	108
	17.31 blobs32vector/shared.	108
	17.32 blobf32vector/shared	108
	17.33 blobf64vector/shared	108
	17.34 subu8vector.	109
	17.35 subu16vector.	109
	17.36 subu32vector.	109
	17.37 subs8vector.	109
	<u>17.38 subs16vector</u>	109
	17.39 subs32vector.	109
	17.40 subf32vector	109
	<u>17.41 subf64vector</u>	109
	17.42 read-u8vector.	110
	17.43 read-u8vector!	110
	17.44 write-u8vector.	110
18 U	<u>Init srfi-13</u>	111
19 U	<u> </u>	112
<b>20 U</b> 1	<u> </u>	113
<b>21 U</b> 1	<u>Init regex</u>	114
	<u>21.1 grep</u>	114
	21.2 globregexp.	114
	<u>21.3 glob?</u>	114
	<u>21.4 regexp</u>	115
	<u>21.5 regexp?</u>	115
	21.6 string-match	115
	21.7 string-match-positions.	115
	21.8 string-search	115
	21.9 string-search-positions.	116
	21.10 string-split-fields.	116
	21.11 string-substitute.	116
	21.12 string-substitute*	117
	21.13 regexp-escape	117
<b>22 U</b> 1	<u>Init srfi-18</u>	118
	22.1 thread-signal!	118
	22.2 thread-quantum	118
	22.3 thread-quantum-set!	
	22.4 thread-suspend!	119
	22.5 thread-resume!	119
	22.6 timemilliseconds	119
<b>23 U</b> 1	<u>Init posix</u>	
	23.1 Directories	120
	23.1.1 change-directory.	120
	23.1.2 current-directory.	120
	23.1.3 create-directory.	120

	23 Unit posix	
	23.1.4 delete-directory.	120
	<u>23.1.5 directory.</u>	121
	23.1.6 directory?	121
	23.1.7 glob.	121
	23.1.8 set-root-directory!	121
23.2 Pir	•	
	23.2.1 call-with-input-pipe	
	23.2.2 call-with-output-pipe.	
	23.2.3 close-input-pipe.	
	23.2.4 close-output-pipe.	
	23.2.5 create-pipe.	
	23.2.6 open-input-pipe.	
	23.2.7 open-output-pipe.	
	23.2.8 pipe/buf	
	23.2.9 with-input-from-pipe.	
	23.2.10 with-output-to-pipe.	
72 2 EH	<u>23.2.10 wttn-оцфис-to-рipe</u>	
23.3 FII	23.3.1 create-fifo	
	23.3.2 fifo?	
22 4 E:1	e descriptors and low-level I/Q.	
<u> 23.4 FII</u>		
	23.4.1 duplicate-fileno.	
	23.4.2 file-close	
	23.4.3 file-open	
	23.4.4 file-mkstemp.	
	23.4.5 file-read	
	23.4.6 file-select	
	23.4.7 file-write	
	23.4.8 file-control	
	23.4.9 fcntl/dupfd	
	23.4.10 fcntl/getfd	
	23.4.11 fcntl/setfd	
	23.4.12 fcntl/getfl	
	<u>23.4.13 fcntl/setfl.</u>	
	23.4.14 fileno/stdin.	
	23.4.15 fileno/stdout	
	23.4.16 fileno/stderr.	
	23.4.17 open/rdonly.	
	23.4.18 open/wronly	
	23.4.19 open/rdwr.	
	23.4.20 open/read	
	<u>23.4.21 open/write</u>	127
	23.4.22 open/creat	127
	23.4.23 open/append.	127
	23.4.24 open/excl	127
	23.4.25 open/noctty.	127
	23.4.26 open/nonblock	
	23.4.27 open/trunc.	
	23.4.28 open/sync.	
	23.4.29 open/fsync	
	23.4.30 open/binary	
	23.4.31 open/text.	
	23.4.32 open-input-file*	

23 Unit posix		
23.4.33 open-output-file*		128
23.4.34 portfileng		128
23.5 Retrieving file attributes		128
23.5.1 file-access-time		128
· · · · · · · · · · · · · · · · · · ·		
<u> </u>		
*		
•		
*		
*		
<u> </u>		
*		
23.8 Hard and symbolic links		132
23.8.1 symbolic-link?		133
23.8.2 create-symbolic-link		133
23.8.3 read-symbolic-link		133
23.8.4 file-link		133
23.9 Permissions.		133
23.9.1 file-owner		133
	id.	
· · · · · · · · · · · · · · · · · · ·	<u>-ru</u> <u>ıp-id</u>	
•	<del>10-14</del>	
* •		
*		
<u> </u>		
23.9.22 perm/ixgrp		136

	23 Unit posix	
	23.9.23 perm/iroth	136
	23.9.24 perm/iwoth	136
	23.9.25 perm/ixoth	137
	23.9.26 perm/irwxu	137
	23.9.27 perm/irwxg	137
	23.9.28 perm/irwxo	137
	23.9.29 perm/isvtx	137
	23.9.30 perm/isuid	137
	23.9.31 perm/isgid	137
	23.9.32 set-process-group-id!	137
	23.9.33 user-information.	137
	23.9.34 create-session.	138
23.10	0 Record locking	
	23.10.1 file-lock	138
	23.10.2 file-lock/blocking.	
	23.10.3 file-test-lock	
	23.10.4 file-unlock	
23.1	1 Signal handling.	
	23.11.1 set-alarm!	
	23.11.2 set-signal-handler!	
	23.11.3 signal-handler.	
	23.11.4 set-signal-mask!	
	23.11.5 signal-mask	
	23.11.6 signal-masked?	
	23.11.7 signal-mask!	
	23.11.8 signal-unmask!	
	23.11.9 signal/term	
	23.11.10 signal/kill	
	23.11.11 signal/int	
	23.11.12 signal/hup	
	23.11.13 signal/fpe	
	23.11.14 signal/ill	
	23.11.15 signal/segy	
	23.11.16 signal/abrt	
	23.11.17 signal/trap	
	23.11.18 signal/quit	
	23.11.19 signal/alrm	
	23.11.20 signal/vtalrm	
	23.11.21 signal/prof	
	23.11.22 signal/io	
	23.11.23 signal/urg	
	23.11.24 signal/chld	
	23.11.25 signal/cont	
	23.11.26 signal/stop.	
	23.11.27 signal/tstp.	
	23.11.28 signal/pipe.	
	23.11.29 signal/xcpu	
	23.11.30 signal/xfsz	
	23.11.31 signal/usr1.	
	23.11.32 signal/usr2	
	23.11.33 signal/winch.	
23.12	2 Environment access.	142

	23 Unit posix	
	23.12.1 current-environment	.142
	<u>23.12.2 setenv</u>	.143
	<u>23.12.3 unsetenv</u>	.143
23.13 I	Memory mapped I/O	.143
	23.13.1 memory-mapped-file?	.143
	23.13.2 map-file-to-memory.	.143
	23.13.3 memory-mapped-file-pointer.	.143
	23.13.4 unmap-file-from-memory.	
23.14 I	Date and time routines.	
	23.14.1 secondslocal-time.	.144
	23.14.2 local-timeseconds.	
	23.14.3 local-timezone-abbreviation.	.145
	23.14.4 secondsstring	
	23.14.5 secondsutc-time.	
	23.14.6 utc-timeseconds	
	23.14.7 timestring.	
23.15 I	Raw exit	
	23.15.1 exit	
23 16 I	ERRNO values	
20.10	23.16.1 errno/perm	
	23.16.2 errno/noent.	
	23.16.3 errno/srch.	
	23.16.4 errno/intr.	
	23.16.5 errno/io.	
	23.16.6 errno/noexec.	
	23.16.7 errno/badf.	
	23.16.8 errno/child	
	23.16.9 errno/nomem	
	23.16.10 errno/acces.	
	23.16.11 errno/fault	
	23.16.12 errno/busy	
	23.16.13 errno/notdir	
	23.16.14 errno/isdir.	
	23.16.15 errno/inval	
	23.16.17 arms (reserve	
	23.16.19 crmo/nospc.	
	23.16.18 errno/spipe	
	23.16.19 errno/pipe.	
	23.16.20 errno/again	
	23.16.21 errno/rofs	
	23.16.22 errno/exist	
	23.16.23 errno/wouldblock	
<u>23.17 l</u>	Finding files.	
	<u>23.17.1 find-files</u>	
<u>23.18 (</u>	Getting the hostname and system information.	
	23.18.1 get-host-name	
	23.18.2 system-information.	
23.19 S	Setting the file buffering mode.	
	23.19.1 set-buffering-mode!	
<u> 23.20                                  </u>	<u>Ferminal ports</u>	
	23.20.1 terminal-name.	
	23.20.2 terminal-port?	149

23 Unit posix	
23.21 How Scheme procedures relate to UNIX C functions	150
23.22 Windows specific notes	
23.22.1 Procedure Changes.	
23.22.2 Unsupported Definitions	155
23.22.3 Additional Definitions	155
23.22.4 process-spawn	156
24 Unit utils	
24.1 Environment Query.	
<u>24.1.1 apropos</u>	
24.1.2 apropos-list	
24.2 Pathname operations.	
24.2.1 absolute-pathname?	
24.2.2 decompose-pathname	
24.2.3 make-pathname.	158
24.2.4 make-absolute-pathname.	
24.2.5 pathname-directory	
24.2.6 pathname-file	
24.2.7 pathname-extension.	158
24.2.8 pathname-replace-directory	159
24.2.9 pathname-replace-file	159
24.2.10 pathname-replace-extension	159
24.2.11 pathname-strip-directory.	159
24.2.12 pathname-strip-extension	159
24.2.13 directory-null?	159
24.3 Temporary files	159
24.3.1 create-temporary-file	160
24.4 Deleting a file without signalling an error.	160
24.4.1 delete-file*	160
24.5 Iterating over input lines and files	160
24.5.1 for-each-line	160
24.5.2 for-each-argy-line.	160
24.5.3 port-for-each.	161
24.5.4 port-map	161
24.5.5 port-fold.	161
24.6 Executing shell commands with formatstring and error checking	
24.6.1 system*	
24.7 Reading a file's contents	161
24.7.1 read-all	
24.8 Funky ports	
24.8.1 make-broadcast-port.	
24.8.2 make-concatenated-port	
24.9 Miscellaneous handy things.	
24.9.1 shift!	
24.9.2 unshift!	
25 Unit ton	474
25 Unit tep	
25.1 tcp-listen	
25.2 tcp-listener?	
25.3 tcp-close	
25.4 tcp-accept	
25.5 tcp-accept-ready?	165

	25 Unit tep	
	25.6 tcp-listener-port	165
	25.7 tcp-listener-fileno	165
	25.8 tcp-connect	165
	25.9 tcp-addresses	166
	25.10 tcp-port-numbers	166
	25.11 tcp-abandon-port	166
	25.12 tcp-buffer-size.	
	25.13 tcp-read-timeout.	
	25.14 tcp-write-timeout	167
	25.15 tcp-connect-timeout	
	25.16 tcp-accept-timeout.	
	25.17 Example.	
26 Unit	t lolevel	169
	26.1 Foreign pointers.	
	26.1.1 addresspointer.	
	26.1.2 allocate	
	26.1.3 free	
	26.1.4 null-pointer	
	26.1.5 null-pointer?	
	26.1.6 objectpointer.	
	<u>26.1.7 pointer?</u>	
	26.1.8 pointer=?.	
	26.1.9 pointeraddress	
	26.1.10 pointerobject.	170
	26.1.11 pointer-offset	171
	26.1.12 pointer-u8-ref	171
	<u>26.1.13 pointer-s8-ref.</u>	171
	26.1.14 pointer-u16-ref.	171
	26.1.15 pointer-s16-ref	171
	26.1.16 pointer-u32-ref	
	26.1.17 pointer-s32-ref	
	26.1.18 pointer-f32-ref	
	26.1.19 pointer-f64-ref.	
	26.1.20 pointer-u8-set!	
	26.1.21 pointer-s8-set!	
	26.1.21 pointer-s8-set! 26.1.22 pointer-u16-set!	
	26.1.23 pointer-s16-set!	
	<u> </u>	
	26.1.24 pointer-u32-set!	
	26.1.25 pointer-s32-set!	
	<u>26.1.26 pointer-f32-set!</u>	
	<u>26.1.27 pointer-f64-set!</u>	
	26.1.28 align-to-word.	
	agged pointers	
	26.2.1 tag-pointer	174
	26.2.2 tagged-pointer?	174
	26.2.3 pointer-tag	174
26.3 Ex	stending procedures with data	174
	26.3.1 extend-procedure.	174
	26.3.2 extended-procedure?	
	26.3.3 procedure-data.	
	26.3.4 set-procedure-data!	

<u>26 Unit loievel</u>	
26.4 Data in unmanaged memory.	
26.4.1 object-evict	
26.4.2 object-evict-to-location	
26.4.3 object-evicted?	
26.4.4 object-size.	
26.4.5 object-release	
26.4.6 object-unevict	170
26.5 Locatives	17
26.5.1 make-locative	
26.5.2 make-weak-locative.	
<u>26.5.3 locative?</u>	17′
26.5.4 locative-ref.	17
<u>26.5.5 locative-set!</u>	178
26.5.6 locativeobject	178
26.6 Accessing toplevel variables	178
26.6.1 global-bound?	178
<u>26.6.2 global-ref</u>	178
26.6.3 global-set!	178
26.7 Low-level data access.	179
<u>26.7.1 block-ref</u>	179
26.7.2 block-set!	179
26.7.3 object-copy	179
26.7.4 make-record-instance.	
26.7.5 move-memory!	180
26.7.6 number-of-bytes	180
26.7.7 number-of-slots	180
26.7.8 record-instance?	180
26.7.9 recordvector.	
26.8 Procedure-call- and variable reference hooks.	
26.8.1 set-invalid-procedure-call-handler!	
26.8.2 unbound-variable-value.	
26.9 Magic	
26.9.1 object-become!	
26.9.2 mutate-procedure.	
<u>-00) 12 III.W.W.C p. 0000010</u>	
27 Interface to external functions and variables	182
28 Accessing external objects	184
28.1 foreign-code.	
28.2 foreign-value	
28.3 foreign-declare.	
28.4 define-foreign-type.	
28.5 define-foreign-variable	
28.6 define-foreign-record.	
28.6.1 TYPENAME-SLOTNAME	
28.6.2 TYPENAME-SLOTNAME-set!	
28.6.3 constructor.	
28.6.4 destructor.	
28.6.5 rename	
28.7 define-foreign-enum.	
28.8 foreign-lambda	
28.9 foreign-lambda*	188

28 Accessing external objects	
28.10 foreign-safe-lambda.	189
28.11 foreign-safe-lambda*.	189
28.12 foreign-primitive.	189
29 Foreign type specifiers	190
29.1 scheme-object	190
<u>29.2 bool</u>	190
29.3 byte unsigned-byte	190
29.4 char unsigned-char.	190
29.5 short unsigned-short	190
29.6 int unsigned-int int32 unsigned-int32.	190
29.7 integer unsigned-integer integer32 unsigned-integer32 integer64	190
29.8 long unsigned-long	191
29.9 float double	191
29.10 number	191
29.11 symbol	191
29.12 scheme-pointer.	191
29.13 nonnull-scheme-pointer.	191
29.14 c-pointer.	192
29.15 nonnull-c-pointer	192
29.16 [nonnull-] blob	192
29.17 [nonnull-] u8vector [nonnull-] u16vector [nonnull-] u32vector [nonnull-] s8vector	
[nonnull-] s16vector [nonnull-] s32vector [nonnull-] f32vector [nonnull-] f64vector	192
29.18 c-string	192
29.19 nonnull-c-string	192
29.20 [nonnull-] c-string*	193
29.21 [nonnull-] unsigned-c-string[*]	193
29.22 c-string-list	193
29.23 c-string-list*	193
<u>29.24 void</u>	193
29.25 (const TYPE)	193
29.26 (enum NAME)	193
29.27 (pointer TYPE) (c-pointer TYPE)	194
29.28 (nonnull-pointer TYPE) (nonnull-c-pointer TYPE)	194
29.29 (ref TYPE).	194
29.30 (struct NAME)	194
29.31 (template TYPE ARGTYPE)	194
29.32 (union NAME)	194
29.33 (instance CNAME SCHEMECLASS)	194
29.34 (instance-ref CNAME SCHEMECLASS)	195
29.35 (function RESULTTYPE (ARGUMENTTYPE1 []) [CALLCONV])	195
29.36 Mappings	
30 Embedding	197
30.1 CHICKEN parse command line.	
30.2 CHICKEN initialize	
30.3 CHICKEN run.	
30.4 return-to-host	
30.5 CHICKEN eval	
30.6 CHICKEN eval string	
30.7 CHICKEN eval to string	
30.8 CHICKEN eval string to string.	

	30 Embedding	
	30.9 CHICKEN apply	199
	30.10 CHICKEN apply to string	199
	30.11 CHICKEN read	199
	30.12 CHICKEN load	199
	30.13 CHICKEN get error message	199
	30.14 CHICKEN yield	199
	30.15 CHICKEN continue.	201
	30.16 CHICKEN new gc root.	202
	30.17 CHICKEN delete gc root.	202
	30.18 CHICKEN gc root ref.	202
	30.19 CHICKEN gc root set.	202
	30.20 CHICKEN global lookup	203
	30.21 CHICKEN global ref.	203
	30.22 CHICKEN global set.	203
<u>31 (</u>	<u>Callbacks</u>	<b>20</b> 4
	31.1 define-external.	204
	31.2 C callback	205
	31.3 C callback adjust stack limits	205
<u>32 I</u>	<u>Locations</u>	206
	32.1 define-location.	206
	32.2 let-location	206
	32.3 location	206
<u>33 (</u>	Other support procedures	208
	33.1 argc+argv.	208
<u>34 (</u>	<u>Cinterface</u>	
	<u>34.1 C save</u>	209
	34.2 C restore	
	<u>34.3 C fix</u>	209
	34.4 C make character.	
	34.5 C SCHEME END OF LIST	
	34.6 C word C SCHEME END OF FILE	
	34.7 C word C SCHEME FALSE	210
	34.8 C word C SCHEME TRUE.	210
	34.9 C string	210
	<u>34.10 C string2</u>	210
	<u>34.11 C intern2</u>	210
	<u>34.12 C intern3</u>	210
	<u>34.13 C pair</u>	210
	<u>34.14 C flonum</u>	211
	<u>34.15 C int to num</u>	211
	<u>34.16 C mpointer</u>	211
	34.17 C vector.	211
	<u>34.18 C list</u>	211
	34.19 C alloc.	211
	34.20 C SIZEOF LIST.	212
	34.21 C SIZEOF STRING	212
	34.22 C SIZEOF VECTOR.	212
	34.23 C SIZEOF INTERNED SYMBOL	212

	34 C Interface	
	34.24 C SIZEOF PAIR	212
	34.25 C SIZEOF FLONUM	212
	34.26 C SIZEOF POINTER	212
	34.27 C SIZEOF LOCATIVE	212
	34.28 C SIZEOF TAGGED POINTER	213
	34.29 C character code	213
	<u>34.30 C unfix</u>	213
	34.31 C flonum magnitude	213
	<u>34.32 C c string</u>	213
	34.33 C num to int	213
	34.34 C pointer address	213
	34.35 C header size	214
	34.36 C header bits.	214
	34.37 C block item	214
	34.38 C u i car.	214
	34.39 C u i cdr.	214
	34.40 C data pointer	214
	34.41 C make header	215
	34.42 C mutate	215
	34.43 C symbol value	215
	34.44 C gc protect	215
	34.45 C gc unprotect	
	34.46 C post gc hook	
	<u>*</u>	
35 c	chicken-setup.	218
	35.1 Extension libraries.	218
	35.2 Installing extensions.	218
	35.3 Creating extensions.	218
	35.4 Procedures and macros available in setup scripts	219
	35.4.1 install-extension.	219
	35.4.2 install-program	221
	35.4.3 install-script	221
	<u>35.4.4 run</u>	221
	35.4.5 compile	221
	35.4.6 make	221
	35.4.7 patch	221
	35.4.8 copy-file	222
	35.4.9 move-file	222
	35.4.10 remove-file*	222
	35.4.11 find-library	222
	35.4.12 find-header	
	35.4.13 try-compile	223
	35.4.14 create-directory.	
	35.4.15 installation-prefix.	
	35.4.16 program-path	223
	35.4.17 setup-root-directory	
	35.4.18 setup-build-directory.	
	35.4.19 setup-verbose-flag	
	35.4.20 setup-install-flag.	
	35.4.21 required-chicken-version.	
	35.4.22 required-extension-version.	
	35.4.23 cross-chicken.	

35 chicken-setup	
35.5 Examples for extensions	225
35.6 chicken-setup reference	227
35.7 Windows notes	229
35.8 Security.	229
35.9 Other modes of installation.	229
35.10 Linking extensions statically	230
36 Data representation	231
36.1 Immediate objects.	231
36.2 Non-immediate objects.	231
37 Bugs and limitations.	233
<u>38 FAQ</u>	
38.1 General	
38.1.1 Why yet another Scheme implementation?	234
38.1.2 What should I do if I find a bug?	234
38.1.3 Why are values defined with define-foreign-variable or define-constant or	
define-inline not seen outside of the containing source file?	234
38.1.4 How does cond-expand know which features are registered in used units?	235
38.1.5 Why are constants defined by define-constant not honoured in case constructs?	
38.1.6 How can I enable case sensitive reading/writing in user code?	
38.1.7 How can I change match-error-control during compilation?	
38.1.8 Why doesn't CHICKEN support the full numeric tower by default?	
38.1.9 How can I specialize a generic function method to match instances of every	230
class?	236
38.1.10 Does CHICKEN support native threads?	
38.2 Platform specific.	
38.2.1 How do I generate a DLL under MS Windows (tm)?	
38.2.2 How do I generate a GUI application under Windows(tm)?	
**	231
38.2.3 Compiling very large files under Windows with the Microsoft C compiler fails with a	225
message indicating insufficient heap space	
38.2.4 When I run csi inside an emacs buffer under Windows, nothing happens	
38.2.5 I load compiled code dynamically in a Windows GUI application and it crashes	
38.2.6 On Windows, csc.exe seems to be doing something wrong.	
38.2.7 On Windows source and/or output filenames with embedded whitespace are not found	
	238
38.3.1 How do I run custom startup code before the runtime-system is invoked?	
38.3.2 How can I add compiled user passes?	
38.4 Compiled macros.	
38.4.1 Why is define-macro complaining about unbound variables?	
38.4.2 Why isn't load properly loading my library of macros?	239
38.4.3 Why is include unable to load my hygienic macros?	239
38.4.4 Why are macros not visible outside of the compilation unit in which they are defined?	239
38.5 Warnings and errors.	239
38.5.1 Why does my program crash when I use callback functions (from Scheme to C and back	
to Scheme again)?	239
38.5.2 Why does the linker complain about a missing function C toplevel?	
38.5.3 Why does the linker complain about a missing function C toplevel?	
38.5.4 Why does my program crash when I compile a file with -unsafe or unsafe declarations?	
38.5.5 Why do I get a warning when I define a global variable named match?	
38.5.6 Why don't toplevel-continuations captured in interpreted code work?	
50.5.0 11 my don't topic vor continuations captured in interpreted code work	1

<u>38 FAQ</u>	
38.5.7 Why does define-reader-ctor not work in my compiled program?	241
38.5.8 Why do built-in units, such as srfi-1, srfi-18, and posix fail to load?	241
38.5.9 How can I increase the size of the trace shown when runtime errors are detected?	242
38.6 Optimizations	242
38.6.1 How can I obtain smaller executables?	
38.6.2 How can I obtain faster executables?	242
38.6.3 Which non-standard procedures are treated specially when the extended-bindings or	
usual-integrations declaration or compiler option is used?	243
38.6.4 Can I load compiled code at runtime?	243
38.7 Garbage collection	244
38.7.1 Why does a loop that doesn't cons still trigger garbage collections?	244
38.7.2 Why do finalizers not seem to work in simple cases in the interpeter?	244
38.8 Interpreter.	
38.8.1 Does CSI support history and autocompletion?	245
38.8.2 Does code loaded with load run compiled or interpreted?	245
38.9 Extensions.	245
38.9.1 How can I install Chicken eggs to a non-default location?	
38.9.2 Can I install chicken eggs as a non-root user?.	246
39 Acknowledgements	247
40 Bibliography.	249

## 1 The User's Manual

(This document describes version 2.702)

**CHICKEN** is a compiler that translates Scheme source files into C, which in turn can be fed to a C-compiler to generate a standalone executable. An interpreter is also available and can be used as a scripting environment or for testing programs before compilation.

This package is distributed under the **BSD license** and as such is free to use and modify.

The method of compilation and the design of the runtime-system follow closely Henry Baker's <u>CONS Should Not CONS Its Arguments</u>, <u>Part II: Cheney on the M.T.A.</u> paper and expose a number of interesting properties:

- Consing (creation of data on the heap) is relatively inexpensive, because a generational garbage collection scheme is used, in which short-lived data structures are reclaimed extremely quickly.
- Moreover, call-with-current-continuation is practically for free and CHICKEN does not suffer under any performance penalties if first-class continuations are used in complex ways.

The generated C code is fully tail-recursive.

Some of the features supported by CHICKEN:

- SRFIs 0, 1, 2, 4, 6-19, 23, 25-31, 37-40, 42, 43, 45, 47, 55, 57, 60-63, 66, 69, 72, 78, 85 and 95.
- Lightweight threads based on first-class continuations
- Pattern matching with Andrew Wright's match package
- Record structures
- Extended comment- and string-literal syntaxes
- Libraries for regular expressions, string handling
- UNIX system calls and extended data structures
- Create interpreted or compiled shell scripts written in Scheme for UNIX or Windows
- Compiled C files can be easily distributed
- Allows the creation of fully self-contained statically linked executables
- On systems that support it, compiled code can be loaded dynamically

This manual is merely a reference for the CHICKEN system and assumes a working knowledge of Scheme.

The manual is split in the following sections:

### Basic mode of operation

Compiling Scheme files.

### Using the compiler

Explains how to use CHICKEN to compile programs and execute them.

### Using the interpreter

Invocation and usage of CSi, the CHICKEN interpreter

## Supported language

The language implemented by CHICKEN (deviations from the standard and extensions).

## <u>Interface to external functions and variables</u>

Accessing C and C++ code and data.

### chicken-setup

Packaging and installing extension libraries.

### Data representation

How Scheme data is internally represented.

## **Bugs and limitations**

Yes, there are some.

1 The User's Manual

## <u>FAQ</u>

A list of Frequently Asked Questions about CHICKEN (and their answers!).

# Acknowledgements

A list of some of the people that have contributed to make CHICKEN what it is. Bibliography

Links to documents that may be of interest.

1 The User's Manual 2

# 2 Basic mode of operation

The compiler translates Scheme source code into fairly portable C that can be compiled and linked with most available C compilers. CHICKEN supports the generation of executables and libraries, linked either statically or dynamically. Compiled Scheme code can be loaded dynamically, or can be embedded in applications written in other languages. Separate compilation of modules is fully supported.

The most portable way of creating separately linkable entities is supported by so-called *units*. A unit is a single compiled object module that contains a number of toplevel expressions that are executed either when the unit is the *main* unit or if the unit is *used*. To use a unit, the unit has to be *declareed* as used, like this:

```
(declare (uses UNITNAME))
```

The toplevel expressions of used units are executed in the order in which the units appear in the uses declaration. Units may be used multiple times and uses declarations may be circular (the unit is initialized at most once). To compile a file as a unit, add a unit declaration:

```
(declare (unit UNITNAME))
```

When compiling different object modules, make sure to have one main unit. This unit is called initially and initializes all used units before executing its toplevel expressions. The main-unit has no unit declaration.

Another method of using definitions in separate source files is to *include* them. This simply inserts the code in a given file into the current file:

```
(include "FILENAME")
```

Macro definitions are only available when processed by include or require-for-syntax. Macro definitions in separate units are not available, since they are defined at compile time, i.e the time when that other unit was compiled (macros can optionally be available at runtime, see define-macro in <u>Substitution</u> forms and macros).

On platforms that support dynamic loading of compiled code (Windows, most ELF based systems like Linux or BSD, MacOS X, and others) code can be compiled into a shared object .dll, .so, .dylib) and loaded dynamically into a running application.

Previous: index.html Next: Using the compiler

# 3 Using the compiler

The interface to Chicken is intentionally simple. System dependent makefiles, shell-scripts or batch-files should perform any necessary steps before and after invocation of Chicken. A program named CSC provides a much simpler interface to the Scheme- and C-compilers and linker. Enter

```
csc -help
```

on the command line for more information.

# 3.1 Compiler command line format

chicken FILENAME {OPTION}

**FILENAME** is the complete pathname of the source file that is to be translated into C. A filename argument of - specifies that the source text should be read from standard input. Note that the filename has to be the first argument to chicken.

Possible options are:

-analyze-only

Stop compilation after first analysis pass.

-benchmark-mode

Equivalent to -no-trace -no-lambda-info -optimize-level 3 -fixnum-arithmetic -disable-interrupts -block -lambda-lift.

-block

Enable block-compilation. When this option is specified, the compiler assumes that global variables are not modified outside this compilation-unit. Specifically, toplevel bindings are not seen by eval and unused toplevel bindings are removed.

-case-insensitive

Enables the reader to read symbols case insensitive. The default is to read case sensitive (in violation of R5RS). This option registers the Case-insensitive feature identifier.

-check-imports

Search for references to undefined global variables. For each library unit accessed via (declare (uses ...)), the compiler will search a file named UNITNAME.exports in the current include path and load its contents into the *import-table* (if found). Also, export-information for extensions (accessed through (require-extension ...)) will be searched and stored in the import-table. If a required extension does not provide explicit export-information a .exports file is searched (as with used units). After the analysis phase of the compiler, referenced toplevel variables for which no assignment was found will generate a warning. Also, re-assignments of imported variables will trigger a warning.

-check-syntax

Aborts compilation process after macro-expansion and syntax checks.

### -compress-literals THRESHOLD

Compiles quoted literals that exceed the size THRESHOLD as strings and parse the strings at run-time. This reduces the size of the code and speeds up compile-times of the host C compiler, but has a small run-time performance penalty. The size of a literal is computed by counting recursively the objects in the literal, so a vector counts as 1 plus the count of the elements, a pair counts as the counts of the car and the cdr, respectively. All other objects count 1.

-debug MODES

3 Using the compiler 4

Enables one or more compiler debugging modes. MODES is a string of characters that select debugging information about the compiler that will be printed to standard output.

```
show time needed for compilation
t
           show breakdown of time needed for each compiler pass
b
           show performed optimizations
0
           show invocation parameters
r
S
           show program-size information and other statistics
           show node-matching during simplification
а
           show execution of compiler sub-passes
           show lambda-lifting information
l
           show GC statistics during compilation
m
           print the line-number database
n
           print every expression before macro-expansion
C
           lists all unassigned global variable references
u
           display information about experimental features
Х
D
           when printing nodes, use node-tree output
           show the real-name mapping table
Ν
           show expressions after the secondary user pass
U
           show database before lambda-lifting pass
0
           show expressions after lambda-lifting
L
М
           show unit-information and syntax-/runtime-requirements
1
           show source expressions
2
           show canonicalized expressions
3
           show expressions converted into CPS
4
           show database after each analysis pass
5
           show expressions after each optimization pass
6
           show expressions after each inlining pass
7
           show expressions after complete optimization
8
           show database after final analysis
9
           show expressions after closure conversion
```

#### -debug-level LEVEL

Selects amount of debug-information. LEVEL should be an integer.

### -disable-interrupts

Equivalent to the (disable-interrupts) declaration. No interrupt-checks are generated for compiled programs.

### -disable-compiler-macros

disable expansion of compiler macros.

#### -disable-stack-overflow-checks

Disables detection of stack overflows. This is equivalent to running the compiled executable with the -: 0 runtime option.

-disable-warning CLASS : Disables specific class of warnings, may be given multiple times. The following classes are defined

usage	warnings related to command-line arguments
type	warnings related to type-conversion
ext	warnings related to extension libraries
var	warnings related to variable- and syntax-definitions and
const	warnings related to constant-definitions

syntax syntax-related warnings

redef warnings about redefinitions of standard- or extended-bi

call warnings related to known procedure calls

ffi warnings related to the foreign function interface

### -dynamic

This option should be used when compiling files intended to be loaded dynamically into a running Scheme program.

## -epilogue FILENAME

Includes the file named FILENAME at the end of the compiled source file. The include-path is not searched. This option may be given multiple times.

### -emit-exports FILENAME

Write exported toplevel variables to FILENAME.

## -emit-external-prototypes-first

Emit prototypes for callbacks defined with define-external before any other foreign declarations. This is sometimes useful, when C/C++ code embedded into the a Scheme program has to access the callbacks. By default the prototypes are emitted after foreign declarations.

## -explicit-use

Disables automatic use of the units library, eval and extras. Use this option if compiling a library unit instead of an application unit.

## -extend FILENAME

Loads a Scheme source file or compiled Scheme program (on systems that support it) before compilation commences. This feature can be used to extend the compiler. This option may be given multiple times. The file is also searched in the current include path and in the extension-repository.

#### -extension

Mostly equivalent to -prelude '(define-extension <NAME>)', where <NAME> is the basename of the currently compiled file. Note that if you want to compile a file as a normal (dynamically loadable) extension library, you should also pass the -shared option.

## -feature SYMBOL

Registers SYMBOL to be a valid feature identifier for cond-expand. Multiple symbols may be given, if comma-separated.

#### -fixnum-arithmetic

Equivalent to (fixnum-arithmetic) declaration. Assume all mathematical operations use small integer arguments.

### -heap-size NUMBER

Sets a fixed heap size of the generated executable to NUMBER bytes. The parameter may be followed by a M(m) or K(k) suffix which stand for mega- and kilobytes, respectively. The default heap size is 5 kilobytes. Note that only half of it is in use at every given time.

### -heap-initial-size NUMBER

Sets the size that the heap of the compiled application should have at startup time.

#### -heap-growth PERCENTAGE

Sets the heap-growth rate for the compiled program at compile time (see: -:hg).

### -heap-shrinkage PERCENTAGE

Sets the heap-shrinkage rate for the compiled program at compile time (see: -: hs).

## -help

Print a summary of available options and the format of the command line parameters and exit the compiler.

## -import FILENAME

Read exports from linked or loaded libraries from given file. See also -check-imports. This is equivalent to declaring (declare (import FILENAME)). Implies -check-imports.

### -include-path PATHNAME

Specifies an additional search path for files included via the include special form. This option may be given multiple times. If the environment variable CHICKEN\_INCLUDE\_PATH is set, it should contain a list of alternative include pathnames separated by ; . The environment variable

CHICKEN HOME is also considered as a search path.

#### -inline

Enable procedure inlining for known procedures of a size below the threshold (which can be set through the -inline-limit option).

#### -inline-limit THRESHOLD

Sets the maximum size of a potentially inlinable procedure. This option is only effective when inlining has been enabled with the -inline option. The default threshold is 10.

### -keyword-style STYLE

Enables alternative keyword syntax, where STYLE may be either prefix (as in Common Lisp), suffix (as in DSSSL) or none. Any other value is ignored. The default is suffix.

### -keep-shadowed-macros

Do not remove macro definitions with the same name as assigned toplevel variables (the default is to remove the macro definition).

#### -lambda-lift

Enable the optimization known as lambda-lifting.

#### -no-lambda-info

Don't emit additional information for each lambda expression (currently the argument-list, after alpha-conversion/renaming).

#### -no-trace

Disable generation of tracing information. If a compiled executable should halt due to a runtime error, then a list of the name and the line-number (if available) of the last procedure calls is printed, unless -no-trace is specified. With this option the generated code is slightly faster.

### -no-warnings

Disable generation of compiler warnings.

### -nursery NUMBER

### -stack-size NUMBER

Sets the size of the first heap-generation of the generated executable to NUMBER bytes. The parameter may be followed by a M (m) or K (k) suffix. The default stack-size depends on the target platform.

## -optimize-leaf-routines

Enable leaf routine optimization.

#### -optimize-level LEVEL

Enables certain sets of optimization options. LEVEL should be an integer.

-optimize-level 0	does nothing.
-optimize-level 1	is equivalent to -optimize-leaf-routines
-optimize-level 2	is currently the same as -optimize-level 1
-optimize-level 3	is equivalent to -optimize-leaf-routines -unsafe

## -output-file FILENAME

Specifies the pathname of the generated C file. Default is FILENAME. c.

#### -postlude EXPRESSIONS

Add EXPRESSIONS after all other toplevel expressions in the compiled file. This option may be given multiple times. Processing of this option takes place after processing of -epilogue.

## -prelude EXPRESSIONS

Add EXPRESSIONS before all other toplevel expressions in the compiled file. This option may be given multiple times. Processing of this option takes place before processing of -prologue.
-profile

#### -accumulate-profile

Instruments the source code to count procedure calls and execution times. After the program terminates (either via an explicit exit or implicitly), profiling statistics are written to a file named PROFILE. Each line of the generated file contains a list with the procedure name, the number of calls and the time spent executing it. Use the chicken-profile program to display the profiling information in a more user-friendly form. Enter chicken-profile with no arguments at the command line to get a list of available options. The -accumulate-profile option is similar to

-profile, but the resulting profile information will be appended to any existing PROFILE file. chicken-profile will merge and sum up the accumulated timing information, if several entries for the same procedure calls exist.

## -profile-name FILENAME

Specifies name of the generated profile information (which defaults to PROFILE. Implies -profile.

### -prologue FILENAME

Includes the file named FILENAME at the start of the compiled source file. The include-path is not searched. This option may be given multiple times.

-quiet

Disables output of compile information.

-raw

Disables the generation of any implicit code that uses the Scheme libraries (that is all runtime system files besides runtime.c and chicken.h).

## -require-extension NAME

Loads the extension NAME before the compilation process commences. This is identical to adding (require-extension NAME) at the start of the compiled program. If -uses NAME is also given on the command line, then any occurrences of -require-extension NAME are replaced with (declare (uses NAME)). Multiple names may be given and should be separated by ,.

#### -run-time-macros

Makes macros also available at run-time. By default macros are not available at run-time.

#### -to-stdout

Write compiled code to standard output instead of creating a . C file.

#### -unit NAME

Compile this file as a library unit. Equivalent to -prelude "(declare (unit NAME))" -unsafe

Disable runtime safety checks.

#### -unsafe-libraries

Marks the generated file for being linked with the unsafe runtime system. This should be used when generating shared object files that are to be loaded dynamically. If the marker is present, any attempt to load code compiled with this option will signal an error.

#### -uses NAME

Use definitions from the library unit NAME. This is equivalent to -prelude "(declare (uses NAME))". Multiple arguments may be given, separated by ,.

### -no-usual-integrations

Specifies that standard procedures and certain internal procedures may be redefined, and can not be inlined. This is equivalent to declaring (not usual-integrations).

#### -version

Prints the version and some copyright information and exit the compiler.

#### -verbose

Prints progress information to standard output during compilation.

The environment variable CHICKEN\_OPTIONS can be set to a string with default command-line options for the compiler.

# 3.2 Runtime options

After successful compilation a C source file is generated and can be compiled with a C compiler. Executables generated with CHICKEN (and the compiler itself) accept a small set of runtime options:

-:?

Shows a list of the available runtime options and exits the program.

3.2 Runtime options

#### -: aNUMBER

Specifies the length of the buffer for recording a trace of the last invoked procedures. Defaults to 16.

-:b

Enter a read-eval-print-loop when an error is encountered.

-:B

Sounds a bell (ASCII 7) on every major garbage collection.

-: C

Forces console mode. Currently this is only used in the interpreter (CSi) to force output of the #; N> prompt even if stdin is not a terminal (for example if running in an emacs buffer under Windows).

-:d

Prints some debug-information at runtime.

-:D

Prints some more debug-information at runtime.

### -: fNUMBER

Specifies the maximal number of currently pending finalizers before finalization is forced.

#### -: hNUMBER

Specifies fixed heap size

### -: hgPERCENTAGE

Sets the growth rate of the heap in percent. If the heap is exhausted, then it will grow by PERCENTAGE. The default is 200.

### -: hiNUMBER

Specifies the initial heap size

#### -: hmNUMBER

Specifies a maximal heap size. The default is (2GB - 15).

#### -: hsPERCENTAGE

Sets the shrink rate of the heap in percent. If no more than a quarter of PERCENTAGE of the heap is used, then it will shrink to PERCENTAGE. The default is 50. Note: If you want to make sure that the heap never shrinks, specify a value of 0. (this can be useful in situations where an optimal heap-size is known in advance).

-:0

Disables detection of stack overflows at run-time.

-:r

Writes trace output to stderr. This option has no effect with in files compiled with the -no-trace options.

#### -: sNUMBER

Specifies stack size.

### -: tNUMBER

Specifies symbol table size.

- :W

Enables garbage collection of unused symbols. By default unused and unbound symbols are not garbage collected.

-:X

Raises uncaught exceptions of separately spawned threads in primordial thread. By default uncaught exceptions in separate threads are not handled, unless the primordial one explicitly joins them. When warnings are enabled (the default) and -: X is not given, a warning will be shown, though.

The argument values may be given in bytes, in kilobytes (suffixed with K or k), in megabytes (suffixed with M or m), or in gigabytes (suffixed with G or g). Runtime options may be combined, like -:dc, but everything following a NUMBER argument is ignored. So -:wh64m is OK, but -:h64mw will not enable GC of unused symbols.

3.2 Runtime options 9

# 3.3 Examples

# 3.3.1 A simple example (with one source file)

To compile a Scheme program (assuming a UNIX-like environment) consisting of a single source file, perform the following steps.

## 3.3.1.1 Writing your source file

In this example we will assume your source file is called foo.scm:

## 3.3.1.2 Compiling your program

```
Compile the file foo.scm:
```

```
% csc foo.scm
```

This will produce the foo executable:

```
% ls
foo foo.scm
```

## 3.3.1.3 Running your program

To run your newly compiled executable use:

```
% foo
3628800
```

If you get a foo: command not found error, you might want to try with ./foo instead (or, in Unix machines, modify your PATH environment variable to include your current directory).

3.3 Examples 10

## 3.3.2 An example with multiple files

If multiple bodies of Scheme code are to be combined into a single executable, then we have to compile each file and link the resulting object files together with the runtime system.

Let's consider an example where your program consists of multiple source files.

## 3.3.2.1 Writing your source files

The declarations in these files specify which of the compiled files is the main module, and which is the library module. An executable can only have one main module, since a program has only a single entry-point. In this case foo.scm is the main module, because it doesn't have a unit declaration:

# 3.3.2.2 Compiling and running your program

You should compile your two files with the following commands:

```
% csc -c bar.scm
% csc -c foo.scm
```

That should produce two files, bar. 0 and foo. 0. They contain the code from your source files in compiled form.

To link your compiled files use the following command:

```
% csc foo.o bar.o -o foo
```

This should produce the foo executable, which you can run just as in the previous example. At this point you

can also erase the \*. 0 files.

You could avoid one step and link the two files just as foo.scm is compiled:

```
% csc -c bar.scm
% csc foo.scm bar.o -o foo
```

Note that if you want to distribute your program, you might want it to follow the GNU Coding Standards. One relatively easy way to achieve this is to use Autoconf and Automake, two tools made for this specific purpose.

# 3.4 Extending the compiler

The compiler supplies a couple of hooks to add user-level passes to the compilation process. Before compilation commences any Scheme source files or compiled code specified using the -extend option are loaded and evaluated. The parameters user-options-pass, user-read-pass, user-preprocessor-pass, user-pass, user-pass-2 and user-post-analysis-pass can be set to procedures that are called to perform certain compilation passes instead of the usual processing (for more information about parameters see: Supported language.

## [parameter] user-options-pass

Holds a procedure that will be called with a list of command-line arguments and should return two values: the source filename and the actual list of options, where compiler switches have their leading

- (hyphen) removed and are converted to symbols. Note that this parameter is invoked **before** processing of the -extend option, and so can only be changed in compiled user passes.

### [parameter] user-read-pass

Holds a procedure of three arguments. The first argument is a list of strings with the code passed to the compiler via -prelude options. The second argument is a list of source files including any files specified by -prologue and -epilogue. The third argument is a list of strings specified using -postlude options. The procedure should return a list of toplevel Scheme expressions.

## [parameter] user-preprocessor-pass

Holds a procedure of one argument. This procedure is applied to each toplevel expression in the source file **before** macro-expansion. The result is macro-expanded and compiled in place of the original expression.

### [parameter] user-pass

Holds a procedure of one argument. This procedure is applied to each toplevel expression **after** macro-expansion. The result of the procedure is then compiled in place of the original expression.

## [parameter] user-pass-2

Holds a procedure of three arguments, which is called with the canonicalized node-graph as its sole argument. The result is ignored, so this pass has to mutate the node-structure to cause any effect. [parameter] user-post-analysis-pass

Holds a procedure that will be called after every performed program analysis pass. The procedure (when defined) will be called with seven arguments: a symbol indicating the analysis pass, the program database, the current node graph, a getter and a setter-procedure which can be used to access and manipulate the program database, which holds various information about the compiled program, a pass iteration count, and an analysis continuation flag. The getter procedure should be called with two arguments: a symbol representing the binding for which information should be retrieved, and a symbol that specifies the database-entry. The current value of the database entry will be returned or #f, if no such entry is available. The setter procedure is called with three arguments: the symbol and key and the new value. The pass iteration count currently is meaningful only for the 'opt pass. The analysis continuation flag will be #f for the last 'opt pass. For information about the contents of the program database contact the author.

Loaded code (via the -extend option) has access to the library units extras, srfi-1, srfi-4, utils, regex and the pattern matching macros. Multithreading is not available.

Note that the macroexpansion/canonicalization phase of the compiler adds certain forms to the source program. These extra expressions are not seen by user-preprocessor-pass but by user-pass.

# 3.5 Distributing compiled C files

It is relatively easy to create distributions of Scheme projects that have been compiled to C. The runtime system of CHICKEN consists of only two handcoded C files (runtime.c and chicken.h), plus the file chicken-config.h, which is generated by the build process. All other modules of the runtime system and the extension libraries are just compiled Scheme code. The following example shows a minimal application, which should run without changes on the most frequent operating systems, like Windows, Linux or FreeBSD:

Let's take a simple "Hello, world!":

```
; hello.scm
(print "Hello, world!")
```

Compiled to C, we get hello.c. We need the files chicken.h and runtime.c, which contain the basic runtime system, plus the three basic library files library.c, eval.c and extras.c which contain the same functionality as the library linked into a plain CHICKEN-compiled application, or which is available by default in the interpreter, CSi:

```
% csc hello.scm -02 -d1
```

A simple makefile is needed as well:

```
# Makefile for UNIX systems
```

library.o: chicken.h eval.o: chicken.h extras.o: chicken.h

Now we have all files together, and can create an tarball containing all the files:

```
% tar cf hello.tar Makefile hello.c runtime.c library.c eval.c extras.c chicken
% gzip hello.tar
```

This is of naturally rather simplistic. Things like enabling dynamic loading, estimating the optimal stack-size and selecting supported features of the host system would need more configuration- and build-time support. All this can be addressed using more elaborate build-scripts, makefiles or by using autoconf/automake.

Note also that the size of the application can still be reduced by removing extras and eval and compiling hello.scm with the -explicit-use option.

For more information, study the CHICKEN source code and/or get in contact with the author.

Previous: <u>index.html</u>

Next: <u>Using the interpreter</u>

## 4 Using the interpreter

CHICKEN provides an interpreter named CS1 for evaluating Scheme programs and expressions interactively.

### 4.1 Interpreter command line format

#### csi {FILENAME|OPTION}

where FILENAME specifies a file with Scheme source-code. If the extension of the source file is .SCM, it may be omitted. The runtime options described in <u>Compiler command line format</u> are also available for the interpreter. If the environment variable CSI\_OPTIONS is set to a list of options, then these options are additionally passed to every direct or indirect invocation of CSi. Please note that runtime options (like -:...) can not be passed using this method. The options recognized by the interpreter are:

Ignore everything on the command-line following this marker. Runtime options (-:...) are still recognized.

#### -i -case-insensitive

Enables the reader to read symbols case insensitive. The default is to read case sensitive (in violation of R5RS). This option registers the Case-insensitive feature identifier.

#### -b -batch

Quit the interpreter after processing all command line options.

#### -e -eval EXPRESSIONS

Evaluate EXPRESSIONS. This option implies -batch and -quiet, so no startup message will be printed and the interpreter exits after processing all -eval options and/or loading files given on the command-line.

#### -D -feature SYMBOL

Registers SYMBOL to be a valid feature identifier for cond-expand.

#### -h -help

Write a summary of the available command line options to standard output and exit.

#### -I -include-path PATHNAME

Specifies an alternative search-path for files included via the include special form. This option may be given multiple times. If the environment variable CHICKEN\_INCLUDE\_PATH is set, it should contain a list of alternative include pathnames separated by ;. The environment variable CHICKEN HOME is also considered as a search path.

#### -k -keyword-style STYLE

Enables alternative keyword syntax, where STYLE may be either prefix (as in Common Lisp) or suffix (as in DSSSL). Any other value is ignored.

#### -n -no-init

Do not load initialization-file. If this option is not given and the file ./.csirc or \$HOME/.csirc exists, then it is loaded before the read-eval-print loop commences.

#### -w -no-warnings

Disables any warnings that might be issued by the reader or evaluated code.

#### -q -quiet

Do not print a startup message.

#### -s -script PATHNAME

This is equivalent to -batch -quiet -no-init PATHNAME. Arguments following PATHNAME are available by using command-line-arguments and are not processed as interpreter options. Extra options in the environment variable CSI\_OPTIONS are ignored.

#### -ss PATHNAME

4 Using the interpreter

The same as -s PATHNAME but invokes the procedure main with the value of (command-line-arguments) as its single argument. If the main procedure returns an integer result, then the interpreter is terminated, returning the integer as the status code back to the invoking process. Any other result terminates the interpreter with a zero exit status.

-R -require-extension NAME

Equivalent to evaluating (require-extension NAME).

-v -version

Write the banner with version information to standard output and exit.

## 4.2 Writing Scheme scripts

Since UNIX shells use the #! notation for starting scripts, anything following the characters #! is ignored, with the exception of the special symbols #!optional, #!key, #!rest and #!eof.

The easiest way is to use the -script option like this:

The parameter command-line-arguments is set to a list of the parameters that were passed to the Scheme script. Scripts can be compiled to standalone executables (don't forget to declare used library units).

CHICKEN supports writing shell scripts in Scheme for these platforms as well, using a slightly different approach. The first example would look like this on Windows:

Like UNIX scripts, batch files can be compiled. Windows batch scripts do not accept more than 8 arguments.

Since it is sometimes useful to run a script into the interpreter without actually running it (for example to test specific parts of it), the option -ss can be used as an alternative to -script.-ss PATHNAME is equivalent to -script PATHNAME but invokes (main (command-line-arguments)) after loading all top-level forms of the script file. The result of main is returned as the exit status to the shell. Any non-numeric result exits with status zero:

```
% cat hi.scm
(define (main args)
   (print "Hi, " (car args))
```

```
0)
% csi -ss hi.scm you
Hi, you
% csi -q
#;1> ,l hi.scm
#;2> (main (list "ye all"))
Hi, ye all
0
#;3>
```

## 4.3 Toplevel commands

```
The toplevel loop understands a number of special commands:
,?
       Show summary of available toplevel commands.
,1 FILENAME ...
       Load files with given FILENAMEs
,ln FILENAME ...
       Load files and print result(s) of each top-level expression.
,p EXP
       Pretty-print evaluated expression EXP.
       Describe result of evaluated expression EXP.
,du EXP
       Dump contents of the result of evaluated expression EXP.
dur EXP N
       Dump N bytes of the result of evaluated expression EXP.
,exn
       Describes the last exception that occurred and adds it to the result history (it can be accessed using the
       # notation).
,q
       Quit the interpreter.
r,
       Show system information.
,s TEXT ...
       Execute shell-command.
,t EXP
       Evaluate form and print elapsed time.
       Pretty-print macroexpanded expression EXP (the expression is not evaluated).
,tr SYMBOL ...
       Enables tracing of the toplevel procedures with the given names.
#;1> (fac 10)
                                                   ==> 3628800
#;2> ,tr fac
#;3> (fac 3)
(fac 3)
  (fac 2)
    (fac 1)
```

(fac 0) fac -> 1 CHICKEN User's Manual - The User's Manual

,utr SYMBOL ...

Disables tracing of the given toplevel procedures.

br SYMBOL ...

Sets a breakpoint at the procedures named SYMBOL .... Breakpoint can also be trigged using the breakpoint procedure.

,ubr SYMBOL ...

Removes breakpoints.

,c

Continues execution from the last invoked breakpoint.

,breakall

Enable breakpoints for all threads (this is the default).

,breakonly THREAD

Enable breakpoints only for the thread returned by the expression THREAD.

,info

Lists traced procedures and breakpoints.

,step EXPR

Evaluates EXPR in single-stepping mode. On each procedure call you will be presented with a menu that allows stepping to the next call, leaving single-stepping mode or triggering a breakpoint. Note that you will see some internal calls, and unsafe or heavily optimized compiled code might not be stepped at all. Single-stepping mode is also possible by invoking the singlestep procedure.

You can define your own toplevel commands using the toplevel-command procedure:

## 4.4 toplevel-command

```
[procedure] (toplevel-command SYMBOL PROC [HELPSTRING])
```

Defines or redefines a toplevel interpreter command which can be invoked by entering , SYMBOL. PROC will be invoked when the command is entered and may read any required argument via read (or read-line). If the optional argument HELPSTRING is given, it will be listed by the ,? command.

## 4.5 History access

The interpreter toplevel accepts the special object #[INDEX] which returns the result of entry number INDEX in the history list. If the expression for that entry resulted in multiple values, the first result (or an unspecified value for no values) is returned. If no INDEX is given (and if a whitespace or closing paranthesis character follows the #, then the result of the last expression is returned. Note that the value returned is implicitly quoted.

#### 4.6 set-describer!

```
[procedure] (set-describer! TAG PROC)
```

Sets a custom description handler that invokes PROC when the , d command is invoked with a record-type object that has the type TAG (a symbol). PROC is called with two arguments: the object to be described and an output-port. It should write a possibly useful textual description of the object to the passed output-port. For example:

```
#;1> (define-record point x y)
#;2> (set-describer! 'point (lambda (pt o) (print "a point with x=" (point-x pt
#;3> ,d (make-point 1 2)
a point with x=1 and y=2
```

## 4.7 Auto-completion and edition

On platforms that support it, it is possible to get auto-completion of symbols, history (over different CSi sessions) and a more feature-full editor for the expressions you type using the <a href="http://www.call-with-current-continuation.org/eggs/readline.html">http://www.call-with-current-continuation.org/eggs/readline.html</a> egg by Tony Garnock Jones. It is very useful for interactive use of csi.

To enable it install the egg and put this in your ~/.csirc file:

```
(use readline regex)
(current-input-port (make-gnu-readline-port))
(gnu-history-install-file-manager (string-append (or (getenv "HOME") ".") "/.cs
```

More details are available in the egg's documentation.

## 4.8 Accessing documentation

You can access the manual directly from CSi using the man extension by Mario Domenech Goulart.

To enable it install the egg and put this in your ~/.csirc file:

```
(use man)
(man:load)
```

Then, in CSi, you can search for definitions using man: search as in:

```
(man:search "case")
```

Note that the search uses regular expressions. To view the documentation for one entry from the manual, use man: help as in:

```
(man:help "case-lambda")
```

Note: Currently the documentation provided by the man extension corresponds to Chicken's 2.429, one of the

4.6 set-describer!

#### CHICKEN User's Manual - The User's Manual

last releases whose documentation was in the texinfo format (the format the man extension parses).

Previous: <u>Using the compiler</u>

Next: Supported language

## 5 Supported language

- Deviations from the standard
- Extensions to the standard
- Non-standard read syntax
- Non-standard macros and special forms
- Pattern matching
- <u>Declarations</u>
- Parameters
- <u>Unit library</u> basic Scheme definitions
- <u>Unit eval</u> evaluation and macro-handling
- <u>Unit extras</u> useful utility definitions
- <u>Unit srfi-1</u> List Library
- <u>Unit srfi-4</u> Homogeneous numeric vectors
- <u>Unit srfi-13</u> String library
- <u>Unit srfi-14</u> character set library
- <u>Unit match</u> pattern matching runtime-support
- <u>Unit regex</u> regular expressions
- <u>Unit srfi-18</u> multithreading
- <u>Unit posix</u> Unix-like services
- <u>Unit utils</u> Shell scripting and file operations
- <u>Unit tcp</u> basic TCP-sockets
- <u>Unit lolevel</u> low-level operations

Previous: <u>Using the interpreter</u>

Next: Interface to external functions and variables

5 Supported language 21

### 6 Deviations from the standard

- Identifiers are by default case-sensitive (see Compiler command line format).
- [4.1.3] The maximal number of arguments that may be passed to a compiled procedure or macro is 120. A macro-definition that has a single rest-parameter can have any number of arguments. If the libffi library is available on this platform, and if it is installed, then CHICKEN can take advantage of this. See the README file for more details.
- [4.2.2] letrec does evaluate the initial values for the bound variables sequentially and not in parallel, that is:

```
(letrec ((x 1) (y 2)) (cons x y))
is equivalent to

(let ((x (void)) (y (void)))
   (set! x 1)
   (set! y 2)
   (cons x y) )

where R5RS requires

(let ((x (void)) (y (void)))
   (let ((tmp1 1) (tmp2 2))
        (set! x tmp1)
        (set! y tmp2)
        (cons x y) )
```

- [4.3] syntax-rules macros are not provided but available separately.
- [6.1] equal? compares all structured data recursively, while R5RS specifies that eqv? is used for data other than pairs, strings and vectors.
- [6.2.4] The runtime system uses the numerical string-conversion routines of the underlying C library and so does only understand standard (C-library) syntax for floating-point constants.
- [6.2.5] There is no built-in support for rationals, complex numbers or extended-precision integers (bignums). The routines complex?, real? and rational? are identical to the standard procedure number?. The procedures numerator, denominator, rationalize, make-rectangular and make-polar are not implemented. Fixnums are limited to ±2<sup>30</sup> (or ±2<sup>62</sup> on 64-bit hardware). Support for extended numbers is available as a separate package, provided the GNU multiprecision library is installed.
- [6.2.6] The procedure string->number does not obey read/write invariance on inexact numbers.
- [6.4] The maximum number of values that can be passed to continuations captured using call-with-current-continuation is 120.
- [6.5] Code evaluated in scheme-report-environment or null-environment still sees non-standard syntax.
- [6.6.2] The procedure char-ready? always returns #t for terminal ports. The procedure read does not obey read/write invariance on inexact numbers.
- [6.6.3] The procedures write and display do not obey read/write invariance to inexact numbers.
- [6.6.4] The transcript-on and transcript-off procedures are not implemented.

Previous: Supported language

Next: Extensions to the standard

### 7 Extensions to the standard

- [2.1] Identifiers may contain special characters if delimited with | ... |.
- [2.3] The brackets [ . . . ] are provided as an alternative syntax for ( . . . ). A number of reader extensions is provided. See Non-standard read syntax.
- [4] Numerous non-standard macros are provided. See <u>Non-standard macros and special forms</u> for more information.
- [4.1.4] Extended DSSSL style lambda lists are supported. DSSSL parameter lists are defined by the following grammar:

When a procedure is applied to a list of arguments, the parameters and arguments are processed from left to right as follows:

- Required-parameters are bound to successive arguments starting with the first argument. It shall be an error if there are fewer arguments than required-parameters.
- Next, the optional-parameters are bound with the remaining arguments. If there are fewer arguments than optional-parameters, then the remaining optional-parameters are bound to the result of the evaluation of their corresponding <initializer>, if one was specified, otherwise #f. The corresponding <initializer> is evaluated in an environment in which all previous parameters have been bound.
- If there is a rest-parameter, then it is bound to a list containing all the remaining arguments left over after the argument bindings with required-parameters and optional-parameters have been made. These remaining arguments are also eligible to be bound to keyword-parameters, in which case the argument will be a member of both the rest-parameter list and the keyword-parameter. If there is no rest-parameter and there are no matching keyword-parameters, then it shall be an error for there to be any remaining arguments left unbound.
- If #! key was specified in the parameter-list, there shall be an even number of remaining arguments. These are interpreted as a series of pairs, where the first member of each pair is a keyword specifying the parameter name, and the second member is the corresponding value. It shall be an error if the first member of an argument pair is not a keyword, unless there is a rest-parameter. If the same keyword occurs more than once in the list of arguments, then the corresponding value of the first keyword is the binding value. If there is no argument for a particular keyword-parameter, then the variable is bound to the result of evaluating <initializer>, if one was specified, otherwise #f. The corresponding <initializer> is evaluated in an environment in which all previous parameters have been bound.

It shall be an error for an **<ident>** to appear more than once in a parameter-list.

Keyword arguments are internally handled as rest-parameters with subsequent processing of the argument list. Extra arguments (for example by specifying keyword arguments but no rest argument) are not checked and simply ignored.

Example:

- [4.1.6] set! for unbound toplevel variables is allowed. set! (PROCEDURE ...) ...) is supported, as CHICKEN implements <u>SRFI-17</u>. [4.2.1] The cond form supports <u>SRFI-61</u>.
- [4.2.2] It is allowed for initialization values of bindings in a letrec construct to refer to previous variables in the same set of bindings, so

```
(letrec ((foo 123)
(bar foo) )
bar)
```

is allowed and returns 123.

- [4.2.3] (begin) is allowed in non-toplevel contexts and evaluates to an unspecified value.
- [4.2.5] Delayed expressions may return multiple values.
- [5.2.2] CHICKEN extends standard semantics by allowing internal definitions everywhere, and not only at the beginning of a body. A set of internal definitions is equivalent to a letrec form enclosing all following expressions in the body:

```
(let ((foo 123))
  (bar)
  (define foo 456)
  (baz foo) )

expands into

(let ((foo 123))
  (bar)
  (letrec ((foo 456))
        (baz foo) ) )
```

[5.2] **define** with a single argument is allowed and initializes the toplevel or local binding to an unspecified value. CHICKEN supports *curried* definitions, where the variable name may also be a list specifying a name and a nested lambda list. So

```
(define ((make-adder x) y) (+ x y))
is equivalent to
(define (make-adder x) (lambda (y) (+ x y)))
```

[6] CHICKEN provides numerous non-standard procedures. See the manual sections on library units for more information.

CHICKEN User's Manual - The User's Manual

[6.2.4] The special IEEE floating-point numbers +nan, +inf and -inf are supported, as is negative zero.

[6.3.4] User defined character names are supported. See Char-name. Characters can be given in hexadecimal notation using the  $\#\xspace$ xxx syntax where XX specifies the character code. Character codes above 255 are supported and can be read (and are written) using the  $\#\arrow$ xxxxxxxx and  $\#\arrow$ xxxxxxxxx notations.

Non-standard characters names supported are #\tab, #\linefeed, #\return, #\alarm, #\vtab, #\nul, #\page, #\esc, #\delete and #\backspace.

The third argument to **substring** is optional and defaults to the length of the string.

[6.4] force called with an argument that is not a promise returns that object unchanged. Captured continuations can be safely invoked inside before- and after-thunks of a dynamic-wind form and execute in the outer dynamic context of the dynamic-wind form.

**Implicit** non-multival continuations accept multiple values by discarding all but the first result. Zero values result in the continuation receiving an unspecified value. Note that this slight relaxation of the behaviour of returning multiple values to non-multival continuations does not apply to explicit continuations (created with call-with-current-continuation).

[6.5] The second argument to eval is optional and defaults to the value of (interaction-environment). scheme-report-environment and null-environment accept an optional 2nd parameter: if not #f (which is the default), toplevel bindings to standard procedures are mutable and new toplevel bindings may be introduced.

[6.6] The *tilde* character (~) is automatically expanded in pathnames. Additionally, if a pathname starts with \$VARIABLE..., then the prefix is replaced by the value of the given environment variable.

[6.6.1] if the procedures <code>current-input-port</code> and <code>current-output-port</code> are called with an argument (which should be a port), then that argument is selected as the new current input- and output-port, respectively. The procedures <code>open-input-file</code>, <code>open-output-file</code>, <code>with-input-from-file</code>, <code>with-output-to-file</code>, <code>call-with-input-file</code> and <code>call-with-output-file</code> accept an optional second (or third) argument which should be one or more keywords, if supplied. These arguments specify the mode in which the file is opened. Possible values are the keywords <code>#:text, #:binary</code> or <code>#:append</code>.

Previous: Deviations from the standard

Next: Non-standard read syntax

## 8 Non-standard read syntax

### **8.1 Multiline Block Comment**

#| ... |#

A multiline *block* comment. May be nested. Implements <u>SRFI-30</u>

## **8.2 Expression Comment**

#; EXPRESSION

Treats EXPRESSION as a comment.

### 8.3 External Representation

#, (CONSTRUCTORNAME DATUM ...)

Allows user-defined extension of external representations. (For more information see the documentation for <u>SRFI-10</u>)

# 8.4 Syntax Expression

#'EXPRESSION

An abbreviation for (syntax EXPRESSION).

## 8.5 Location Expression

#\$EXPRESSION

An abbreviation for (location EXPRESSION).

### 8.6 Keyword

### #:SYMBOL

Syntax for keywords. Keywords are symbols that evaluate to themselves, and as such don't have to be quoted.

## 8.7 Multiline String Constant

#### #<<TAG

Specifies a multiline string constant. Anything up to a line equal to TAG (or end of file) will be returned as a single string:

```
(define msg #<<END
  "Hello, world!", she said.
END
)
is equivalent to
(define msg "\"Hello, world!\", she said.")</pre>
```

# 8.8 Multiline String Constant with Embedded Expressions

#### #<#TAG

Similar to #<<, but allows substitution of embedded Scheme expressions prefixed with # and optionally enclosed in curly brackets. Two consecutive #s are translated to a single #:

```
(define three 3)
(display #<#E0F
This is a simple string with an embedded `##' character
and substituted expressions: (+ three 99) ==> #(+ three 99)
(three is "#{three}")
E0F
)
prints
This is a simple string with an embedded `#' character
and substituted expressions: (+ three 99) ==> 102
(three is "3")
```

8.6 Keyword 27

### 8.9 Foreign Declare

```
#> ... <#
```

Abbreviation for foreign-declare " ... ").

## 8.10 Sharp Prefixed Symbol

#%...

Reads like a normal symbol.

## 8.11 Bang

#!...

Interpretation depends on the directly following characters. Only the following are recognized. Any other case results in a read error.

### 8.11.1 Line Comment

• If followed by whitespace or a slash, then everything up the end of the current line is ignored

## 8.11.2 Eof Object

• If followed by the character sequence eof, then the (self-evaluating) end-of-file object is returned

#### 8.11.3 DSSSL Formal Parameter List Annotation

• If followed by any of the character sequences optional, rest or key, then a symbol with the same name (and prefixed with #!) is returned

### 8.11.4 Read Mark Invocation

• If a *read mark* with the same name as the token is registered, then its procedure is called and the result of the read-mark procedure will be returned

8.9 Foreign Declare

## 8.12 Case Sensitive Expression

#cs...

Read the next expression in case-sensitive mode (regardless of the current global setting).

## 8.13 Case Insensitive Expression

#ci...

Read the next expression in case-insensitive mode (regardless of the current global setting).

# 8.14 Conditional Expansion

#+FEATURE EXPR

Equivalent to

(cond-expand (FEATURE EXPR) (else))

Previous: Extensions to the standard

Next: Non-standard macros and special forms

## 9 Non-standard macros and special forms

## 9.1 Making extra libraries and extensions availablee

### 9.1.1 require-extension

```
[syntax] (require-extension ID ...)
[syntax] (use ID ...)
```

This form does all necessary steps to make the libraries or extensions given in **ID** ... available. It loads syntactic extension, if needed and generates code for loading/linking with core library modules or separately installed extensions. **use** is just a shorter alias for **require-extension**. This implementation of **require-extension** is compliant to <u>SRFI-55</u> (see the <u>SRFI-55</u> document for more information).

During interpretation/evaluation require-extension performs one of the following:

- If ID names a built-in feature chicken srfi-0 srfi-2 srfi-6 srfi-8 srfi-9 srfi-10 srfi-17 srfi-23 srfi-30 srfi-39 srfi-55, then nothing is done.
- If ID names one of the syntactic extensions chicken-more-macros chicken-ffi-macros, then this extension will be loaded.
- ID names one of the core library units shipped with CHICKEN, then a (load-library 'ID) will be performed.
- ID names an installed extension with the syntax or require-at-runtime attribute, then the equivalent of (require-for-syntax 'ID) is performed, probably followed by (require . . .) for any run-time requirements.
- Otherwise (require-extension ID) is equivalent to (require 'ID).

During compilation one of the following happens instead:

- If ID names a built-in feature chicken srfi-0 srfi-2 srfi-6 srfi-8 srfi-9 srfi-10 srfi-17 srfi-23 srfi-30 srfi-39 srfi-55, then nothing is done.
- If ID names one of the syntactic extensions Chicken-more-macros chicken-ffi-macros, then this extension will be loaded at compile-time, making the syntactic extensions available in compiled code.
- If ID names one of the core library units shipped with CHICKEN, or if the option -uses ID has been passed to the compiler then a (declare (uses ID)) is generated.
- If ID names an installed extension with the syntax or require-at-runtime attribute, then the equivalent of (require-for-syntax 'ID) is performed, and code is emitted to (require ...) any needed run-time requirements.
- Otherwise (require-extension ID) is equivalent to (require 'ID).

To make long matters short - just use require-extension and it will normally figure everything out for dynamically loadable extensions and core library units.

ID should be a pure extension name and should not contain any path prefixes (for example dir/lib...) is illegal).

**ID** may also be a list that designates an extension-specifier. Currently the following extension specifiers are defined:

CHICKEN User's Manual - The User's Manual

- (srfi NUMBER ...) is required for SRFI-55 compatibility and is fully implemented
- (version ID NUMBER) is equivalent to ID, but checks at compile-time whether the extension named ID is installed and whether its version is equal or higher than NUMBER. NUMBER may be a string or a number, the comparison is done lexicographically (using string>=?).

See also: set-extension-specifier!

When syntax extensions are loaded that redefine the global toplevel macro-expander (for example the syntax-case extension), then all remaining expression in the same toplevel form are still expanded with the old toplevel macro-expander.

#### 9.1.2 define-extension

```
[syntax] (define-extension NAME CLAUSE ...)
```

This macro simplifies the task of writing extensions that can be linked both statically and dynamically. If encountered in interpreted code or code that is compiled into a shared object (specifically if compiled with the feature chicken-compile-shared, done automatically by CSC when compiling with the -shared or -dynamic option) then the code given by clauses of the form

```
(dynamic EXPRESSION ...)
```

are inserted into the output as a begin form.

If compiled statically (specifically if the feature chicken-compile-shared has not been given), then this form expands into the following:

```
(declare (unit NAME))
(provide 'NAME)
```

and all clauses of the form

```
(static EXPRESSION ...)
```

all additionally inserted into the expansion.

As a convenience, the clause

```
(export IDENTIFIER ...)
```

is also allowed and is identical to (declare (export IDENTIFIER ...)) (unless the define-extension form occurs in interpreted code, in with it is simply ignored).

Note that the compiler option -extension NAME is equivalent to prefixing the compiled file with

```
(define-extension NAME)
```

## 9.2 Binding forms for optional arguments

### 9.2.1 optional

```
[syntax] (optional ARGS DEFAULT)
```

Use this form for procedures that take a single optional argument. If ARGS is the empty list DEFAULT is evaluated and returned, otherwise the first element of the list ARGS. It is an error if ARGS contains more than one value.

#### 9.2.2 case-lambda

```
[syntax] (case-lambda (LAMBDA-LIST1 EXP1 ...) ...)
```

Expands into a lambda that invokes the body following the first matching lambda-list.

```
(define plus
  (case-lambda
       (() 0)
       ((x) x)
       ((x y) (+ x y))
       ((x y z) (+ (+ x y) z))
       (args (apply + args))))

(plus)
  (plus 1)
  (plus 1 2 3)
==> 6
```

For more information see the documentation for <u>SRFI-16</u>

## 9.2.3 let-optionals

```
[syntax] (let-optionals ARGS ((VAR1 DEFAULT1) ...) BODY ...)
```

Binding constructs for optional procedure arguments. ARGS should be a rest-parameter taken from a lambda-list. let-optionals binds VAR1 ... to available arguments in parallel, or to DEFAULT1 ... if not enough arguments were provided. let-optionals\* binds VAR1 ... sequentially, so every variable sees the previous ones. it is an error if any excess arguments are provided.

```
(let-optionals '(one two) ((a 1) (b 2) (c 3))
(list a b c)) ==> (one two 3)
```

### 9.2.4 let-optionals\*

```
[syntax] (let-optionals* ARGS ((VAR1 DEFAULT1) ... [RESTVAR]) BODY ...)
```

Binding constructs for optional procedure arguments. ARGS should be a rest-parameter taken from a lambda-list. let-optionals binds VAR1 ... to available arguments in parallel, or to DEFAULT1 ... if not enough arguments were provided. let-optionals\* binds VAR1 ... sequentially, so every variable sees the previous ones. If a single variable RESTVAR is given, then it is bound to any remaining arguments, otherwise it is an error if any excess arguments are provided.

```
(let-optionals* '(one two) ((a 1) (b 2) (c a))

(list a b c) ==> (one two one)
```

## 9.3 Other binding forms

#### 9.3.1 and-let\*

```
[syntax] (and-let* (BINDING ...) EXP1 EXP2 ...)
```

SRFI-2. Bind sequentially and execute body. BINDING can be a list of a variable and an expression, a list with a single expression, or a single variable. If the value of an expression bound to a variable is #f, the and-let\* form evaluates to #f (and the subsequent bindings and the body are not executed). Otherwise the next binding is performed. If all bindings/expressions evaluate to a true result, the body is executed normally and the result of the last expression is the result of the and-let\* form. See also the documentation for SRFI-2.

#### 9.3.2 rec

```
[syntax] (rec NAME EXPRESSION)
[syntax] (rec (NAME VARIABLE ...) BODY ...)
Allows simple definition of recursive definitions. (rec NAME EXPRESSION) is equivalent to (letrec ((NAME EXPRESSION)) NAME) and (rec (NAME VARIABLE ...) BODY ...) is the same as (letrec ((NAME (lambda (VARIABLE ...) BODY ...))) NAME).
```

#### 9.3.3 cut

```
[syntax] (cut SLOT ...)
[syntax] (cute SLOT ...)
```

Syntactic sugar for specializing parameters.

9.2.4 let-optionals\*

#### 9.3.4 define-values

```
[syntax] (define-values (NAME ...) EXP)
```

Defines several variables at once, with the result values of expression EXP.

#### 9.3.5 fluid-let

```
[syntax] (fluid-let ((VAR1 X1) ...) BODY ...)
```

Binds the variables VAR1 ... dynamically to the values X1 ... during execution of BODY ....

#### 9.3.6 let-values

```
[syntax] (let-values (((NAME ...) EXP) ...) BODY ...)
```

Binds multiple variables to the result values of EXP .... All variables are bound simultaneously.

#### 9.3.7 let\*-values

```
[syntax] (let*-values (((NAME ...) EXP) ...) BODY ...)
```

Binds multiple variables to the result values of EXP .... The variables are bound sequentially.

#### 9.3.8 letrec-values

(odd 17) )

9.3.4 define-values

==> #t

### 9.3.9 parameterize

```
[syntax] (parameterize ((PARAMETER1 X1) ...) BODY ...)
```

Binds the parameters PARAMETER1 ... dynamically to the values X1 ... during execution of BODY ... (see also: make-parameter in <u>Parameters</u>). Note that PARAMETER may be any expression that evaluates to a parameter procedure.

#### **9.3.10** receive

```
[syntax] (receive (NAME1 ... [. NAMEn]) VALUEEXP BODY ...)
[syntax] (receive VALUEEXP)
```

SRFI-8. Syntactic sugar for call-with-values. Binds variables to the result values of VALUEEXP and evaluates BODY ....

The syntax

```
(receive VALUEEXP)
```

is equivalent to

```
(receive VALUEEXP )
```

#### 9.3.11 set!-values

```
[syntax] (set!-values (NAME ...) EXP)
```

Assigns the result values of expression EXP to multiple variables.

### 9.4 Substitution forms and macros

#### 9.4.1 define-constant

```
[syntax] (define-constant NAME CONST)
```

Define a variable with a constant value, evaluated at compile-time. Any reference to such a constant should appear textually **after** its definition. This construct is equivalent to **define** when evaluated or interpreted. Constant definitions should only appear at toplevel. Note that constants are local to the current compilation unit and are not available outside of the source file in which they are defined. Names of constants still exist in the Scheme namespace and can be lexically shadowed. If the value is mutable, then the compiler is careful to preserve its identity. **CONST** may be any constant expression, and may also refer to constants defined via **define-constant** previously. This for should only be used at top-level.

9.3.9 parameterize 35

#### 9.4.2 define-inline

```
[syntax] (define-inline (NAME VAR ... [. VAR]) BODY ...)
[syntax] (define-inline NAME EXP)
```

Defines an inline procedure. Any occurrence of NAME will be replaced by EXP or (lambda (VAR ... [. VAR]) BODY ...). This is similar to a macro, but variable-names and -scope will be correctly handled. Inline substitutions take place **after** macro-expansion. EXP should be a lambda-expression. Any reference to NAME should appear textually **after** its definition. Note that inline procedures are local to the current compilation unit and are not available outside of the source file in which they are defined. Names of inline procedures still exist in the Scheme namespace and can be lexically shadowed. This construct is equivalent to define when evaluated or interpreted. Inline definitions should only appear at toplevel.

#### 9.4.3 define-macro

```
[syntax] (define-macro (NAME VAR ... [. VAR]) EXP1 ...)
[syntax] (define-macro NAME (lambda (VAR ... [. VAR]) EXP1 ...))
[syntax] (define-macro NAME1 NAME2)
```

Define a globally visible macro special form. The macro is available as soon as it is defined, i.e. it is registered at compile-time. If the file containing this definition invokes eval and the declaration run-time-macros (or the command line option -run-time-macros) has been used, then the macro is visible in evaluated expressions during runtime. The second possible syntax for define-macro is allowed for portability purposes only. In this case the second argument **must** be a lambda-expression or a macro name. Only global macros can be defined using this form. (define-macro NAME1 NAME2) simply copies the macro definition from NAME2 to NAME1, creating an alias.

Extended lambda list syntax (#!optional, etc.) can be used but note that arguments are source expressions and thus default values for optional or keyword arguments should take this into consideration.

## 9.4.4 define-for-syntax

```
[syntax] (define-for-syntax (NAME VAR ... [. VAR]) EXP1 ...)
[syntax] (define-for-syntax NAME [VALUE])
```

Defines the toplevel variable NAME at macro-expansion time. This can be helpful when you want to define support procedures for use in macro-transformers, for example.

### 9.5 Conditional forms

9.4.2 define-inline

#### **9.5.1** select

```
[syntax] (select EXP ((KEY ...) EXP1 ...) ... [(else EXPn ...)])
```

This is similar to Case, but the keys are evaluated.

#### **9.5.2 unless**

```
[syntax] (unless TEST EXP1 EXP2 ...)
Equivalent to:
(if (not TEST) (begin EXP1 EXP2 ...))
```

#### 9.5.3 when

```
[syntax] (when TEST EXP1 EXP2 ...)
Equivalent to:
(if TEST (begin EXP1 EXP2 ...))
```

### 9.6 Record structures

#### 9.6.1 define-record

```
[syntax] (define-record NAME SLOTNAME ...)
```

Defines a record type. Call make-NAME to create an instance of the structure (with one initialization-argument for each slot). (NAME? STRUCT) tests any object for being an instance of this structure. Slots are accessed via (NAME-SLOTNAME STRUCT) and updated using (NAME-SLOTNAME-set! STRUCT VALUE).

9.5.1 select 37

### 9.6.2 define-record-printer

```
[syntax] (define-record-printer (NAME RECORDVAR PORTVAR) BODY ...)
[syntax] (define-record-printer NAME PROCEDURE)
```

Defines a printing method for record of the type NAME by associating a procedure with the record type. When a record of this type is written using display, write or print, then the procedure is called with two arguments: the record to be printed and an output-port.

define-record-printer works also with SRFI-9 record types.

### 9.6.3 define-record-type

SRFI-9 record types. For more information see the documentation for <u>SRFI-9</u>.

### 9.7 Other forms

#### 9.7.1 assert

```
[syntax] (assert EXP [STRING ARG ...])
```

Signals an error if EXP evaluates to false. An optional message STRING and arguments ARG ... may be supplied to give a more informative error-message. If compiled in *unsafe* mode (either by specifying the -unsafe compiler option or by declaring (unsafe)), then this expression expands to an unspecified value. The result is the value of EXP.

### 9.7.2 cond-expand

```
[syntax] (cond-expand FEATURE-CLAUSE ...)
```

Expands by selecting feature clauses. This form is allowed to appear in non-toplevel expressions.

Predefined feature-identifiers are "situation" specific:

The following feature-identifiers are available in all situations: (machine-byte-order), (machine-type), (software-type), (software-version), where the actual feature-identifier is platform dependent.

In addition the following feature-identifiers may exist: applyhook, extraslot, ptables, dload, libffi.

For further information, see the documentation for <u>SRFI-0</u>.

#### **9.7.3** ensure

```
[syntax] (ensure PREDICATE EXP [ARGUMENTS ...])
```

Evaluates the expression EXP and applies the one-argument procedure PREDICATE to the result. If the predicate returns #f an error is signaled, otherwise the result of EXP is returned. If compiled in *unsafe* mode (either by specifying the -unsafe compiler option or by declaring (unsafe)), then this expression expands to an unspecified value. If specified, the optional ARGUMENTS are used as arguments to the invocation of the error-signalling code, as in (error ARGUMENTS . . . ). If no ARGUMENTS are given, a generic error message is displayed with the offending value and PREDICATE expression.

### 9.7.4 eval-when

```
[syntax] (eval-when (SITUATION ...) EXP ...)
```

Controls evaluation/compilation of subforms. SITUATION should be one of the symbols eval, compile or load. When encountered in the evaluator, and the situation specifier eval is not given, then this form is

9.7.2 cond-expand

not evaluated and an unspecified value is returned. When encountered while compiling code, and the situation specifier <code>compile</code> is given, then this form is evaluated at compile-time. When encountered while compiling code, and the situation specifier <code>load</code> is not given, then this form is ignored and an expression resulting into an unspecified value is compiled instead.

The following table should make this clearer:

	In compiled code	In interpreted
		code
eval	ignore	evaluate
compile	evaluate at compile time	ignore
load	compile as normal	ignore

The situation specifiers compile-time and run-time are also defined and have the same meaning as compile and load, respectively.

#### 9.7.5 include

[syntax] (include STRING)

Include toplevel-expressions from the given source file in the currently compiled/interpreted program. If the included file has the extension . SCM, then it may be omitted. The file is searched in the current directory and, if not found, in all directories specified in the -include-path option.

#### 9.7.6 nth-value

[syntax] (nth-value N EXP)

Returns the Nth value (counting from zero) of the values returned by expression EXP.

#### 9.7.7 time

[syntax] (time EXP1 ...)

Evaluates EXP1 ... and prints elapsed time and some values about GC use, like time spent in major GCs, number of minor and major GCs.

Previous: Non-standard read syntax

Next: Pattern matching

9.7.4 eval-when 40

## 10 Pattern matching

(This description has been taken mostly from Andrew Wright's postscript document)

Pattern matching allows complicated control decisions based on data structure to be expressed in a concise manner. Pattern matching is found in several modern languages, notably Standard ML, Haskell and Miranda. These syntactic extensions internally use the match library unit.

The basic form of pattern matching expression is:

```
(match exp [pat body] ...)
```

where exp is an expression, pat is a pattern, and body is one or more expressions (like the body of a lambda-expression). The match form matches its first subexpression against a sequence of patterns, and branches to the body corresponding to the first pattern successfully matched. For example, the following code defines the usual map function:

The first pattern () matches the empty list. The second pattern  $(x \cdot y)$  matches a pair, binding x to the first component of the pair and y to the second component of the pair.

## 10.1 Pattern Matching Expressions

exp ::= (match exp clause ...)

's-expression

The complete syntax of the pattern matching expressions follows:

```
(match-lambda clause ...)
        (match-lambda* clause ...)
        (match-let ([pat exp] ...) body)
        (match-let* ([pat exp] ...) body)
        (match-letrec ([pat exp] ...) body)
        (match-let var ([pat exp] ...) body)
        (match-define pat exp)
clause ::= [pat body]
        [ pat (=> identifier) body]
pat ::= identifier
                             matches anything, and binds identifier as a variab
                             anything
        ()
                             itself (the empty list)
        #t
                             itself
     | #f
                             itself
                             an `equal?' string
       string
        number
                             an `equal?' number
        character
                            an `equal?' character
```

10 Pattern matching 41

an `equal?' s-expression

```
(pat-1 ... pat-n)
                             a proper list of n elements
        (pat-1 ... pat-n . pat-n+1)
                             a list of n or more elements
        (pat-1 ... pat-n pat-n+1 ..k)
                             a proper list of n+k or more elements [1]
       #(pat-1 ... pat-n)
                             a vector of n elements
       #(pat-1 ... pat-n pat-n+1 ..k)
                             a vector of n+k or more elements
        ($ struct pat-1 ... pat-n)
                             a structure
        (= field pat)
                             a field of a structure
        (and pat-1 ... pat-n)
                             if all of pat-1 through pat-n match
        (or pat-1 ... pat-n)
                             if any of pat-1 through pat-n match
        (not pat-1 ... pat-n)
                             if none of pat-1 through pat-n match
        (? predicate pat-1 ... pat-n)
                             if predicate true and pat-1 through pat-n all matc
                             anything, and binds identifier as a setter
        (set! identifier)
                             anything, and binds identifier as a getter
        (get! identifier)
                             a quasipattern
         qp
                             itself (the empty list)
qp ::= ()
                             itself
       #t
       #f
                             itself
       string
                             an `equal?' string
                             an `equal?' number
       number
                             an `equal?' character
       character
                             an `equal?' symbol
       symbol
       (qp-1 ... qp-n)
                             a proper list of n elements
       (qp-1 ... qp-n . qp-n+1)
                             a list of n or more elements
       (qp-1 \ldots qp-n qp-n+1 \ldots k)
                             a proper list of n+k or more elements
       #(qp-1 ... qp-n)
                             a vector of n elements
       \#(qp-1 ... qp-n qp-n+1 ..k)
                             a vector of n+k or more elements
       ,pat
                             a pattern
                             a pattern, spliced
       ,@pat
```

The notation . . k denotes a keyword consisting of three consecutive dots (ie., . . . ), or two dots and an non-negative integer (eg., . . 1, . . 2), or three consecutive underscores (ie., \_ \_ \_ ), or two underscores and a non-negative integer. The keywords . . . k and \_ \_ k are equivalent. The keywords . . . , \_ \_ \_ , . .  $\theta$ , and \_ \_  $\theta$  are equivalent.

The next subsection describes the various patterns.

The match-lambda and match-lambda\* forms are convenient combinations of match and lambda, and can be explained as follows:

```
(match-lambda [pat body] ...) = (lambda (x) (match x [pat body] ...))

(match-lambda* [pat body] ...) = (lambda x (match x [pat body] ...))
```

where x is a unique variable. The match-lambda form is convenient when defining a single argument function that immediately destructures its argument. The match-lambda\* form constructs a function that accepts any number of arguments; the patterns of match-lambda\* should be lists.

The match-let, match-let\*, match-letrec, and match-define forms generalize Scheme's let, let\*, letrec, and define expressions to allow patterns in the binding position rather than just variables. For example, the following expression:

```
(match-let ([(x y z) (list 1 2 3)]) body ...)
```

binds X to 1, y to 2, and Z to 3 in body .... These forms are convenient for destructuring the result of a function that returns multiple values as a list or vector. As usual for letrec and define, pattern variables bound by match-letrec and match-define should not be used in computing the bound value.

The match, match-lambda, and match-lambda\* forms allow the optional syntax (=> identifier) between the pattern and the body of a clause. When the pattern match for such a clause succeeds, the identifier is bound to a `failure procedure' of zero arguments within the body. If this procedure is invoked, it jumps back to the pattern matching expression, and resumes the matching process as if the pattern had failed to match. The body must not mutate the object being matched, otherwise unpredictable behavior may result.

### 10.2 Patterns

identifier: (excluding the reserved names ?, , =,  $_-$ , and, or, not, set!, get!, ..., and ..k for non-negative integers k) matches anything, and binds a variable of this name to the matching value in the body.

: matches anything, without binding any variables.

(), #t, #f, string, number, character, 's-expression: These constant patterns match themselves, i.e., the corresponding value must be equal? to the pattern.

```
(pat-1 ... pat-n): matches a proper list of n elements that match pat-1 through pat-n.
```

(pat-1 ... pat-n . pat-n+1): matches a (possibly improper) list of at least n elements that ends in something matching pat-n+1.

(pat-1 ... pat-n pat-n+1 ...): matches a proper list of n or more elements, where each element of the tail matches pat-n+1. Each pattern variable in pat-n+1 is bound to a list of the matching values. For example, the expression:

```
(match '(let ([x 1][y 2]) z)
  [('let ((binding values) ...) exp) body])
```

binds binding to the list '(x y), values to the list \'(1 2), and exp to 'z in the body of the match-expression. For the special case where pat-n+1 is a pattern variable, the list bound to that variable may share with the matched value.

```
(pat-1 ... pat-n pat-n+1 ): This pattern means the same thing as the previous pattern.
```

(pat-1 ... pat-n pat-n+1 ..k): This pattern is similar to the previous pattern, but the tail must be at least k elements long. The pattern keywords ..0 and ... are equivalent.

10.2 Patterns 43

```
(pat-1 ... pat-n \sim pat-n+1 k): This pattern means the same thing as the previous pattern.
```

- #(pat-1 ... pat-n): matches a vector of length n, whose elements match pat-1 through pat-n.
- $\#(pat-1 \dots pat-n + 1 \dots)$ : matches a vector of length n or more, where each element beyond n matches pat-n+1.
- #(pat-1 ... pat-n pat-n+1 ..k): matches a vector of length n+k or more, where each element beyond n matches pat-n+1.
- (\$ struct pat-1 ... pat-n): matches a structure declared with define-record or define-record-type.
- (= field pat): is intended for selecting a field from a structure. *field* may be any expression; it is applied to the value being matched, and the result of this application is matched against pat.
- (and pat-1 ... pat-n): matches if all of the subpatterns match. At least one subpattern must be present. This pattern is often used as (and x pat) to bind x to to the entire value that matches pat (cf. as-patterns in ML or Haskell).
- (or pat-1 ... pat-n): matches if any of the subpatterns match. At least one subpattern must be present. All subpatterns must bind the same set of pattern variables.
- (not pat-1 ... pat-n): matches if none of the subpatterns match. At least one subpattern must be present. The subpatterns may not bind any pattern variables.
- (? predicate pat-1 ... pat-n): In this pattern, predicate must be an expression evaluating to a single argument function. This pattern matches if predicate applied to the corresponding value is true, and the subpatterns pat-1 ... pat-n all match. The predicate should not have side effects, as the code generated by the pattern matcher may invoke predicates repeatedly in any order. The predicate expression is bound in the same scope as the match expression, i.e., free variables in predicate are not bound by pattern variables.
- (set! identifier): matches anything, and binds identifier to a procedure of one argument that mutates the corresponding field of the matching value. This pattern must be nested within a pair, vector, box, or structure pattern. For example, the expression:

```
(define x (list 1 (list 2 3)))
(match x [(_ (set! setit))) (setit 4)])
```

mutates the cadadr of x to 4, so that x is '(1(24)).

(get! identifier): matches anything, and binds identifier to a procedure of zero arguments that accesses the corresponding field of the matching value. This pattern is the complement to set!. As with set!, this pattern must be nested within a pair, vector, box, or structure pattern.

*Quasipatterns*: Quasiquote introduces a quasipattern, in which identifiers are considered to be symbolic constants. Like Scheme's quasiquote for data, unquote (,) and unquote-splicing (,@) escape back to normal patterns.

10.2 Patterns 44

#### 10.3 Match Failure

If no clause matches the value, the default action is to invoke the procedure (match-error-procedure) with the value that did not match. The default definition of (match-error-procedure) calls error with an appropriate message:

```
#;1> (match 1 (2 2))
Failed match:
Error: no matching clause for : 1
```

For most situations, this behavior is adequate, but it can be changed by altering the value of the parameter match-error-control:

{procedure} match-error-control

```
(match-error-control [MODE])
```

Selects a mode that specifies how match... macro forms are to be expanded. With no argument this procedure returns the current mode. A single argument specifies the new mode that decides what should happen if no match-clause applies. The following modes are supported:

Signal an error. This is the default.

1.:error

Signal an error and output the offending form.

1.:match

Omits pair? tests when the consequence is to fail in car or cdr rather than to signal an error.

1.:fail

unspecified Non-matching expressions will either fail in car or cdr or return an unspecified value. This mode applies to files compiled with the unsafe option or declaration.

When an error is signalled, the raised exception will be of kind (exn match).

[procedure] match-error-procedure

```
(match-error-procedure [PROCEDURE])
```

Sets or returns the procedure called upon a match error. The procedure takes one argument, the value which failed to match. When the error control mode is #:match a second argument, the source form of the match expression is available.

### 10.4 Record Structures Pattern

The \$ pattern handles native record structures and <u>SRFI-9</u> records transparently. Currently it is required that <u>SRFI-9</u> record predicates are named exactly like the record type name, followed by a ? (question mark) character.

10.3 Match Failure 45

### 10.5 Code Generation

Pattern matching macros are compiled into if-expressions that decompose the value being matched with standard Scheme procedures, and test the components with standard predicates. Rebinding or lexically shadowing the names of any of these procedures will change the semantics of the match macros. The names that should not be rebound or shadowed are:

```
null? pair? number? string? symbol? boolean? char? procedure? vector? list?
equal?
car cdr cadr cdddr ...
vector-length vector-ref
reverse length call/cc
```

Additionally, the code generated to match a structure pattern like (\$ Foo pat-1 ... pat-n) refers to the name Foo?. This name also should not be shadowed.

Previous: Non-standard macros and special forms

Next: <u>Declarations</u>

10.5 Code Generation 46

### 11 Declarations

#### 11.1 declare

```
[syntax] (declare DECLSPEC ...)
```

Process declaration specifiers. Declarations always override any command-line settings. Declarations are valid for the whole compilation-unit (source file), the position of the declaration in the source file can be arbitrary. Declarations are ignored in the interpreter but not in code evaluated at compile-time (by eval-when or in syntax extensions loaded via require-extension or require-for-syntax. DECLSPEC may be any of the following:

## 11.2 always-bound

```
[declaration specifier] (always-bound SYMBOL ...)
```

Declares that the given variables are always bound and accesses to those have not to be checked.

#### 11.3 block

```
[declaration specifier] (block)
```

Assume global variables are never redefined. This is the same as specifying the -block option.

## 11.4 block-global

#### 11.5 hide

```
[declaration specifier] (block-global SYMBOL ...)
[declaration specifier] (hide SYMBOL ...)
```

Declares that the toplevel bindings for SYMBOL ... should not be accessible from code in other compilation units or by eval. Access to toplevel bindings declared as block global is also more efficient.

11 Declarations 47

### 11.6 bound-to-procedure

```
[declaration specifier] (bound-to-procedure SYMBOL ...)
```

Declares that the given identifiers are always bound to procedure values.

### 11.7 c-options

```
[declaration specifier] (c-options STRING ...)
```

Declares additional C/C++ compiler options that are to be passed to the subsequent compilation pass that translates C to machine code. This declaration will only work if the source file is compiled with the CSC compiler driver.

## 11.8 check-c-syntax

```
[declaration specifier] (check-c-syntax)
[declaration specifier] (not check-c-syntax)
```

Enables or disables syntax-checking of embedded C/C++ code fragments. Checking C syntax is the default.

## 11.9 compress-literals

```
[declaration specifier] (compress-literals [THRESHOLD [INITIALIZER]])
```

The same as the -compress-literals compiler option. The threshold argument defaults to 50. If the optional argument INITIALIZER is given, then the literals will not be created at module startup, but when the procedure with this name will be called.

#### 11.10 constant

```
[declaration specifier] (constant SYMBOL ...)
```

Declares the procedures with the names SYMBOL ... as constant, that is, as not having any side effects. This can help the compiler to remove non-side-effecting expressions.

### **11.11** export

```
[declaration specifier] (export SYMBOL ...)
```

The opposite of hide. All given identifiers will be exported and all toplevel variables not listed will be hidden and not be accessible outside of this compilation unit.

### 11.12 emit-exports

```
[declaration specifier] (emit-exports STRING)
```

Write exported toplevel variables to file with name STRING.

## 11.13 emit-external-prototypes-first

```
[declaration specifier] (emit-external-prototypes-first)
```

Emit prototypes for callbacks defined with define-external before any other foreign declarations. Equivalent to giving the -emit-external-prototypes-first option to the compiler.

## 11.14 disable-interrupts

```
[declaration specifier] (disable-interrupts)
[declaration specifier] (not interrupts-enabled)
```

Disable timer-interrupts checks in the compiled program. Threads can not be preempted in main- or library-units that contain this declaration.

## 11.15 disable-warning

```
[declaration specifier] (disable-warning CLASS ...)
```

Disable warnings of type CLASS ... (equivalent to the -disable-warning CLASS compiler option).

# **11.16 import**

```
[declaration specifier] (import SYMBOL-OR-STRING ...)
```

Adds new imports to the list of externally available toplevel variables. Arguments to this declaration may be either strings (designating .exports files, without the file-extension) or symbols which directly designate

11.11 export 49

imported variables.

#### 11.17 inline

```
[declaration specifier] (inline)
[declaration specifier] (not inline)
[declaration specifier] (inline IDENTIFIER ...)
[declaration specifier] (not inline IDENTIFIER ...)
```

If given without an identifier-list, inlining of known procedures is enabled (this is equivalent to the -inline compiler option). When an identifier-list is given, then inlining is enabled only for the specified global procedures. The negated forms (not inline) and (not inline IDENTIFIER) disable global inlining, or inlining for the given global procedures only, respectively.

#### 11.18 inline-limit

```
[declaration specifier] (inline-limit THRESHOLD)
```

Sets the maximum size of procedures which may potentially be inlined. The default threshold is 10.

### 11.19 interrupts-enabled

```
[declaration specifier] (interrupts-enabled)
```

Enable timer-interrupts checks in the compiled program (the default).

## 11.20 keep-shadowed-macros

```
[declaration specifier] (keep-shadowed-macros)
```

Normally, when a toplevel variable is assigned or defined that has the same name as a macro, the macro-definition will be removed (in addition to showing a warning). This declaration will disable the removal of the macro.

#### 11.21 lambda-lift

```
[declaration specifier] (lambda-lift)
```

Enables lambda-lifting (equivalent to the -lambda-lift option).

11.16 import 50

## 11.22 link-options

```
[declaration specifier] (link-options STRING ...)
```

Declares additional linker compiler options that are to be passed to the subsequent compilation pass that links the generated code into an executable or library. This declaration will only work if the source file is compiled with the CSC compiler driver.

## 11.23 no-argc-checks

```
[declaration specifier] (no-argc-checks)
```

Disables argument count checking.

### 11.24 no-bound-checks

```
[declaration specifier] (no-bound-checks)
```

Disables the bound-checking of toplevel bindings.

# 11.25 no-procedure-checks

```
[declaration specifier] (no-procedure-checks)
```

Disables checking of values in operator position for being of procedure type.

# 11.26 post-process

```
[declaration specifier] (post-process STRING ...)
```

Arranges for the shell commands STRING . . . to be invoked after the current file has been translated to C. Any occurrences of the substring \$@@ in the strings given for this declaration will be replaced by the pathname of the currently compiled file, without the file-extension. This declaration will only work if the source file is compiled with the CSC compiler driver.

11.22 link-options 51

## 11.27 number-type

## 11.28 fixnum-arithmetic

```
[declaration specifier] ([number-type] TYPE)
[declaration specifier] (fixnum-arithmetic)
```

Declares that only numbers of the given type are used. TYPE may be fixnum or generic (which is the default).

### 11.29 run-time-macros

```
[declaration specifier] (run-time-macros)
```

Equivalent to the compiler option of the same name - macros defined in the compiled code are also made available at runtime.

# 11.30 standard-bindings

```
[declaration specifier] (standard-bindings SYMBOL ...)
[declaration specifier] (not standard-bindings SYMBOL ...)
```

Declares that all given standard procedures (or all if no symbols are specified) are never globally redefined. If not is specified, then all but the given standard bindings are assumed to be never redefined.

## 11.31 extended-bindings

```
[declaration specifier] (extended-bindings SYMBOL ...)
[declaration specifier] (not extended-bindings SYMBOL ...)
```

Declares that all given non-standard and CHICKEN-specific procedures (or all if no symbols are specified) are never globally redefined. If not is specified, then all but the given extended bindings are assumed to be never redefined.

# 11.32 usual-integrations

```
[declaration specifier] (usual-integrations SYMBOL ...) [declaration specifier] (not usual-integrations SYMBOL ...)
```

11.27 number-type 52

Declares that all given standard and extended bindings (or all if no symbols are specified) are never globally redefined. If not is specified, then all but the given standard and extended bindings are assumed to be never redefined. Note that this is the default behaviour, unless the -no-usual-integrations option has been given.

### 11.33 unit

```
[declaration specifier] (unit SYMBOL)
```

Specify compilation unit-name (if this is a library)

### 11.34 unsafe

```
[declaration specifier] (unsafe)
[declaration specifier] (not safe)
```

Do not generate safety-checks. This is the same as specifying the -unsafe option. Also implies

```
(declare (no-bound-checks) (no-procedure-checks) (no-argc-checks))
```

### **11.35 unused**

```
[declaration specifier] (unused SYMBOL ...)
```

Disables any warnings when the global variable SYMBOL is not defined but used, or defined but never used and not exported.

#### 11.36 uses

```
[declaration specifier] (uses SYMBOL ...)
```

Gives a list of used library-units. Before the toplevel-expressions of the main-module are executed, all used units evaluate their toplevel-expressions in the order in which they appear in this declaration. If a library unit A uses another unit B, then B's toplevel expressions are evaluated before A's. Furthermore, the used symbols are registered as features during compile-time, so cond-expand knows about them.

Previous: Pattern matching

Next: Parameters

### 12 Parameters

Certain behavior of the interpreter and compiled programs can be customized via 'parameters', where a parameter is a procedure of zero or one arguments. To retrieve the value of a parameter call the parameter-procedure with zero arguments. To change the setting of the parameter, call the parameter-procedure with the new value as argument:

Parameters are fully thread-local, each thread of execution owns a local copy of a parameters' value.

CHICKEN implements SRFI-39.

## 12.1 make-parameter

```
[procedure] (make-parameter VALUE [GUARD])
```

Returns a procedure that accepts zero or one argument. Invoking the procedure with zero arguments returns VALUE. Invoking the procedure with one argument changes its value to the value of that argument (subsequent invocations with zero parameters return the new value). GUARD should be a procedure of a single argument. Any new values of the parameter (even the initial value) are passed to this procedure. The guard procedure should check the value and/or convert it to an appropriate form.

### 12.2 case-sensitive

If true, then read reads symbols and identifiers in case-sensitive mode and uppercase characters in symbols are printed escaped. Defaults to #t.

## 12.3 dynamic-load-libraries

A list of strings containing shared libraries that should be checked for explicitly loaded library units (this facility is not available on all platforms). See load-library.

# 12.4 command-line-arguments

Contains the list of arguments passed to this program, with the name of the program and any runtime options (all options starting with -:) removed.

12 Parameters 54

#### 12.5 current-read-table

A read-table object that holds read-procedures for special non-standard read-syntax (see set-read-syntax! for more information).

### 12.6 exit-handler

A procedure of a single optional argument. When exit is called, then this procedure will be invoked with the exit-code as argument. The default behavior is to terminate the program.

#### 12.7 eval-handler

A procedure of one or two arguments. When eval is invoked, it calls the value of this parameter with the same arguments. The default behavior is to evaluate the argument expression and to ignore the second parameter.

## 12.8 force-finalizers

If true, force and execute all pending finalizers before exiting the program (either explicitly by exit or implicitly when the last toplevel expression has been executed). Default is #t.

# 12.9 implicit-exit-handler

A procedure of no arguments. When the last toplevel expression of the program has executed, then the value of this parameter is called. The default behaviour is to invoke all pending finalizers.

# 12.10 keyword-style

Enables alternative keyword syntax, where STYLE may be either #:prefix (as in Common Lisp) or #:suffix (as in DSSSL). Any other value disables the alternative syntaxes.

#### 12.11 load-verbose

A boolean indicating whether loading of source files, compiled code (if available) and compiled libraries should display a message.

12.5 current-read-table 55

## 12.12 program-name

The name of the currently executing program. This is equivalent to (car (argv)) for compiled programs or the filename following the -script option in interpreted scripts.

## 12.13 repl-prompt

A procedure that should evaluate to a string that will be printed before reading interactive input from the user in a read-eval-print loop. Defaults to (lambda () "#; N> ").

### 12.14 reset-handler

A procedure of zero arguments that is called via reset. The default behavior in compiled code is to invoke the value of (exit-handler). The default behavior in the interpreter is to abort the current computation and to restart the read-eval-print loop.

Previous: <u>Declarations</u>

Next: <u>Unit library</u>

12.12 program-name 56

# 13 Unit library

This unit contains basic Scheme definitions. This unit is used by default, unless the program is compiled with the -explicit-use option.

### 13.1 Arithmetic

### 13.1.1 add1/sub1

[procedure] (add1 N) [procedure] (sub1 N)

Adds/subtracts 1 from N.

## 13.1.2 Binary integer operations

Binary integer operations. arithmetic-shift shifts the argument N1 by N2 bits to the left. If N2 is negative, than N1 is shifted to the right. These operations only accept exact integers or inexact integers in word range (32 bit signed on 32-bit platforms, or 64 bit signed on 64-bit platforms).

```
[procedure] (bitwise-and N1 ...)
[procedure] (bitwise-ior N1 ...)
[procedure] (bitwise-xor N1 ...)
[procedure] (bitwise-not N)
[procedure] (arithmetic-shift N1 N2)
```

#### 13.1.3 bit-set?

```
[procedure] (bit-set? N INDEX)
```

Returns #t if the bit at the position INDEX in the integer N is set, or #f otherwise. The rightmost/least-significant bit is bit 0.

### 13.1.4 fixnum?

```
[procedure] (fixnum? X)
```

Returns #t if X is a fixnum, or #f otherwise.

13 Unit library 57

## 13.1.5 Arithmetic fixnum operations

These procedures do not check their arguments, so non-fixnum parameters will result in incorrect results. fxneq negates its argument.

On division by zero, fx/ and fxmod signal a condition of kind (exn arithmetic).

fxshl and fxshr perform arithmetic shift left and right, respectively.

```
[procedure] (fx+ N1 N2)
[procedure] (fx- N1 N2)
[procedure] (fx* N1 N2)
[procedure] (fx/ N1 N2)
[procedure] (fxmod N1 N2)
[procedure] (fxneg N)
[procedure] (fxmin N1 N2)
[procedure] (fxmax N1 N2)
[procedure] (fx= N1 N2)
[procedure] (fx> N1 N2)
[procedure] (fx< N1 N2)
[procedure] (fx>= N1 N2)
[procedure] (fx N1 N2)
[procedure] (fxand N1 N2)
[procedure] (fxior N1 N2)
[procedure] (fxxor N1 N2)
[procedure] (fxnot N)
[procedure] (fxshl N1 N2)
[procedure] (fxshr N1 N2)
```

## 13.1.6 Arithmetic floating-point operations

In safe mode, these procedures throw a type error with non-float arguments (except flonum?, which returns #f). In unsafe mode, these procedures do not check their arguments. A non-flonum argument in unsafe mode can crash the system.

```
[procedure] (flonum? X)
[procedure] (fp+ X Y)
[procedure] (fp- X Y)
[procedure] (fp* X Y)
[procedure] (fp/ X Y)
[procedure] (fpneg X)
[procedure] (fpmin X Y)
[procedure] (fpmax X Y)
[procedure] (fp= X Y)
[procedure] (fp> X Y)
[procedure] (fp> X Y)
[procedure] (fp> X Y)
[procedure] (fp> X Y)
```

CHICKEN User's Manual - The User's Manual

## 13.1.7 signum

```
[procedure] (signum N)
```

Returns 1 if N is positive, -1 if N is negative or 0 if N is zero. Signum is exactness preserving.

### 13.1.8 finite?

```
[procedure] (finite? N)
```

Returns #f if N is negative or positive infinity, and #t otherwise.

## 13.2 File Input/Output

## 13.2.1 current-output-port

```
[procedure] (current-output-port [PORT])
```

Returns default output port. If PORT is given, then that port is selected as the new current output port.

Note that the default output port is not buffered. Use set-buffering-mode! if you need a different behaviour.

## 13.2.2 current-error-port

```
[procedure] (current-error-port [PORT])
```

Returns default error output port. If PORT is given, then that port is selected as the new current error output port.

Note that the default error output port is not buffered. Use set-buffering-mode! if you need a different behaviour.

## 13.2.3 flush-output

```
[procedure] (flush-output [PORT])
```

Write buffered output to the given output-port. PORT defaults to the value of (current-output-port).

13.1.7 signum 59

### 13.2.4 port-name

```
[procedure] (port-name [PORT])
```

Fetch filename from PORT. This returns the filename that was used to open this file. Returns a special tag string, enclosed into parentheses for non-file ports. PORT defaults to the value of (current-input-port).

## 13.2.5 port-position

```
[procedure] (port-position [PORT])
```

Returns the current position of PORT as two values: row and column number. If the port does not support such an operation an error is signaled. This procedure is currently only available for input ports. PORT defaults to the value of (current-input-port).

## 13.2.6 set-port-name!

```
[procedure] (set-port-name! PORT STRING)
```

Sets the name of PORT to STRING.

### **13.3 Files**

#### 13.3.1 delete-file

```
[procedure] (delete-file STRING)
```

Deletes the file with the pathname STRING. If the file does not exist, an error is signaled.

### 13.3.2 file-exists?

```
[procedure] (file-exists? STRING)
```

Returns STRING if a file with the given pathname exists, or #f otherwise.

13.2.4 port-name 60

#### 13.3.3 rename-file

```
[procedure] (rename-file OLD NEW)
```

Renames the file or directory with the pathname OLD to NEW. If the operation does not succeed, an error is signaled.

## 13.4 String ports

## 13.4.1 get-output-string

```
[procedure] (get-output-string PORT)
```

Returns accumulated output of a port created with (open-output-string).

## 13.4.2 open-input-string

[procedure] (open-input-string STRING)

Returns a port for reading from STRING.

# 13.4.3 open-output-string

[procedure] (open-output-string)

Returns a port for accumulating output in a string.

#### 13.5 Feature identifiers

CHICKEN maintains a global list of *features* naming functionality available int the current system. Additionally the <code>cond-expand</code> form accesses this feature list to infer what features are provided. Predefined features are <code>chicken</code>, and the SRFIs (Scheme Request For Implementation) provided by the base system: <code>srfi-23</code>, <code>srfi-30</code>, <code>srfi-39</code>. If the <code>eval</code> unit is used (the default), the features <code>srfi-0</code>, <code>srfi-2</code>, <code>srfi-6</code>, <code>srfi-8</code>, <code>srfi-9</code> and <code>srfi-10</code> are defined. When compiling code (during compile-time) the feature <code>compiling</code> is registered. When evaluating code in the interpreter (csi), the feature <code>csi</code> is registered.

13.3.3 rename-file 61

#### **13.5.1 features**

```
[procedure] (features)
```

Returns a list of all registered features that will be accepted as valid feature-identifiers by cond-expand.

#### 13.5.2 feature?

```
[procedure] (feature? ID ...)
```

Returns #t if all features with the given feature-identifiers ID ... are registered.

## 13.5.3 register-feature!

```
[procedure] (register-feature! FEATURE ...)
```

Register one or more features that will be accepted as valid feature-identifiers by cond-expand. FEATURE . . . may be a keyword, string or symbol.

## 13.5.4 unregister-feature!

```
[procedure] (unregister-feature! FEATURE ...)
```

Unregisters the specified feature-identifiers. FEATURE ... may be a keyword, string or symbol.

# 13.6 Keywords

Keywords are special symbols prefixed with #: that evaluate to themselves. Procedures can use keywords to accept optional named parameters in addition to normal required parameters. Assignment to and bindings of keyword symbols is not allowed. The parameter keyword-style and the compiler/interpreter option -keyword-style can be used to allow an additional keyword syntax, either compatible to Common LISP, or to DSSSL.

## 13.6.1 get-keyword

```
[procedure] (get-keyword KEYWORD ARGLIST [THUNK])
```

Returns the argument from ARGLIST specified under the keyword KEYWORD. If the keyword is not found, then the zero-argument procedure THUNK is invoked and the result value is returned. If THUNK is not given, #f is returned.

13.5.1 features 62

CHICKEN User's Manual - The User's Manual

Note: the KEYWORD may actually be any kind of object.

## 13.6.2 keyword?

```
[procedure] (keyword? X)
```

Returns #t if X is a keyword symbol, or #f otherwise.

## 13.6.3 keywordstring

```
[procedure] (keyword->string KEYWORD)
```

Transforms KEYWORD into a string.

## 13.6.4 stringkeyword

```
[procedure] (string->keyword STRING)
```

Returns a keyword with the name STRING.

## 13.7 Exceptions

CHICKEN implements the (currently withdrawn) <u>SRFI-12</u> exception system. For more information, see the <u>SRFI-12</u> document.

### 13.7.1 condition-case

```
[syntax] (condition-case EXPRESSION CLAUSE ...)
```

Evaluates EXPRESSION and handles any exceptions that are covered by CLAUSE ..., where CLAUSE should be of the following form:

```
CLAUSE = ([VARIABLE] (KIND ...) BODY ...)
```

If provided, VARIABLE will be bound to the signalled exception object. BODY ... is executed when the exception is a property- or composite condition with the kinds given KIND ... (unevaluated). If no clause

13.6.1 get-keyword 63

applies, the exception is re-signalled in the same dynamic context as the condition-case form.

```
(define (check thunk)
  (condition-case (thunk)
    [(exn file) (print "file error")]
    [(exn) (print "other error")]
    [var () (print "something else")] ) )

(check (lambda () (open-input-file "")))  ; -> "file error"
(check (lambda () some-unbound-variable))  ; -> "othererror"
(check (lambda () (signal 99)))  ; -> "something else"

(condition-case some-unbound-variable
  [(exn file) (print "ignored")] )  ; -> signals error
```

## 13.7.2 breakpoint

```
[procedure] (breakpoint [NAME])
```

Programmatically triggers a breakpoint (similar to the , br top-level csi command).

All error-conditions signalled by the system are of kind exn. The following composite conditions are additionally defined:

```
(exn arity)
```

Signalled when a procedure is called with the wrong number of arguments.

```
(exn type)
```

Signalled on type-mismatch errors, for example when an argument of the wrong type is passed to a builtin procedure.

```
(exn arithmetic)
```

Signalled on arithmetic errors, like division by zero.

```
(exn i/o)
```

Signalled on input/output errors.

```
(exn i/o file)
```

Signalled on file-related errors.

```
(exn i/o net)
```

Signalled on network errors.

```
(exn bounds)
```

Signalled on errors caused by accessing non-existent elements of a collection.

```
(exn runtime)
```

Signalled on low-level runtime-system error-situations.

13.7.1 condition-case 64

```
CHICKEN User's Manual - The User's Manual
```

```
(exn runtime limit)
```

Signalled when an internal limit is exceeded (like running out of memory).

(exn match)

Signalled on errors raised by failed matches (see the section on match).

(exn syntax)

Signalled on syntax errors.

(exn breakpoint)

Signalled when a breakpoint is reached.

Notes:

- All error-exceptions (of the kind exn) are non-continuable.
- Error-exceptions of the exn kind have additional arguments and location properties that contain the arguments passed to the exception-handler and the name of the procedure where the error occurred (if available).
- When the posix unit is available and used, then a user-interrupt (signal/int) signals an exception of the kind user-interrupt.
- the procedure condition-property-accessor accepts an optional third argument. If the condition does not have a value for the desired property and if the optional argument is given, no error is signalled and the accessor returns the third argument.
- In composite conditions all properties are currently collected in a single property-list, so in the case that to conditions have the same named property, only one will be visible.

## 13.8 Environment information and system interface

## 13.8.1 argv

```
[procedure] (argv)
```

Return a list of all supplied command-line arguments. The first item in the list is a string containing the name of the executing program. The other items are the arguments passed to the application. This list is freshly created on every invocation of (argv). It depends on the host-shell whether arguments are expanded ('globbed') or not.

#### 13.8.2 exit

```
[procedure] (exit [CODE])
```

Exit the running process and return exit-code, which defaults to 0 (Invokes exit-handler).

13.7.2 breakpoint 65

## 13.8.3 build-platform

```
[procedure] (build-platform)
```

Returns a symbol specifying the toolset which has been used for building the executing system, which is one of the following:

cygwin mingw32 gnu intel unknown

### 13.8.4 chicken-version

```
[procedure] (chicken-version [FULL])
```

Returns a string containing the version number of the CHICKEN runtime system. If the optional argument FULL is given and true, then a full version string is returned.

### 13.8.5 errno

```
[procedure] (errno)
```

Returns the error code of the last system call.

## 13.8.6 getenv

```
[procedure] (getenv STRING)
```

Returns the value of the environment variable STRING or #f if that variable is not defined.

## 13.8.7 machine-byte-order

```
[procedure] (machine-byte-order)
```

Returns the symbol little-endian or big-endian, depending on the machine's byte-order.

13.8.3 build-platform 66

## 13.8.8 machine-type

```
[procedure] (machine-type)
```

Returns a symbol specifying the processor on which this process is currently running, which is one of the following:

```
alpha
mips
hppa
ultrasparc
sparc
ppc
ppc64
ia64
x86
x86-64
unknown
```

### 13.8.9 on-exit

```
[procedure] (on-exit THUNK)
```

Schedules the zero-argument processures THUNK to be executed before the process exits, either explicitly via exit or implicitly after exection of the last toplevel form. Note that finalizers for unreferenced finalized data are run before exit procedures.

# 13.8.10 software-type

```
[procedure] (software-type)
```

Returns a symbol specifying the operating system on which this process is currently running, which is one of the following:

```
windows
unix
macos
ecos
unknown
```

#### 13.8.11 software-version

```
[procedure] (software-version)
```

Returns a symbol specifying the operating system version on which this process is currently running, which is one of the following:

13.8.8 machine-type 67

CHICKEN User's Manual - The User's Manual

linux freebsd netbsd openbsd macosx hpux solaris sunos unknown

### 13.8.12 c-runtime

```
[procedure] (c-runtime)
```

Returns a symbol that designates what kind of C runtime library has been linked with this version of the Chicken libraries. Possible return values are static, dynamic or unknown. On systems not compiled with the Microsoft C compiler, c-runtime always returns unknown.

## 13.8.13 system

[procedure] (system STRING)

Execute shell command. The functionality offered by this procedure depends on the capabilities of the host shell. If the forking of a subprocess failed, an exception is raised. Otherwise the return status of the subprocess is returned unaltered.

### 13.9 Execution time

## 13.9.1 cpu-time

```
[procedure] (cpu-time)
```

Returns the used CPU time of the current process in milliseconds as two values: the time spent in user code, and the time spent in system code. On platforms where user and system time can not be differentiated, system time will be always be 0.

#### 13.9.2 current-milliseconds

```
[procedure] (current-milliseconds)
```

Returns the number of milliseconds since process- or machine startup.

13.8.11 software-version 68

#### 13.9.3 current-seconds

```
[procedure] (current-seconds)
```

Returns the number of seconds since midnight, Jan. 1, 1970.

## 13.9.4 current-gc-milliseconds

```
[procedure] (current-gc-milliseconds)
```

Returns the number of milliseconds spent in major garbage collections since the last call of current-gc-milliseconds and returns an exact integer.

## 13.10 Interrupts and error-handling

## 13.10.1 enable-warnings

```
[procedure] (enable-warnings [BOOL])
```

Enables or disables warnings, depending on wether B00L is true or false. If called with no arguments, this procedure returns #t if warnings are currently enabled, or #f otherwise. Note that this is not a parameter. The current state (whether warnings are enabled or disabled) is global and not thread-local.

#### 13.10.2 error

```
[procedure] (error [LOCATION] [STRING] EXP ...)
```

Prints error message, writes all extra arguments to the value of (current-error-port) and invokes the current exception-handler. This conforms to <u>SRFI-23</u>. If LOCATION is given and a symbol, it specifies the *location* (the name of the procedure) where the error occurred.

## 13.10.3 get-call-chain

```
[procedure] (get-call-chain [START [THREAD]])
```

Returns a list with the call history. Backtrace information is only generated in code compiled without -no-trace and evaluated code. If the optional argument START is given, the backtrace starts at this offset, i.e. when START is 1, the next to last trace-entry is printed, and so on. If the optional argument THREAD is given, then the call-chain will only be constructed for calls performed by this thread.

13.9.3 current-seconds 69

### 13.10.4 print-call-chain

```
[procedure] (print-call-chain [PORT [START [THREAD]]])
```

Prints a backtrace of the procedure call history to PORT, which defaults to (current-output-port).

## 13.10.5 print-error-message

```
[procedure] (print-error-message EXN [PORT [STRING]])
```

Prints an appropriate error message to PORT (which defaults to the value of (current-output-port) for the object EXN. EXN may be a condition, a string or any other object. If the optional argument STRING is given, it is printed before the error-message. STRING defaults to "Error:".

## 13.10.6 procedure-information

[procedure] (procedure-information PROC)

Returns an s-expression with debug information for the procedure PROC, or #f, if PROC has no associated debug information.

#### 13.10.7 reset

```
[procedure] (reset)
```

Reset program (Invokes reset-handler).

## 13.10.8 warning

```
[procedure] (warning STRING EXP ...)
```

Displays a warning message (if warnings are enabled with enable-warnings) and continues execution.

# 13.10.9 singlestep

```
[procedure] (singlestep THUNK)
```

Executes the code in the zero-procedure THUNK in single-stepping mode.

## 13.11 Garbage collection

### 13.11.1 gc

```
[procedure] (gc [FLAG])
```

Invokes a garbage-collection and returns the number of free bytes in the heap. The flag specifies whether a minor (#f) or major (#t) GC is to be triggered. If no argument is given, #t is assumed. An explicit #t argument will cause all pending finalizers to be executed.

## 13.11.2 memory-statistics

```
[procedure] (memory-statistics)
```

Performs a major garbage collection and returns a three element vector containing the total heap size in bytes, the number of bytes currently used and the size of the nursery (the first heap generation). Note that the actual heap is actually twice the size given in the heap size, because CHICKEN uses a copying semi-space collector.

### 13.11.3 set-finalizer!

```
[procedure] (set-finalizer! X PROC)
```

Registers a procedure of one argument PROC, that will be called as soon as the non-immediate data object X is about to be garbage-collected (with that object as its argument). Note that the finalizer will **not** be called while interrupts are disabled. This procedure returns X.

# 13.11.4 set-gc-report!

```
[procedure] (set-gc-report! FLAG)
```

Print statistics after every GC, depending on FLAG. A value of #t shows statistics after every major GC. A true value different from #t shows statistics after every minor GC. #f switches statistics off.

### 13.12 Other control structures

## 13.12.1 andmap

```
[procedure] (andmap PROC LIST1 ...)
```

Repeatedly calls PROC with arguments taken from LIST1 .... If any invocation should return #f, the result of andmap is #f. If all invocations return a true result, then the result of andmap is #t.

## 13.12.2 ormap

```
[procedure] (ormap PROC LIST1 ...)
```

Repeatedly calls PROC with arguments taken from LIST1 .... If any invocation should return a value different from #f, then this value is returned as the result of ormap. If all invocations return #f, then the result of ormap is #f.

## 13.12.3 promise?

```
[procedure] (promise? X)
```

Returns #t if X is a promise returned by delay, or #f otherwise.

# 13.13 String utilities

## 13.13.1 reverse-liststring

```
[procedure] (reverse-list->string LIST)
```

Returns a string with the characters in LIST in reverse order. This is equivalent to (list->string (reverse LIST)), but much more efficient.

## 13.14 Generating uninterned symbols

## 13.14.1 gensym

```
[procedure] (gensym [STRING-OR-SYMBOL])
```

Returns a newly created uninterned symbol. If an argument is provided, the new symbol is prefixed with that argument.

13.12.1 andmap 72

## 13.14.2 stringuninterned-symbol

[procedure] (string->uninterned-symbol STRING)

Returns a newly created, unique symbol with the name STRING.

## 13.15 Standard Input/Output

## 13.15.1 port?

```
[procedure] (port? X)
```

Returns #t if X is a port object or #f otherwise.

# 13.15.2 print

```
[procedure] (print [EXP1 ...])
```

Outputs the optional arguments EXP1 ... using display and writes a newline character to the port that is the value of (current-output-port). Returns its first argument, or (void) when no supplied arguments.

## 13.15.3 print\*

```
[procedure] (print* [EXP1 ...])
```

Similar to print, but does not output a terminating newline character and performs a flush-outout after writing its arguments.

## 13.16 User-defined named characters

#### 13.16.1 char-name

```
[procedure] (char-name SYMBOL-OR-CHAR [CHAR])
```

#### CHICKEN User's Manual - The User's Manual

This procedure can be used to inquire about character names or to define new ones. With a single argument the behavior is as follows: If SYMBOL-OR-CHAR is a symbol, then char-name returns the character with this name, or #f if no character is defined under this name. If SYMBOL-OR-CHAR is a character, then the name of the character is returned as a symbol, or #f if the character has no associated name.

If the optional argument CHAR is provided, then SYMBOL-OR-CHAR should be a symbol that will be the new name of the given character. If multiple names designate the same character, then the write will use the character name that was defined last.

```
(char-name 'space) ==> #\space
(char-name #\space) ==> space
(char-name 'bell) ==> #f
(char-name (integer->char 7)) ==> #f
(char-name 'bell (integer->char 7))
(char-name 'bell) ==> #\bell
(char->integer (char-name 'bell)) ==> 7
```

### 13.17 Blobs

"blobs" are collections of unstructured bytes. You can't do much with them, but allow conversion to and from SRFI-4 number vectors.

#### 13.17.1 make-blob

```
[procedure] (make-blob SIZE)
```

Returns a blob object of SIZE bytes, aligned on an 8-byte boundry, un-initialized.

#### 13.17.2 blob?

```
[procedure] (blob? X)
```

Returns #t if X is a blob object, or #f otherwise.

#### 13.17.3 blob-size

```
[procedure] (blob-size BLOB)
```

Returns the number of bytes in BL0B.

13.16.1 char-name 74

## 13.17.4 blobstring

[procedure] (blob->string BLOB)

Returns a string with the contents of BLOB.

## 13.17.5 stringblob

[procedure] (string->blob STRING)

Returns a blob with the contents of STRING.

### 13.18 Vectors

## 13.18.1 vector-copy!

[procedure] (vector-copy! VECTOR1 VECTOR2 [COUNT])

Copies contents of VECTOR1 into VECTOR2. If the argument COUNT is given, it specifies the maximal number of elements to be copied. If not given, the minimum of the lengths of the argument vectors is copied.

Exceptions: (exn bounds)

#### 13.18.2 vector-resize

[procedure] (vector-resize VECTOR N [INIT])

Creates and returns a new vector with the contents of VECTOR and length N. If N is greater than the original length of VECTOR, then all additional items are initialized to INIT. If INIT is not specified, the contents are initialized to some unspecified value.

# 13.19 The unspecified value

#### 13.19.1 void

[procedure] (void)

Returns an unspecified value.

13.17.4 blobstring 75

### 13.20 Continuations

#### 13.20.1 call/cc

```
[procedure] (call/cc PROCEDURE)
```

An alias for call-with-current-continuation.

### 13.20.2 continuation-capture

```
[procedure] (continuation-capture PROCEDURE)
```

Creates a continuation object representing the current continuation and tail-calls PROCEDURE with this continuation as the single argument.

More information about this continuation API can be found in the paper <a href="http://repository.readscheme.org/ftp/papers/sw2001/feeley.pdf">http://repository.readscheme.org/ftp/papers/sw2001/feeley.pdf</a> A Better API for first class Continuations by Marc Feeley.

#### 13.20.3 continuation?

```
[procedure] (continuation? X)
```

Returns #t if X is a continuation object, or #f otherwise.

## 13.20.4 continuation-graft

```
[procedure] (continuation-graft CONT THUNK)
```

Calls the procedure THUNK with no arguments and the implicit continuation CONT.

#### 13.20.5 continuation-return

```
[procedure] (continuation-return CONT VALUE ...)
```

Returns the value(s) to the continuation CONT. continuation-return could be implemented like this:

```
(define (continuation-return k . vals)
  (continuation-graft
```

13.20 Continuations 76

CHICKEN User's Manual - The User's Manual

```
k
(lambda () (apply values vals)) ) )
```

### 13.21 Setters

SRFI-17 is fully implemented. For more information see: <u>SRFI-17</u>.

#### 13.21.1 setter

```
[procedure] (setter PROCEDURE)
```

Returns the setter-procedure of  $\mathsf{PROCEDURE}$ , or signals an error if  $\mathsf{PROCEDURE}$  has no associated setter-procedure.

Note that (set! (setter PROC) ...) for a procedure that has no associated setter procedure yet is a very slow operation (the old procedure is replaced by a modified copy, which involves a garbage collection).

## 13.21.2 getter-with-setter

```
[procedure] (getter-with-setter GETTER SETTER)
```

Returns a copy of the procedure GETTER with the associated setter procedure SETTER. Contrary to the SRFI specification, the setter of the returned procedure may be changed.

#### 13.22 Reader extensions

#### 13.22.1 define-reader-ctor

```
[procedure] (define-reader-ctor SYMBOL PROC)
```

Define new read-time constructor for **#**, read syntax. For further information, see the documentation for <u>SRFI-10</u>.

## 13.22.2 set-read-syntax!

```
[procedure] (set-read-syntax! CHAR-OR-SYMBOL PROC)
```

When the reader is encounting the non-whitespace character CHAR while reading an expression from a given

13.20.5 continuation-return 77

port, then the procedure PROC will be called with that port as its argument. The procedure should return a value that will be returned to the reader:

If CHAR-OR-SYMBOL is a symbol, then a so-called *read-mark* handler is defined. In that case the handler procedure will be called when a character-sequence of the form

#!SYMBOL

is encountered.

You can undo special handling of read-syntax by passing #f as the second argument (if the syntax was previously defined via set-read-syntax!).

Note that all of CHICKEN's special non-standard read-syntax is handled directly by the reader. To disable built-in read-syntax, define a handler that triggers an error (for example).

## 13.22.3 set-sharp-read-syntax!

```
[procedure] (set-sharp-read-syntax! CHAR-OR-SYMBOL PROC)
```

Similar to set-read-syntax!, but allows defining new #<CHAR> ... reader syntax. If the first argument is a symbol, then this procedure is equivalent to set-read-syntax!.

## 13.22.4 set-parameterized-read-syntax!

```
[procedure] (set-parameterized-read-syntax! CHAR-OR-SYMBOL PROC)
```

Similar to set-sharp-read-syntax!, but intended for defining reader syntax of the form #<NUMBER><CHAR> . . . . The handler procedure PROC will be called with two arguments: the input port and the number preceding the dispatching character. If the first argument is a symbol, then this procedure is equivalent to set-read-syntax!.

# 13.22.5 copy-read-table

[procedure] (copy-read-table READ-TABLE)

Returns a copy of the given read-table. You can access the currently active read-table with (current-read-table).

Previous: Parameters

Next: <u>Unit eval</u>

### 14 Unit eval

This unit has support for evaluation and macro-handling. This unit is used by default, unless the program is compiled with the -explicit-use option.

# 14.1 Loading code

#### 14.1.1 load

```
[procedure] (load FILE [EVALPROC])
```

Loads and evaluates expressions from the given source file, which may be either a string or an input port. Each expression read is passed to EVALPROC (which defaults to eval). On platforms that support it (currently native Windows, Linux ELF and Solaris), load can be used to load compiled programs:

```
% cat x.scm
(define (hello) (print "Hello!"))
% csc -s x.scm
% csi -q
#;1> (load "x.so")
; loading x.so ...
#;2> (hello)
Hello!
#;3>
```

The second argument to load is ignored when loading compiled code. If source code is loaded from a port, then that port is closed after all expressions have been read.

Compiled code can be re-loaded, but care has to be taken, if code from the replaced dynamically loaded module is still executing (i.e. if an active continuation refers to compiled code in the old module).

Support for reloading compiled code dynamically is still experimental.

### 14.1.2 load-relative

```
[procedure] (load-relative FILE [EVALPROC])
```

Similar to load, but loads FILE relative to the path of the currently loaded file.

14 Unit eval 80

## 14.1.3 load-noisily

[procedure] (load-noisily FILE #!key EVALUATOR TIME PRINTER)

As load but the result(s) of each evaluated toplevel-expression is written to standard output. If EVALUATOR is given and not #f, then each expression is evaluated by calling this argument with the read expression as argument. If TIME is given and not false, then the execution time of each expression is shown (as with the time macro). If PRINTER is given and not false, then each expression is printed before evaluation by applying the expression to the value of this argument, which should be a one-argument procedure.

See also the <u>load-verbose</u> parameter.

## 14.1.4 load-library

[procedure] (load-library UNIT [LIBRARYFILE])

On platforms that support dynamic loading, load-library loads the compiled library unit UNIT (which should be a symbol). If the string LIBRARYFILE is given, then the given shared library will be loaded and the toplevel code of the contained unit will be executed. If no LIBRARYFILE argument is given, then the following libraries are checked for the required unit:

- a file named <**UNIT**>.so
- the files given in the parameter dynamic-load-libraries

If the unit is not found, an error is signaled. When the library unit can be successfully loaded, a feature-identifier named UNIT is registered. If the feature is already registered before loading, the load-library does nothing.

# 14.1.5 set-dynamic-load-mode!

[procedure] (set-dynamic-load-mode! MODELIST)

On systems that support dynamic loading of compiled code via the dlopen(3) interface (for example Linux and Solaris), some options can be specified to fine-tune the behaviour of the dynamic linker. MODE should be a list of symbols (or a single symbol) taken from the following set:

#### local

If local is given, then any C/C++ symbols defined in the dynamically loaded file are not available for subsequently loaded files and libraries. Use this if you have linked foreign code into your dynamically loadable file and if you don't want to export them (for example because you want to load another file that defines the same symbols).

global

The default is global, which means all C/C++ symbols are available to code loaded at a later stage.

If now is specified, all symbols are resolved immediately.

lazy

Unresolved symbols are resolved as code from the file is executed. This is the default.

14.1.3 load-noisily 81

Note that this procedure does not control the way Scheme variables are handled - this facility is mainly of interest when accessing foreign code.

## 14.2 Read-eval-print loop

## 14.2.1 repl

[procedure] (repl)

Start a new read-eval-print loop. Sets the reset-handler so that any invocation of reset restarts the read-eval-print loop. Also changes the current exception-handler to display a message, write any arguments to the value of (current-error-port) and reset.

### 14.3 Macros

## 14.3.1 get-line-number

[procedure] (get-line-number EXPR)

If EXPR is a pair with the car being a symbol, and line-number information is available for this expression, then this procedure returns the associated line number. If line-number information is not available, then #f is returned. Note that line-number information for expressions is only available in the compiler.

#### 14.3.2 macro?

[procedure] (macro? SYMBOL)

Returns #t if there exists a macro-definition for SYMBOL.

# 14.3.3 macroexpand

[procedure] (macroexpand X)

If X is a macro-form, expand the macro (and repeat expansion until expression is a non-macro form). Returns the resulting expression.

## 14.3.4 macroexpand-1

```
[procedure] (macroexpand-1 X)
```

If X is a macro-form, expand the macro. Returns the resulting expression.

#### 14.3.5 undefine-macro!

```
[procedure] (undefine-macro! SYMBOL)
```

Remove the current macro-definition of the macro named SYMBOL.

## 14.3.6 syntax-error

```
[procedure] (syntax-error [LOCATION] MESSAGE ARGUMENT ...)
```

Signals an exception of the kind (exn syntax). Otherwise identical to error.

## 14.4 Loading extension libraries

This functionality is only available on platforms that support dynamic loading of compiled code. Currently Linux, BSD, Solaris, Windows (with Cygwin) and HP/UX are supported.

## 14.4.1 repository-path

[parameter] repository-path

Contains a string naming the path to the extension repository, which defaults to either the value of the environment variable CHICKEN\_REPOSITORY, the value of the environment variable CHICKEN\_HOME or the default library path (usually /usr/local/lib/chicken on UNIX systems).

#### 14.4.2 extension-information

```
[procedure] (extension-information ID)
```

If an extension with the name ID is installed and if it has a setup-information list registered in the extension repository, then the info-list is returned. Otherwise extension-information returns #f.

14.3.4 macroexpand-1 83

### **14.4.3** provide

```
[procedure] (provide ID ...)
```

Registers the extension IDs ID . . . as loaded. This is mainly intended to provide aliases for certain extension identifiers.

## 14.4.4 provided?

```
[procedure] (provided? ID ...)
```

Returns #t if the extension with the IDs ID ... are currently loaded, or #f otherwise.

## **14.4.5** require

```
[procedure] (require ID ...)
[procedure] (require-for-syntax ID ...)
```

If the extension library ID is not already loaded into the system, then require will lookup the location of the shared extension library and load it. If ID names a library-unit of the base system, then it is loaded via load-library. If no extension library is available for the given ID, then an attempt is made to load the file ID.so or ID.scm (in that order) from one of the following locations:

- the current include path, which defaults to the pathnames given in CHICKEN\_INCLUDE\_PATH and CHICKEN HOME.
- the current directory

ID should be a string or a symbol. The difference between require and require-for-syntax is the the latter loads the extension library at compile-time (the argument is still evaluated), while the former loads it at run-time.

## 14.4.6 set-extension-specifier!

```
[procedure] (set-extension-specifier! SYMBOL PROC)
```

Registers the handler-procedure PROC as a extension-specifier with the name SYMBOL. This facility allows extending the set of valid extension specifiers to be used with require-extension. When register-extension is called with an extension specifier of the form (SPEC ...) and SPEC has been registered with set-extension-specifier!, then PROC will be called with two arguments: the specifier and the previously installed handler (or #f if no such handler was defined). The handler should return a new specifier that will be processed recursively. If the handler returns a vector, then each element of the vector will be processed recursively. Alternatively the handler may return a string which specifies a file to be loaded:

```
(eval-when (compile eval)
  (set-extension-specifier!
  'my-package
```

14.4.3 provide 84

CHICKEN User's Manual - The User's Manual

Note that the handler has to be registered at compile time, if it is to be visible in compiled code.

## 14.5 System information

#### 14.5.1 chicken-home

```
[procedure] (chicken-home)
```

Returns a string given the installation directory (usually /usr/local/share/chicken on UNIX-like systems). If the environment variable CHICKEN\_HOME is set, then its value will be returned. As a last option, if the environment variable CHICKEN\_PREFIX is set, then chicken-home will return \$CHICKEN\_PREFIX/share.

### 14.6 Eval

#### 14.6.1 eval

```
[procedure] (eval EXP [ENVIRONMENT])
```

Evaluates EXP and returns the result of the evaluation. The second argument is optional and defaults to the value of (interaction-environment).

Previous: Unit library

Next: <u>Unit extras</u>

### 15 Unit extras

This unit contains a collection of useful utility definitions. This unit is used by default, unless the program is compiled with the -explicit-use option.

### **15.1 Lists**

#### 15.1.1 alist-ref

```
[procedure] (alist-ref KEY ALIST [TEST [DEFAULT]])
```

Looks up KEY in ALIST using TEST as the comparison function (or eqv? if no test was given) and returns the cdr of the found pair, or DEFAULT (which defaults to #f).

## 15.1.2 alist-update!

```
[procedure] (alist-update! KEY VALUE ALIST [TEST])
```

If the list ALIST contains a pair of the form (KEY . X), then this procedure replaces X with VALUE and returns ALIST. If ALIST contains no such item, then alist-update! returns ((KEY . VALUE) . ALIST). The optional argument TEST specifies the comparison procedure to search a matching pair in ALIST and defaults to eqv?.

#### 15.1.3 atom?

```
[procedure] (atom? X)
```

Returns #t if X is not a pair. This is identical to not-pair? from <u>Unit srfi-1</u> but kept for historical reasons.

#### 15.1.4 rassoc

```
[procedure] (rassoc KEY LIST [TEST])
```

Similar to assoc, but compares KEY with the cdr of each pair in LIST using TEST as the comparison procedures (which defaults to eqv?.

15 Unit extras 86

#### 15.1.5 butlast

```
[procedure] (butlast LIST)
```

Returns a fresh list with all elements but the last of LIST.

### 15.1.6 chop

```
[procedure] (chop LIST N)
```

Returns a new list of sublists, where each sublist contains N elements of LIST. If LIST has a length that is not a multiple of N, then the last sublist contains the remaining elements.

```
(chop '(1 2 3 4 5 6) 2) ==> ((1 2) (3 4) (5 6))

(chop '(a b c d) 3) ==> ((a b c) (d))
```

### **15.1.7 compress**

```
[procedure] (compress BLIST LIST)
```

Returns a new list with elements taken from LIST with corresponding true values in the list BLIST.

```
(define nums '(99 100 110 401 1234))
(compress (map odd? nums) nums) ==> (99 401)
```

#### 15.1.8 flatten

```
[procedure] (flatten LIST1 ...)
```

Returns LIST1 ... concatenated together, with nested lists removed (flattened).

# 15.1.9 intersperse

```
[procedure] (intersperse LIST X)
```

Returns a new list with X placed between each element.

15.1.5 butlast 87

### 15.1.10 join

```
[procedure] (join LISTOFLISTS [LIST])
```

Concatenates the lists in LIST0FLISTS with LIST placed between each sublist. LIST defaults to the empty list.

```
(join '((a b) (c d) (e)) '(x y)) ==> (a b x y c d x y e)
(join '((p q) () (r (s) t)) '(-)) ==> (p q - - r (s) t)
join could be implemented as follows:
(define (join lstoflsts #!optional (lst '()))
```

(apply append (intersperse lstoflists lst)) )

### 15.1.11 shuffle

```
[procedure] (shuffle LIST)
```

Returns LIST with its elements sorted in a random order.

### 15.1.12 tail?

```
[procedure] (tail? X LIST)
```

Returns true if X is one of the tails (cdr's) of LIST.

# 15.2 String-port extensions

# 15.2.1 call-with-input-string

```
[procedure] (call-with-input-string STRING PROC)
```

Calls the procedure PROC with a single argument that is a string-input-port with the contents of STRING.

# 15.2.2 call-with-output-string

```
[procedure] (call-with-output-string PROC)
```

Calls the procedure PROC with a single argument that is a string-output-port. Returns the accumulated output-string.

15.1.10 join 88

### 15.2.3 with-input-from-string

```
[procedure] (with-input-from-string STRING THUNK)
```

Call procedure THUNK with the current input-port temporarily bound to an input-string-port with the contents of STRING.

### 15.2.4 with-output-to-string

```
[procedure] (with-output-to-string THUNK)
```

Call procedure THUNK with the current output-port temporarily bound to a string-output-port and return the accumulated output string.

# 15.3 Formatted output

### 15.3.1 printf

# **15.3.2 fprintf**

# **15.3.3 sprintf**

```
[procedure] (fprintf PORT FORMATSTRING ARG ...)
[procedure] (printf FORMATSTRING ARG)
[procedure] (sprintf FORMATSTRING ARG ...)
```

Simple formatted output to a given port (fprintf), the value of (current-output-port) (printf) or a string (sprintf). The FORMATSTRING can contain any sequence of characters. The character`~' prefixes special formatting directives:

```
~%
write newline character
~N
the same as ~%
~S
```

```
CHICKEN User's Manual - The User's Manual
write the next argument
~A
display the next argument
~\n
skip all whitespace in the format-string until the next non-whitespace character
~B
write the next argument as a binary number
~0
write the next argument as an octal number
~X
write the next argument as a hexadecimal number
~C
write the next argument as a character
display \~'
~!
flush all pending output
~?
invoke formatted output routine recursively with the next two arguments as format-string and list of
parameters
15.3.4 format
```

```
[procedure] (format [DESTINATION] FORMATSTRING ARG ...)
The parameters FORMATSTRING and ARG ... are as for (printf/sprintf/fprintf).
```

The optional DESTINATION, when supplied, performs a (sprintf) for a #f, a (printf) for a #t, and a (fprintf) for an output-port. When missing a (sprintf) is performed.

#### 15.4 Hash tables

```
CHICKEN implements SRFI-69. For more information, see <u>SRFI-69</u>.
A setter for hash-table-ref is defined, so
```

(set! (hash-table-ref HT KEY) VAL)

is equivalent to

15.3.3 sprintf 90 CHICKEN User's Manual - The User's Manual

```
(hash-table-set! HT KEY VAL)
```

As an extension to SRFI-69, hash-table-update! and hash-table-update!/default return the new value (after applying the update procedure).

#### 15.4.1 hash-table-remove!

```
[procedure] (hash-table-remove! HASHTABLE PROC)
```

Calls PROC for all entries in HASHTABLE with the key and value of each entry. If PROC returns true, then that entry is removed.

#### 15.5 Queues

### 15.5.1 listqueue

```
[procedure] (list->queue LIST)
```

Returns LIST converted into a queue, where the first element of the list is the same as the first element of the queue. The resulting queue may share memory with the list and the list should not be modified after this operation.

# 15.5.2 make-queue

```
[procedure] (make-queue)
```

Returns a newly created queue.

# 15.5.3 queue?

```
[procedure] (queue? X)
```

Returns #t if X is a queue, or #f otherwise.

# 15.5.4 queuelist

```
[procedure] (queue->list QUEUE)
```

15.4 Hash tables 91

Returns QUEUE converted into a list, where the first element of the list is the same as the first element of the queue. The resulting list may share memory with the queue object and should not be modified.

### 15.5.5 queue-add!

```
[procedure] (queue-add! QUEUE X)
```

Adds X to the rear of QUEUE.

### 15.5.6 queue-empty?

```
[procedure] (queue-empty? QUEUE)
```

Returns #t if QUEUE is empty, or #f otherwise.

### 15.5.7 queue-first

```
[procedure] (queue-first QUEUE)
```

Returns the first element of QUEUE. If QUEUE is empty an error is signaled

# 15.5.8 queue-last

```
[procedure] (queue-last QUEUE)
```

Returns the last element of QUEUE. If QUEUE is empty an error is signaled

# 15.5.9 queue-remove!

```
[procedure] (queue-remove! QUEUE)
```

Removes and returns the first element of QUEUE. If QUEUE is empty an error is signaled

# 15.5.10 queue-push-back!

```
[procedure] (queue-push-back! QUEUE ITEM)
```

Pushes an item into the first position of a queue, i.e. the next queue-remove! will return ITEM.

15.5.4 queuelist 92

### 15.5.11 queue-push-back-list!

```
[procedure] (queue-push-back-list! QUEUE LIST)
```

Pushes the items in item-list back onto the queue, so that (car LIST) becomes the next removable item.

# 15.6 Sorting

### 15.6.1 merge

```
[procedure] (merge LIST1 LIST2 LESS?)
[procedure] (merge! LIST1 LIST2 LESS?)
```

Joins two lists in sorted order. merge! is the destructive version of merge. LESS? should be a procedure of two arguments, that returns true if the first argument is to be ordered before the second argument.

#### 15.6.2 sort

```
[procedure] (sort SEQUENCE LESS?)
[procedure] (sort! SEQUENCE LESS?)
```

Sort SEQUENCE, which should be a list or a vector. sort! is the destructive version of sort.

#### 15.6.3 sorted?

```
[procedure] (sorted? SEQUENCE LESS?)
```

Returns true if the list or vector **SEQUENCE** is already sorted.

#### 15.7 Random numbers

#### 15.7.1 random

```
[procedure] (random N)
```

Returns an exact random integer from 0 to N-1.

#### 15.7.2 randomize

```
[procedure] (randomize [X])
```

Set random-number seed. If X is not supplied, the current time is used. On startup (when the extras unit is initialized), the random number generator is initialized with the current time.

# 15.8 Input/Output extensions

### 15.8.1 make-input-port

```
[procedure] (make-input-port READ READY? CLOSE [PEEK])
```

Returns a custom input port. Common operations on this port are handled by the given parameters, which should be procedures of no arguments. READ is called when the next character is to be read and should return a character or #!eof. READY? is called when char-ready? is called on this port and should return #t or #f. CLOSE is called when the port is closed. PEEK is called when peek-char is called on this port and should return a character or #!eof. if the argument PEEK is not given, then READ is used instead and the created port object handles peeking automatically (by calling READ and buffering the character).

# 15.8.2 make-output-port

```
[procedure] (make-output-port WRITE CLOSE [FLUSH])
```

Returns a custom output port. Common operations on this port are handled by the given parameters, which should be procedures. WRITE is called when output is sent to the port and receives a single argument, a string. CLOSE is called when the port is closed and should be a procedure of no arguments. FLUSH (if provided) is called for flushing the output port.

# 15.8.3 pretty-print

```
[procedure] (pretty-print EXP [PORT])
[procedure] (pp EXP [PORT])
```

Print expression nicely formatted. PORT defaults to the value of (current-output-port).

15.7.2 randomize 94

### 15.8.4 pretty-print-width

(Parameter) Specifies the maximal line-width for pretty printing, after which line wrap will occur.

### 15.8.5 read-byte

### 15.8.6 write-byte

```
[procedure] (read-byte [PORT])
[procedure] (write-byte BYTE [PORT])
```

Read/write a byte to the port given in PORT, which default to the values of (current-input-port) and (current-output-port), respectively.

#### 15.8.7 read-file

```
[procedure] (read-file [FILE-OR-PORT [READER [MAXCOUNT]]])
```

Returns a list containing all toplevel expressions read from the file or port FILE-OR-PORT. If no argument is given, input is read from the port that is the current value of (current-input-port). After all expressions are read, and if the argument is a port, then the port will not be closed. The READER argument specifies the procedure used to read expressions from the given file or port and defaults to read. The reader procedure will be called with a single argument (an input port). If MAXCOUNT is given then only up to MAXCOUNT expressions will be read in.

#### 15.8.8 read-line

#### 15.8.9 write-line

```
[procedure] (read-line [PORT [LIMIT]])
[procedure] (write-line STRING [PORT])
```

Line-input and -output. PORT defaults to the value of (current-input-port) and (current-output-port), respectively. if the optional argument LIMIT is given and not #f, then read-line reads at most LIMIT characters per line.

#### 15.8.10 read-lines

```
[procedure] (read-lines [PORT [MAX]])
```

Read MAX or fewer lines from PORT. PORT defaults to the value of (current-input-port). PORT may optionally be a string naming a file. Returns a list of strings, each string representing a line read, not including any line separation character(s).

### 15.8.11 read-string

### **15.8.12 read-string!**

# 15.8.13 write-string

```
[procedure] (read-string [NUM [PORT]])
[procedure] (read-string! NUM STRING [PORT [START]])
[procedure] (write-string STRING [NUM [PORT]]
```

Read or write NUM characters from/to PORT, which defaults to the value of (current-input-port) or (current-output-port), respectively. If NUM is #f or not given, then all data up to the end-of-file is read, or, in the case of write-string the whole string is written. If no more input is available, read-string returns the empty string. read-string! reads destructively into the given STRING argument, but never more characters that would fit into STRING. If START is given, then the read characters are stored starting at that position. read-string! returns the actual number of characters read.

#### 15.8.14 read-token

```
[procedure] (read-token PREDICATE [PORT])
```

Reads characters from PORT (which defaults to the value of (current-input-port)) and calls the procedure PREDICATE with each character until PREDICATE returns false. Returns a string with the accumulated characters.

# 15.8.15 with-error-output-to-port

```
[procedure] (with-error-output-to-port PORT THUNK)
```

Call procedure THUNK with the current error output-port temporarily bound to PORT.

15.8.10 read-lines 96

### 15.8.16 with-input-from-port

```
[procedure] (with-input-from-port PORT THUNK)
```

Call procedure THUNK with the current input-port temporarily bound to PORT.

### 15.8.17 with-output-to-port

```
[procedure] (with-output-to-port PORT THUNK)
```

Call procedure THUNK with the current output-port temporarily bound to PORT.

# 15.9 Strings

#### 15.9.1 conc

```
[procedure] (conc X ...)
```

Returns a string with the string-represenation of all arguments concatenated together. CONC could be implemented as

```
(define (conc . args)
  (apply string-append (map ->string args)) )
```

# 15.9.2 string

```
[procedure] (->string X)
```

Returns a string-representation of X.

# 15.9.3 string-chop

```
[procedure] (string-chop STRING LENGTH)
```

Returns a list of substrings taken by *chopping* STRING every LENGTH characters:

```
(string-chop "one two three" 4) ==> ("one " "two " "thre" "e")
```

### 15.9.4 string-chomp

```
[procedure] (string-chomp STRING [SUFFIX])
```

If STRING ends with SUFFIX, then this procedure returns a copy of its first argument with the suffix removed, otherwise returns STRING unchanged. SUFFIX defaults to "\n".

### 15.9.5 string-compare3

```
[procedure] (string-compare3 STRING1 STRING2)
[procedure] (string-compare3-ci STRING1 STRING2)
```

Perform a three-way comparison between the STRING1 and STRING2, returning either -1 if STRING1 is lexicographically less than STRING2, 0 if it is equal, or 1 if it s greater. string-compare3-ci performs a case-insensitive comparison.

### 15.9.6 string-intersperse

```
[procedure] (string-intersperse LIST [STRING])
```

Returns a string that contains all strings in LIST concatenated together. STRING is placed between each concatenated string and defaults to " ".

```
(string-intersperse '("one" "two") "three")
is equivalent to

(apply string-append (intersperse '("one" "two") "three"))
```

# 15.9.7 string-split

```
[procedure] (string-split STRING [DELIMITER-STRING [KEEPEMPTY]])
```

Split string into substrings separated by the given delimiters. If no delimiters are specified, a string comprising the tab, newline and space characters is assumed. If the parameter KEEPEMPTY is given and not #f, then empty substrings are retained:

```
(string-split "one two three") ==> ("one" "two" "three")
(string-split "foo:bar::baz:" ":" #t) ==> ("foo" "bar" "" "baz" "")
```

15.9.4 string-chomp 98

### 15.9.8 string-translate

```
[procedure] (string-translate STRING FROM [TO])
```

Returns a fresh copy of STRING with characters matching FROM translated to T0. If T0 is omitted, then matching characters are removed. FROM and T0 may be a character, a string or a list. If both FROM and T0 are strings, then the character at the same position in T0 as the matching character in FROM is substituted.

# 15.9.9 string-translate\*

```
[procedure] (string-translate* STRING SMAP)
```

Substitutes elements of STRING according to SMAP. SMAP should be an association-list where each element of the list is a pair of the form (MATCH \. REPLACEMENT). Every occurrence of the string MATCH in STRING will be replaced by the string REPLACEMENT:

```
(string-translate*
  "<h1>this is a \"string\"</h1>"
  '(("<" . "&lt;") (">" . "&gt;") ("\"" . "&quot;")) )
=> "&lt;h1&gt;this is a &quot;string&quot;&lt;/ht&gt;"
```

### 15.9.10 substring=?

```
[procedure] (substring=? STRING1 STRING2 [START1 [START2 [LENGTH]]])
[procedure] (substring-ci=? STRING1 STRING2 [START1 [START2 [LENGTH]]])
```

Returns #t if the strings STRING1 and STRING2 are equal, or #f otherwise. The comparison starts at the positions START1 and START2 (which default to 0), comparing LENGTH characters (which defaults to the minimum of the remaining length of both strings).

# 15.9.11 substring-index

```
[procedure] (substring-index WHICH WHERE [START])
[procedure] (substring-index-ci WHICH WHERE [START])
```

Searches for first index in string WHERE where string WHICH occurs. If the optional argument START is given, then the search starts at that index. Substring-index-ci is a case-insensitive version of substring-index.

15.9.8 string-translate

### 15.10 Combinators

# 15.10.1 any?

```
[procedure] (any? X)
```

Ignores its argument and always returns #t. This is actually useful sometimes.

### 15.10.2 constantly

```
[procedure] (constantly X ...)
```

Returns a procedure that always returns the values X ... regardless of the number and value of its arguments.

```
(constantly X) <=> (lambda args X)
```

### 15.10.3 complement

```
[procedure] (complement PROC)
```

Returns a procedure that returns the boolean inverse of PROC.

```
(complement PROC) <=> (lambda (x) (not (PROC x)))
```

# 15.10.4 compose

```
[procedure] (compose PROC1 PROC2 ...)
```

Returns a procedure that represents the composition of the argument-procedures PROC1 PROC2 ....

(compose) is equivalent to values.

15.10 Combinators 100

### 15.10.5 conjoin

```
[procedure] (conjoin PRED ...)
Returns a procedure that returns #t if its argument satisfies the predicates PRED ....
((conjoin odd? positive?) 33)
((conjoin odd? positive?) -33) ==> #f
15.10.6 disjoin
[procedure] (disjoin PRED ...)
Returns a procedure that returns #t if its argument satisfies any predicate PRED ....
((disjoin odd? positive?) 32)
                                              #t
((disjoin odd? positive?) -32) ==> #f
15.10.7 each
[procedure] (each PROC ...)
Returns a procedure that applies PROC ... to its arguments, and returns the result(s) of the last procedure
application. For example
(each pp eval)
is equivalent to
(lambda args
  (apply pp args)
  (apply eval args) )
(each PROC) is equivalent to PROC and (each) is equivalent to noop.
```

### 15.10.8 flip

```
[procedure] (flip PROC)
Returns a two-argument procedure that calls PROC with its arguments swapped:
(flip PROC) <=> (lambda (x y) (PROC y x))
```

15.10.5 conjoin 101

### **15.10.9 identity**

```
[procedure] (identity X)
```

Returns its sole argument X.

### 15.10.10 project

```
[procedure] (project N)
```

Returns a procedure that returns its Nth argument (starting from 0).

#### 15.10.11 list-of

```
[procedure] (list-of PRED)
```

Returns a procedure of one argument that returns #t when applied to a list of elements that all satisfy the predicate procedure PRED, or #f otherwise.

```
((list-of even?) '(1 2 3)) ==> #f
((list-of number?) '(1 2 3)) ==> #t
```

# 15.10.12 noop

```
[procedure] (noop X ...)
```

Ignores it's arguments, does nothing and returns an unspecified value.

#### 15.10.13 o

```
[procedure] (o PROC ...)
```

A single value version of compose (slightly faster). (o) is equivalent to identity.

# 15.11 Binary searching

15.10.9 identity 102

# 15.11.1 binary-search

[procedure] (binary-search SEQUENCE PROC)

Performs a binary search in SEQUENCE, which should be a sorted list or vector. PROC is called to compare items in the sequence, should accept a single argument and return an exact integer: zero if the searched value is equal to the current item, negative if the searched value is *less* than the current item, and positive otherwise. Returns the index of the found value or #f otherwise.

Previous: Unit eval

Next: <u>Unit srfi-1</u>

15.11.1 binary-search

# 16 Unit srfi-1

List library, see the documentation for <u>SRFI-1</u>

Previous: <u>Unit extras</u>

Next: <u>Unit srfi-4</u>

16 Unit srfi-1 104

### 17 Unit srfi-4

Homogeneous numeric vectors, see the documentation for <u>SRFI-4</u> 64-bit integer vectors (u64vector and s64vector are not supported.

The basic constructor procedures for number vectors are extended to allow allocating the storage in non garbage collected memory:

### 17.1 make-XXXvector

[procedure] (make-XXXvector SIZE [INIT NONGC FINALIZE])

Creates a SRFI-4 homogenous number vector of length SIZE. If INIT is given, it specifies the initial value for each slot in the vector. The optional arguments NONGC and FINALIZE define whether the vector should be allocated in a memory area not subject to garbage collection and whether the associated storage should be automatically freed (using finalization) when there are no references from Scheme variables and data. NONGC defaults to #f (the vector will be located in normal garbage collected memory) and FINALIZE defaults to #t. Note that the FINALIZE argument is only used when NONGC is true.

Additionally, the following procedures are provided:

#### 17.2 u8vectorblob

#### 17.3 s8vectorblob

#### 17.4 u16vectorblob

#### 17.5 s16vectorblob

#### 17.6 u32vectorblob

17 Unit srfi-4

### 17.7 s32vectorblob

17.8	f32vectorbl	ob
------	-------------	----

#### 17.9 f64vectorblob

#### 17.10 u8vectorblob/shared

#### 17.11 s8vectorblob/shared

#### 17.12 u16vectorblob/shared

#### 17.13 s16vectorblob/shared

#### 17.14 u32vectorblob/shared

#### 17.15 s32vectorblob/shared

### 17.16 f32vectorblob/shared

### 17.17 f64vectorblob/shared

```
[procedure] (u8vector->blob U8VECTOR)
[procedure] (s8vector->blob S8VECTOR)
[procedure] (u16vector->blob U16VECTOR)
[procedure] (s16vector->blob S16VECTOR)
```

17.7 s32vectorblob 106

#### CHICKEN User's Manual - The User's Manual

```
[procedure] (u32vector->blob U32VECTOR)
[procedure] (s32vector->blob S32VECTOR)
[procedure] (f32vector->blob F32VECTOR)
[procedure] (f64vector->blob F64VECTOR)
[procedure] (u8vector->blob/shared U8VECTOR)
[procedure] (s8vector->blob/shared S8VECTOR)
[procedure] (u16vector->blob/shared U16VECTOR)
[procedure] (s16vector->blob/shared S16VECTOR)
[procedure] (u32vector->blob/shared U32VECTOR)
[procedure] (s32vector->blob/shared S32VECTOR)
[procedure] (f32vector->blob/shared F32VECTOR)
[procedure] (f64vector->blob/shared F64VECTOR)
```

Each of these procedures return the contents of the given vector as a 'packed' blob. The byte order in that vector is platform-dependent (for example little-endian on an **Intel** processor). The /shared variants return a blob that shares memory with the contents of the vector.

### 17.18 blobu8vector

### 17.19 blobs8vector

#### 17.20 blobu16vector

#### 17.21 blobs16vector

#### 17.22 blobu32vector

#### 17.23 blobs32vector

#### 17.24 blobf32vector

#### 17.25 blobf64vector

#### 17.26 blobu8vector/shared

#### 17.27 blobs8vector/shared

### 17.28 blobu16vector/shared

#### 17.29 blobs16vector/shared

### 17.30 blobu32vector/shared

#### 17.31 blobs32vector/shared

#### 17.32 blobf32vector/shared

#### 17.33 blobf64vector/shared

```
[procedure] (blob->u8vector BLOB)
[procedure] (blob->s8vector BLOB)
[procedure] (blob->u16vector BLOB)
[procedure] (blob->s16vector BLOB)
[procedure] (blob->u32vector BLOB)
[procedure] (blob->s32vector BLOB)
[procedure] (blob->f32vector BLOB)
[procedure] (blob->f64vector BLOB)
[procedure] (blob->u8vector/shared BLOB)
[procedure] (blob->s8vector/shared BLOB)
[procedure] (blob->s16vector/shared BLOB)
[procedure] (blob->s32vector/shared BLOB)
[procedure] (blob->s32vector/shared BLOB)
[procedure] (blob->s32vector/shared BLOB)
```

17.25 blobf64vector 108

CHICKEN User's Manual - The User's Manual

```
[procedure] (blob->f32vector/shared BLOB)
[procedure] (blob->f64vector/shared BLOB)
```

Each of these procedures return a vector where the argument BLOB is taken as a 'packed' representation of the contents of the vector. The /shared variants return a vector that shares memory with the contents of the blob.

#### 17.34 subu8vector

### 17.35 subu16vector

### 17.36 subu32vector

#### 17.37 subs8vector

#### 17.38 subs16vector

#### 17.39 subs32vector

### 17.40 subf32vector

#### 17.41 subf64vector

```
[procedure] (subu8vector U8VECTOR FROM TO)
[procedure] (subu16vector U16VECTOR FROM TO)
[procedure] (subu32vector U32VECTOR FROM TO)
[procedure] (subs8vector S8VECTOR FROM TO)
[procedure] (subs16vector S16VECTOR FROM TO)
[procedure] (subs32vector S32VECTOR FROM TO)
[procedure] (subf32vector F32VECTOR FROM TO)
[procedure] (subf64vector F64VECTOR FROM TO)
```

17.33 blobf64vector/shared 109

CHICKEN User's Manual - The User's Manual

Creates a number vector of the same type as the argument vector with the elements at the positions FR0M up to but not including T0.

SRFI-17 Setters for XXXvector-ref are defined.

#### 17.42 read-u8vector

[procedure] (read-u8vector LENGTH [PORT])

Reads LENGTH bytes from the PORT and returns a fresh u8vector or less if end-of-file is encountered. PORT defaults to the value of (current-input-port). If LENGTH is #f, the vector will be filled completely until end-of-file is reached.

#### 17.43 read-u8vector!

[procedure] (read-u8vector! LENGTH U8VECTOR [PORT [START]])

Reads LENGTH bytes from the PORT writing the read input into U8VECTOR beginning at START (or 0 if not given). PORT defaults to the value of (current-input-port). If LENGTH is #f, the vector will be filled completely until end-of-file is reached. This procedure returns the number of bytes read.

#### 17.44 write-u8vector

[procedure] (write-u8vector U8VECTOR [PORT [START [END]]])

Writes the bytes U8VECTOR between the indices START (inclusive) and END (exclusive) to PORT. PORT defaults to the value of (current-output-port).

Previous: <u>Unit srfi-1</u>

Next: Unit srfi-13

17.41 subf64vector 110

# 18 Unit srfi-13

String library, see the documentation for <u>SRFI-13</u>

On systems that support dynamic loading, the srfi-13 unit can be made available in the interpreter (CSi) by entering

(require-extension srfi-13)

Previous: <u>Unit srfi-4</u>

Next: <u>Unit srfi-14</u>

18 Unit srfi-13

# 19 Unit srfi-14

Character set library, see the documentation for <u>SRFI-14</u>

On systems that support dynamic loading, the Srfi-14 unit can be made available in the interpreter (CSi) by entering

(require-extension srfi-14)

This library provides only the Latin-1 character set.

Previous: <u>Unit srfi-13</u>

Next: <u>Unit match</u>

19 Unit srfi-14 112

# 20 Unit match

The runtime-support code for the <u>Pattern Matching</u> extensions. Note that to use the macros in normal compiled code it is not required to declare this unit as used. It is only necessary to do so if forms containing these macros are to be expanded at runtime.

Previous: <u>Unit srfi-14</u>

Next: <u>Unit regex</u>

20 Unit match

# 21 Unit regex

This library unit provides support for regular expressions. The regular expression package used is PCRE (*Perl Compatible Regular Expressions*) written by Philip Hazel. See <a href="http://www.pcre.org">http://www.pcre.org</a> for information about the particular regexp flavor and extensions provided by this library.

To test that PCRE support has been built into Chicken properly, try:

```
(require 'regex)
(test-feature? 'pcre) => t
```

# 21.1 grep

```
[procedure] (grep REGEX LIST)
```

Returns all items of LIST that match the regular expression REGEX. This procedure could be defined as follows:

```
(define (grep regex lst)
  (filter (lambda (x) (string-search regex x)) lst) )
```

# 21.2 globregexp

```
[procedure] (glob->regexp PATTERN)
```

Converts the file-pattern PATTERN into a regular expression.

```
(glob->regexp "foo.*")
=> "foo\..*"
```

PATTERN should follow "glob" syntax. Allowed wildcards are

```
[C...]
[C1-C2]
[-C...]
```

# 21.3 glob?

```
[procedure] (glob? STRING)
```

Does the STRING have any "glob" wildcards?

A string without any "glob" wildcards does not meet the criteria, even though it technically is a valid "glob" file-pattern.

21 Unit regex 114

# 21.4 regexp

```
[procedure] (regexp STRING [IGNORECASE [IGNORESPACE [UTF8]]])
```

Returns a precompiled regular expression object for string. The optional arguments IGNORECASE, IGNORESPACE and UTF8 specify whether the regular expression should be matched with case- or whitespace-differences ignored, or whether the string should be treated as containing UTF-8 encoded characters, respectively.

### 21.5 regexp?

```
[procedure] (regexp? X)
```

Returns #t if X is a precompiled regular expression, or #f otherwise.

# 21.6 string-match

# 21.7 string-match-positions

```
[procedure] (string-match REGEXP STRING [START])
[procedure] (string-match-positions REGEXP STRING [START])
```

Matches the regular expression in REGEXP (a string or a precompiled regular expression) with STRING and returns either #f if the match failed, or a list of matching groups, where the first element is the complete match. If the optional argument START is supplied, it specifies the starting position in STRING. For each matching group the result-list contains either: #f for a non-matching but optional group; a list of start- and end-position of the match in STRING (in the case of string-match-positions); or the matching substring (in the case of string-match). Note that the exact string is matched. For searching a pattern inside a string, see below. Note also that string-match is implemented by calling string-search with the regular expression wrapped in ^ . . . \$. If invoked with a precompiled regular expression argument (by using regexp), string-match is identical to string-search.

# 21.8 string-search

21.4 regexp 115

# 21.9 string-search-positions

```
[procedure] (string-search REGEXP STRING [START [RANGE]])
[procedure] (string-search-positions REGEXP STRING [START [RANGE]])
```

Searches for the first match of the regular expression in REGEXP with STRING. The search can be limited to RANGE characters.

# 21.10 string-split-fields

```
[procedure] (string-split-fields REGEXP STRING [MODE [START]])
```

Splits STRING into a list of fields according to MODE, where MODE can be the keyword #:infix (REGEXP matches field separator), the keyword #:suffix (REGEXP matches field terminator) or #t (REGEXP matches field), which is the default.

```
(define s "this is a string 1, 2, 3,")
(string-split-fields "[^ ]+" s)
    => ("this" "is" "a" "string" "1," "2," "3,")
(string-split-fields " " s #:infix)
    => ("this" "is" "a" "string" "1," "2," "3,")
(string-split-fields "," s #:suffix))
    => ("this is a string 1" " 2" " 3")
```

# 21.11 string-substitute

```
[procedure] (string-substitute REGEXP SUBST STRING [MODE])
```

Searches substrings in STRING that match REGEXP and substitutes them with the string SUBST. The substitution can contain references to subexpressions in REGEXP with the \NUM notation, where NUM refers to the NUMth parenthesized expression. The optional argument MODE defaults to 1 and specifies the number of the match to be substituted. Any non-numeric index specifies that all matches are to be substituted.

Note that a regular expression that matches an empty string will signal an error.

# 21.12 string-substitute\*

```
[procedure] (string-substitute* STRING SMAP [MODE])
```

Substitutes elements of STRING with string-substitute according to SMAP. SMAP should be an association-list where each element of the list is a pair of the form (MATCH . REPLACEMENT). Every occurrence of the regular expression MATCH in STRING will be replaced by the string REPLACEMENT

# 21.13 regexp-escape

```
[procedure] (regexp-escape STRING)
```

Escapes all special characters in STRING with \, so that the string can be embedded into a regular expression.

```
(regexp-escape "^[0-9]+:.*$")
=> "\^\[0-9\]\\+:.\n.\\*\\$"
```

Previous: Unit match

Next: Unit srfi-18

### 22 Unit srfi-18

A simple multithreading package. This threading package follows largely the specification of SRFI-18. For more information see the documentation for <u>SRFI-18</u>.

#### **Notes:**

- thread-start! accepts a thunk (a zero argument procedure) as argument, which is equivalent to (thread-start! (make-thread THUNK)).
- thread-sleep! accepts a seconds real number value in addition to a time object.
- When an uncaught exception (i.e. an error) is signalled in a thread other than the primordial thread and warnings are enabled (see: enable-warnings, then a warning message is written to the port that is the value of (current-error-port).
- Blocking I/O will block all threads, except for some socket operations (see the section about the tcp unit). An exception is the read-eval-print loop on UNIX platforms: waiting for input will not block other threads, provided the current input port reads input from a console.
- It is generally not a good idea for one thread to call a continuation created by another thread, if dynamic-wind is involved.
- When more than one thread compete for the current time-slice, the thread that was waiting first will become the next runnable thread.
- The dynamic environment of a thread consists of the following state:
  - ♦ The current input-, output- and error-port
  - ♦ The current exception handler
  - ◆The values of all current parameters (created by make-parameter)
  - ♦ Any pending dynamic-wind thunks.

The following procedures are provided, in addition to the procedures defined in SRFI-18:

# 22.1 thread-signal!

[procedure] (thread-signal! THREAD X)

This will cause THREAD to signal the condition X once it is scheduled for execution. After signalling the condition, the thread continues with its normal execution.

# 22.2 thread-quantum

[procedure] (thread-quantum THREAD)

Returns the quantum of THREAD, which is an exact integer specifying the approximate time-slice of the thread in milliseconds.

22 Unit srfi-18

# 22.3 thread-quantum-set!

[procedure] (thread-quantum-set! THREAD QUANTUM)

Sets the quantum of THREAD to QUANTUM.

# 22.4 thread-suspend!

[procedure] (thread-suspend! THREAD)

Suspends the execution of THREAD until resumed.

### 22.5 thread-resume!

[procedure] (thread-resume! THREAD)

Readies the suspended thread THREAD.

### 22.6 timemilliseconds

[procedure] (time->milliseconds TIME)

Converts a time object (as created via current-time) into an exact integer representing the number of milliseconds since process startup.

Previous: <u>Unit regex</u>

Next: <u>Unit posix</u>

# 23 Unit posix

This unit provides services as used on many UNIX-like systems. Note that the following definitions are not all available on non-UNIX systems like Windows. See below for Windows specific notes.

This unit uses the regex, scheduler, extras and utils units.

All errors related to failing file-operations will signal a condition of kind (exn i/o file).

### 23.1 Directories

### 23.1.1 change-directory

[procedure] (change-directory NAME)

Changes the current working directory to NAME.

### 23.1.2 current-directory

[procedure] (current-directory [DIR])

Returns the name of the current working directory. If the optional argument DIR is given, then (current-directory DIR) is equivalent to (change-directory DIR).

# 23.1.3 create-directory

[procedure] (create-directory NAME)

Creates a directory with the pathname NAME.

# 23.1.4 delete-directory

[procedure] (delete-directory NAME)

Deletes the directory with the pathname NAME. The directory has to be empty.

23 Unit posix 120

### 23.1.5 directory

```
[procedure] (directory [PATHNAME [SHOW-DOTFILES?]])
```

Returns a list with all files that are contained in the directory with the name PATHNAME (which defaults to the value of (current-directory)). Files beginning with . are included only if SHOW-DOTFILES? is given and not #f.

### 23.1.6 directory?

```
[procedure] (directory? NAME)
```

Returns #t if there exists a file with the name NAME and if that file is a directory, or #f otherwise.

### 23.1.7 glob

```
[procedure] (glob PATTERN1 ...)
```

Returns a list of the pathnames of all existing files matching PATTERN1 ..., which should be strings containing the usual file-patterns (with \* matching zero or more characters and ? matching zero or one character).

# 23.1.8 set-root-directory!

```
[procedure] (set-root-directory! STRING)
```

Sets the root directory for the current process to the path given in STRING (using the chroot function). If the current process has no root permissions, the operation will fail.

# **23.2 Pipes**

# 23.2.1 call-with-input-pipe

# 23.2.2 call-with-output-pipe

```
[procedure] (call-with-input-pipe CMDLINE PROC [MODE])
[procedure] (call-with-output-pipe CMDLINE PROC [MODE])
```

23.1.5 directory 121

Call PROC with a single argument: a input- or output port for a pipe connected to the subprocess named in CMDLINE. If PROC returns normally, the pipe is closed and any result values are returned.

### 23.2.3 close-input-pipe

### 23.2.4 close-output-pipe

```
[procedure] (close-input-pipe PORT)
[procedure] (close-output-pipe PORT)
```

Closes the pipe given in PORT and waits until the connected subprocess finishes. The exit-status code of the invoked process is returned.

### 23.2.5 create-pipe

```
[procedure] (create-pipe)
```

The fundamental pipe-creation operator. Calls the C function pipe () and returns 2 values: the file-descriptors of the input- and output-ends of the pipe.

# 23.2.6 open-input-pipe

```
[procedure] (open-input-pipe CMDLINE [MODE])
```

Spawns a subprocess with the command-line string CMDLINE and returns a port, from which the output of the process can be read. If MODE is specified, it should be the keyword #:text (the default) or #:binary.

# 23.2.7 open-output-pipe

```
[procedure] (open-output-pipe CMDLINE [MODE])
```

Spawns a subprocess with the command-line string CMDLINE and returns a port. Anything written to that port is treated as the input for the process. If MODE is specified, it should be the keyword #:text (the default) or #:binary.

### 23.2.8 pipe/buf

This variable contains the maximal number of bytes that can be written atomically into a pipe or FIFO.

## 23.2.9 with-input-from-pipe

## 23.2.10 with-output-to-pipe

```
[procedure] (with-input-from-pipe CMDLINE THUNK [MODE])
[procedure] (with-output-to-pipe CMDLINE THUNK [MODE])
```

Temporarily set the value of current-input-port/current-output-port to a port for a pipe connected to the subprocess named in CMDLINE and call the procedure THUNK with no arguments. After THUNK returns normally the pipe is closed and the standard input-/output port is restored to its previous value and any result values are returned.

## 23.3 Fifos

#### 23.3.1 create-fifo

```
[procedure] (create-fifo FILENAME [MODE])
Creates a FIFO with the name FILENAME and the permission bits MODE, which defaults to
[procedure] (+ perm/irwxu perm/irwxg perm/irwxo)
```

23.2.8 pipe/buf 123

#### 23.3.2 fifo?

```
[procedure] (fifo? FILENAME)
```

Returns #t if the file with the name FILENAME names a FIFO.

# 23.4 File descriptors and low-level I/O

## 23.4.1 duplicate-fileno

```
[procedure] (duplicate-fileno OLD [NEW])
```

If NEW is given, then the file-descriptor NEW is opened to access the file with the file-descriptor OLD. Otherwise a fresh file-descriptor accessing the same file as OLD is returned.

#### 23.4.2 file-close

```
[procedure] (file-close FILENO)
```

Closes the input/output file with the file-descriptor FILENO.

# 23.4.3 file-open

```
[procedure] (file-open FILENAME FLAGS [MODE])
```

Opens the file specified with the string FILENAME and open-flags FLAGS using the C function open (). On success a file-descriptor for the opened file is returned. FLAGS should be a bitmask containing one or more of the open/... values ored together using bitwise-ior (or simply added together). The optional MODE should be a bitmask composed of one or more permission values like perm/irusr and is only relevant when a new file is created. The default mode is perm/irwxu | perm/irgrp | perm/iroth.

# 23.4.4 file-mkstemp

```
[procedure] (file-mkstemp TEMPLATE-FILENAME)
```

Create a file based on the given TEMPLATE-FILENAME, in which the six last characters must be *XXXXXX*. These will be replaced with a string that makes the filename unique. The file descriptor of the created file and the generated filename is returned. See the mkstemp(3) manual page for details on how this function works. The template string given is not modified.

Example usage:

23.3.2 fifo?

```
(let-values (((fd temp-path) (file-mkstemp "/tmp/mytemporary.XXXXXX")))
(let ((temp-port (open-output-file* fd)))
  (format temp-port "This file is ~A.~%" temp-path)
  (close-output-port temp-port)))
```

#### 23.4.5 file-read

```
[procedure] (file-read FILENO SIZE [BUFFER])
```

Reads SIZE bytes from the file with the file-descriptor FILENO. If a string or bytevector is passed in the optional argument BUFFER, then this string will be destructively modified to contain the read data. This procedure returns a list with two values: the buffer containing the data and the number of bytes read.

#### 23.4.6 file-select

```
[procedure] (file-select READFDLIST WRITEFDLIST [TIMEOUT])
```

Waits until any of the file-descriptors given in the lists READFDLIST and WRITEFDLIST is ready for input or output, respectively. If the optional argument TIMEOUT is given and not false, then it should specify the number of seconds after which the wait is to be aborted (the value may be a floating point number). This procedure returns two values: the lists of file-descriptors ready for input and output, respectively. READFDLIST and WRITEFDLIST may also by file-descriptors instead of lists. In this case the returned values are booleans indicating whether input/output is ready by #t or #f otherwise. You can also pass #f as READFDLIST or WRITEFDLIST argument, which is equivalent to ().

#### 23.4.7 file-write

```
[procedure] (file-write FILENO BUFFER [SIZE])
```

Writes the contents of the string or bytevector BUFFER into the file with the file-descriptor FILENO. If the optional argument SIZE is given, then only the specified number of bytes are written.

#### 23.4.8 file-control

```
[procedure] (file-control FILENO COMMAND [ARGUMENT])
```

Performs the fcntl operation COMMAND with the given FILENO and optional ARGUMENT. The return value is meaningful depending on the COMMAND.

23.4.4 file-mkstemp 125

CHICKEN	Her's	Manual -	The l	Her's	Manual
CHICKEN	USULS	ivianuai -	1110	USUI S	ivianuai

# 23.4.9 fcntl/dupfd

# 23.4.10 fcntl/getfd

# 23.4.11 fcntl/setfd

# 23.4.12 fcntl/getfl

#### 23.4.13 fcntl/setfl

These variables contain commands for file-control.

#### 23.4.14 fileno/stdin

## 23.4.15 fileno/stdout

#### 23.4.16 fileno/stderr

These variables contain file-descriptors for the standard I/O files.

# 23.4.17 open/rdonly

# 23.4.18 open/wronly

23.4.9 fcntl/dupfd 126

# 23.4.19 open/rdwr

23.4.20 open/read

23.4.21 open/write

23.4.22 open/creat

23.4.23 open/append

23.4.24 open/excl

23.4.25 open/noctty

23.4.26 open/nonblock

23.4.27 open/trunc

23.4.28 open/sync

23.4.29 open/fsync

23.4.19 open/rdwr 127

## 23.4.30 open/binary

## 23.4.31 open/text

Flags for use with file-open.

# 23.4.32 open-input-file\*

## 23.4.33 open-output-file\*

```
[procedure] (open-input-file* FILENO [OPENMODE])
[procedure] (open-output-file* FILENO [OPENMODE])
```

Opens file for the file-descriptor FILENO for input or output and returns a port. FILENO should be a positive exact integer. OPENMODE specifies an additional mode for opening the file (currently only the keyword #:append is supported, which opens an output-file for appending).

## 23.4.34 portfileno

```
[procedure] (port->fileno PORT)
```

If PORT is a file- or tcp-port, then a file-descriptor is returned for this port. Otherwise an error is signaled.

# 23.5 Retrieving file attributes

#### 23.5.1 file-access-time

# 23.5.2 file-change-time

23.4.30 open/binary 128

#### 23.5.3 file-modification-time

```
[procedure] (file-access-time FILE)
[procedure] (file-change-time FILE)
[procedure] (file-modification-time FILE)
```

Returns time (in seconds) of the last access, modification or change of FILE. FILE may be a filename or a file-descriptor. If the file does not exist, an error is signaled.

#### 23.5.4 file-stat

```
[procedure] (file-stat FILE [LINK])
```

Returns a 13-element vector with the following contents: inode-number, mode (as with file-permissions), number of hard links, uid of owner (as with file-owner), gid of owner, size (as with file-size) and access-, change- and modification-time (as with file-access-time, file-change-time and file-modification-time, device id, device type (for special file inode, blocksize and blocks allocated. On Windows systems the last 4 values are undefined. If the optional argument LINK is given and not #f, then the file-statistics vector will be resolved for symbolic links (otherwise symbolic links are not resolved).

## 23.5.5 file-position

```
[procedure] (file-position FILE)
```

Returns the current file position of FILE, which should be a port or a file-descriptor.

#### 23.5.6 file-size

```
[procedure] (file-size FILENAME)
```

Returns the size of the file designated by FILE. FILE may be a filename or a file-descriptor. If the file does not exist, an error is signaled.

# 23.5.7 regular-file?

```
[procedure] (regular-file? FILENAME)
```

Returns true, if FILENAME names a regular file (not a directory or symbolic link).

# 23.6 Changing file attributes

#### 23.6.1 file-truncate

```
[procedure] (file-truncate FILE OFFSET)
```

Truncates the file FILE to the length OFFSET, which should be an integer. If the file-size is smaller or equal to OFFSET then nothing is done. FILE should be a filename or a file-descriptor.

## 23.6.2 set-file-position!

```
[procedure] (set-file-position! FILE POSITION [WHENCE])
[procedure] (set! (file-position FILE) POSITION)
```

Sets the current read/write position of FILE to POSITION, which should be an exact integer. FILE should be a port or a file-descriptor. WHENCE specifies how the position is to interpreted and should be one of the values seek/set, seek/cur and seek/end. It defaults to seek/set.

Exceptions: (exn bounds), (exn i/o file)

### 23.7 Processes

# 23.7.1 current-process-id

[procedure] (current-process-id)

Returns the process ID of the current process.

# 23.7.2 parent-process-id

[procedure] (parent-process-id)

Returns the process ID of the parent of the current process.

### 23.7.3 process-execute

```
[procedure] (process-execute PATHNAME [ARGUMENT-LIST [ENVIRONMENT-LIST]])
```

Creates a new child process and replaces the running process with it using the C library function execvp(3). If the optional argument ARGUMENT-LIST is given, then it should contain a list of strings which are passed as arguments to the subprocess. If the optional argument ENVIRONMENT-LIST is supplied, then the library function execve(2) is used, and the environment passed in ENVIRONMENT-LIST (which should be of the form ("<NAME>=<VALUE>" . . .) is given to the invoked process. Note that execvp(3) respects the current setting of the PATH environment variable while execve(3) does not.

## 23.7.4 process-fork

```
[procedure] (process-fork [THUNK])
```

Creates a new child process with the UNIX system call fork(). Returns either the PID of the child process or 0. If THUNK is given, then the child process calls it as a procedure with no arguments and terminates.

## 23.7.5 process-run

```
[procedure] (process-run COMMANDLINE])
[procedure] (process-run COMMAND ARGUMENT-LIST)
```

Creates a new child process. The PID of the new process is returned.

- The single parameter version passes the **COMMANDLINE** to the system shell, so usual argument expansion can take place.
- The multiple parameter version directly invokes the COMMAND with the ARGUMENT-LIST.

# 23.7.6 process-signal

```
[procedure] (process-signal PID [SIGNAL])
```

Sends SIGNAL to the process with the id PID using the UNIX system call kill(). SIGNAL defaults to the value of the variable signal/term.

# 23.7.7 process-wait

```
[procedure] (process-wait [PID [NOHANG]])
```

Suspends the current process until the child process with the id PID has terminated using the UNIX system call waitpid(). If PID is not given, then this procedure waits for any child process. If NOHANG is given and not #f then the current process is not suspended. This procedure returns three values:

23.7.3 process-execute 131

- PID or 0, if NOHANG is true and the child process has not terminated yet.
- #t if the process exited normally or #f otherwise.
- either the exit status, if the process terminated normally or the signal number that terminated/stopped the process.

## **23.7.8 process**

```
[procedure] (process COMMANDLINE)
[procedure] (process COMMAND ARGUMENT-LIST [ENVIRONMENT-LIST])
```

Creates a subprocess and returns three values: an input port from which data written by the sub-process can be read, an output port from which any data written to will be received as input in the sub-process and the process-id of the started sub-process. Blocking reads and writes to or from the ports returned by process only block the current thread, not other threads executing concurrently.

- The single parameter version passes the string **COMMANDLINE** to the host-system's shell that is invoked as a subprocess.
- The multiple parameter version directly invokes the COMMAND as a subprocess. The ARGUMENT-LIST is directly passed, as is ENVIRONMENT-LIST.

Not using the shell may be preferrable for security reasons.

## 23.7.9 process\*

```
[procedure] (process* COMMANDLINE)
[procedure] (process* COMMAND ARGUMENT-LIST [ENVIRONMENT-LIST])
```

Like process but returns 4 values: an input port from which data written by the sub-process can be read, an output port from which any data written to will be received as input in the sub-process, the process-id of the started sub-process, and an input port from which data written by the sub-process to stderr can be read.

# 23.7.10 sleep

```
[procedure] (sleep SECONDS)
```

Puts the process to sleep for SECONDS. Returns either 0 if the time has completely elapsed, or the number of remaining seconds, if a signal occurred.

# 23.8 Hard and symbolic links

23.7.7 process-wait 132

## 23.8.1 symbolic-link?

[procedure] (symbolic-link? FILENAME)

Returns true, if FILENAME names a symbolic link.

## 23.8.2 create-symbolic-link

[procedure] (create-symbolic-link OLDNAME NEWNAME)

Creates a symbolic link with the filename NEWNAME that points to the file named OLDNAME.

## 23.8.3 read-symbolic-link

[procedure] (read-symbolic-link FILENAME)

Returns the filename to which the symbolic link FILENAME points.

#### 23.8.4 file-link

[procedure] (file-link OLDNAME NEWNAME)

Creates a hard link from **OLDNAME** to **NEWNAME** (both strings).

## 23.9 Permissions

#### 23.9.1 file-owner

[procedure] (file-owner FILE)

Returns the user-id of FILE. FILE may be a filename or a file-descriptor.

# 23.9.2 file-permissions

[procedure] (file-permissions FILE)

Returns the permission bits for FILE. You can test this value by performing bitwise operations on the result and the perm/... values. FILE may be a filename or a file-descriptor.

23.8.1 symbolic-link?

#### 23.9.3 file-read-access?

### 23.9.4 file-write-access?

#### 23.9.5 file-execute-access?

```
[procedure] (file-read-access? FILENAME)
[procedure] (file-write-access? FILENAME)
[procedure] (file-execute-access? FILENAME)
```

These procedures return #t if the current user has read, write or execute permissions on the file named FILENAME.

## 23.9.6 change-file-mode

```
[procedure] (change-file-mode FILENAME MODE)
```

Changes the current file mode of the file named FILENAME to MODE using the chmod() system call. The perm/... variables contain the various permission bits and can be combinded with the bitwise-ior procedure.

# 23.9.7 change-file-owner

```
[procedure] (change-file-owner FILENAME UID GID)
```

Changes the owner information of the file named FILENAME to the user- and group-ids UID and GID (which should be exact integers) using the Chown() system call.

#### 23.9.8 current-user-id

# 23.9.9 current-group-id

23.9.3 file-read-access?

#### 23.9.10 current-effective-user-id

## 23.9.11 current-effective-group-id

```
[procedure] (current-user-id)
[setter] (set! (current-user-id) UID)
[procedure] (current-group-id)
[setter] (set! (current-group-id) GID)
[procedure] (current-effective-user-id)
[setter] (set! (current-effective-user-id) UID)
[procedure] (current-effective-group-id)
[setter] (set! (current-effective-group-id) GID)
```

Get or set the real/effective user- and group-ids of the current process.

## 23.9.12 process-group-id

```
[procedure] (process-group-id PID)
```

Returns the process group ID of the process specified by PID.

# 23.9.13 group-information

```
[procedure] (group-information GROUP)
```

If GROUP specifies a valid group-name or group-id, then this procedure returns a list of four values: the group-name, the encrypted group password, the group ID and a list of the names of all group members. If no group with the given name or ID exists, then #f is returned.

# 23.9.14 get-groups

```
[procedure] (get-groups)
```

Returns a list with the supplementary group IDs of the current user.

# 23.9.15 set-groups!

```
[procedure] (set-groups! GIDLIST)
```

Sets the supplementrary group IDs of the current user to the IDs given in the list GIDLIST.

CHICKEN	Her's	Manual -	The l	Her's	Manual
CHICKEN	USULS	ivianuai -	1110	USUI S	ivianuai

Only the superuser may invoke this procedure.

# 23.9.16 initialize-groups

[procedure] (initialize-groups USERNAME BASEGID)

Sets the supplementary group IDs of the current user to the IDs from the user with name USERNAME (a string), including BASEGID.

Only the superuser may invoke this procedure.

## 23.9.17 perm/irusr

23.9.18 perm/iwusr

23.9.19 perm/ixusr

23.9.20 perm/irgrp

23.9.21 perm/iwgrp

23.9.22 perm/ixgrp

23.9.23 perm/iroth

# 23.9.24 perm/iwoth

23.9.15 set-groups!

## 23.9.25 perm/ixoth

## 23.9.26 perm/irwxu

## 23.9.27 perm/irwxg

## 23.9.28 perm/irwxo

## 23.9.29 perm/isvtx

# 23.9.30 perm/isuid

## 23.9.31 perm/isgid

These variables contain permission bits as used in change-file-mode.

# 23.9.32 set-process-group-id!

```
[procedure] (set-process-group-id! PID PGID)
[setter] (set! (process-group-id PID) PGID)
```

Sets the process group ID of the process specifed by PID to PGID.

#### 23.9.33 user-information

```
[procedure] (user-information USER)
```

If USER specifes a valid username (as a string) or user ID, then the user database is consulted and a list of 7 values are returned: the user-name, the encrypted password, the user ID, the group ID, a user-specific string, the home directory and the default shell. If no user with this name or ID can be found, then #f is returned.

23.9.25 perm/ixoth 137

#### 23.9.34 create-session

```
[procedure] (create-session)
```

Creates a new session if the calling process is not a process group leader and returns the session ID.

# 23.10 Record locking

### 23.10.1 file-lock

```
[procedure] (file-lock PORT [START [LEN]])
```

Locks the file associated with PORT for reading or writing (according to whether PORT is an input- or output-port). START specifies the starting position in the file to be locked and defaults to 0. LEN specifies the length of the portion to be locked and defaults to #t, which means the complete file. file-lock returns a *lock*-object.

## 23.10.2 file-lock/blocking

```
[procedure] (file-lock/blocking PORT [START [LEN]])
```

Similar to file-lock, but if a lock is held on the file, the current process blocks (including all threads) until the lock is released.

#### 23.10.3 file-test-lock

```
[procedure] (file-test-lock PORT [START [LEN]])
```

Tests whether the file associated with PORT is locked for reading or writing (according to whether PORT is an input- or output-port) and returns either #f or the process-id of the locking process.

#### 23.10.4 file-unlock

```
[procedure] (file-unlock LOCK)
```

Unlocks the previously locked portion of a file given in LOCK.

23.9.34 create-session 138

# 23.11 Signal handling

#### 23.11.1 set-alarm!

```
[procedure] (set-alarm! SECONDS)
```

Sets an internal timer to raise the signal/alrm after SECONDS are elapsed. You can use the set-signal-handler! procedure to write a handler for this signal.

## 23.11.2 set-signal-handler!

```
[procedure] (set-signal-handler! SIGNUM PROC)
```

Establishes the procedure of one argument PROC as the handler for the signal with the code SIGNUM. PROC is called with the signal number as its sole argument. If the argument PROC is #f then any signal handler will be removed.

Note that is is unspecified in which thread of execution the signal handler will be invoked.

## 23.11.3 signal-handler

```
[procedure] (signal-handler SIGNUM)
```

Returns the signal handler for the code SIGNUM or #f.

# 23.11.4 set-signal-mask!

```
[procedure] (set-signal-mask! SIGLIST)
```

Sets the signal mask of the current process to block all signals given in the list SIGLIST. Signals masked in that way will not be delivered to the current process.

# 23.11.5 signal-mask

```
[procedure] (signal-mask)
```

Returns the signal mask of the current process.

23.11 Signal handling

CHICKEN User's Manual - The User's Manual

## 23.11.6 signal-masked?

[procedure] (signal-masked? SIGNUM)

Returns whether the signal for the code  ${\sf SIGNUM}$  is currently masked.

## 23.11.7 signal-mask!

[procedure] (signal-mask! SIGNUM)

Masks (blocks) the signal for the code SIGNUM.

## 23.11.8 signal-unmask!

[procedure] (signal-unmask! SIGNUM)

Unmasks (unblocks) the signal for the code SIGNUM.

## 23.11.9 signal/term

23.11.10 signal/kill

23.11.11 signal/int

23.11.12 signal/hup

23.11.13 signal/fpe

# 23.11.14 signal/ill

# 23.11.15 signal/segv

23.11.16 signal/abrt

23.11.17 signal/trap

23.11.18 signal/quit

23.11.19 signal/alrm

23.11.20 signal/vtalrm

23.11.21 signal/prof

23.11.22 signal/io

23.11.23 signal/urg

23.11.24 signal/chld

23.11.25 signal/cont

23.11.15 signal/segv 141

CHICKEN	User's	Manual	- The l	User's N	Manua

## 23.11.26 signal/stop

## 23.11.27 signal/tstp

# 23.11.28 signal/pipe

# 23.11.29 signal/xcpu

## 23.11.30 signal/xfsz

# 23.11.31 signal/usr1

## 23.11.32 signal/usr2

# 23.11.33 signal/winch

These variables contain signal codes for use with process-signal, set-signal-handler!, signal-handler, signal-masked?, signal-mask!, or signal-unmask!.

## 23.12 Environment access

#### 23.12.1 current-environment

[procedure] (current-environment)

Returns a association list of the environment variables and their current values.

23.11.26 signal/stop 142

#### 23.12.2 seteny

[procedure] (setenv VARIABLE VALUE)

Sets the environment variable named VARIABLE to VALUE. Both arguments should be strings. If the variable is not defined in the environment, a new definition is created.

#### 23.12.3 unsetenv

[procedure] (unsetenv VARIABLE)

Removes the definition of the environment variable VARIABLE from the environment of the current process. If the variable is not defined, nothing happens.

# 23.13 Memory mapped I/O

## 23.13.1 memory-mapped-file?

[pocedure] (memory-mapped-file? X)

Returns #t, if X is an object representing a memory mapped file, or #f otherwise.

# 23.13.2 map-file-to-memory

[procedure] (map-file-to-memory ADDRESS LEN PROTECTION FLAG FILENO [OFFSET])

Maps a section of a file to memory using the C function mmap(). ADDRESS should be a foreign pointer object or #f; LEN specifies the size of the section to be mapped; PROTECTION should be one or more of the flags prot/read, prot/write, prot/exec or prot/none bitwise-iored together; FLAG should be one or more of the flags map/fixed, map/shared, map/private, map/anonymous or map/file; FILENO should be the file-descriptor of the mapped file. The optional argument OFFSET gives the offset of the section of the file to be mapped and defaults to 0. This procedure returns an object representing the mapped file section. The procedure move-memory! can be used to access the mapped memory.

# 23.13.3 memory-mapped-file-pointer

[procedure] (memory-mapped-file-pointer MMAP)

Returns a machine pointer to the start of the memory region to which the file is mapped.

23.12.2 setenv 143

## 23.13.4 unmap-file-from-memory

```
[procedure] (unmap-file-from-memory MMAP [LEN])
```

Unmaps the section of a file mapped to memory using the C function munmap(). MMAP should be a mapped file as returned by the procedure map-file-to-memory. The optional argument LEN specifies the length of the section to be unmapped and defaults to the complete length given when the file was mapped.

#### 23.14 Date and time routines

#### 23.14.1 secondslocal-time

```
[procedure] (seconds->local-time SECONDS)
```

Breaks down the time value represented in SECONDS into a 10 element vector of the form #(seconds minutes hours mday month year wday yday dstflag timezone), in the following format:

```
seconds (0)
        the number of seconds after the minute (0 - 59)
minutes (1)
        the number of minutes after the hour (0 - 59)
hours (2)
        the number of hours past midnight (0 - 23)
mday (3)
        the day of the month (1 - 31)
month (4)
        the number of months since january (0 - 11)
year(5)
        the number of years since 1900
wday (6)
        the number of days since Sunday (0 - 6)
yday(7)
        the number of days since January 1 (0 - 365)
dstflag (8)
        a flag that is true if Daylight Saving Time is in effect at the time described.
timezone (9)
        the difference between UTC and the latest local standard time, in seconds west of UTC.
```

#### 23.14.2 local-timeseconds

```
[procedure] (local-time->seconds VECTOR)
```

CHICKEN User's Manual - The User's Manual

Converts the ten-element vector VECTOR representing the time value relative to the current timezone into the number of seconds since the first of January, 1970 UTC.

#### 23.14.3 local-timezone-abbreviation

[procedure] (local-timezone-abbreviation)

Returns the abbreviation for the local timezone as a string.

## 23.14.4 secondsstring

[procedure] (seconds->string SECONDS)

Converts the local time represented in SECONDS into a string of the form "Tue May 21 13:46:22  $1991\n$ ".

#### 23.14.5 secondsutc-time

[procedure] (seconds->utc-time SECONDS)

Similar to seconds->local-time, but interpretes SECONDS as UTC time.

#### 23.14.6 utc-timeseconds

[procedure] (utc-time->seconds VECTOR)

Converts the ten-element vector VECTOR representing the UTC time value into the number of seconds since the first of January, 1970 UTC.

## 23.14.7 timestring

[procedure] (time->string VECTOR)

Converts the broken down time represented in the 10 element vector VECT0R into a string of the form "Tue May 21 13:46:22  $1991\n$ ".

23.14.2 local-timeseconds 145

## 23.15 Raw exit

## 23.15.1 exit

[procedure] (\_exit [CODE])

Exits the current process without flushing any buffered output (using the C function  $_exit$ ). Note that the exit-handler is not called when this procedure is invoked. The optional return-code CODE defaults to 0.

### 23.16 ERRNO values

23.16.1 errno/perm

23.16.2 errno/noent

23.16.3 errno/srch

23.16.4 errno/intr

23.16.5 errno/io

23.16.6 errno/noexec

23.16.7 errno/badf

23.15 Raw exit 146

## 23.16.8 errno/child

23.16.9 errno/nomem

23.16.10 errno/acces

23.16.11 errno/fault

23.16.12 errno/busy

23.16.13 errno/notdir

23.16.14 errno/isdir

23.16.15 errno/inval

23.16.16 errno/mfile

23.16.17 errno/nospc

23.16.18 errno/spipe

23.16.8 errno/child 147

## 23.16.19 errno/pipe

23.16.20 errno/again

23.16.21 errno/rofs

23.16.22 errno/exist

#### 23.16.23 errno/wouldblock

These variables contain error codes as returned by errno.

# 23.17 Finding files

#### 23.17.1 find-files

[procedure] (find-files DIRECTORY PREDICATE [ACTION [IDENTITY [LIMIT]]])

Recursively traverses the contents of DIRECTORY (which should be a string) and invokes the procedure ACTION for all files for which the procedure PREDICATE is true. PREDICATE may me a procedure of one argument or a regular-expression string. ACTION should be a procedure of two arguments: the currently encountered file and the result of the previous invocation of ACTION, or, if this is the first invocation, the value of IDENTITY. ACTION defaults to cons, IDENTITY defaults to (). LIMIT should a procedure of one argument that is called for each nested directory and which should return true, if that directory is to be traversed recursively. LIMIT may also be an exact integer that gives the maximum recursion depth. A depth of 0 means the files in the specified directory are traversed but not any nested directories. LIMIT may also be #f (the default), which is equivalent to (constantly #t).

Note that ACTION is called with the full pathname of each file, including the directory prefix.

# 23.18 Getting the hostname and system information

23.16.19 errno/pipe 148

## 23.18.1 get-host-name

```
[procedure] (get-host-name)
```

Returns the hostname of the machine that this process is running on.

## 23.18.2 system-information

```
[procedure] (system-information)
```

Invokes the UNIX system call uname () and returns a list of 5 values: system-name, node-name, OS release, OS version and machine.

# 23.19 Setting the file buffering mode

## 23.19.1 set-buffering-mode!

```
[procedure] (set-buffering-mode! PORT MODE [BUFSIZE])
```

Sets the buffering-mode for the file associated with PORT to MODE, which should be one of the keywords #:full, #:line or #:none. If BUFSIZE is specified it determines the size of the buffer to be used (if any).

# 23.20 Terminal ports

#### 23.20.1 terminal-name

```
[procedure] (terminal-name PORT)
```

Returns the name of the terminal that is connected to PORT.

# 23.20.2 terminal-port?

```
[procedure] (terminal-port? PORT)
```

Returns #t if PORT is connected to a terminal and #f otherwise.

23.18.1 get-host-name 149

# 23.21 How Scheme procedures relate to UNIX C functions

```
change-directory
chdir
change-file-mode
chmod
change-file-owner
chown
create-directory
mkdir
create-fifo
mkfifo
create-pipe
pipe
create-session
setsid
create-symbolic-link
link
current-directory
curdir
current-effective-groupd-id
getegid
current-effective-user-id
geteuid
current-group-id
getgid
current-parent-id
getppid
current-process-id
getpid
current-user-id
getuid
delete-directory
rmdir
duplicate-fileno
```

```
CHICKEN User's Manual - The User's Manual
dup/dup2
_exit
_exit
file-close
close
file-access-time
stat
file-change-time
stat
file-modification-time
stat
file-execute-access?
access
file-open
open
file-lock
fcntl
file-position
ftell/lseek
file-read
read
file-read-access?
access
file-select
select
file-control
fcntl
file-stat
stat
file-test-lock
fcntl
file-truncate
```

truncate/ftruncate file-unlock

```
CHICKEN User's Manual - The User's Manual
fcntl
file-write
write
file-write-access?
access
get-groups
getgroups
get-host-name
gethostname
initialize-groups
initgroups
local-time->seconds
mktime
local-timezone-abbreviation
localtime
map-file-to-memory
mmap
open-input-file*
fdopen
open-output-file*
fdopen
open-input-pipe
popen
open-output-pipe
popen
port->fileno
fileno
process-execute
execvp
process-fork
fork
process-group-id
getpgid
```

process-signal

```
CHICKEN User's Manual - The User's Manual
kill
process-wait
waitpid
close-input-pipe
pclose
close-output-pipe
pclose
read-symbolic-link
readlink
seconds->local-time
localtime
seconds->string
ctime
seconds->utc-time
gmtime
set-alarm!
alarm
set-buffering-mode!
setvbuf
set-file-position!
fseek/seek
set-groups!
setgroups
set-signal-mask!
sigprocmask
set-group-id!
setgid
set-process-group-id!
setpgid
set-user-id!
setuid
set-root-directory!
chroot
```

setenv

```
CHICKEN User's Manual - The User's Manual
setenv/putenv
sleep
sleep
system-information
uname
terminal-name
ttyname
terminal-port?
isatty
time->string
asctime
unsetenv
putenv
unmap-file-from-memory
munmap
user-information
getpwnam/getpwuid
utc-time->seconds
```

# 23.22 Windows specific notes

timegm

Use of UTF8 encoded strings is for pathnames is not supported. Windows uses a 16-bit UNICODE encoding with special system calls for wide-character support. Only single-byte string encoding can be used.

# 23.22.1 Procedure Changes

Exceptions to the above procedure definitions.

```
[procedure] (create-pipe [MODE])
```

The optional parameter MODE, default open/binary | open/noinherit. This can be open/binary or open/text, optionally or'ed with open/noinherit.

```
[procedure] (process-wait [PID [NOHANG]])
```

process-wait always returns #t for a terminated process and only the exit status is available. (Windows does not provide signals as an interprocess communication method.)

```
[procedure] (process-execute PATHNAME [ARGUMENT-LIST [ENVIRONMENT-LIST [EXACT-F
[procedure] (process COMMAND ARGUMENT-LIST [ENVIRONMENT-LIST [EXACT-FLAG]])
[procedure] (process* COMMAND ARGUMENT-LIST [ENVIRONMENT-LIST [EXACT-FLAG]])
```

The optional parameter EXACT-FLAG, default #f. When #f any argument string with embedded whitespace will be wrapped in quotes. When #t no such wrapping occurs.

## 23.22.2 Unsupported Definitions

The following definitions are not supported for native Windows builds (compiled with the Microsoft tools or with MinGW):

```
open/noctty open/nonblock open/fsync open/sync
perm/isvtx perm/isuid perm/isgid
file-select file-control
signal/... (except signal/term, signal/int, signal/fpe, signal/ill, signal/segv
set-signal-mask! signal-mask signal-masked? signal-mask! signal-unmask!
user-information group-information get-groups set-groups! initialize-groups
errno/wouldblock
change-file-owner
current-user-id current-group-id current-effective-user-id current-effective
set-user-id! set-group-id!
create-session
process-group-id set-process-group-id!
create-symbolic-link read-symbolic-link
file-truncate
file-lock file-lock/blocking file-unlock file-test-lock
create-fifo fifo?
prot/...
map/...
map-file-to-memory unmap-file-from-memory memory-mapped-file-pointer memory-
set-alarm!
terminal-port? terminal-name
process-fork process-signal
parent-process-id
set-root-directory!
utc-time->seconds
```

### 23.22.3 Additional Definitions

Only available for Windows

• open/noinherit

This variable is a mode value for create-pipe. Useful when spawning a child process.

- spawn/overlay
- spawn/wait
- spawn/nowait

#### CHICKEN User's Manual - The User's Manual

- spawn/nowaito
- spawn/detach

These variables contains special flags that specify the exact semantics of process-spawn: spawn/overlay replaces the current process with the new one. spawn/wait suspends execution of the current process until the spawned process returns. spawn/nowait does the opposite (spawn/nowaito is identical, according to the Microsoft documentation) and runs the process asynchronously. spawn/detach runs the new process in the background, without being attached to a console.

## 23.22.4 process-spawn

[procedure] (process-spawn MODE COMMAND [ARGUMENT-LIST [ENVIRONMENT-LIST [EXACT

Creates and runs a new process with the given COMMAND filename and the optional ARGUMENT-LIST and ENVIRONMENT-LIST. MODE specifies how exactly the process should be executed and must be one or more of the Spawn/... flags defined above.

The EXACT-FLAG, default #f, controls quote-wrapping of argument strings. When #t quote-wrapping is not performed.

#### Returns:

- the exit status when synchronous
- the PID when asynchronous
- -1 when failure

Previous: Unit srfi-18

Next: Unit utils

### 24 Unit utils

This unit contains file/pathname oriented procedures, apropos, plus acts as a "grab bag" for procedures without a good home, and which don't have to be available by default (as compared to the extras unit).

This unit uses the extras and regex units.

# 24.1 Environment Query

## **24.1.1** apropos

```
[procedure] (apropos SYMBOL-PATTERN [ENVIRONMENT] [#:MACROS?])
```

Displays symbols & type matching SYMBOL-PATTERN in the ENVIRONMENT on the (current-output-port).

#### SYMBOL-PATTERN

A symbol, string, or regex. When symbol or string substring matching is performed. **ENVIRONMENT** 

An environment. When missing the (interaction-environment) is assumed. #:MACROS?

Keyword argument. A boolean. Include macro symbols? When missing #f is assumed.

# 24.1.2 apropos-list

```
[procedure] (apropos-list SYMBOL-PATTERN [ENVIRONMENT] [#:MACROS?])
```

Like apropos but returns a list of matching symbols.

# 24.2 Pathname operations

# 24.2.1 absolute-pathname?

```
[procedure] (absolute-pathname? PATHNAME)
```

Returns #t if the string PATHNAME names an absolute pathname, and returns #f otherwise.

24 Unit utils 157

## 24.2.2 decompose-pathname

[procedure] (decompose-pathname PATHNAME)

Returns three values: the directory-, filename- and extension-components of the file named by the string PATHNAME. For any component that is not contained in PATHNAME, #f is returned.

## 24.2.3 make-pathname

## 24.2.4 make-absolute-pathname

```
[procedure] (make-pathname DIRECTORY FILENAME [EXTENSION [SEPARATOR]])
[procedure] (make-absolute-pathname DIRECTORY FILENAME [EXTENSION [SEPARATOR]])
```

Returns a string that names the file with the components DIRECTORY, FILENAME and (optionally) EXTENSION with SEPARATOR being the directory separation indicator (usually / on UNIX systems and \ on Windows, defaulting to whatever platform this is running on). DIRECTORY can be #f (meaning no directory component), a string or a list of strings. FILENAME and EXTENSION should be strings or #f. make-absolute-pathname returns always an absolute pathname.

## 24.2.5 pathname-directory

[procedure] (pathname-directory PATHNAME)

# 24.2.6 pathname-file

[procedure] (pathname-file PATHNAME)

# 24.2.7 pathname-extension

[procedure] (pathname-extension PATHNAME)

Accessors for the components of PATHNAME. If the pathname does not contain the accessed component, then #f is returned.

### 24.2.8 pathname-replace-directory

[procedure] (pathname-replace-directory PATHNAME DIRECTORY)

### 24.2.9 pathname-replace-file

[procedure] (pathname-replace-file PATHNAME FILENAME)

### 24.2.10 pathname-replace-extension

[procedure] (pathname-replace-extension PATHNAME EXTENSION)

Return a new pathname with the specified component of PATHNAME replaced by a new value.

### 24.2.11 pathname-strip-directory

[procedure] (pathname-strip-directory PATHNAME)

### 24.2.12 pathname-strip-extension

[procedure] (pathname-strip-extension PATHNAME)

Return a new pathname with the specified component of PATHNAME stripped.

### 24.2.13 directory-null?

[procedure] (directory-null? DIRECTORY)

Does the DIRECTORY consist only of path separators and the period?

**DIRECTORY** may be a string or a list of strings.

### 24.3 Temporary files

#### 24.3.1 create-temporary-file

```
[procedure] (create-temporary-file [EXTENSION])
```

Creates an empty temporary file and returns its pathname. If EXTENSION is not given, then .tmp is used. If the environment variable TMPDIR, TEMP or TMP is set, then the pathname names a file in that directory.

### 24.4 Deleting a file without signalling an error

#### 24.4.1 delete-file\*

```
[procedure] (delete-file* FILENAME)
```

If the file FILENAME exists, it is deleted and #t is returned. If the file does not exist, nothing happens and #f is returned.

### 24.5 Iterating over input lines and files

#### 24.5.1 for-each-line

```
[procedure] (for-each-line PROCEDURE [PORT])
```

Calls PROCEDURE for each line read from PORT (which defaults to the value of (current-input-port). The argument passed to PORCEDURE is a string with the contents of the line, excluding any line-terminators. When all input has been read from the port, for-each-line returns some unspecified value.

### 24.5.2 for-each-argv-line

```
[procedure] (for-each-argy-line PROCEDURE)
```

Opens each file listed on the command line in order, passing one line at a time into PROCEDURE. The filename - is interpreted as (current-input-port). If no arguments are given on the command line it again uses the value of (current-input-port). During execution of PROCEDURE, the current input port will be correctly bound to the current input source.

This code will act as a simple Unix cat(1) command:

```
(for-each-argv-line print)
```

#### 24.5.3 port-for-each

```
[procedure] (port-for-each FN THUNK)
```

Apply FN to successive results of calling the zero argument procedure THUNK until it returns #!eof, discarding the results.

### 24.5.4 port-map

```
[procedure] (port-map FN THUNK)
```

Apply FN to successive results of calling the zero argument procedure THUNK until it returns #!eof, returning a list of the collected results.

### 24.5.5 port-fold

```
[procedure] (port-map FN ACC THUNK)
```

Apply FN to successive results of calling the zero argument procedure THUNK, passing the ACC value as the second argument. The FN result becomes the new ACC value. When THUNK returns #!eof, the last FN result is returned.

# 24.6 Executing shell commands with formatstring and error checking

### 24.6.1 system\*

```
[procedure] (system* FORMATSTRING ARGUMENT1 ...)
```

Similar to (system (sprintf FORMATSTRING ARGUMENT1 ...)), but signals an error if the invoked program should return a nonzero exit status.

### 24.7 Reading a file's contents

24.5.3 port-for-each 161

#### 24.7.1 read-all

```
[procedure] (read-all [FILE-OR-PORT])
```

If FILE-OR-PORT is a string, then this procedure returns the contents of the file as a string. If FILE-OR-PORT is a port, all remaining input is read and returned as a string. The port is not closed. If no argument is provided, input will be read from the port that is the current value of (current-input-port).

### 24.8 Funky ports

### 24.8.1 make-broadcast-port

```
[procedure] (make-broadcast-port PORT ...)
```

Returns a custom output port that emits everything written into it to the ports given as PORT .... Closing the broadcast port does not close any of the argument ports.

### 24.8.2 make-concatenated-port

```
[procedure] (make-concatenated-port PORT1 PORT2 ...)
```

Returns a custom input port that reads its input from PORT1, until it is empty, then from PORT2 and so on. Closing the concatenated port does not close any of the argument ports.

### 24.9 Miscellaneous handy things

#### 24.9.1 shift!

```
[procedure] (shift! LIST [DEFAULT])
```

Returns the car of LIST (or DEFAULT if LIST is empty) and replaces the car of LIST with it's cadr and the cdr with the cddr. If DEFAULT is not given, and the list is empty, #f is returned. An example might be clearer, here:

```
(define lst '(1 2 3))
(shift! lst) ==> 1, lst is now (2 3)
```

The list must contain at least 2 elements.

24.7.1 read-all 162

### 24.9.2 unshift!

```
[procedure] (unshift! X PAIR)

Sets the car of PAIR to X and the cdr to its cddr. Returns PAIR:

(define lst '(2))
(unshift! 99 lst) ; lst is now (99 2)

Previous: Unit posix

Next: Unit tcp
```

24.9.2 unshift! 163

### 25 Unit tcp

This unit provides basic facilities for communicating over TCP sockets. The socket interface should be mostly compatible to the one found in PLT Scheme.

This unit uses the extras unit.

All errors related to failing network operations will raise a condition of kind (exn i/o network).

### 25.1 tcp-listen

```
[procedure] (tcp-listen TCPPORT [BACKLOG [HOST]])
```

Creates and returns a TCP listener object that listens for connections on TCPPORT, which should be an exact integer. BACKLOG specifies the number of maximally pending connections (and defaults to 4). If the optional argument HOST is given and not #f, then only incoming connections for the given host (or IP) are accepted.

### 25.2 tcp-listener?

```
[procedure] (tcp-listener? X)
```

Returns #t if X is a TCP listener object, or #f otherwise.

### 25.3 tcp-close

```
[procedure] (tcp-close LISTENER)
```

Reclaims any resources associated with LISTENER.

### 25.4 tcp-accept

```
[procedure] (tcp-accept LISTENER)
```

Waits until a connection is established on the port on which LISTENER is listening and returns two values: an input- and output-port that can be used to communicate with the remote process. The current value of tcp-accept-timeout is used to determine the maximal number of milliseconds (if any) to wait until a connection is established. When a client connects any read- and write-operations on the returned ports will use the current values (at the time of the connection) of tcp-read-timeout and tcp-write-timeout, respectively, to determine the maximal number of milliseconds to wait for input/output before a timeout error is signalled.

Note: this operation and any I/O on the ports returned will not block other running threads.

25 Unit tcp 164

### 25.5 tcp-accept-ready?

[procedure] (tcp-accept-ready? LISTENER)

Returns #t if there are any connections pending on LISTENER, or #f otherwise.

### 25.6 tcp-listener-port

[procedure] (tcp-listener-port LISTENER)

Returns the port number assigned to LISTENER (If you pass 0 to tcp-listen, then the system will choose a port-number for you).

### 25.7 tcp-listener-fileno

[procedure] (tcp-listener-fileno LISTENER)

Returns the file-descriptor associated with LISTENER.

### 25.8 tcp-connect

[procedure] (tcp-connect HOSTNAME [TCPPORT])

Establishes a client-side TCP connection to the machine with the name HOSTNAME (a string) at TCPPORT (an exact integer) and returns two values: an input- and output-port for communicating with the remote process. The current value of tcp-connect-timeout is used to determine the maximal number of milliseconds (if any) to wait until the connection is established. When the connection takes place any read-and write-operations on the returned ports will use the current values (at the time of the call to tcp-connect) of tcp-read-timeout and tcp-write-timeout, respectively, to determine the maximal number of milliseconds to wait for input/output before a timeout error is signalled.

If the TCPPORT is omitted, the port is parsed from the HOSTNAME string. The format expected is HOSTNAME: PORT. The PORT can either be a string representation of an integer or a service name which is translated to an integer using the POSIX function getservbyname.

Note: any I/O on the ports returned will not block other running threads.

### 25.9 tcp-addresses

[procedure] (tcp-addresses PORT)

Returns two values for the input- or output-port PORT (which should be a port returned by either tcp-accept or tcp-connect): the IP address of the local and the remote machine that are connected over the socket associated with PORT. The returned addresses are strings in XXX.XXX.XXX notation.

### 25.10 tcp-port-numbers

[procedure] (tcp-port-numbers PORT)

Returns two values for the input- or output-port PORT (which should be a port returned by either tcp-accept or tcp-connect): the TCP port numbers of the local and the remote machine that are connected over the socket associated with PORT.

### 25.11 tcp-abandon-port

[procedure] (tcp-abandon-port PORT)

Marks the socket port PORT as abandoned. This is mainly useful to close down a port without breaking the connection.

### 25.12 tcp-buffer-size

[parameter] tcp-buffer-size

Sets the size of the output buffer. By default no output-buffering for TCP output is done, but to improve performance by minimizing the number of TCP packets, buffering may be turned on by setting this parameter to an exact integer greater zero. A buffer size of zero or #f turns buffering off. The setting of this parameter takes effect at the time when the I/O ports for a particular socket are created, i.e. when tcp-connect or tcp-accept is called.

Note that since output is not immediately written to the associated socket, you may need to call flush-output, once you want the output to be transmitted. Closing the output port will flush automatically.

### 25.13 tcp-read-timeout

[parameter] tcp-read-timeout

Determines the timeout for TCP read operations in milliseconds. A timeout of #f disables timeout checking. The default read timeout is 60000, i.e. 1 minute.

25.9 tcp-addresses 166

### 25.14 tcp-write-timeout

```
[parameter] tcp-write-timeout
```

Determines the timeout for TCP write operations in milliseconds. A timeout of #f disables timeout checking. The default write timeout is 60000, i.e. 1 minute.

### 25.15 tcp-connect-timeout

```
[parameter] tcp-connect-timeout
```

Determines the timeout for tcp-connect operations in milliseconds. A timeout of #f disables timeout checking and is the default.

### 25.16 tcp-accept-timeout

```
[parameter] tcp-accept-timeout
```

Determines the timeout for tcp-accept operations in milliseconds. A timeout of #f disables timeout checking and is the default.

### **25.17 Example**

A very simple example follows. Say we have the two files client.scm and server.scm:

```
; client.scm
(declare (uses tcp))
(define-values (i o) (tcp-connect "localhost" 4242))
(write-line "Good Bye!" o)
(print (read-line i))
; server.scm
(declare (uses tcp))
(define l (tcp-listen 4242))
(define-values (i o) (tcp-accept l))
(write-line "Hello!" o)
(print (read-line i))
(close-input-port i)
(close-output-port o)
% csc server.scm
% csc client.scm
% ./server &
```

#### CHICKEN User's Manual - The User's Manual

% ./client Good Bye! Hello!

Previous: <u>Unit utils</u>

Next: <u>Unit lolevel</u>

25.17 Example 168

#### 26 Unit lolevel

This unit provides a number of handy low-level operations. Use at your own risk.

This unit uses the srfi-4 and extras units.

### 26.1 Foreign pointers

### 26.1.1 addresspointer

```
[procedure] (address->pointer ADDRESS)
```

Creates a new foreign pointer object initialized to point to the address given in the integer ADDRESS.

#### 26.1.2 allocate

```
[procedure] (allocate BYTES)
```

Returns a pointer to a freshly allocated region of static memory. This procedure could be defined as follows:

```
(define allocate (foreign-lambda c-pointer "malloc" integer))
```

#### 26.1.3 free

```
[procedure] (free POINTER)
```

Frees the memory pointed to by POINTER. This procedure could be defined as follows:

```
(define free (foreign-lambda c-pointer "free" integer))
```

### 26.1.4 null-pointer

```
[procedure] (null-pointer)
```

Another way to say (address->pointer 0).

26 Unit lolevel 169

CHICKEN User's Manual - The User's Manual

### 26.1.5 null-pointer?

```
[procedure] (null-pointer? PTR)
```

Returns #t if PTR contains a NULL pointer, or #f otherwise.

#### 26.1.6 objectpointer

```
[procedure] (object->pointer X)
```

Returns a pointer pointing to the Scheme object X, which should be a non-immediate object. Note that data in the garbage collected heap moves during garbage collection.

### 26.1.7 pointer?

```
[procedure] (pointer? X)
```

Returns #t if X is a foreign pointer object, and #f otherwise.

### 26.1.8 pointer=?

```
[procedure] (pointer=? PTR1 PTR2)
```

Returns #t if the pointer-like objects PTR1 and PTR2 point to the same address.

### 26.1.9 pointeraddress

```
[procedure] (pointer->address PTR)
```

Returns the address, to which the pointer PTR points.

### 26.1.10 pointerobject

```
[procedure] (pointer->object PTR)
```

Returns the Scheme object pointed to by the pointer PTR.

26.1.5 null-pointer? 170

### 26.1.11 pointer-offset

```
[procedure] (pointer-offset PTR N)
```

Returns a new pointer representing the pointer PTR increased by N.

#### 26.1.12 pointer-u8-ref

```
[procedure] (pointer-u8-ref PTR)
```

Returns the unsigned byte at the address designated by PTR.

### 26.1.13 pointer-s8-ref

```
[procedure] (pointer-s8-ref PTR)
```

Returns the signed byte at the address designated by PTR.

### 26.1.14 pointer-u16-ref

```
[procedure] (pointer-u16-ref PTR)
```

Returns the unsigned 16-bit integer at the address designated by PTR.

### 26.1.15 pointer-s16-ref

```
[procedure] (pointer-s16-ref PTR)
```

Returns the signed 16-bit integer at the address designated by PTR.

### 26.1.16 pointer-u32-ref

```
[procedure] (pointer-u32-ref PTR)
```

Returns the unsigned 32-bit integer at the address designated by PTR.

26.1.11 pointer-offset

### 26.1.17 pointer-s32-ref

```
[procedure] (pointer-s32-ref PTR)
```

Returns the signed 32-bit integer at the address designated by PTR.

### 26.1.18 pointer-f32-ref

```
[procedure] (pointer-f32-ref PTR)
```

Returns the 32-bit float at the address designated by PTR.

### 26.1.19 pointer-f64-ref

```
[procedure] (pointer-f64-ref PTR)
```

Returns the 64-bit double at the address designated by PTR.

### 26.1.20 pointer-u8-set!

```
[procedure] (pointer-u8-set! PTR N)
[procedure] (set! (pointer-u8-ref PTR) N)
```

Stores the unsigned byte N at the address designated by PTR.

### 26.1.21 pointer-s8-set!

```
[procedure] (pointer-s8-set! PTR N)
[procedure] (set! (pointer-s8-ref PTR) N)
```

Stores the signed byte N at the address designated by PTR.

### 26.1.22 pointer-u16-set!

```
[procedure] (pointer-u16-set! PTR N)
[procedure] (set! (pointer-u16-ref PTR) N)
```

Stores the unsigned 16-bit integer N at the address designated by PTR.

#### 26.1.23 pointer-s16-set!

```
[procedure] (pointer-s16-set! PTR N)
[procedure] (set! (pointer-s16-ref PTR) N)
```

Stores the signed 16-bit integer N at the address designated by PTR.

### 26.1.24 pointer-u32-set!

```
[procedure] (pointer-u32-set! PTR N)
[procedure] (set! (pointer-u32-ref PTR) N)
```

Stores the unsigned 32-bit integer N at the address designated by PTR.

### 26.1.25 pointer-s32-set!

```
[procedure] (pointer-s32-set! PTR N)
[procedure] (set! (pointer-s32-ref PTR) N)
```

Stores the 32-bit integer N at the address designated by PTR.

### 26.1.26 pointer-f32-set!

```
[procedure] (pointer-f32-set! PTR N)
[procedure] (set! (pointer-f32-ref PTR) N)
```

Stores the 32-bit floating-point number N at the address designated by PTR.

### 26.1.27 pointer-f64-set!

```
[procedure] (pointer-f64-set! PTR N)
[procedure] (set! (pointer-f64-ref PTR) N)
```

Stores the 64-bit floating-point number N at the address designated by PTR.

### 26.1.28 align-to-word

```
[procedure] (align-to-word PTR-OR-INT)
```

Accepts either a machine pointer or an integer as argument and returns a new pointer or integer aligned to the native word size of the host platform.

### 26.2 Tagged pointers

Tagged pointers are foreign pointer objects with an extra tag object.

### 26.2.1 tag-pointer

[procedure] (tag-pointer PTR TAG)

Creates a new tagged pointer object from the foreign pointer PTR with the tag TAG, which may an arbitrary Scheme object.

### 26.2.2 tagged-pointer?

[procedure] (tagged-pointer? X TAG)

Returns #t, if X is a tagged pointer object with the tag TAG (using an eq? comparison), or #f otherwise.

### 26.2.3 pointer-tag

[procedure] (pointer-tag PTR)

If PTR is a tagged pointer object, its tag is returned. If PTR is a normal, untagged foreign pointer object #f is returned. Otherwise an error is signalled.

### 26.3 Extending procedures with data

### 26.3.1 extend-procedure

[procedure] (extend-procedure PROCEDURE X)

Returns a copy of the procedure PROCEDURE which contains an additional data slot initialized to X. If PROCEDURE is already an extended procedure, then its data slot is changed to contain X and the same procedure is returned.

26.2 Tagged pointers 174

### 26.3.2 extended-procedure?

```
[procedure] (extended-procedure? PROCEDURE)
```

Returns #t if PROCEDURE is an extended procedure, or #f otherwise.

### 26.3.3 procedure-data

```
[procedure] (procedure-data PROCEDURE)
```

Returns the data object contained in the extended procedure PROCEDURE, or #f if it is not an extended procedure.

### 26.3.4 set-procedure-data!

```
[procedure] (set-procedure-data! PROCEDURE X)
```

Changes the data object contained in the extended procedure PROCEDURE to X.

### 26.4 Data in unmanaged memory

### 26.4.1 object-evict

```
[procedure] (object-evict X [ALLOCATOR])
```

Copies the object X recursively into the memory pointed to by the foreign pointer object returned by ALLOCATOR, which should be a procedure of a single argument (the number of bytes to allocate). The freshly copied object is returned. This facility allows moving arbitrary objects into static memory, but care should be taken when mutating evicted data: setting slots in evicted vector-like objects to non-evicted data is not allowed. It is possible to set characters/bytes in evicted strings or byte-vectors, though. It is advisable not to evict ports, because they might be mutated by certain file-operations. Object-evict is able to handle circular and shared structures, but evicted symbols are no longer unique: a fresh copy of the symbol is created,

```
(define x 'foo)
```

CHICKEN User's Manual - The User's Manual

The ALLOCATOR defaults to allocate.

### 26.4.2 object-evict-to-location

```
[procedure] (object-evict-to-location X PTR [LIMIT])
```

As object-evict but moves the object at the address pointed to by the machine pointer PTR. If the number of copied bytes exceeds the optional LIMIT then an error is signalled (specifically a composite condition of types exn and evict. The latter provides a limit property which holds the exceeded limit. Two values are returned: the evicted object and a new pointer pointing to the first free address after the evicted object.

### 26.4.3 object-evicted?

```
[procedure] (object-evicted? X)
```

Returns #t if X is a non-immediate evicted data object, or #f otherwise.

### 26.4.4 object-size

```
[procedure] (object-size X)
```

Returns the number of bytes that would be needed to evict the data object X.

### 26.4.5 object-release

```
[procedure] (object-release X [RELEASER])
```

Frees memory occupied by the evicted object X recursively. RELEASER should be a procedure of a single argument (a foreign pointer object to the static memory to be freed) and defaults to free.

### 26.4.6 object-unevict

```
[procedure] (object-unevict X [FULL])
```

26.4.1 object-evict

Copies the object X and nested objects back into the normal Scheme heap. Symbols are re-interned into the symbol table. Strings and byte-vectors are **not** copied, unless FULL is given and not **#f**.

#### 26.5 Locatives

A *locative* is an object that points to an element of a containing object, much like a *pointer* in low-level, imperative programming languages like *C*. The element can be accessed and changed indirectly, by performing access or change operations on the locative. The container object can be computed by calling the location->object procedure.

Locatives may be passed to foreign procedures that expect pointer arguments. The effect of creating locatives for evicted data (see object-evict) is undefined.

#### 26.5.1 make-locative

```
[procedure] (make-locative EXP [INDEX])
```

Creates a locative that refers to the element of the non-immediate object EXP at position INDEX. EXP may be a vector, pair, string, blob, SRFI-4 number-vector, or record. INDEX should be a fixnum. INDEX defaults to 0.

#### 26.5.2 make-weak-locative

```
[procedure] (make-weak-locative EXP [INDEX])
```

Creates a *weak* locative. Even though the locative refers to an element of a container object, the container object will still be reclaimed by garbage collection if no other references to it exist.

#### 26.5.3 locative?

```
[procedure] (locative? X)
```

Returns #t if X is a locative, or #f otherwise.

#### 26.5.4 locative-ref

```
[procedure] (locative-ref LOC)
```

Returns the element to which the locative LOC refers. If the containing object has been reclaimed by garbage collection, an error is signalled.

26.4.6 object-unevict

#### 26.5.5 locative-set!

```
[procedure] (locative-set! LOC X)
[procedure] (set! (locative-ref LOC) X)
```

Changes the element to which the locative LOC refers to X. If the containing object has been reclaimed by garbage collection, an error is signalled.

### 26.5.6 locativeobject

```
[procedure] (locative->object LOC)
```

Returns the object that contains the element referred to by LOC or #f if the container has been reclaimed by garbage collection.

### 26.6 Accessing toplevel variables

### 26.6.1 global-bound?

```
[procedure] (global-bound? SYMBOL)
```

Returns #t, if the global (toplevel) variable with the name SYMBOL is bound to a value, or #f otherwise.

### 26.6.2 global-ref

```
[procedure] (global-ref SYMBOL)
```

Returns the value of the global variable SYMBOL. If no variable under that name is bound, an error is signalled.

Note that it is not possible to access a toplevel binding with global-ref or global-set! if it has been hidden in compiled code via (declare (hide ...)), or if the code has been compiled in block mode.

### 26.6.3 global-set!

```
[procedure] (global-set! SYMBOL X)
[procedure] (set! (global-ref SYMBOL) X)
```

Sets the global variable named SYMBOL to the value X.

26.5.5 locative-set! 178

#### 26.7 Low-level data access

#### 26.7.1 block-ref

```
[procedure] (block-ref BLOCK INDEX)
```

Returns the contents of the INDEXth slot of the object BLOCK. BLOCK may be a vector, record structure, pair or symbol.

#### 26.7.2 block-set!

```
[procedure] (block-set! BLOCK INDEX X)
[procedure] (set! (block-ref BLOCK INDEX) X)
```

Sets the contents of the INDEXth slot of the object BLOCK to the value of X. BLOCK may be a vector, record structure, pair or symbol.

### 26.7.3 object-copy

```
[procedure] (object-copy X)
```

Copies X recursively and returns the fresh copy. Objects allocated in static memory are copied back into garbage collected storage.

#### 26.7.4 make-record-instance

(define (point-x p) (block-ref p 1))

26.7 Low-level data access 179

```
(define (point-x-set! p x) (block-set! p 1 x))
(define (point-y p) (block-ref p 2))
(define (point-y-set! p y) (block-set! p 1 y)) )
```

### 26.7.5 move-memory!

```
[procedure] (move-memory! FROM TO [BYTES [FROM-OFFSET [TO-OFFSET]])
```

Copies BYTES bytes of memory from FROM to T0. FROM and T0 may be strings, primitive byte-vectors, SRFI-4 byte-vectors (see: @ref{Unit srfi-4}), memory mapped files, foreign pointers (as obtained from a call to foreign-lambda, for example) or locatives. if BYTES is not given and the size of the source or destination operand is known then the maximal number of bytes will be copied. Moving memory to the storage returned by locatives will cause havoc, if the locative refers to containers of non-immediate data, like vectors or pairs.

The additional fourth and fifth argument specify starting offsets (in bytes) for the source and destination arguments.

### 26.7.6 number-of-bytes

```
[procedure] (number-of-bytes BLOCK)
```

Returns the number of bytes that the object BLOCK contains. BLOCK may be any non-immediate value.

#### 26.7.7 number-of-slots

```
[procedure] (number-of-slots BLOCK)
```

Returns the number of slots that the object BLOCK contains. BLOCK may be a vector, record structure, pair or symbol.

#### 26.7.8 record-instance?

```
[procedure] (record-instance? X)
```

Returns #t if X is an instance of a record type. See also: make-record-instance.

#### 26.7.9 recordvector

```
[procedure] (record->vector BLOCK)
```

Returns a new vector with the type and the elements of the record BLOCK.

#### 26.8 Procedure-call- and variable reference hooks

### 26.8.1 set-invalid-procedure-call-handler!

```
[procedure] (set-invalid-procedure-call-handler! PROC)
```

Sets an internal hook that is invoked when a call to an object other than a procedure is executed at runtime. The procedure PROC will in that case be called with two arguments: the object being called and a list of the passed arguments.

```
;;; Access sequence-elements as in ARC:

(set-invalid-procedure-call-handler!
   (lambda (proc args)
        (cond [(string? proc) (apply string-ref proc args)]
              [(vector? proc) (apply vector-ref proc args)]
              [else (error "call of non-procedure" proc)] ) ) )

("hello" 4) ==> #\0
```

This facility does not work in code compiled with the *unsafe* setting.

#### 26.8.2 unbound-variable-value

```
[procedure] (unbound-variable-value [X])
```

Defines the value that is returned for unbound variables. Normally an error is signalled, use this procedure to override the check and return X instead. To set the default behavior (of signalling an error), call unbound-variable-value with no arguments.

This facility does not work in code compiled with the *unsafe* setting.

### **26.9 Magic**

### 26.9.1 object-become!

```
[procedure] (object-become! ALIST)
```

26.7.9 recordvector

Changes the identity of the value of the car of each pair in ALIST to the value of the cdr. Both values may not be immediate (i.e. exact integers, characters, booleans or the empty list).

Note: this operation invokes a major garbage collection.

The effect of using object-become! on evicted data (see object-evict) is undefined.

### 26.9.2 mutate-procedure

```
[procedure] (mutate-procedure OLD PROC)
```

Replaces the procedure OLD with the result of calling the one-argument procedure PROC. PROC will receive a copy of OLD that will be identical in behaviour to the result of PROC:

#### ;;; Replace arbitrary procedure with tracing one:

Previous: Unit tcp

Next: Interface to external functions and variables

### 27 Interface to external functions and variables

- Accessing external objects
- Foreign type specifiers
- Embedding
- Callbacks
- <u>Locations</u>
- Other support procedures
- <u>C interface</u>

Previous: Supported language

Next: <u>chicken-setup</u>

### 28 Accessing external objects

### 28.1 foreign-code

```
[syntax] (foreign-code STRING ...)
```

Executes the embedded C/C++ code STRING ..., which should be a sequence of C statements, which are executed and return an unspecified result.

```
(foreign-code "doSomeInitStuff();") => #<unspecified>
```

Code wrapped inside foreign-code may not invoke callbacks into Scheme.

### 28.2 foreign-value

```
[syntax] (foreign-value STRING TYPE)
```

Evaluates the embedded C/C++ expression STRING, returning a value of type given in the foreign-type specifier TYPE.

```
(print (foreign-value "my_version_string" c-string))
```

### 28.3 foreign-declare

```
[syntax] (foreign-declare STRING ...)
```

Include given strings verbatim into header of generated file.

### 28.4 define-foreign-type

```
[syntax] (define-foreign-type NAME TYPE [ARGCONVERT [RETCONVERT]])
```

Defines an alias for TYPE with the name NAME (a symbol). TYPE may be a type-specifier or a string naming a C type. The namespace of foreign type specifiers is separate from the normal Scheme namespace. The optional arguments ARGCONVERT and RETCONVERT should evaluate to procedures that map argument- and result-values to a value that can be transformed to TYPE:

```
(define-foreign-type char-vector
  nonnull-c-string
  (compose list->string vector->list)
  (compose list->vector string->list) )
(define strlen
```

CHICKEN User's Manual - The User's Manual

Foreign type-definitions are only visible in the compilation-unit in which they are defined, so use include to use the same definitions in multiple files.

### 28.5 define-foreign-variable

```
[syntax] (define-foreign-variable NAME TYPE [STRING])
```

Defines a foreign variable of name NAME (a symbol). STRING should be the real name of a foreign variable or parameterless macro. If STRING is not given, then the variable name NAME will be converted to a string and used instead. All references and assignments (via set!) are modified to correctly convert values between Scheme and C representation. This foreign variable can only be accessed in the current compilation unit, but the name can be lexically shadowed. Note that STRING can name an arbitrary C expression. If no assignments are performed, then STRING doesn't even have to specify an Ivalue.

### 28.6 define-foreign-record

```
[syntax] (define-foreign-record NAME [DECL ...] SLOT ...)
```

Defines accessor procedures for a C structure definition. NAME should either be a symbol or a list of the form (TYPENAME FOREIGNNAME). If NAME is a symbol, then a C declaration will be generated that defines a C struct named struct NAME. If NAME is a list, then no struct declaration will be generated and FOREIGNNAME should name an existing C record type. A foreign-type specifier named NAME (or TYPENAME) will be defined as a pointer to the given C structure. A SLOT definition should be a list of one of the following forms:

CHICKEN User's Manual - The User's Manual

(TYPE SLOTNAME)

or

(TYPE SLOTNAME SIZE)

The latter form defines an array of SIZE elements of the type TYPE embedded in the structure. For every slot, the following accessor procedures will be generated:

#### 28.6.1 TYPENAME-SLOTNAME

(TYPENAME-SLOTNAME FOREIGN-RECORD-POINTER [INDEX])

A procedure of one argument (a pointer to a C structure), that returns the slot value of the slot SLOTNAME. If a SIZE has been given in the slot definition, then an additional argument INDEX is required that specifies the index of an array-element.

#### 28.6.2 TYPENAME-SLOTNAME-set!

(TYPENAME-SLOTNAME-set! FOREIGN-RECORD-POINTER [INXDEX] VALUE)

A procedure of two arguments (a pointer to a C structure) and a value, that sets the slot value of the slot SLOTNAME in the structure. If a SIZE has been given in the slot definition, then an additional argument INDEX is required for the array index.

If a slot type is of the form (const ...), then no setter procedure will be generated. Slots of the types (struct ...) or (union ...) are accessed as pointers to the embedded struct (or union) and no setter will be generated.

Additionally, special record-declarations (DECL ...) may be given, where each declaration consists of a list of the form (KEYWORD ARGUMENT ...). The available declarations are:

#### 28.6.3 constructor

(constructor: NAME)

Generate a constructor-procedure with no arguments that has the name NAME (a symbol) that returns a pointer to a structure of this type. The storage will be allocated with malloc(3).

#### 28.6.4 destructor

(destructor: NAME)

Generate a destructor function with the name NAME that takes a pointer to a structure of this type as its single argument and releases the storage with free(3). If the argument is #f, the destructor procedure does nothing.

#### 28.6.5 rename

```
(rename: EXPRESSION)
```

Evaluates EXPRESSION at compile-/macro-expansion-time and applies the result, which should be a procedure, to the string-representation of the name of each accessor-procedure generated. Another (or the same) string should be returned, which in turn is taken as the actual name of the accessor.

An example:

```
(require-for-syntax 'srfi-13)
(define-foreign-record Some Struct
  (rename: (compose string-downcase (cut string-translate <> " " "-")))
  (constructor: make-some-struct)
  (destructor: free-some-struct)
  (int xCoord)
  (int yCoord) )
will generate the following procedures:
(make-some-struct)
                                  --> C-POINTER
(free-some-struct C-POINTER)
(some-struct-xcoord C-POINTER)
                                 --> NUMBER
(some-struct-ycoord C-POINTER)
                                 --> NUMBER
(some-struct-xcoord-set! C-POINTER NUMBER)
(some-struct-ycoord-set! C-POINTER NUMBER)
```

### 28.7 define-foreign-enum

```
[syntax] (define-foreign-enum TYPENAME ITEM ...)
```

Defines a foreign type (as with define-foreign-type) that maps the elements of a C/C++ enum (or a enum-like list of constants) to and from a set of symbols.

TYPENAME specifies a foreign type that converts a symbol argument from the set ITEM ... into the appropriate enum value when passed as an argument to a foreign function.

A list of symbols passed as an argument will be combined using bitwise-ior. An empty list will be passed as 0 (zero). Results of the enum type are automatically converted into a scheme value (note that combinations are not supported in this case).

28.6.4 destructor 187

TYPENAME maybe a symbol or a list of the form (SCHEMENAME REALTYPE

[DEFAULT-SCHEME-VALUE]), where REALTYPE designates the native type used. The default native type is "TYPENAME". The DEFAULT-SCHEME-VALUE overrides the default result of mapping from the native type; i.e. when no such mapping exists. When supplied the form is used unquoted, otherwise the result is '().

ITEM is a symbol or a list of the form (SCHEMENAME REALTYPE [SCHEME-VALUE]), where REALTYPE designates the native type used. The default native type is "ITEM". The SCHEME-VALUE overrides the result of mapping from the native type. When supplied the form is used unquoted, otherwise the SCHEMENAME symbol is returned.

Additionally two procedures are defined named SCHEMENAME->number and number->SCHEMENAME. SCHEMENAME->number takes one argument and converts a symbol (or a list of symbols) into its numeric value. number->SCHEMENAME takes one argument and converts a numeric value into its scheme value.

Note that the specification of a scheme value override means the mapping may not be closed! (number->SCHEMENAME (SCHEMENAME->number SCHEMENAME)) may not equal SCHEMENAME.

Here a heavily contrived example:

```
#>
enum foo { a_foo = 4, b_foo, c_foo };
enum foo bar(enum foo x) { printf("%d\n", x); return b_foo; }
<#

(define-foreign-enum (foo (enum "foo")) a_foo b_foo (c c_foo))

(define bar (foreign-lambda foo bar foo))

(pp (bar '()))
(pp (bar 'a_foo))
(pp (bar '(b_foo c)))</pre>
```

### 28.8 foreign-lambda

```
[syntax] (foreign-lambda RETURNTYPE NAME ARGTYPE ...)
```

Represents a binding to an external routine. This form can be used in the position of an ordinary lambda expression. NAME specifies the name of the external procedure and should be a string or a symbol.

### 28.9 foreign-lambda\*

```
[syntax] (foreign-lambda* RETURNTYPE ((ARGTYPE VARIABLE) ...) STRING ...)
```

Similar to foreign-lambda, but instead of generating code to call an external function, the body of the C procedure is directly given in STRING . . . :

```
(define my-strlen
  (foreign-lambda* int ((c-string str))
    "int n = 0; while(*(str++)) ++n; C_return(n);") )
```

```
(my-strlen "one two three") ==> 13
```

For obscure technical reasons you should use the C\_return macro instead of the normal return statement to return a result from the foreign lambda body as some cleanup code has to be run before execution commences in the calling code.

### 28.10 foreign-safe-lambda

```
[syntax] (foreign-safe-lambda RETURNTYPE NAME ARGTYPE ...)
```

This is similar to foreign-lambda, but also allows the called function to call Scheme functions and allocate Scheme data-objects. See <u>Callbacks</u>.

### 28.11 foreign-safe-lambda\*

```
[syntax] (foreign-safe-lambda* RETURNTYPE ((ARGTYPE VARIABLE)...) STRING ...)
```

This is similar to foreign-lambda\*, but also allows the called function to call Scheme functions and allocate Scheme data-objects. See <u>Callbacks</u>.

### 28.12 foreign-primitive

```
[syntax] (foreign-primitive [RETURNTYPE] ((ARGTYPE VARIABLE) ...) STRING ...)
```

This is also similar to foreign-lambda\* but the code will be executed in a *primitive* CPS context, which means it will not actually return, but call it's continuation on exit. This means that code inside this form may allocate Scheme data on the C stack (the *nursery*) with C\_alloc (see below). If the RETURNTYPE is omitted it defaults to void. You can return multiple values inside the body of the foreign-primitive form by calling this C function:

```
C values(N + 2, C SCHEME UNDEFINED, C k, X1, ...)
```

where N is the number of values to be returned, and X1, ... are the results, which should be Scheme data objects. When returning multiple values, the return-type should be omitted.

Previous: Interface to external functions and variables

Next: Foreign type specifiers

28.9 foreign-lambda\*

### 29 Foreign type specifiers

Here is a list of valid foreign type specifiers:

### 29.1 scheme-object

An arbitrary Scheme data object (immediate or non-immediate).

#### 29.2 bool

As argument: any value (#f is false, anything else is true). As result: anything different from 0 and the NULL-pointer is #t.

### 29.3 byte unsigned-byte

A byte.

### 29.4 char unsigned-char

A character.

### 29.5 short unsigned-short

A short integer number.

### 29.6 int unsigned-int int32 unsigned-int32

An small integer number in fixnum range (at least 30 bit).

## 29.7 integer unsigned-integer integer32 unsigned-integer32 integer64

Either a fixnum or a flonum in the range of a (unsigned) machine int or with 32/64 bit width.

### 29.8 long unsigned-long

Either a fixnum or a flonum in the range of a (unsigned) machine *long* or with 32 bit width.

#### 29.9 float double

A floating-point number. If an exact integer is passed as an argument, then it is automatically converted to a float.

#### 29.10 number

A floating-point number. Similar to double, but when used as a result type, then either an exact integer or a floating-point number is returned, depending on whether the result fits into an exact integer or not.

### **29.11 symbol**

A symbol, which will be passed to foreign code as a zero-terminated string. When declared as the result of foreign code, the result should be a string and a symbol with the same name will be interned in the symbol table (and returned to the caller).

### 29.12 scheme-pointer

An untyped pointer to the contents of a non-immediate Scheme object (not allowed as return type). The value #f is also allowed and is passed as a NULL pointer. Don't confuse this type with (pointer ...) which means something different (a machine-pointer object).

### 29.13 nonnull-scheme-pointer

As pointer, but guaranteed not to be #f. Don't confuse this type with (nonnull-pointer ...) which means something different (a machine-pointer object).

### 29.14 c-pointer

An untyped operating-system pointer or a locative. The value #f is also allowed and is passed as a NULL pointer. If uses as the type of a return value, a NULL pointer will be returned as #f.

### 29.15 nonnull-c-pointer

As c-pointer, but guaranteed not to be #f/NULL.

### 29.16 [nonnull-] blob

A blob object, passed as a pointer to its contents. Arguments of type blob may optionally be #f, which is passed as a NULL pointer. This is not allowed as a return type.

# 29.17 [nonnull-] u8vector [nonnull-] u16vector [nonnull-] u32vector [nonnull-] s8vector [nonnull-] s16vector [nonnull-] s32vector [nonnull-] f64vector

A SRFI-4 number-vector object, passed as a pointer to its contents. These type specifiers are not allowed as return types.

### 29.18 c-string

A C string (zero-terminated). The value #f is also allowed and is passed as a NULL pointer. If uses as the type of a return value, a NULL pointer will be returned as #f. Note that the string is copied (with a zero-byte appended) when passed as an argument to a foreign function. Also a return value of this type is copied into garbage collected memory.

### 29.19 nonnull-c-string

As c-string, but guaranteed not to be #f/NULL.

29.14 c-pointer 192

### 29.20 [nonnull-] c-string\*

Similar to [nonnull-]c-string, but if used as a result-type, the pointer returned by the foreign code will be freed (using the C-libraries free(1)) after copying. This type specifier is not valid as a result type for callbacks defined with define-external.

### 29.21 [nonnull-] unsigned-c-string[\*]

Same as c-string, but maps to the unsigned char \* C type.

### 29.22 c-string-list

Expects a pointer to a list of C strings teminated by a NULL pointer and returns a list of strings. Only valid as a result type of non-callback functions.

### 29.23 c-string-list\*

Similar to c-string-list but releases the storage of each string and the pointer array using free(1).

#### 29.24 void

Specifies an undefined return value. Not allowed as argument type.

### 29.25 (const TYPE)

The foreign type TYPE with an additional const specifier.

### 29.26 (enum NAME)

An enumeration type. Handled internally as an integer.

### 29.27 (pointer TYPE) (c-pointer TYPE)

An operating-system pointer or a locative to an object of TYPE.

### 29.28 (nonnull-pointer TYPE) (nonnull-c-pointer TYPE)

As (pointer TYPE), but guaranteed not to be #f/NULL.

### 29.29 (ref TYPE)

A C++ reference type. Reference types are handled the same way as pointers inside Scheme code.

### 29.30 (struct NAME)

A struct of the name NAME, which should be a string. Structs can not be directly passed as arguments to foreign function, neither can they be result values. Pointers to structs are allowed, though.

### 29.31 (template TYPE ARGTYPE ...)

A C++ template type. For example vector<int> would be specified as (template "vector" int). Template types can not be directly passed as arguments or returned as results.

### 29.32 (union NAME)

A union of the name NAME, which should be a string. Unions can not be directly passed as arguments to foreign function, neither can they be result values. Pointers to unions are allowed, though.

### 29.33 (instance CNAME SCHEMECLASS)

A pointer to a C++ class instance. CNAME should designate the name of the C++ class, and SCHEMECLASS should be the class that wraps the instance pointer. Normally SCHEMECLASS should be a subclass of <c++-object>.

# 29.34 (instance-ref CNAME SCHEMECLASS)

A reference to a C++ class instance.

# 29.35 (function RESULTTYPE (ARGUMENTTYPE1 ... [...]) [CALLCONV])

A function pointer. CALLCONV specifies an optional calling convention and should be a string. The meaning of this string is entirely platform dependent. The value #f is also allowed and is passed as a NULL pointer.

# 29.36 Mappings

Foreign types are mapped to C types in the following manner:

bool int

[unsigned-]char[unsigned] char[unsigned-]short[unsigned] short[unsigned-]int[unsigned] int[unsigned-]integer[unsigned] int[unsigned-]long[unsigned] long

float float double double number double [nonnull-]pointer void \* [nonnull-]c-pointer void \*

[nonnull-]blob unsigned char \*
[nonnull-]u8vector unsigned char \*

[nonnull-]s8vector char \*

[nonnull-]u16vector unsigned short \*

[nonnull-]s16vectorshort \*[nonnull-]u32vectoruint32\_t \*[nonnull-]s32vectorint32\_t \*[nonnull-]f32vectorfloat \*[nonnull-]f64vectordouble \*[nonnull-]c-stringchar \*

[nonnull-]unsigned-c-string unsigned char \*

c-string-list char \*\*
symbol char \*
void void
([nonnull-]pointer TYPE) TYPE \*
(enum NAME) enum NAME
(struct NAME) struct NAME

### CHICKEN User's Manual - The User's Manual

 $\begin{array}{ll} \text{(ref TYPE)} & \text{TYPE \&} \\ \text{(template T1 T2 ...)} & \text{T1<T2, ...>} \\ \text{(union NAME)} & \text{union NAME} \\ \end{array}$ 

(function RTYPE (ATYPE ...) [CALLCONV]) [CALLCONV] RTYPE (\*)(ATYPE, ...)

(instance CNAME SNAME) CNAME \*
(instance-ref CNAME SNAME) CNAME &

Previous: Accessing external objects

Next: Embedding

29.36 Mappings 196

# 30 Embedding

Compiled Scheme files can be linked with C code, provided the Scheme code was compiled in *embedded* mode by passing -DC\_EMBEDDED to the C compiler (this will disable generation of a main() function). CSC will do this, when given the -embedded option. Alternatively pass -embedded to CSC.

The following C API is available:

# 30.1 CHICKEN parse command line

[C function] void CHICKEN\_parse\_command\_line (int argc, char \*argv[], int \*heap

Parse the programs command-line contained in argc and argv and return the heap-, stack- and symbol table limits given by runtime options of the form -:..., or choose default limits. The library procedure argv can access the command-line only if this function has been called by the containing application.

# 30.2 CHICKEN\_initialize

[C function] int CHICKEN\_initialize (int heap, int stack, int symbols, void \*to

Initializes the Scheme execution context and memory. heap holds the number of bytes that are to be allocated for the secondary heap. <code>stack</code> holds the number of bytes for the primary heap. <code>symbols</code> contains the size of the symbol table. Passing 0 to one or more of these parameters will select a default size. <code>toplevel</code> should be a pointer to the toplevel entry point procedure. You should pass <code>C\_toplevel</code> here. In any subsequent call to <code>CHICKEN\_run</code> you can simply pass <code>NULL</code>. Calling this function more than once has no effect. If enough memory is available and initialization was successful, then 1 is returned, otherwise this function returns 0.

# 30.3 CHICKEN run

[C function] C word CHICKEN run (void \*toplevel)

Starts the Scheme program. Call this function once to execute all toplevel expressions in your compiled Scheme program. If the runtime system was not initialized before, then CHICKEN\_initialize is called with default sizes. toplevel is the toplevel entry-point procedure, you usually pass C\_toplevel here. The result value is the continuation that can be used to re-invoke the Scheme code from the point after it called return-to-host (see below).

If you just need a Scheme interpreter, you can also pass CHICKEN\_default\_toplevel as the toplevel procedure, which just uses the default library units.

Once CHICKEN\_run has been called, Scheme code is executing until all toplevel expressions have been evaluated or until return-to-host is called inside the Scheme program.

30 Embedding

### 30.4 return-to-host

[procedure] (return-to-host)

Exits the Scheme code and returns to the invoking context that called CHICKEN\_run or CHICKEN\_continue.

After return-to-host has been executed and once CHICKEN\_run returns, you can invoke callbacks which have been defined with define-external. The eval library unit also provides *boilerplate* callbacks, that simplify invoking Scheme code embedded in a C or C++ application a lot.

# 30.5 CHICKEN eval

[C macro] int CHICKEN\_eval (C\_word exp, C\_word \*result)

Evaluates the Scheme object passed in exp, writing the result value to result. The return value is 1 if the operation succeeded, or 0 if an error occurred. Call CHICKEN\_get\_error\_message to obtain a description of the error.

# 30.6 CHICKEN\_eval\_string

[C macro] int CHICKEN eval string (char \*str, C word \*result)

Evaluates the Scheme expression passed in the string str, writing the result value to result.

# 30.7 CHICKEN\_eval\_to\_string

[C macro] int CHICKEN eval to string (C word exp, char \*result, int size)

Evaluates the Scheme expression passed in exp, writing a textual representation of the result into result. size should specify the maximal size of the result string.

# 30.8 CHICKEN\_eval\_string\_to\_string

[C macro] int CHICKEN\_eval\_string\_to\_string (char \*str, char \*result, int size)

Evaluates the Scheme expression passed in the string str, writing a textual representation of the result into result. size should specify the maximal size of the result string.

30.4 return-to-host

# 30.9 CHICKEN\_apply

```
[C macro] int CHICKEN apply (C word func, C word args, C word *result)
```

Applies the procedure passed in func to the list of arguments args, writing the result value to result.

# 30.10 CHICKEN\_apply\_to\_string

```
[C macro] int CHICKEN_apply_to_string (C_word func, C_word args, char *result,
```

Applies the procedure passed in func to the list of arguments args, writing a textual representation of the result into result.

# 30.11 CHICKEN read

```
[C macro] int CHICKEN read (char *str, C word *result)
```

Reads a Scheme object from the string str, writing the result value to result.

# 30.12 CHICKEN\_load

```
[C macro] int CHICKEN load (char *filename)
```

Loads the Scheme file filename (either in source form or compiled).

# 30.13 CHICKEN\_get\_error\_message

```
[C macro] void CHICKEN get error message (char *result, int size)
```

Returns a textual description of the most recent error that occurred in executing embedded Scheme code.

# 30.14 CHICKEN yield

```
[C macro] int CHICKEN yield (int *status)
```

If threads have been spawned during earlier invocations of embedded Scheme code, then this function will run the next scheduled thread for one complete time-slice. This is useful, for example, inside an *idle* handler in a GUI application with background Scheme threads. Note that the <code>srfi-18</code> library unit has to be linked in for this.

199

30.9 CHICKEN\_apply

```
An example:
% cat x.scm
;;; x.scm
(define (bar x) (gc) (* x x))
(define-external (baz (int i)) double
  (sqrt i))
(return-to-host)
% cat y.c
/* y.c */
#include <chicken.h>
#include <assert.h>
extern double baz(int);
int main() {
  char buffer[ 256 ];
  int status;
 C word val = C SCHEME UNDEFINED;
 C word *data[ 1 ];
 data[ 0 ] = &val;
  CHICKEN run(C toplevel);
  status = CHICKEN read("(bar 99)", &val);
  assert(status);
 C gc protect(data, 1);
  printf("data: %08x\n", val);
  status = CHICKEN eval string to string("(bar)", buffer, 255);
  assert(!status);
  CHICKEN get error message(buffer, 255);
  printf("ouch: %s\n", buffer);
  status = CHICKEN eval string to string("(bar 23)", buffer, 255);
  assert(status);
  printf("-> %s\n", buffer);
  printf("data: %08x\n", val);
  status = CHICKEN eval to string(val, buffer, 255);
  assert(status);
  printf("-> %s\n", buffer);
  printf("->` %g\n", baz(22));
  return 0;
```

```
CHICKEN User's Manual - The User's Manual
}
% csc x.scm y.c -embedded
```

It is also possible to re-enter the computation following the call to return-to-host by calling CHICKEN continue:

# 30.15 CHICKEN continue

```
[C function] C_word CHICKEN_continue (C_word k)
```

Re-enters Scheme execution. k is the continuation received from the previous invocation of CHICKEN\_run or CHICKEN\_continue. When return-to-host is called again, this function returns another continuation that can be used to restart again.

If you invoke callbacks prior to calling CHICKEN\_continue, make sure that the continuation is not reclaimed by garbage collection. This can be avoided by using C\_gc\_protect or gc-roots.

Another example:

```
% cat x.scm
(require-extension srfi-18)
(define m (make-mutex))
(define (t)
  (mutex-lock! m)
  (thread-sleep! 1)
  (print (thread-name (current-thread)))
  (mutex-unlock! m)
  (t))
(thread-start! (make-thread t 'PING!))
(thread-start! (make-thread t 'PONG!))
(let loop ()
  (return-to-host)
  (thread-yield!)
  (loop) )
% cat y.c
#include <chicken.h>
int main()
  C word k = CHICKEN run(C toplevel);
  for(;;)
    k = CHICKEN continue(k);
  return 0;
}
```

```
% csc x.scm y.c -embedded
```

It is advisable not to mix repeated uses of CHICKEN\_continue/return-to-host (as in the example above) with callbacks. Once return-to-host is invoked, the runtime system and any Scheme code executed prior to the invocation is initialized and can be conveniently used via callbacks.

A simpler interface For handling GC-safe references to Scheme data are the so called *gc-roots*:

# 30.16 CHICKEN\_new\_gc\_root

```
[C function] void* CHICKEN_new_gc_root ()
```

Returns a pointer to a *GC root*, which is an object that holds a reference to a Scheme value that will always be valid, even after a garbage collection. The content of the gc root is initialized to an unspecified value.

# 30.17 CHICKEN\_delete\_gc\_root

[C function] void CHICKEN delete gc root (void \*root)

Deletes the gc root.

# 30.18 CHICKEN\_gc\_root\_ref

```
[C macro] C word CHICKEN gc root ref (void *root)
```

Returns the value stored in the gc root.

# 30.19 CHICKEN\_gc\_root\_set

```
[C macro] void CHICKEN gc root set (void *root, C word value)
```

Sets the content of the GC root to a new value.

Sometimes it is handy to access global variables from C code:

# 30.20 CHICKEN\_global\_lookup

[C function] void\* CHICKEN global lookup (char \*name)

Returns a GC root that holds the global variable with the name name. If no such variable exists, NULL is returned.

# 30.21 CHICKEN global ref

[C function] C\_word CHICKEN\_global\_ref (void \*global)

Returns the value of the global variable referenced by the GC root global.

# 30.22 CHICKEN\_global\_set

[C function] void CHICKEN global set (void \*global, C word value)

Sets the value of the global variable referenced by the GC root global to value.

Previous: Foreign type specifiers

Next: Callbacks

### 31 Callbacks

To enable an external C function to call back to Scheme, the form foreign-safe-lambda (or foreign-safe-lambda\*) has to be used. This generates special code to save and restore important state information during execution of C code. There are two ways of calling Scheme procedures from C: the first is to invoke the runtime function C\_callback with the closure to be called and the number of arguments. The second is to define an externally visible wrapper function around a Scheme procedure with the define-external form.

Note: the names of all functions, variables and macros exported by the CHICKEN runtime system start with C\_. It is advisable to use a different naming scheme for your own code to avoid name clashes. Callbacks (defined by define-external) do not capture the lexical environment.

Non-local exits leaving the scope of the invocation of a callback from Scheme into C will not remove the C call-frame from the stack (and will result in a memory leak).

### 31.1 define-external

```
[syntax] (define-external [QUALIFIERS] (NAME (ARGUMENTTYPE1 VARIABLE1) ...) RET [syntax] (define-external NAME TYPE [INIT])
```

The first form defines an externally callable Scheme procedure. NAME should be a symbol, which, when converted to a string, represents a legal C identifier. ARGUMENTTYPE1 ... and RETURNTYPE are foreign type specifiers for the argument variables VAR1 ... and the result, respectively. QUALIFIERS is an optional qualifier for the foreign procedure definition, like stdcall.

```
(define-external (foo (c-string x)) int (string-length x))
```

The second form of define-external can be used to define variables that are accessible from foreign code. It declares a global variable named by the symbol NAME that has the type TYPE. INIT can be an arbitrary expression that is used to initialize the variable. NAME is accessible from Scheme just like any other foreign variable defined by define-foreign-variable.

```
(define-external foo int 42)
((foreign-lambda* int ()
  "C return(foo);")) ==> 42
```

**Note:** don't be tempted to assign strings or bytevectors to external variables. Garbage collection moves those objects around, so it is very bad idea to assign pointers to heap-data. If you have to do so, then copy the data object into statically allocated memory (for example by using <code>object-evict</code>).

Results of type scheme-object returned by define-external are always allocated in the secondary heap, that is, not in the stack.

31 Callbacks 204

# 31.2 C callback

```
[C function] C word C callback (C word closure, int argc)
```

This function can be used to invoke the Scheme procedure closure. argc should contain the number of arguments that are passed to the procedure on the temporary stack. Values are put onto the temporary stack with the C save macro.

# 31.3 C callback adjust stack limits

```
[C function] void C_callback_adjust_stack_limits (C_word *ptr)
```

The runtime-system uses the stack as a special allocation area and internally holds pointers to estimated limits to distinguish between Scheme data objects inside the stack from objects outside of it. If you invoke callbacks at wildly differing stack-levels, these limits may shift from invocation to invocation. Callbacks defined with define-external will perform appropriate adjustments automatically, but if you invoke C\_callback manually, you should perform a C\_callback\_adjust\_stack\_limits to make sure the internal limits are set properly. ptr should point to some data object on the stack. The call will make sure the limits are adjusted so that the value pointed to by ptr is located in the stack.

Previous: Embedding

**Next:** Locations

31.2 C\_callback 205

### 32 Locations

It is also possible to define variables containing unboxed C data, so called *locations*. It should be noted that locations may only contain simple data, that is: everything that fits into a machine word, and double-precision floating point values.

### 32.1 define-location

```
[syntax] (define-location NAME TYPE [INIT])
```

Identical to (define-external NAME TYPE [INIT]), but the variable is not accessible from outside of the current compilation unit (it is declared static).

### 32.2 let-location

```
[syntax] (let-location ((NAME TYPE [INIT]) ...) BODY ...)
```

Defines a lexically bound location.

### 32.3 location

```
[syntax] (location NAME)
[syntax] (location X)
```

This form returns a pointer object that contains the address of the variable NAME. If the argument to location is not a location defined by define-location, define-external or let-location, then

```
(location X)
```

is essentially equivalent to

```
(make-locative X)
```

(See the manual chapter or locatives for more information about locatives.

Note that (location X) may be abbreviated as #\$X.

```
(define-external foo int)
((foreign-lambda* void (((pointer int) ip)) "*ip = 123;")
  (location foo))
foo
```

This facility is especially useful in situations, where a C function returns more than one result value:

#>

32 Locations 206

#### CHICKEN User's Manual - The User's Manual

```
#include <math.h>
<#

(define modf
   (foreign-lambda double "modf" double (pointer double)) )

(let-location ([i double])
   (let ([f (modf 1.99 (location i))])
        (print "i=" i ", f=" f) ) )</pre>
```

See <u>location and c-string\*</u> for a tip on returning a **c-string\*** type.

location returns a value of type c-pointer, when given the name of a callback-procedure defined with define-external.

Previous: Callbacks

Next: Other support procedures

32.3 location 207

# 33 Other support procedures

# 33.1 argc+argv

[procedure] (argc+argv)

Returns two values: an integer and a foreign-pointer object representing the argc and argv arguments passed to the current process.

Previous: Locations

Next: C interface

### 34 C interface

The following functions and macros are available for C code that invokes Scheme or foreign procedures that are called by Scheme:

# 34.1 C\_save

```
[C macro] void C save (C word x) :
```

Saves the Scheme data object x on the temporary stack.

# 34.2 C\_restore

```
[C macro] void C restore
```

Pops and returns the topmost value from the temporary stack.

# 34.3 C fix

```
[C macro] C_word C_fix (int integer)
```

# 34.4 C make character

```
[C macro] C word C make character (int char code)
```

# 34.5 C\_SCHEME\_END\_OF\_LIST

```
[C macro] C SCHEME END OF LIST
```

# 34.6 C\_word C\_SCHEME\_END\_OF\_FILE

```
[C macro] C_SCHEME_END_OF_FILE
```

34 C interface 209

# 34.7 C\_word C\_SCHEME\_FALSE

[C macro] C\_SCHEME\_FALSE

# 34.8 C\_word C\_SCHEME\_TRUE

[C macro] C\_SCHEME\_TRUE

These macros return immediate Scheme data objects.

# 34.9 C string

[C function] C\_word C\_string (C\_word \*\*ptr, int length, char \*string)

# 34.10 C string2

[C function] C\_word C\_string2 (C\_word \*\*ptr, char \*zero\_terminated\_string)

# 34.11 C\_intern2

[C function] C\_word C\_intern2 (C\_word \*\*ptr, char \*zero\_terminated\_string)

# 34.12 C intern3

[C function] C\_word C\_intern3 (C\_word \*\*ptr, char \*zero\_terminated\_string, C\_wo

# 34.13 C\_pair

[C function] C\_word C\_pair (C\_word \*\*ptr, C\_word car, C\_word cdr)

### 34.14 C flonum

```
[C function] C word C flonum (C word **ptr, double number)
```

# 34.15 **C\_int\_to\_num**

```
[C function] C_word C_int_to_num (C_word **ptr, int integer)
```

# 34.16 C\_mpointer

```
[C function] C word C mpointer (C word **ptr, void *pointer)
```

# 34.17 C vector

```
[C function] C_word C_vector (C_word **ptr, int length, ...)
```

### 34.18 C list

```
[C function] C word C list (C word **ptr, int length, ...)
```

These functions allocate memory from ptr and initialize a fresh data object. The new data object is returned. ptr should be the **address** of an allocation pointer created with C\_alloc.

# 34.19 C alloc

```
[C macro] C word* C alloc (int words)
```

Allocates memory from the C stack (C\_alloc) and returns a pointer to it. words should be the number of words needed for all data objects that are to be created in this function. Note that stack-allocated data objects have to be passed to Scheme callback functions, or they will not be seen by the garbage collector. This is really only usable for callback procedure invocations, make sure not to use it in normal code, because the allocated memory will be re-used after the foreign procedure returns. When invoking Scheme callback procedures a minor garbage collection is performed, so data allocated with C\_alloc will already have moved to a safe place.

Note that C\_alloc is really just a wrapper around alloca, and can also be simulated by declaring a stack-allocated array of C words:

34.14 C flonum 211

# 34.20 C SIZEOF LIST

[C macro] int C\_SIZEOF\_LIST (int length)

# 34.21 C SIZEOF STRING

[C macro] int C\_SIZEOF\_STRING (int length)

# 34.22 C\_SIZEOF\_VECTOR

[C macro] int C\_SIZEOF\_VECTOR (int length)

# 34.23 C\_SIZEOF\_INTERNED\_SYMBOL

[C macro] int C\_SIZEOF\_INTERNED\_SYMBOL (int length)

# 34.24 C\_SIZEOF\_PAIR

[C macro] int C SIZEOF PAIR

# 34.25 C\_SIZEOF\_FLONUM

[C macro] int C\_SIZEOF\_FLONUM

# 34.26 C SIZEOF POINTER

[C macro] int C SIZEOF POINTER

# 34.27 C\_SIZEOF\_LOCATIVE

[C macro] int C\_SIZEOF\_LOCATIVE

# 34.28 C\_SIZEOF\_TAGGED\_POINTER

```
[C macro] int C SIZEOF TAGGED POINTER
```

These are macros that return the size in words needed for a data object of a given type.

# 34.29 C character code

```
[C macro] int C_character_code (C_word character)
```

# 34.30 C unfix

```
[C macro] int C unfix (C word fixnum)
```

# 34.31 C flonum magnitude

```
[C macro] double C flonum magnitude (C word flonum)
```

# 34.32 C\_c\_string

```
[C function] char* C_c_string (C_word string)
```

# 34.33 C\_num\_to\_int

```
[C function] int C_num_to_int (C_word fixnum_or_flonum)
```

# 34.34 C\_pointer\_address

```
[C function] void* C pointer address (C word pointer)
```

These macros and functions can be used to convert Scheme data objects back to C data. Note that  $C_c_string()$  returns a pointer to the character buffer of the actual Scheme object and is not zero-terminated.

### 34.35 C header size

```
[C macro] int C_header_size (C_word x)
```

### 34.36 C header bits

```
[C macro] int C_header_bits (C_word x)
```

Return the number of elements and the type-bits of the non-immediate Scheme data object x.

# 34.37 C block item

```
[C macro] C word C block item (C word x, int index)
```

This macro can be used to access slots of the non-immediate Scheme data object x. index specifies the index of the slot to be fetched, starting at 0. Pairs have 2 slots, one for the **car** and one for the **cdr**. Vectors have one slot for each element.

# 34.38 C u i car

```
[C macro] C word C u i car (C word x)
```

# 34.39 C\_u\_i\_cdr

```
[C macro] C_word C_u_i_cdr (C_word x)
```

Aliases for  $C_block_item(x, 0)$  and  $C_block_item(x, 1)$ , respectively.

# 34.40 C data pointer

```
[C macro] void* C data pointer (C word x)
```

Returns a pointer to the data-section of a non-immediate Scheme object.

34.35 C\_header\_size

# 34.41 C make header

```
[C macro] C word C make header (C word bits, C word size)
```

A macro to build a Scheme object header from its bits and size parts.

### 34.42 C mutate

```
[C function] C word C mutate (C word *slot, C word val)
```

Assign the Scheme value val to the location specified by slot. If the value points to data inside the nursery (the first heap-generation), then the garbage collector will remember to handle the data appropriately. Assigning nursery-pointers directly will otherwise result in lost data. Note that no copying takes place at the moment when C mutate is called, but later - at the next (minor) garbage collection.

# 34.43 C\_symbol\_value

```
[C macro] C word C symbol value (C word symbol)
```

Returns the global value of the variable with the name symbol. If the variable is unbound C\_SCHEME\_UNBOUND is returned. You can set a variable's value with C\_mutate(&C\_symbol\_value(SYMBOL), VALUE).

# 34.44 C\_gc\_protect

```
[C function] void C gc protect (C word *ptrs[], int n)
```

Registers n variables at address ptrs to be garbage collection roots. The locations should not contain pointers to data allocated in the nursery, only immediate values or pointers to heap-data are valid. Any assignment of potential nursery data into a root-array should be done via C\_mutate(). The variables have to be initialized to sensible values before the next garbage collection starts (when in doubt, set all locations in ptrs to C\_SCHEME\_UNDEFINED) C\_gc\_protect may not called before the runtime system has been initialized (either by CHICKEN initialize, CHICKEN run or CHICKEN invoke.

For a slightly simpler interface to creating and using GC roots see CHICKEN new gc root.

# 34.45 C\_gc\_unprotect

```
[C function] void C gc unprotect (int n)
```

Removes the last n registered variables from the set of root variables.

# 34.46 C\_post\_gc\_hook

```
[C Variable] void (*C post gc hook)(int mode)
```

If not NULL, the function pointed to by this variable will be called after each garbage collection with a flag indicating what kind of collection was performed (either  $\theta$  for a minor collection or 1 for a major collection). Minor collections happen very frequently, so the hook function should not consume too much time. The hook function may not invoke Scheme callbacks.

An example:

```
% cat foo.scm
#>
extern int callout(int, int, int);
(define callout (foreign-safe-lambda int "callout" int int int))
(define-external (callin (scheme-object xyz)) int
  (print "This is 'callin': " xyz)
  123)
(print (callout 1 2 3))
% cat bar.c
#include <stdio.h>
#include "chicken.h"
extern int callout(int, int, int);
extern int callin(C word x);
int callout(int x, int y, int z)
  C word *ptr = C alloc(C SIZEOF LIST(3));
  C word lst;
  printf("This is 'callout': %d, %d, %d\n", x, y, z);
  lst = C_{\text{list}(\&ptr, 3, C_{\text{fix}(x), C_{\text{fix}(y), C_{\text{fix}(z))}}}
  return callin(lst); /* Note: `callin' will have GC'd the data in `ptr' */
}
% csc foo.scm bar.c -o foo
% foo
This is 'callout': 1, 2, 3
This is 'callin': (1 2 3)
123
```

#### **Notes:**

Scheme procedures can call C functions, and C functions can call Scheme procedures, but for every pending C stack frame, the available size of the first heap generation (the *nursery*) will be decreased, because the C stack is identical to the nursery. On systems with a small nursery this might result in thrashing, since the C code between the invocation of C from Scheme and the actual calling back to Scheme might build up several stack-frames or allocates large amounts of stack data. To prevent this it is advisable to increase the default

#### CHICKEN User's Manual - The User's Manual

nursery size, either when compiling the file (using the -nursery option) or when running the executable (using the -: S runtime option).

Calls to Scheme/C may be nested arbitrarily, and Scheme continuations can be invoked as usual, but keep in mind that C stack frames will not be recovered, when a Scheme procedure call from C does not return normally.

When multiple threads are running concurrently, and control switches from one thread to another, then the continuation of the current thread is captured and saved. Any pending C stack frame still active from a callback will remain on the stack until the threads is re-activated again. This means that in a multithreading situation, when C callbacks are involved, the available nursery space can be smaller than expected. So doing many nested SchemeCScheme calls can reduce the available memory up to the point of thrashing. It is advisable to have only a single thread with pending C stack-frames at any given time.

Pointers to Scheme data objects should not be stored in local or global variables while calling back to Scheme. Any Scheme object not passed back to Scheme will be reclaimed or moved by the garbage collector.

Calls from C to Scheme are never tail-recursive.

Continuations captured via call-with-current-continuation and passed to C code can be invoked like any other Scheme procedure.

Previous: Other support procedures

Next: chicken-setup

# 35 chicken-setup

### 35.1 Extension libraries

Extension libraries (*eggs*) are extensions to the core functionality provided by the basic CHICKEN system, to be built and installed separately. The mechanism for loading compiled extensions is based on dynamically loadable code and as such is only available on systems on which loading compiled code at runtime is supported. Currently these are most UNIX-compatible platforms that provide the libdl functionality like Linux, Solaris, BSD, Mac OS X and Windows using Cygwin.

Note: Extension may also be normal applications or shell scripts, but are usually libraries.

chicken-setup will download the source code for extension automatically from the canonical server at <a href="http://www.call-with-current-continuation.org/eggs">http://www.call-with-current-continuation.org/eggs</a> if the requested egg does not exist in the current directory. Various command-line options exist for customizing the process and/or retrieving the egg from other locations or in other formats.

# 35.2 Installing extensions

To install an extension library, run the <code>chicken-setup</code> program with the extension name as argument. The extension archive is downloaded, its contents extracted and the contained <code>setup</code> script is executed. This setup script is a normal Scheme source file, which will be interpreted by <code>chicken-setup</code>. The complete language supported by <code>csi</code> is available, and the library units <code>srfi-l</code> regex utils <code>posix tcp</code> are loaded. Additional libraries can be loaded at run-time.

The setup script should perform all necessary steps to build the new library (or application). After a successful build, the extension can be installed by invoking one of the procedures install-extension, install-program or install-script. These procedures will copy a number of given files into the extension repository or in the path where the CHICKEN executables are located (in the case of executable programs or scripts). Additionally the list of installed files, and user-defined metadata is stored in the repository.

If no extension name is given on the command-line, and if none of the options -list, -version, -repository (without argument), -program-path (without argument), -fetch, -fetch-tree or -docindex is given, then all .setup scripts in the current directory are processed.

# 35.3 Creating extensions

Extensions can be created by creating an (optionally gzipped) tar archive named EXTENSION.egg containing all needed files plus a .setup script in the root directory. After Chicken-setup has extracted the files, the setup script will be invoked. There are no additional constraints on the structure of the archive, but the setup script has to be in the root path of the archive.

35 chicken-setup 218

# 35.4 Procedures and macros available in setup scripts

#### 35.4.1 install-extension

```
(install-extension ID FILELIST [INFOLIST])
```

Installs the extension library with the name ID. All files given in the list of strings FILELIST will be copied to the extension repository. It should be noted here that the extension id has to be identical to the name of the file implementing the extension. The extension may load or include other files, or may load other extensions at runtime specified by the require-at-runtime property.

FILELIST may be a filename, a list of filenames, or a list of pairs of the form (SOURCE DEST) (if you want to copy into a particular sub-directory - the destination directory will be created as needed). If DEST is a relative pathname, < it will be copied into the extension repository.

The optional argument INFOLIST should be an association list that maps symbols to values, this list will be stored as ID.setup at the same location as the extension code. Currently the following properties are used:

### 35.4.1.1 syntax

[extension property] (syntax)

Marks the extension as syntax-only. No code is compiled, the extension is intended as a file containing macros to be loaded at compile/macro-expansion time.

#### 35.4.1.2 require-at-runtime

```
[extension property] (require-at-runtime ID ...)
```

Specifies extensions that should be loaded (via require) at runtime. This is mostly useful for syntax extensions that need additional support code at runtime.

### 35.4.1.3 version

[extension property] (version STRING)

Specifies version string.

#### 35.4.1.4 documentation

```
[extension property] (documentation FILENAME)
```

The filename of a HTML document containing extension-specific documentation. This file should be given in the file-list passed to install-extension and a link to it will be automatically included in the index page (accessible via Chicken-setup -docindex).

### 35.4.1.5 examples

```
[extension property] (examples FILENAME ...)
```

Copies the given files into the examples directory, which is usually \$prefix/share/chicken/examples (equivalent to \$CHICKEN\_HOME/examples or (make-pathname (chicken-home) "examples")).

Note that the files listed in this property should not be listed in the normal list of files to install passed to install-extension. This is the only exception - other files that are installed in the repository must be given in the file list.

### 35.4.1.6 exports

```
[extension property] (exports EXPORT ...)
```

Add export-information to the generated extension-information. EXPORT may be a symbol naming an exported toplevel variable or a string designating a file with exported variables, as generated by the -emit-exports option or the emit-exports declaration specifier.

#### 35.4.1.7 static

```
[extension property] (static STRING)
```

If the extension also provides a static library, then STRING should contain the name of that library. Used by CSC when compiling with the -static-extensions option.

### 35.4.1.8 static-options

```
[extension property] (static-options STRING)
```

Additional options that should be passed to the linker when linking with the static version of an extension (see static above). Used by CSC when compiling with the -static-extensions option.

All other properties are currently ignored. The FILELIST argument may also be a single string.

35.4.1 install-extension 220

### 35.4.2 install-program

```
[procedure] (install-program ID FILELIST [INFOLIST])
```

Similar to install-extension, but installs an executable program in the executable path (usually /usr/local/bin).

# 35.4.3 install-script

```
[procedure] (install-script ID FILELIST [INFOLIST])
```

Similar to install-program, but additionally changes the file permissions of all files in FILELIST to executable (for installing shell-scripts).

### 35.4.4 run

```
[syntax] (run FORM ...)
```

Runs the shell command FORM, which is wrapped in an implicit quasiquote. (run (csc ...)) is treated specially and passes -v (if -verbose has been given to chicken-setup) and -feature compiling-extension options to the compiler.

# 35.4.5 compile

```
[syntax] (compile FORM ...)
Equivalent to (run (csc FORM ...)).
```

### 35.4.6 make

```
[syntax] (make ((TARGET (DEPENDENT ...) COMMAND ...) ...) ARGUMENTS)
```

A *make* macro that executes the expressions COMMAND ..., when any of the dependents DEPENDENT ... have changed, to build TARGET. This is the same as the make extension, which is available separately. For more information, see <u>make</u>.

# 35.4.7 patch

```
[procedure] (patch WHICH REGEX SUBST)
```

35.4.2 install-program 221

Replaces all occurrences of the regular expression REGEX with the string SUBST, in the file given in WHICH. If WHICH is a string, the file will be patched and overwritten. If WHICH is a list of the form OLD NEW, then a different file named NEW will be generated.

### 35.4.8 copy-file

```
[procedure] (copy-file FROM TO)
```

Copies the file or directory (recursively) given in the string FROM to the destination file or directory T0.

### 35.4.9 move-file

```
[procedure] (move-file FROM TO)
```

Moves the file or directory (recursively) given in the string FROM to the destination file or directory T0.

### 35.4.10 remove-file\*

```
[procedure] (remove-file* PATH)
```

Removes the file or directory given in the string PATH.

# 35.4.11 find-library

```
[procedure] (find-library NAME PROC)
```

Returns #t if the library named libNAME. [a|so] (unix) or NAME. lib (windows) could be found by compiling and linking a test program. PROC should be the name of a C function that must be provided by the library. If no such library was found or the function could not be resolved, #f is returned.

### 35.4.12 find-header

```
[procedure] (find-header NAME)
```

Returns #t if a C include-file with the given name is available, or #f otherwise.

35.4.7 patch 222

### 35.4.13 try-compile

```
[procedure] (try-compile CODE #!key cc cflags ldflags compile-only c++)
```

Returns #t if the C code in CODE compiles and links successfully, or #f otherwise. The keyword parameters CC (compiler name, defaults to the C compiler used to build this system), Cflags and ldflags accept additional compilation and linking options. If Compile-only is true, then no linking step takes place. If the keyword argument C++ is given and true, then the code will be compiled in C++ mode.

# 35.4.14 create-directory

```
[procedure] (create-directory PATH)
```

Creates the directory given in the string PATH, with all parent directories as needed.

### 35.4.15 installation-prefix

```
[parameter] installation-prefix
```

Holds the prefix under which CHICKEN executables and libraries have been installed (either the value of the environment variable CHICKEN\_PREFIX or whatever prefix was specified at the time the system was built.

# 35.4.16 program-path

```
[parameter] (program-path [PATH])
```

Holds the path where executables are installed and defaults to either \$CHICKEN\_PREFIX/bin, if the environment variable CHICKEN\_PREFIX is set, \$CHICKEN\_HOME or the path where the CHICKEN binaries (Chicken, csi, etc.) are installed.

# 35.4.17 setup-root-directory

```
[parameter] (setup-root-directory [PATH])
```

Contains the path of the directory where chicken-setup was invoked.

# 35.4.18 setup-build-directory

```
[parameter] (setup-build-directory [PATH])
```

35.4.13 try-compile 223

CHICKEN User's Manual - The User's Manual

Contains the path of the directory where the extension is built. This is not necessarily identical to setup-root-directory.

### 35.4.19 setup-verbose-flag

```
[parameter] (setup-verbose-flag [BOOL])
```

Reflects the setting of the -verbose option, i.e. is #t, if -verbose was given.

### 35.4.20 setup-install-flag

```
[parameter] (setup-install-flag [BOOL])
```

Reflects the setting of the --no-install option, i.e. is #f, if -no-install was given.

### 35.4.21 required-chicken-version

```
[procedure] (required-chicken-version VERSION)
```

Signals an error if the version of CHICKEN that this script runs under is lexicographically less than VERSION (the argument will be converted to a string, first).

# 35.4.22 required-extension-version

```
[procedure] (required-extension-version EXTENSION1 VERSION1 ...)
```

Checks whether the extensions EXTENSION1 ... are installed and at least of version VERSION1 .... The test is made by lexicographically comparing the string-representations of the given version with the version of the installed extension. If one of the listed extensions is not installed, has no associated version information or is of a version older than the one specified.

### 35.4.23 cross-chicken

```
[procedure] (cross-chicken)
```

Retrusn #t if this system is configured for cross-compilation or #f otherwise.

# 35.5 Examples for extensions

;;;; hello.scm

The simplest case is a single file that does not export any syntax. For example

```
(define (hello name)
  (print "Hello, " name " !") )
We need a .setup script to build and install our nifty extension:
:::: hello.setup
;; compile the code into a dynamically loadable shared object
;; (will generate hello.so)
(compile -s hello.scm)
;; Install as extension library
(install-extension 'hello "hello.so")
After entering
$ chicken-setup hello
at the shell prompt (and in the same directory where the two files exist), the file hello.scm will be
compiled into a dynamically loadable library. If the compilation succeeds, hello. so will be stored in the
repository, together with a file named hello.setup-info containing an a-list with metadata. If no
extension name is given to Chicken-Setup, it will simply execute the first file with the .Setup extension
it can find.
Use it like any other CHICKEN extension:
$ csi -q
#;1> (require-extension hello)
; loading /usr/local/lib/chicken/1/hello.so ...
#;2> (hello "me")
Hello, me!
#;3>
Here we create a simple application:
;;;; hello2.scm
(print "Hello, ")
(for-each (lambda (x) (printf "~A " x)) (command-line-arguments))
(print "!")
We also need a setup script:
;;;; hello2.setup
(compile hello2.scm) ; compile `hello2'
(install-program 'hello2 "hello2"); name of the extension and files to be inst
```

To use it, just run chicken-setup in the same directory:

#### \$ chicken-setup

(Here we omit the extension name)

Now the program hello2 will be installed in the same location as the other CHICKEN tools (like chicken, csi, etc.), which will normally be /usr/local/bin. Note that you need write-permissions for those locations and may have to run chicken-setup with administrative rights.

Uninstallation is just as easy:

```
$ chicken-setup -uninstall hello2
```

chicken-setup provides a make macro, so build operations can be of arbitrary complexity. When running chicken-setup with an argument NAME, for which no associated file NAME.setup, NAME.egg or NAME.scm exists will ask you to download the extension via HTTP from the default URL <a href="http://www.call-with-current-continuation.org/eggs">http://www.call-with-current-continuation.org/eggs</a>. You can use the -host option to specify an alternative source location. Extensions that are required to compile and/or use the requested extension are downloaded and installed automatically.

If the given extension name contains a path prefix and the -host option is given, then chicken-setup can also download and install eggs from an arbitrary HTTP server. Alternatively you can pass a full URL (including the http://prefix. Note that no dependency checks are done when downloading eggs directly with the URL syntax.

Finally a somewhat more complex example: We want to package a syntax extension with additional support code that is to be loaded at run-time of any Scheme code that uses that extension. We create a *glass* lambda, a procedure with free variables that can be manipulated from outside:

```
;;;; glass.scm
```

```
(define-macro (glass-lambda llist vars . body)
 ;; Low-level macros are fun!
 (let ([lvar (gensym)]
        [svar (gensym)]
       [x (gensym)]
       [y (gensym)]
        [yn (gensym)] )
    `(let ,(map (lambda (v) (list v #f)) vars)
       (define (,svar ,x . ,y)
 let* ([(yn (pair? ,y)]
    and ,yn (caf,yy))))
   case ,x(
            lambda (v)
              if ,yn `([,v] (
 set! ,v ,y)
                                 ,v)))
                    vars)
     else (e(ror "variable not found" ,x)) ) )
       (define ,lvar (lambda ,llist ,@body))
       (extend-procedure ,lvar ,svar) ) )
```

Here some support code that needs to be loaded at runtime:

```
;;;; glass-support.scm
(require-extension lolevel)

(define glass-lambda-accessor procedure-data)
(define (glass-lambda-ref gl v) ((procedure-data gl) v))
(define (glass-lambda-set! gl v x) ((procedure-data gl) v x))

The setup script looks like this:

(compile -s glass-support.scm)

(install-extension
   'glass
   '("glass.scm" "glass-support.so")
   '((syntax) (require-at-runtime glass-support)) )
```

The invocation of install-extension provides the files that are to be copied into the extension repository, and a metadata list that specifies that the extension glass is a syntax extension and that, if it is declared to be used by other code (either with the require-extension or require-for-syntax form), then client code should perform an implicit (require 'glass-support) at startup.

This can be conveniently packaged as an egg:

```
$ tar cfz glass.egg glass.setup glass.scm glass-support.scm
And now we use it:

$ chicken-setup glass
$ csi -quiet
#;1> (require-extension glass)
; loading /usr/local/lib/chicken/1/glass.scm ...
; loading /usr/local/lib/chicken/1/glass-support.so ...
#;2> (define foo (glass-lambda (x) (y) (+ x y)))
#;3> (glass-lambda-set! foo 'y 99)
#;4> (foo 33)
132
```

# 35.6 chicken-setup reference

Available options:

-R -repository [PATHNAME]

When used without an argument, the path of the extension repository is displayed on standard output. When given an argument, the repository pathname (and the repository-path parameter) will be set to PATHNAME for all subsequent operations. The default repository path is the installation library directory (usually /usr/local/lib/chicken), or (if set) the directory given in the environment variable CHICKEN\_REPOSITORY. PATHNAME should be an absolute pathname.

#### -P -program-path [PATHNAME]

When used without an argument, the path for executables is displayed on standard output. When given an argument, the program path for installing executables and scripts will be set to PATHNAME for all subsequent operations. PATHNAME should be an absolute pathname.

#### -h -host HOSTNAME[:PORT]

Specifies alternative host for downloading extensions, optionally with a TCP port number (which defaults to 80).

#### -u -uninstall EXTENSION

Removes all files that were installed for EXTENSION from the file-system, together with any metadata that has been stored.

#### -l -list [NAME ...]

List all installed extensions or show extension information.

#### -r -run FILENAME

Load and execute given file.

#### -s -script FILENAME

Executes the given Scheme source file with all remaining arguments and exit. The *she-bang* shell script header is recognized, so you can write Scheme scripts that use Chicken-setup just as with CSi.

#### -e -eval EXPRESSION

Evaluates the given expression(s).

#### -v -verbose

Display additional debug information.

### -k -keep

Keep temporary files and directories.

#### -c -csc-option OPTION

Passes OPTION as an extra argument to invocations of the compiler-driver (CSC). This works only if CSC is invoked as (run (CSC ...)).

#### -d -dont-ask

Do not ask the user before trying to download required extensions.

#### -n -no-install

Do not install generated binaries and/or support files. Any invocations of install-program, install-extension or install-script will be be no-ops.

#### -i -docindex

Displays the path to the index-page of any installed extension-documentation. If the index page does not exist, it is created.

#### -t -test EXTENSION ...

return success if all given extensions are installed

#### -ls EXTENSION

List installed files for extension

#### -fetch-tree

Download and print the repository catalog

### -t -test

If the extension sources contain a directory named tests and this directory includes a file named run.scm then this file is executed (with tests being the current working directory).

#### -tree FILENAME

Download and show the repository catalog

### -svn URL

Fetch extension from Subversion repository

### -revision REV

Specifies SVN revision to check out

#### -local PATHNAME

Fetch extension from local file

#### -destdir PATHNAME

Specify alternative installation prefix (for packaging)

- -

Ignore all following arguments.

Note that the options are processed exactly in the order in which they appear in the command-line.

### 35.7 Windows notes

chicken-setup works on Windows, when compiled with Visual C++, but depends on the tar and gunzip tools to extract the contents of an egg. The best way is to download an egg either manually (or with chicken-setup -fetch) and extract its contents with a separate program (like winzip). the CHICKEN\_REPOSITORY environment variable has to be set (in addition to CHICKEN\_HOME) to a directory where your compiled extensions should be located.

The .setup scripts will not always work under Windows, and the extensions may require libraries that are not provided for Windows or work differently. Under these circumstances it is recommended to perform the required steps to build an extension manually.

The required UNIX tools are also available as Windows binaries. Google or ask on the CHICKEN mailing list if you need help locating them.

# 35.8 Security

When extensions are downloaded and installed one is executing code from potentially compromised systems. This applies also when <code>Chicken-setup</code> executes system tests for required extensions. As the code has been retrieved over the network effectively untrusted code is going to be evaluated. When <code>Chicken-setup</code> is run as *root* the whole system is at the mercy of the build instructions (note that this is also the case every time you install software via <code>Sudo make install</code>, so this is not specific to the <code>CHICKEN</code> extension mechanism).

Security-conscious users should never run Chicken-setup as root. A simple remedy is to set the environment variable CHICKEN\_REPOSITORY, which will transparently place the repository at an arbitrary user-selected location. Alternatively obtain write/execute access to the default location of the repository (usually /usr/local/lib/chicken) to avoid running as root.

#### 35.9 Other modes of installation

It is possible to install extensions directly from a <u>Subversion</u> repository or from a local checkout by using the -svn or -local options. By using either the svn client program (which must be installed) or file-system operations, all necessary files will be copied into the current directory (creating a subdirectory named EXTENSIONNAME.eqg-dir), built and subsequently installed.

Dependency information, which is necessary to ensure required extensions are also installed, is downloaded automatically. If you have no internet connection or don't want to connect, you can also use a local file containing the necessary dependency information. The -fetch-tree option retrieves the canonical repository file at <a href="http://www.call-with-current-continuation.org/eggs/repository">http://www.call-with-current-continuation.org/eggs/repository</a>, writing it to stdout. Redirecting this output into a file and passing the file via the -tree option to Chicken-setup allows you

35.7 Windows notes

CHICKEN User's Manual - The User's Manual

now to use the local repository file:

Retrieve complete extension repository (big):

```
% cd /opt
% svn co <a href="https://galinha.ucpel.tche.br/svn/chicken-eggs">https://galinha.ucpel.tche.br/svn/chicken-eggs</a>
```

Get your own copy of the repository file:

```
% chicken-setup -fetch-tree >~/my-repository-file
```

Now you can install eggs from your local checkout, with full dependency tracking and without being connected to the internet:

```
% cd ~/tmp
% chicken-setup -local /opt/eggs/chicken-eggs -tree ~/my-repository-file opengl
```

# 35.10 Linking extensions statically

The compiler and <a href="mailto:chicken-setup">chicken-setup</a> support statically linked eggs. The general approach is to generate an object file or static library (in addition to the usual shared library) in your . Setup script and install it along with the dynamically loadable extension. The setup properties Static should contain the name of the object file (or static library) to be linked, when CSC gets passed the -static-extensions option:

```
(compile -s -02 -d1 my-ext.scm) ; dynamically loadable "normal" version
(compile -c -02 -d1 my-ext -unit my-ext) ; statically linkable version
(install-extension
  'my-ext
  '("my-ext.so" "my-ext.o")
  '((static "my-ext.o"))))
```

Note the use of the -unit option in the second compilation step: static linking must use static library units. chicken-setup will perform platform-dependent file-extension translation for the file list, but does currently not do that for the static extension property.

To actually link with the static version of my-ext, do:

```
% csc -static-extensions my-program.scm -uses my-ext
```

The compiler will try to do the right thing, but can not handle all extensions, since the ability to statically link eggs is relatively new. Eggs that support static linking are designated as being able to do so. If you require a statically linkable version of an egg that has not been converted yet, contact the extension author or the CHICKEN mailing list.

Previous: Interface to external functions and variables

Next: <u>Data representation</u>

#### 36 Data representation

Note: In all cases below, bits are numbered starting at 1 and beginning with the lowest-order bit.

There exist two different kinds of data objects in the CHICKEN system: immediate and non-immediate objects.

#### 36.1 Immediate objects

Immediate objects are represented by a single machine word, which is usually of 32 bits length, or 64 bits on 64-bit architectures. The immediate objects come in four different flavors:

**fixnums**, that is, small exact integers, where bit 1 is set to 1. This gives fixnums a range of 31 bits for the actual numeric value (63 bits on 64-bit architectures).

**characters**, where bits 1-4 are equal to C\_CHARACTER\_BITS. The Unicode code point of the character is encoded in bits 9 to 32.

booleans, where bits 1-4 are equal to C BOOLEAN BITS. Bit 5 is one for #t and zero for #f.

**other values**: the empty list, the value of unbound identifiers, the undefined value (void), and end-of-file. Bits 1-4 are equal to C\_SPECIAL\_BITS; bits 5 to 8 contain an identifying number for this type of object. The following constants are defined: C\_SCHEME\_END\_OF\_LIST C\_SCHEME\_UNDEFINED C\_SCHEME\_UNBOUND C\_SCHEME\_END\_OF\_FILE

Collectively, bits 1 and 2 are known as the *immediate mark bits*. When bit 1 is set, the object is a fixnum, as described above. When bit 2 is set, it is an immediate object other than a fixnum. If neither is set, the object is non-immediate, as described below. (By definition, bits 1 and 2 may not both be set.)

#### 36.2 Non-immediate objects

Non-immediate objects are blocks of data represented by a pointer into the heap. The pointer's immediate mark bits (bits 1 and 2) must be zero to indicate the object is non-immediate; this guarantees the data block is aligned on a 4-byte boundary, at minimum. Alignment of data words is required on modern architectures anyway, so we get the ability to distinguish between immediate and non-immediate objects for free.

The first word of the data block contains a header, which gives information about the type of the object. The header has the size of a machine word, usually 32 bits (64 bits on 64 bit architectures).

Bits 1 to 24 contain the length of the data object, which is either the number of bytes in a string (or byte-vector) or the the number of elements for a vector or for a structure type.

Bits 25 to 28 contain the type code of the object.

Bits 29 to 32 contain miscellaneous flags used for garbage collection or internal data type dispatching. These flags are:

C\_GC\_FORWARDING\_BIT

Flag used for forwarding garbage collected object pointers.

#### C\_BYTEBLOCK\_BIT

Flag that specifies whether this data object contains raw bytes (a string or byte-vector) or pointers to other data objects.

#### C\_SPECIALBLOCK\_BIT

Flag that specifies whether this object contains a *special* non-object pointer value in its first slot. An example for this kind of objects are closures, which are a vector-type object with the code-pointer as the first item.

#### C 8ALIGN BIT

Flag that specifies whether the data area of this block should be aligned on an 8-byte boundary (floating-point numbers, for example).

The actual data follows immediately after the header. Note that block-addresses are always aligned to the native machine-word boundary. Scheme data objects map to blocks in the following manner:

**pairs**: vector-like object (type bits C\_PAIR\_TYPE), where the car and the cdr are contained in the first and second slots, respectively.

vectors: vector object (type bits C VECTOR TYPE).

**strings**: byte-vector object (type bits C STRING TYPE).

**procedures**: special vector object (type bits C\_CLOSURE\_TYPE). The first slot contains a pointer to a compiled C function. Any extra slots contain the free variables (since a flat closure representation is used).

**flonums**: a byte-vector object (type bits C\_FLONUM\_BITS). Slots one and two (or a single slot on 64 bit architectures) contain a 64-bit floating-point number, in the representation used by the host systems C compiler.

**symbols**: a vector object (type bits C\_SYMBOL\_TYPE). Slots one and two contain the toplevel variable value and the print-name (a string) of the symbol, respectively.

**ports**: a special vector object (type bits C\_PORT\_TYPE). The first slot contains a pointer to a file- stream, if this is a file-pointer, or NULL if not. The other slots contain housekeeping data used for this port.

**structures**: a vector object (type bits C\_STRUCTURE\_TYPE). The first slot contains a symbol that specifies the kind of structure this record is an instance of. The other slots contain the actual record items.

**pointers**: a special vector object (type bits C POINTER TYPE). The single slot contains a machine pointer.

**tagged pointers**: similar to a pointer (type bits C\_TAGGED\_POINTER\_TYPE), but the object contains an additional slot with a tag (an arbitrary data object) that identifies the type of the pointer.

Data objects may be allocated outside of the garbage collected heap, as long as their layout follows the above mentioned scheme. But care has to be taken not to mutate these objects with heap-data (i.e. non-immediate objects), because this will confuse the garbage collector.

For more information see the header file chicken.h.

Previous: chicken-setup

Next: Bugs and limitations

#### 37 Bugs and limitations

- Compiling large files takes too much time.
- If a known procedure has unused arguments, but is always called without those parameters, then the optimizer *repairs* the procedure in certain situations and removes the parameter from the lambda-list.
- port-position currently works only for input ports.
- Leaf routine optimization can theoretically result in code that thrashes, if tight loops perform excessively many mutations.

Previous: Data representation

Next: FAQ

#### **38 FAQ**

This is the list of Frequently Asked Questions about Chicken Scheme. If you have a question not answered here, feel free to post to the chicken-users mailing list; if you consider your question general enough, feel free to add it to this list.

#### 38.1 General

#### 38.1.1 Why yet another Scheme implementation?

Since Scheme is a relatively simple language, a large number of implementations exist and each has its specific advantages and disadvantages. Some are fast, some provide a rich programming environment. Some are free, others are tailored to specific domains, and so on. The reasons for the existence of CHICKEN are:

- CHICKEN is portable because it generates C code that runs on a large number of platforms.
- CHICKEN is extendable, since its code generation scheme and runtime system/garbage collector fits neatly into a C environment.
- CHICKEN is free and can be freely distributed, including its source code.
- CHICKEN offers better performance than nearly all interpreter based implementations, but still provides full Scheme semantics.
- As far as we know, CHICKEN is the first implementation of Scheme that uses Henry Baker's <u>Cheney on the M.T.A</u> concept.

#### 38.1.2 What should I do if I find a bug?

Send e-mail to <u>felix@call-with-current-continuation.org</u> with some hints about the problem, like version/build of the compiler, platform, system configuration, code that causes the bug, etc.

# 38.1.3 Why are values defined with define-foreign-variable or define-constant or define-inline not seen outside of the containing source file?

Accesses to foreign variables are translated directly into C constructs that access the variable, so the Scheme name given to that variable does only exist during compile-time. The same goes for constant- and inline-definitions: The name is only there to tell the compiler that this reference is to be replaced with the actual value.

38 FAQ 234

### 38.1.4 How does cond-expand know which features are registered in used units?

Each unit used via (declare (uses ...)) is registered as a feature and so a symbol with the unit-name can be tested by cond-expand during macro-expansion-time. Features registered using the register-feature! procedure are only available during run-time of the compiled file. You can use the eval-when form to register features at compile time.

### 38.1.5 Why are constants defined by define-constant not honoured in case constructs?

case expands into a cascaded if expression, where the first item in each arm is treated as a quoted list. So the case macro can not infer wether a symbol is to be treated as a constant-name (defined via define-constant) or a literal symbol.

#### 38.1.6 How can I enable case sensitive reading/writing in user code?

To enable the read procedure to read symbols and identifiers case sensitive, you can set the parameter case-sensitivity to #t.

#### 38.1.7 How can I change match-error-control during compilation?

```
Use eval-when, like this:
  (eval-when (compile)
  (match-error-control #:unspecified) )
```

## 38.1.8 Why doesn't CHICKEN support the full numeric tower by default?

The short answer:

```
% chicken-setup numbers
% csi -q
#;1> (use numbers)
```

The long answer:

There are a number of reasons for this:

- For most applications of Scheme fixnums (exact word-sized integers) and flonums (64-bit floating-point numbers) are more than sufficient;

CHICKEN User's Manual - The User's Manual

- Interfacing to C is simpler;
- Dispatching of arithmetic operations is more efficient.

There is an extension based on the GNU Multiprecision Package that implements most of the full numeric tower, see <a href="http://www.call-with-current-continuation.org/eggs/numbers.html">http://www.call-with-current-continuation.org/eggs/numbers.html</a>.

## 38.1.9 How can I specialize a generic function method to match instances of every class?

Specializing a method on <object> doesn't work on primitive data objects like numbers, strings, etc. so for example

```
(define-method (foo (x <my-class>)) ...)
(define-method (foo (x <object>)) ...)
(foo 123)
```

will signal an error, because to applicable method can be found. To specialize a method for primitive objects, use <top>:

```
(define-method (foo (x <top>)) ...)
```

#### 38.1.10 Does CHICKEN support native threads?

Currently native threads are not supported. The runtime system is not reentrant, and the garbage-collection algorithm would be made much more complicated, since the location of every object (whether it is allocated on the stack or on the heap or completely outside the GC-able data space) has to be checked - this would be rather complex and inefficient in a situation where multiple threads are involved.

#### 38.2 Platform specific

#### 38.2.1 How do I generate a DLL under MS Windows (tm) ?

Use CSC in combination with the -dll option:

```
C:\> csc foo.scm -dll
```

#### 38.2.2 How do I generate a GUI application under Windows(tm)?

Invoke CSC with the -windows option. Or pass the -DC\_WINDOWS\_GUI option to the C compiler and link with the GUI version of the runtime system (that's libchicken-gui[-static].lib. The GUI runtime displays error messages in a message box and does some rudimentary command-line parsing.

## 38.2.3 Compiling very large files under Windows with the Microsoft C compiler fails with a message indicating insufficient heap space.

It seems that the Microsoft C compiler can only handle files up to a certain size, and it doesn't utilize virtual memory as well as the GNU C compiler, for example. Try closing running applications. If that fails, try to break up the Scheme code into several library units.

## 38.2.4 When I run csi inside an emacs buffer under Windows, nothing happens.

Invoke CSi with the -: C runtime option. Under Windows the interpreter thinks it is not running under control of a terminal and doesn't print the prompt and does not flush the output stream properly.

### 38.2.5 I load compiled code dynamically in a Windows GUI application and it crashes.

Code compiled into a DLL to be loaded dynamically must be linked with the same runtime system as the loading application. That means that all dynamically loaded entities (including extensions built and installed with chicken-setup) must be compiled with the -windows csc option.

#### 38.2.6 On Windows, csc.exe seems to be doing something wrong.

The Windows development tools include a C# compiler with the same name. Either invoke CSC.eXe with a full pathname, or put the directory where you installed CHICKEN in front of the MS development tool path in the PATH environment variable.

## 38.2.7 On Windows source and/or output filenames with embedded whitespace are not found.

There is no current workaround. Do not use filenames with embedded whitespace for code. However, command names with embedded whitespace will work correctly.

#### 38.3 Customization

% cat userpass.scm

## 38.3.1 How do I run custom startup code before the runtime-system is invoked?

When you invoke the C compiler for your translated Scheme source program, add the C compiler option -DC\_EMBEDDED, or pass -embedded to the CSC driver program, so no entry-point function will be generated (main()). When your are finished with your startup processing, invoke:

```
CHICKEN main(argc, argv, C toplevel);
```

where C\_toplevel is the entry-point into the compiled Scheme code. You should add the following declarations at the head of your code:

```
#include "chicken.h"
extern void C_toplevel(C_word,C_word,C_word) C_noret;
```

#### 38.3.2 How can I add compiled user passes?

To add a compiled user pass instead of an interpreted one, create a library unit and recompile the main unit of the compiler (in the file Chicken.scm) with an additional uses declaration. Then link all compiler modules and your (compiled) extension to create a new version of the compiler, like this (assuming all sources are in the current directory):

On platforms that support it (Linux ELF, Solaris, Windows + VC++), compiled code can be loaded via -extend just like source files (see load in the User's Manual).

38.3 Customization 238

#### 38.4 Compiled macros

#### 38.4.1 Why is define-macro complaining about unbound variables?

Macro bodies that are defined and used in a compiled source-file are evaluated during compilation and so have no access to anything created with define. Use define-for-syntax instead.

#### 38.4.2 Why isn't load properly loading my library of macros?

During compile-time, macros are only available in the source file in which they are defined. Files included via include are considered part of the containing file.

#### 38.4.3 Why is include unable to load my hygienic macros?

It is not sufficient for the included file to require the syntax-case extension. Call (require-extension syntax-case) before calling include.

## 38.4.4 Why are macros not visible outside of the compilation unit in which they are defined?

Macros are defined during compile time, so when a file has been compiled, the definitions are gone. An exception to this rule are macros defined with define-macro, which are also visible at run-time, i.e. in eval. To use macros defined in other files, use the include special form.

#### 38.5 Warnings and errors

## 38.5.1 Why does my program crash when I use callback functions (from Scheme to C and back to Scheme again)?

There are two reasons why code involving callbacks can crash out of no apparent reason:

- 1. It is important to use foreign-safe-lambda/foreign-safe-lambda\* for the C code that is to call back into Scheme. If this is not done than sooner or later the available stack space will be exhausted.
- 2. If the C code uses a large amount of stack storage, or if Scheme-to-C-to-Scheme calls are nested deeply, then the available nursery space on the stack will run low. To avoid this it might be advisable to run the compiled code with a larger nursery setting, i.e. run the code with -: s... and a larger value than the default (for example -: s300k), or use the -nursery compiler option. Note that this

38.4 Compiled macros 239

can decrease runtime performance on some platforms.

## 38.5.2 Why does the linker complain about a missing function \_C\_...\_toplevel?

This message indicates that your program uses a library-unit, but that the object-file or library was not supplied to the linker. If you have the unit foo, which is contained in foo. O than you have to supply it to the linker like this (assuming a GCC environment):

% csc program.scm foo.o -o program

## 38.5.3 Why does the linker complain about a missing function \_C\_toplevel?

This means you have compiled a library unit as an application. When a unit-declaration (as in (declare (unit ...))) is given, then this file has a specially named toplevel entry procedure. Just remove the declaration, or compile this file to an object-module and link it to your application code.

### 38.5.4 Why does my program crash when I compile a file with -unsafe or unsafe declarations?

The compiler option -unsafe or the declaration (declare (unsafe)) disable certain safety-checks to improve performance, so code that would normally trigger an error will work unexpectedly or even crash the running application. It is advisable to develop and debug a program in safe mode (without unsafe declarations) and use this feature only if the application works properly.

## 38.5.5 Why do I get a warning when I define a global variable named match?

Even when the match unit is not used, the macros from that package are visible in the compiler. The reason for this is that macros can not be accessed from library units (only when explicitly evaluated in running code). To speed up macro-expansion time, the compiler and the interpreter both already provide the compiled match-... macro definitions. Macros shadowed lexically are no problem, but global definitions of variables named identically to (global) macros are useless - the macro definition shadows the global variable.

This problem can be solved using a different name or undefining the macro, like this:

```
(eval-when (compile eval) (undefine-macro! 'match))
```

## 38.5.6 Why don't toplevel-continuations captured in interpreted code work?

Consider the following piece of code:

```
(define k (call-with-current-continuation (lambda (k) k))) (k k)
```

When compiled, this will loop endlessly. But when interpreted,  $(k \ k)$  will return to the read-eval-print loop! This happens because the continuation captured will eventually read the next toplevel expression from the standard-input (or an input-file if loading from a file). At the moment k was defined, the next expression was  $(k \ k)$ . But when k is invoked, the next expression will be whatever follows after  $(k \ k)$ . In other words, invoking a captured continuation will not rewind the file-position of the input source. A solution is to wrap the whole code into a  $(begin \ ...)$  expression, so all toplevel expressions will be loaded together.

#### 38.5.7 Why does define-reader-ctor not work in my compiled program?

The following piece of code does not work as expected:

```
(eval-when (compile)
(define-reader-ctor 'integer->char integer->char) )
(print #,(integer->char 33))
```

The problem is that the compiler reads the complete source-file before doing any processing on it, so the sharp-comma form is encountered before the reader-ctor is defined. A possible solution is to include the file containing the sharp-comma form, like this:

```
(eval-when (compile)
(define-reader-ctor 'integer->char integer->char) )
(include "other-file")
;;; other-file.scm:
(print #,(integer->char 33))
```

### 38.5.8 Why do built-in units, such as srfi-1, srfi-18, and posix fail to load?

When you try to use a built-in unit such as srfi-18, you may get the following error:

```
#;1> (use srfi-18)
; loading library srfi-18 ...
Error: (load-library) unable to load library
srfi-18
"dlopen(libchicken.dylib, 9): image not found" ;; on a Mac
"libchicken.so: cannot open shared object file: No such file or directory" ;;
```

Another symptom is that (require 'srfi-18) will silently fail.

This typically happens because the Chicken libraries have been installed in a non-standard location, such as your home directory. The workaround is to explicitly tell the dynamic linker where to look for your libraries:

```
export DYLD_LIBRARY_PATH=~/scheme/chicken/lib:$DYLD_LIBRARY_PATH ;; Mac
export LD_LIBRARY_PATH=~/scheme/chicken/lib:$LD_LIBRARY_PATH ;; Linux
```

### 38.5.9 How can I increase the size of the trace shown when runtime errors are detected?

When a runtime error is detected, Chicken will print the last entries from the trace of functions called (unless your executable was compiled with the -no-trace option. By default, only 16 entries will be shown. To increase this number pass the -: aN parameter to your executable.

#### 38.6 Optimizations

#### 38.6.1 How can I obtain smaller executables?

If you don't need eval or the stuff in the extras library unit, you can just use the library unit:

```
(declare (uses library))
(display world!\n")
```

(Don't forget to compile with the -explicit-use option) Compiled with Visual C++ this generates an executable of around 240 kilobytes. It is theoretically possible to compile something without the library, but a program would have to implement quite a lot of support code on its own.

#### 38.6.2 How can I obtain faster executables?

There are a number of declaration specifiers that should be used to speed up compiled files: declaring (standard-bindings) is mandatory, since this enables most optimizations. Even if some standard procedures should be redefined, you can list untouched bindings in the declaration. Declaring (extended-bindings) lets the compiler choose faster versions of certain internal library functions. This might give another speedup. You can also use the the usual-integrations declaration, which is identical to declaring standard-bindings and extended-bindings (note that usual-integrations is set by default). Declaring (block) tells the compiler that global procedures are not changed outside the current compilation unit, this gives the compiler some more opportunities for optimization. If no floating point arithmetic is required, then declaring (number-type fixnum) can give a big performance improvement, because the compiler can now inline most arithmetic operations. Declaring (unsafe) will switch off most safety checks. If threads are not used, you can declare (disable-interrupts). You should always use maximum optimizations settings for your C compiler. Good GCC compiler options on Pentium (and compatible) hardware are: -0s -fomit-frame-pointer-fno-strict-aliasing Some programs are very sensitive to the setting of the nursery (the first

heap-generation). You should experiment with different nursery settings (either by compiling with the -nursery option or by using the -: s... runtime option).

# 38.6.3 Which non-standard procedures are treated specially when the extended-bindings or usual-integrations declaration or compiler option is used?

The following standard bindings are handled specially, depending on optimization options and compiler settings:

+ \* - / quotient eq? eqv? equal? apply c...r values call-with-values
list-ref null? length not char? string? symbol? vector? pair? procedure?
boolean? number? complex? rational? real? exact? inexact? list? eof-object?
string-ref string-set! vector-ref vector-set! char=? char<? char>? char
char-numeric? char-alphabetic? char-whitespace? char-upper-case?
char-lower-case? char-upcae char-downcase list-tail assv memv memq assoc
member set-car! set-cdr! abs exp sin cos tan log asin acos atan sqrt
zero? positive? negative? vector-length string-length char->integer
integer->char inexact->exact = > < >= <= for-each map substring
string-append gcd lcm list exact->inexact string->number number->string
even? odd? remainder floor ceiling truncate round cons vector string
string=? string-ci=? make-vector call-with-current-continuation
write-char read-string

The following extended bindings are handled specially:

bitwise-and bitwise-ior bitwise-xor bitwise-not bit-set? add1 sub1 fx+ fx- fx\* fx/ fxmod fx= fx> fx>= fixnum? fxneq fxmax fxmin fxand fxior fxxor fxnot fxshl fxshr flonum? fp+ fp- fp\* fp/ atom? fp= fp> fp>= fpneq fpmax fpmin arithmetic-shift signum flush-output thread-specific thread-specific-set! not-pair? null-list? print print\* u8vector->blob/shared s8vector->blob/shared u16vector->blob/shared s16vector->blob/shared u32vector->blob/shared s32vector->blob/shared f32vector->blob/shared f64vector->blob/shared block-ref blob-size u8vector-length s8vector-length u16vector-length s16vector-length u32vector-length s32vector-length f32vector-length f64vector-length u8vector-ref s8vector-ref u16vector-ref s16vector-ref u32vector-ref s32vector-ref f32vector-ref f64vector-ref u8vector-set! s8vector-set! u16vector-set! s16vector-set! u32vector-set! s32vector-set! hash-table-ref block-set! number-of-slots first second third fourth null-pointer? pointer->object make-record-instance locative-ref locative-set! locative? locative->object identity cpu-time error call/cc any? substring=? substring-ci=? substring-index substring-index-ci

#### 38.6.4 Can I load compiled code at runtime?

Yes. You can load compiled at code at runtime with load just as well as you can load Scheme source code. Compiled code will, of course, run faster.

To do this, pass to load a path for a shared object. Use a form such as (load "foo.so") and run CSC -shared foo.scm to produce foo.sc from foo.scm (at which point foo.scm will no longer be required).

#### 38.7 Garbage collection

## 38.7.1 Why does a loop that doesn't cons still trigger garbage collections?

Under CHICKENs implementation policy, tail recursion is achieved simply by avoiding to return from a function call. Since the programs is CPS converted, a continuous sequence of nested procedure calls is performed. At some stage the stack-space has to run out and the current procedure and its parameters (including the current continuation) are stored somewhere in the runtime system. Now a minor garbage collection occurs and rescues all live data from the stack (the first heap generation) and moves it into the the second heap generation. Then the stack is cleared (using a longjmp) and execution can continue from the saved state. With this method arbitrary recursion (in tail- or non-tail position) can happen, provided the application doesn't run out of heap-space. (The difference between a tail- and a non-tail call is that the tail-call has no live data after it invokes its continuation - and so the amount of heap-space needed stays constant)

## 38.7.2 Why do finalizers not seem to work in simple cases in the interpeter?

Consider the following interaction in CSI:

```
#;1> (define x '(1 2 3))
#;2> (define (yammer x) (print x " is dead"))
#;3> (set-finalizer! x yammer)
(1 2 3)
#;4> (gc #t)
157812
#;5> (define x #f)
#;6> (gc #t)
157812
#;7>
```

While you might expect objects to be reclaimed and "(1 2 3) is dead" printed, it won't happen: the literal list gets held in the interpreter history, because it is the result value of the set-finalizer! call. Running this in a normal program will work fine.

When testing finalizers from the interpreter, you might want to define a trivial macro such as

```
(define-macro (v x) `(begin (print ,x) (void))) and wrap calls to set-finalizer! in it.
```

#### 38.8 Interpreter

#### 38.8.1 Does CSI support history and autocompletion?

CSI doesn't support it natively but it can be activated with the <a href="http://www.call-with-current-continuation.org/eggs/readline.html">http://www.call-with-current-continuation.org/eggs/readline.html</a> egg. After installing the egg, add the following to your ~/. CSirc or equivalent file:

```
; The regex egg is required for ##csi#name-of-symbols-starting-with
(require 'readline)
(current-input-port (make-gnu-readline-port))
(gnu-history-install-file-manager (string-append (or (getenv "HOME") ".") "/.cs
```

Users of \*nix-like systems (including Cygwin), may also want to check out <u>rlwrap</u>. This program lets you "wrap" another process (e.g. rlwrap CSi) with the readline library, giving you history, autocompletion, and the ability to set the keystroke set. Vi fans can get vi keystrokes by adding "set editing-mode vi" to their .inputrc file.

#### 38.8.2 Does code loaded with load run compiled or interpreted?

If you compile a file with a call to load, the code will be loaded at runtime and, if the file loaded is a Scheme source code file (instead of a shared object), it will be interpreted (even if the caller program is compiled).

#### 38.9 Extensions

#### 38.9.1 How can I install Chicken eggs to a non-default location?

You can just set the CHICKEN\_REPOSITORY environment variable. It should contain the path where you want eggs to be installed:

```
$ export CHICKEN_REPOSITORY=~/chicken/
$ chicken-setup extensionname
```

In order to make programs (including csi) see these eggs, you should set this variable when you run them. Alternatively, you can call the repository-path Scheme procedure before loading the eggs, as in:

```
(repository-path "/home/azul/chicken")
(use format-modular)
```

Note, however, that using repository-path as above hard-codes the location of your eggs in your source files. While this might not be an issue in your case, it might be safe to keep this configuration outside of the source code (that is, specifying it as an environment variable) to make it easier to maintain.

38.8 Interpreter 245

#### 38.9.2 Can I install chicken eggs as a non-root user?

Yes, just install them in a directory you can write.

Previous: Bugs and limitations

Next: <u>Acknowledgements</u>

#### 39 Acknowledgements

Many thanks to Nico Amtsberg, William Annis, Marc Baily, Peter Barabas, Jonah Beckford, Arto Bendiken, Peter Bex, Jean-François Bignolles, Alaric Blagrave-Snellpym, Dave Bodenstab, Fabian Boehlke, T. Kurt Bond, Ashley Bone, Dominique Boucher, Terence Brannon, Roy Bryant, Adam Buchbinder, Hans Bulfone, Category 5, Taylor Campbell, Esteban U. Caamano Castro, Franklin Chen, Thomas Chust, Gian Paolo Ciceri, John Cowan, Grzegorz Chrupała, James Crippen, Tollef Fog Heen, Alejandro Forero Cuervo, Linh Dang, Brian Denheyer, dgym, Chris Double, Jarod Eells, Petter Egesund, Steve Elkins, Daniel B. Faken, Will Farr, Graham Fawcett, Marc Feeley, Fizzie, Kimura Fuyuki, Tony Garnock-Jones, Martin Gasbichler, Joey Gibson, Stephen C. Gilardi, Joshua Griffith, Johannes Groedem, Damian Gryski, Mario Domenech Goulart, Andreas Gustafsson, Sven Hartrumpf, Jun-ichiro itojun Hagino, Ahdi Hargo, Matthias Heiler, Karl M. Hegbloom, William P. Heinemann, Bill Hoffman, Bruce Hoult, Hans Huebner, Markus Huelsmann, Goetz Isenmann, Paulo Jabardo, David Janssens, Christian Jaeger, Dale Jordan, Valentin Kamyshenko, Daishi Kato, Peter Keller, Brad Kind, Ron Kneusel, Matthias Koeppe, Krysztof Kowałczyk, Andre Kuehne, Todd R. Kueny Sr, Goran Krampe, David Krentzlin, Ben Kurtz, Micky Latowicki, John Lenz, Kirill Lisovsky, Kon Lovett, Dennis Marti, Charles Martin, Bob McIsaac, Alain Mellan, Eric Merrit, Perry Metzger, Scott G. Miller, Mikael, Bruce Mitchener, Chris Moline, Eric E. Moore, Julian Morrison, Dan Muresan, Lars Nilsson, Ian Oversby, o.t., Gene Pavlovsky, Levi Pearson, Nicolas Pelletier, Carlos Pita, Robin Lee Powell, Pupeno, Davide Puricelli, Doug Quale, Eric Raible, Ivan Raikov, Joel Reymont, Andreas Rottman, David Rush, Lars Rustemeier, Daniel Sadilek, Oskar Schirmer, Burton Samograd, Reed Sheridan, Ronald Schroeder, Spencer Schumann, Alex Shinn, Ivan Shmakov, Shmul, Tony Sidaway, Jeffrey B. Siegal, Andrey Sidorenko, Michele Simionato, Volker Stolz, Jon Strait, Dorai Sitaram, Robert Skeels, Jason Songhurst, Clifford Stein, Sunnan, Zbigniew Szadkowski, Mike Thomas, Minh Thu, Christian Tismer, Andre van Tonder, John Tobey, Henrik Tramberend, Vladimir Tsichevsky, Neil van Dyke, Sander Vesik, Panagiotis Vossos, Shawn Wagner, Peter Wang, Ed Watkeys, Thomas Weidner, Goeran Weinholt, Matthew Welland, Joerg Wittenberger, Peter Wright, Mark Wutka, Richard Zidlicky and Houman Zolfaghari for bug-fixes, tips and suggestions.

CHICKEN uses the PCRE regular expression package (<a href="http://www.pcre.org">http://www.pcre.org</a>), which is written by Philip Hazel.

Special thanks to Brandon van Every for contributing the <u>CMake</u> support and for helping with Windows build issues.

Also special thanks to Benedikt Rosenau for his constant encouragement.

CHICKEN contains code from several people:

```
Eli Barzilay
```

some performance tweaks used in TinyCLOS.

Mikael Djurfeldt

topological sort used by compiler.

Marc Feeley

pretty-printer.

Aubrey Jaffer

implementation of dynamic-wind.

Richard O'Keefe

sorting routines.

Olin Shivers

implementation of let-optionals[\*] and reference implementations of SRFI-1, SRFI-13 and SRFI-14.

Andrew Wilcox

queues.

Andrew Wright

pattern matcher.

39 Acknowledgements 247

CHICKEN User's Manual - The User's Manual

Previous: FAQ

Next: Bibliography

39 Acknowledgements 248

#### 40 Bibliography

Henry Baker: CONS Should Not CONS Its Arguments, Part II: Cheney on the M.T.A. <a href="http://home.pipeline.com/~hbaker1/CheneyMTA.html">http://home.pipeline.com/~hbaker1/CheneyMTA.html</a>

Revised\(^5\) Report on the Algorithmic Language Scheme <a href="http://www.schemers.org/Documents/Standards/R5RS">http://www.schemers.org/Documents/Standards/R5RS</a>

Previous: <u>Acknowledgements</u>

40 Bibliography 249