Parallel Programming

Parallel Software

Roadmap

- Parallel software
- Input and output
- Performance
- Parallel program design
- Writing and running parallel programs
- Concluding Remarks




PARALLEL SOFTWARE

The burden is on software

- Hardware and compilers can keep up the pace needed for parallelism.
- How does parallel software work?
 - In shared memory programs:
 - Start a single process and fork threads.
 - Threads carry out tasks.
 - In distributed memory programs:
 - Start multiple processes.
 - Processes carry out tasks.

SPMD — single program multiple data

 A SPMD program consists of a single executable that can behave as if it were multiple different programs through the use of conditional branches.



Writing Parallel Programs

- 1. Divide the work among the processes/threads
 - (a) so each process/thread gets roughly the same amount of work
 - (b) and communication is minimized.

```
double x[n], y[n];
...
for (i = 0; i < n; i++)
x[i] += y[i];
```

- 2. Arrange for the processes/threads to synchronize.
- 3. Arrange for communication among processes/threads.

Shared Memory

Dynamic threads

- Master thread waits for work, forks new threads,
 and when threads are done, they terminate
- Efficient use of resources, but thread creation and termination is time consuming.

Static threads

- Pool of threads created and are allocated work,
 but do not terminate until cleanup.
- Better performance, but potential waste of system resources.

Nondeterminism

```
printf ("Thread %d > my_val = %d\n",
         my_rank, my_x);
                          Thread 0 > my_val = 7
                          Thread 1 > my val = 19
  Thread 1 > my_val = 19
  Thread 0 > my val = 7
```

The same input can result in different output.

Race Condition

```
my_val = Compute_val ( my_rank );
x += my_val;
```

Time	Core 0	Core 1		
0	Finish assignment to my_val	In call to Compute_val		
1	Load $x = 0$ into register	Finish assignment to my_val		
2	Load my_val = 7 into register	Load $x = 0$ into register		
3	Add my_val = 7 to x	Load my_val = 19 into register		
4	Store $x = 7$	Add my_val to x		
5	Start other work	Store $x = 19$		

The output depends on the timing of concurrent execution.

Critical Section

- Programmer's job to ensure mutually exclusive access to the critical section
 - Mutual exclusion lock (mutex, or simply lock)

```
my_val = Compute_val ( my_rank );
Lock(&add_my_val_lock );
x += my_val;
Unlock(&add_my_val_lock );
```

A block of code that can only be executed by one thread at a time.

busy-waiting

```
my_val = Compute_val ( my_rank );
i f ( my_rank == 1)
  whi l e (! ok_for_l ); /* Busy-wait loop */
x += my_val; /* Critical section */
i f ( my_rank == 0)
  ok_for_l = true; /* Let thread l update x */
```

message-passing program example

```
char message [100];
my_rank = Get_rank();
i f ( my_rank == 1) {
  sprintf (message, "Greetings from process 1");
   Send (message, MSG_CHAR, 100, 0);
\} elseif (my_rank == 0) {
   Receive (message, MSG_CHAR, 100, 1);
  printf ("Process 0 > \text{Received: } \% \text{s/n"}, \text{message});
```

Notes on the message-passing program

- It is SPMD. The two processes are using the same executable.
- The variable message refers to memory blocks in different processes.
- Process 0 is able to write to stdout.
- Typically both Send and Receive may block until the message is sent/received.
- There are other MPI API functions.

Input and Output

• In distributed memory programs, only process 0 will access *stdin*. In shared memory programs, only the master thread or thread 0 will access *stdin*.

 In both distributed memory and shared memory programs all the processes/threads can access stdout and stderr.

Input and Output

 However, because of the indeterminacy of the order of output to stdout, in most cases only a single process/thread will be used for all output to stdout other than debugging output.

 Debug output should always include the rank or id of the process/thread that's generating the output.

Input and Output

 Only a single process/thread will attempt to access any single file other than stdin, stdout, or stderr. So, for example, each process/thread can open its own, private file for reading or writing, but no two processes/threads will open the same file.



PERFORMANCE

Speedup of a parallel program

- Number of cores = p
- Serial run-time = T_{serial}
- Parallel run-time = T_{parallel}



$$S = \frac{T_{\text{serial}}}{T_{\text{parallel}}}$$

$$T_{parallel} = T_{serial} / p$$

Efficiency of a parallel program


Speedup and efficiency example

p	1	2	4	8	16
S	1.0	1.9	3.6	6.5	10.8
E = S/p	1.0	0.95	0.90	0.81	0.68


Speedups and efficiencies of parallel program on different problem sizes

	p	1	2	4	8	16
Half	S	1.0	1.9	3.1	4.8	6.2
	\boldsymbol{E}	1.0	0.95	0.78	0.60	0.39
Original	S	1.0	1.9	3.6	6.5	10.8
	\boldsymbol{E}	1.0	0.95	0.90	0.81	0.68
Double	S	1.0	1.9	3.9	7.5	14.2
	\boldsymbol{E}	1.0	0.95	0.98	0.94	0.89

Example Speedup Figure



Example Efficiency Figure



Parallel program overhead

$$T_{parallel} = T_{serial} / p + T_{overhead}$$

Amdahl's Law

 Unless virtually all of a serial program is parallelized, the possible speedup is going to be very limited — regardless of the number of cores available.

p: number of cores; f: fraction of the serial time that the parallelizable part takes

Speedup =
$$\frac{T_{\text{serial}}}{f \times T_{\text{serial}} / p + (1-f) \times T_{\text{serial}}} = \frac{1}{1 - f + f/p}$$

Example

- We can parallelize 90% of a serial program.
- Parallelization is "perfect" regardless of the number of cores p we use.
- T_{serial} = 20 seconds
- Parallel runtime of parallelizable part is

$$0.9 \times T_{\text{serial}} / p = 18 / p$$

Example (cont.)

Runtime of "unparallelizable" part is

$$0.1 \times T_{\text{serial}} = 2$$

Overall parallel run-time is

$$T_{parallel} = 0.9 \text{ x } T_{serial} / p + 0.1 \text{ x } T_{serial} = 18 / p + 2$$

Example (cont.)

Speedup

$$S = \frac{T_{\text{serial}}}{0.9 \text{ x T}_{\text{serial}} / p + 0.1 \text{ x T}_{\text{serial}}} = \frac{20}{18 / p + 2}$$

Scalability

- In general, a program is scalable if it can handle ever increasing problem sizes.
- If we increase the number of processes/threads and can keep the efficiency fixed without increasing the problem size, the program is strongly scalable.
- If we keep the efficiency fixed by increasing the problem size at the same rate as we increase the number of processes/threads, the program is weakly scalable.

Time Measurement

- Wall clock time
- CPU time (reported by c function clock)?
- Start to finish (Unix shell command time)?
- A program segment of interest?



Measure Elapsed Time

```
Pseudo function name
double start, finish;
start = Get_current_time();
/* Code that we want to time */
finish = Get_current_time();
printf("The elapsed time
                     omp get wtime
    MPI_Wtime
```

Taking Timings in Parallel Programs

```
private double start, finish;
. . . .
start = Get_current_time();
/* Code that we want to time */
. . .
finish = Get_current_time();
printf("The elapsed time = %e seconds\n", finish-start);
```

Elapsed Time in Parallel Programs

```
shared double global_elapsed;
private double my_start, my_finish, my_elapsed;
/* Synchronize all processes/threads */
Barrier();
my start = Get current time();
/* Code that we want to time */
my_finish = Get_current_time();
my_elapsed = my_finish - my_start;
/* Find the max across all processes/threads */
global_elapsed = Global_max(my_elapsed);
if (my_rank == 0)
   printf("The elapsed time = %e seconds\n", global_elapsed);
```



PARALLEL PROGRAM DESIGN

1. Partitioning: divide the computation to be performed and the data operated on by the computation into small tasks.

The focus here should be on identifying tasks that can be executed in parallel.

 Communication: determine what communication needs to be carried out among the tasks identified in the previous step.

3. Agglomeration or aggregation: combine tasks and communications identified in the first step into larger tasks.


For example, if task A must be executed before task B can be executed, it may make sense to aggregate them into a single composite task.

4. Mapping: assign the composite tasks identified in the previous step to processes/threads.

This should be done so that communication is minimized, and each process/thread gets roughly the same amount of work.

Example – histogram building

1.3, 2.9, 0.4, 0.3, 1.3, 4.4, 1.7, 0.4, 3.2, 0.3, 4.9, 2.4, 3.1, 4.4, 3.9, 0.4, 4.2, 4.5, 4.9, 0.9



Serial program - input


- 1. The number of measurements: data_count
- 2. An array of data_count floats: data
- 3. The minimum value for the bin containing the smallest values: min_meas
- 4. The maximum value for the bin containing the largest values: max_meas
- 5. The number of bins: bin_count

Serial program - output


1. bin_maxes : an array of bin_count floats

2. bin_counts : an array of bin_count ints


First two stages of Foster's Methodology



Alternative definition of tasks and communication



Adding the local arrays



Concluding Remarks (1)

- Serial systems
 - The standard model of computer hardware has been the von Neumann architecture.
- Parallel hardware
 - Flynn's taxonomy.
- Parallel software
 - We focus on software for homogeneous MIMD systems, consisting of a single program that obtains parallelism by branching (SPMD).

Concluding Remarks (2)

- Input and Output
 - We'll write programs in which one process or thread can access stdin, and all processes can access stdout and stderr.
 - However, because of nondeterminism, except for debug output we'll usually have a single process or thread accessing stdout.

Concluding Remarks (3)

- Performance
 - Speedup
 - Efficiency
 - Amdahl's law
 - Scalability
- Parallel Program Design
 - Foster's methodology