Name

passwdmancli — CLI for storing, generating and updating passwords and honeypots.

Synopsis

passwdmancli --i ---interactive --B ---single-backup --U ---utf-8 infile

DESCRIPTION

infile is the file **passwdmancli** will read its commands from, if *infile* is omitted **passwdmancli** will read from standard input. -i or --interactive must be specified if you want the commands **undo** and **redo**, or if you want **passwdmancli** to stay alive after an error.

If you specify the option -B or --single-backup, every change that has been done, will be removed by TWO undos.

You can force **passwdmancli** to use "utf-8" as encoding by specifying the option --utf-8. WARNING: It hasn't been tested with Python 3.x in a non-UTF-8 environment.

passwdmancli reads its input as colon separated values. Quotes are either forbidden or optional (look at unquote() in passwdmanapi(3)). Integers are created with the python built-in int(). All commands are listed in COMMANDS. The first command you really should use is "esc:on". If the line begins with a number-sign, the line will be ignored. If the line begins with a pipe-sign, it will write the rest of the line to standard output.

All outputs that are prefixed with an exclamation mark are error messages. All outputs that are prefixed with a number sign are messages for a human user. All other outputs are prefixed with their command (not their arguments), using dots instead of colons, followed by a question mark.

Beware of whitespace. The whitespace comes after colons and/or question marks and before quotes.

The passwords have meta-data. They have a minimum required length and a maximum allowed length. They also have a type which is one of:

The password may only use digits.

The password can use big letters, small letters, digits, underscores and exclamation marks.

human The password is human generated.

The "honeypots" are weak passwords intended to be used as traps. It was a poor choice of name, but it grew legs and glued its feet to the ground.

WARNING: If a command accepts a name and index argument, any string of digits will be treated as an index.

COMMANDS

bells Show message about the bells and whistles.

bugs Show message about wasps and mosquitoes.

esc:off Disable really simple escapes for quoted strings.

esc:on Enable really simple escapes for quoted strings. They are only

useful for escaping quotes.

hell Synonym for **verbose:on**.

help Help message.

honeypot:add:'value' Add a new honeypot with the value value.

honeypot:help Help message.

honeypot:list List all honeypots. Returns multiple lines of: "honeypot.list?",

the index, a colon and the value surrounded by single quotes.

honeypot:pick Pick a honeypot. Returns a line of: "honeypot.pick?" followed

by the honeypot surrounded by single quotes.

honeypot:pick:n:'sep' Pick n honeypots and separate them with sep. Returns a line

of: "honeypot.pick?" followed by the separator-separated hon-

eypots surrounded by single quotes.

honeypot:pickf:n:'f' Pick n honey-pots. f is a format string of multiple parts. Each

part begins with zero or more whitespace followed by a single character that indicates which option is specified, and ends with

an semicolon.

They use percent-sign escapes (URL escapes); percent-sign followed by two hexadecimal digits representing the ASCII

code.

All the option letters are lower case. "p" for pattern, "r" for replacement, "s" for separator, "h" for head and "t"

for tail.

pattern and replacement are regexps. pattern is sub-

stituted with replacement in every honeypot.

Returns a line of: "honeypot.pickf?" followed by head followed by all the honeypots separated with sep followed by

tail.

The default values for the options are to backslash escape single quotes and backslashes, and put single quotes around the

honeypots and separate them with commas.

Example that replaces s with z: "honeypot:pickf:5:ps;rz;"

honeypot:pickl:n Pick n honey-pots, escape and quote (single quotes). Returns

a line of "honeypot.pickl?" followed by the quoted honey-pots

separated with commas.

honeypot:remove:'value' Remove the honeypot with the value value.

honeypot:remove:index Remove the honeypot at index. WARNING: The indexes of

the following honeypots will be decreased by one!

passwd:add:type:minlength:maxlengthAuthaehew password for name, with at least minlength let-

ters, but no more than maxlength. If type is "10", the password will only contain digits. If type is "64", the password will contain big letters, small letters, digits, underscores and

exclamation marks. It will not give any output.

passwd:add_human:'name' Add a human generated password for name. It will read the

password on a new line. It will not give any output.

passwd:get:'name' Returns a line of: "passwd.get?" followed by the value of the

password for name surrounded by single quotes.

passwd:get:index Returns a line of: "passwd.get?" followed by the value of the

password at index surrounded by single quotes.

passwd:help Help message.

passwd:list List all passwords. Returns multiple lines of: "passwd.list?",

the index, a colon and the name surrounded by single quotes.

passwd:meta:'name' Get the meta-data for the password for name. Returns a line

of: "passwd.meta?", the type surrounded by single quotes, a colon, the minimum length for the password surrounded by single quotes, a colon and the maximum length for the password

surrounded by single quotes.

passwd:meta:index Get the meta-data for the password at index. Returns a line

of: "passwd.meta?", the type surrounded by single quotes, a colon, the minimum length for the password surrounded by single quotes, a colon and the maximum length for the password

surrounded by single quotes.

passwd:remove:'name' Remove the password for name.

passwd:remove:index Remove the password at index. WARNING: The indexes of

the following passwords will be decreased by one!

passwd:update:'name' Update the password for name using its meta-data. Returns a

line of: "passwd.update?", the old password, a colon and the

new password.

passwd:update:index Update the password at index using its meta-data. Returns a

line of: "passwd.update?", the old password, a colon and the

new password.

passwd:update_meta:type:min:max:'naDre'the same thing as passwd:update:'name', but use type,

min, and max as meta-data, instead of the passwords own

(which might not even exist).

passwd:update_meta:type:min:max:index the same thing as passwd:update:index, but use type,

min, and max as meta-data, instead of the passwords own

(which might not even exist).

pb:on Enable progress-counters. start is "Number-sign, tab, zero, per-

cent." Progress is "Enough backspaces, integer decimal digits,

percent." Stop is "Newline."

pb:off Disable progress-counters.

redo Opposite of **undo**.

undo CLI undo button; restore from latest auto-generated backup.

verbose:on Enable verbose mode; release mosquitoes from hell that will be

noisy and give you a headache.

verbose:off Disable verbose mode; kill the mosquitoes.

whistles Show message about the bells and whistles.

FILES

~/.passwdman/passwords is a XML file containing all passwords.

- ~/.passwdman/honeypots is a XML file containing all honeypots.
- ~/.passwdman/undoable is a directory full of backups.
- ~/.passwdman/redoable is a directory full of backups.

DIAGNOSIS

All error messages are sent to standard output and are prefixed with an exclamation mark.

!syntax error Bad speling or incorrect usage. The next line of output will be the offending

input prefixed with an exclamation mark.

!not found Not found or index out of range

SEE ALSO

passwdmanapi(3), random(4), urandom(4), passwdmanfiles(5)

BUGS

Mosquitoes:

• If verbose mode is enabled the message "#READY" is written too many times.

SECURITY

passwdmancli uses random(4) or urandom(4) for everything.

AUTHOR

Written by Oskar Skog (oskar.skog.finland@gmail.com).

Please send patches, questions, bug reports and wish-lists.