### Name

passwdmanapi — library used by passwdmancli and passwdmangui

# **Synopsis**

```
#!/usr/bin/python
import passwdmanapi
code is_anystr(x)
is_bytestr(x)
is_int(x)
is_num(x)
is_unicodestr(x)
u(x)
b(x)
b2u3(x)
open_rng()
get64(length, pb=None)
get10(length, pb=None)
getint(a, b, pb=None)
unquote(x)
randomize(method, minlength, maxlength, pb=None)
undo(passwdobj=None, honeypotobj=None)
redo(passwdobj=None, honeypotobj=None)
no_pb()
no_pb_f(percent, data)
class progress_bar()
class common_data()
class passwd(common_data)
class honeypot(common_data)
```

#### class progress\_bar():

```
__init__(self, start, stop, function, data=None)
progress(self, percent)
minibar(self, start, stop)
```

#### class common\_data():

```
__init__(self, xmlfile)
__iter__(self)
__next__(self)
next(self)
__getitem__(self, i)
__len__(self)
remove(self, x, xmlfile, element_name, attrib_name, is_numstring=False)
writexml(self, xmlfile, pb=None)
__del__(self)
```

#### passwd(common\_data):

```
__init__(self, backups=True)
add(self, name, value, m_type, m_minlength, m_maxlength, pb=None)
add_nometa(self, name, value)
remove(self, x, is_numstring=False)
__repr__(self)
mkindex(self, x, is_numstring=False)
update(self, index, pb=None)
update_meta(self, index, m_type, m_minlength, m_maxlength, pb=None)
```

### class honeypot(common\_data):

```
__init__(self, backups=True)
add(self, value)
remove(self, x, is_numstring=False)
pick(self, n=1, sep=",", log_vs_raise=True, pb=None)
pickl(self, n, log_vs_raise=True, pb=None)
pickf(self, n, **arg)
__repr__(self)
```

### **Exceptions**

```
class err_norandom(Exception)
class err_nolength(Exception)
class err_loaderr(Exception)
class err_notfound(Exception)
class err_duplicate(Exception)
class err_idiot(Exception)
class err_nometa(Exception)
```

### **DESCRIPTION**

```
Unless otherwise noted, xmlfile is a path.
```

```
pb is either None or a progress_bar object.
```

code is the encoding **passwdmanapi** will use to encode and decode. It is set on import, but can be changed.

is\_anystr() returns True if x is any kind of string, and False if x is not.

is\_bytestr() returns True if x is an encoded string/bytes, and False if x is not.

is\_int() returns True if x is an integer, and False if x is not.

is\_num() returns True if x is an integer or a float, and False if x is not.

is unicodestr() returns True if x is a decoded string/unicode, and False if x is not.

u() returns x as a unicode/decoded string.

b() returns x as a byte/encoded string.

b2u3() is the same as b() if the Python version is 2.x.

b2u3() is the same as u() if the Python version is 3.x.

open\_rng() opens random(4) (or urandom(4), if random could not be opened). Returns a file open for reading binary. Raises err\_norandom.

get10() and get64() returns a random string of length letters. get10() returns digits. get64() returns digits, big letters, small letters, underscores and exclamation marks. Raises err\_norandom and err\_nolength.

getint() returns a random integer >= a, <= b. Raises err\_norandom and err\_nolength.

unquote() returns the string x without its surrounding quotes. If the string is not surrounded be quotes, the string will be returned unchanged.

randomize() returns a random string with a length >= minlength and <= maxlength. If method is "10" randomize() will use get10(). If method is "64" randomize() will use get64().

undo() undoes the latest change to the password list or honey pot list, by restoring from the newest auto-generated backup. It requires passwdobj which is the passwd() object and honeypotobj which is the honeypot() object. Raises err\_idiot.

redo() redoes the latest undone change to the password list or honey pot list, by restoring from the newest auto-generated backup from undo(). Raises err\_idiot.

no\_pb() returns a No-op progress\_bar object (which calls no\_pb\_f() instead of a function that would actually do something).

no\_pb\_f() does nothing.

common\_data() is a class defining methods used by both passwd() and honeypot().

passwd() is a class for the password list. honeypot() is a class for the honey-pot list. See FILES.

## class progress\_bar():

The class progress\_bar() is a class for simple interface-independent progress-bars. The keyword-argument pb accepts a progress\_bar object. Only these functions have a pb argument:

- randomize()
- getint()
- get10()
- get64()
- common\_data.writexml()

- passwd.add()
- passwd.update()
- passwd.update\_meta()
- honeypot.pick()
- honeypot.pickl()
- honeypot.pickf()

no\_pb() is a useful function.

progress\_bar.\_\_init\_\_() creates a progress\_bar object. start and stop are floats in the range 0...100. function is a function that will update the progress-bar. It takes exactly two arguments. The first is the percentage and the other is data which defaults to None.

```
#
custom_function(percent, data)
#
```

\_\_len\_\_() returns the number of passwords/honeypots.

percent is a float in the range 0...100 and data is all other necessary data.

progress() updates the progress-bar.

minibar() creates a new progress\_bar with identical function and data. start is where in the parent object the child's 0% is and stop is where in the parent object the child's 100% is.

#### class common\_data():

```
__init__() will load the data from xmlfile. Raises err_loaderr.
__iter__() resets the index and returns self. __getitem__() returns the password/honeypot at i.
```

remove() removes the password/honeypot at x, which can be an integer or a stringed integer or the value of the password/honeypot, from the datastructure self and the file xmlfile.element\_name and attrib\_name tells it what elements in the XML file and attributes it should loop through, remove and find a match for x in. Set is\_numstring to True if x is a string containing digits. If you don't set it, then x will be treated as an index. Raises err notfound.

writexml() writes the datastructure self to the file xmlfile. It creates a backup of xmlfile to ~/.passwdman/undoable.

### class passwd(common\_data)

passwd() loads its data from the XML ~/.passwdman/passwords.

self[index]["name"] is the name/purpose of the password. self[index]["value"] is
the value of the password. self[index]["meta"]["minlength"] is the minimal length required for the password. self[index]["meta"]["maxlength"] is the maximal length allowed for the password. self[index]["meta"]["type"] is the type of the password, which
is one of:

- The password uses digits.
- The password uses big letters, small letters, digits, underscores and exclamation marks.

human The password is human generated.

If a password has no meta-data in ~/.passwdman/passwords, its minlength and maxlength will be zero, and its type will be "human".

Set backups to False in \_\_init\_\_() if you do not want passwd() to make any change undoable (as in can be undone not impossible).

passwd.add() and passwd.add\_nometa() adds a password for name with the value value. add\_nometa() adds a password without real meta-data while add() requires meta-data (the m\_type must be a string and m\_minlength and m\_maxlength can be either an integer or a stringed integer). add() allows value to be None which will make it randomize a value automatically. Raises err\_duplicate.

passwd.remove() removes the password x. x can be either a string matching a password's name or an integer (index) or a stringed integer. Set is\_numstring to True if x is a string containing digits. If you don't set it, then x will be treated as an index. Raises err notfound.

passwd.mkindex() find x and return an index. x can be either a string matching a password's name or a stringed integer (index). Set is\_numstring to True if x is a string containing digits. If you don't set it, then x will be treated as an index. Raises err\_notfound.

passwd.update() and passwd.update\_meta() updates the password at index automatically by generating a password of the right type and an acceptable length. update() uses the password's own metadata while update\_meta() gives the password new meta-data from m\_type, m\_minlength and m\_maxlength. m\_type must be a string, m\_minlength and m\_maxlength can be either an integer or a stringed integer. Raises err\_notfound, err\_idiot and err\_nometa.

#### class honeypot(common\_data)

The honey pots are weak passwords supposed to only be used as traps. It was a poor choice of name, but it grew legs and glued its feet to the ground. honeypot() loads its data from the XML ~/.passwdman/honeypots.self[index] is the value of the honeypot.

Set backups to False in \_\_init\_\_() if you do not want passwd() to make any change undoable (as in can be undone not impossible).

honeypot.add() adds a new honeypot with the value value. Raises err\_duplicate.

honeypot.remove() removes the honeypot x. x is either an index (integer) or a stringed integer or the value of the honeypot. Set  $is\_numstring$  to True if x is a string containing digits. If you don't set it, then x will be treated as an index. Raises  $err\_not found$ .

honeypot.pick() IS DEPRECATED AND WILL BE REMOVED 2015-01-01. honeypot.pick() picks n random honeypots and returns a string of honeypots separated with sep. If log\_vs\_raise is true, it will log an error if n is too big. If log\_vs\_raise is false, it will raise err idiot.

honeypot.pickl() picks n random honeypots and returns a list of honeypots. If log\_vs\_raise is true, it will log an error if n is too big. If log\_vs\_raise is false, it will raise err\_idiot.

honeypot.pickf() picks n random honeypots and returns a string. Arguments:

n Required.

pb Default is None. The progress bar.

pattern Default is single quote. "(['])"

replacement Default is to backslash-escape.

sep Default is single-quote---comma---single-quote. "', ""

head Default is single quote.

tail Default is single quote.

log\_vs\_raise Default is True.

The string is prepended with head and appended with tail. The honeypots are escaped with the regular expressions pattern and replacement, and separated with sep. If log\_vs\_raise is True then honeypot.pickf() will log an error if n is too big. It will pick fewer fake-passwords than it is supposed to. If log\_vs\_raise is False it will raise err\_idiot.

# **Exceptions**

err\_norandom is raised when neither random(4) or urandom(4) can be opened.

- open\_rng()
- get10()
- get64()
- getint()
- randomize()
- passwd.add()
- passwd.update()
- passwd.update\_meta()
- honeypot.pick()
- honeypot.pickl()
- honeypot.pickf()

err\_nolength is raised when a function is called with an invalid length.

- get64()
- get10()
- getint()

err\_loaderr is raised if data cannot be loaded from file.

- common data()
- passwd()
- honeypot()

err\_notfound is raised if index is out of range or if it cannot find a match.

- common\_data.remove()
- passwd.remove()
- passwd.mkindex()
- passwd.update()
- passwd.update\_meta()

• honeypot.remove()

err\_duplicate is raised if it is attempted to add a password with the same name as another or if its is attempted to add a honeypot with the same value as another.

- passwd.add()
- passwd.add\_nometa()
- honeypot.add()

err\_idiot is raised if the function was not used correctly.

- passwd.update\_meta()
- honeypot.pick()
- honeypot.pickl()
- honeypot.pickf()
- undo()
- redo()

err\_nometa is raised when meta-data is required, but the meta-data was nonexistent, corrupt or no good.

- randomize()
- passwd.add()
- passwd.update()

#### **BUGS**

- Single-backup mode actually requires TWO undos.
- honeypot.pick() is deprecated and will be removed 2015-01-01. A new honeypot.pick() will appear in 2015-02-01.

#### **FILES**

- ~/.passwdman/passwords is the XML file containing the passwords and their meta-data.
- ~/.passwdman/honeypots is the XML file containing the honeypots.
- ~/.passwdman/undoable/ is where the auto-generated backups live.

### **EXAMPLES**

```
$(bindir)/passwdmangui
$(bindir)/passwdmancli
$(bindir)/passwdmanrli
```

### **AUTHOR**

Written by Oskar Skog (oskar.skog.finland@gmail.com).

#### PASSWDMANAPI

Please send patches, questions, bug reports and wish-lists.					