NAME

ovn-nb - OVN Northbound database schema

This database is the interface between OVN and the cloud management system (CMS), such as OpenStack, running above it. The CMS produces almost all of the contents of the database. The **ovn-northd** program monitors the database contents, transforms it, and stores it into the **OVN_Southbound** database.

We generally speak of "the" CMS, but one can imagine scenarios in which multiple CMSes manage different parts of an OVN deployment.

External IDs

Each of the tables in this database contains a special column, named **external_ids**. This column has the same form and purpose each place it appears.

external_ids: map of string-string pairs

Key-value pairs for use by the CMS. The CMS might use certain pairs, for example, to identify entities in its own configuration that correspond to those in this database.

TABLE SUMMARY

The following list summarizes the purpose of each of the tables in the **OVN_Northbound** database. Each table is described in more detail on a later page.

Table Purpose

NB_Global Northbound configuration
Copp Control plane protection
Logical_Switch L2 logical switch

Logical_Switch_Port

L2 logical switch port

Forwarding_Group

forwarding group

Address_Set Address Sets
Port_Group Port Groups
Load_Balancer load balancer

Load_Balancer_Group

load balancer group

Load_Balancer_Health_Check

load balancer

ACL Access Control List (ACL) rule

Logical_Router L3 logical router

QoSQoS ruleMirrorMirror EntryMeterMeter entry

Meter_Band Band for meter entries

Logical_Router_Port

L3 logical router port

Logical_Router_Static_Route

Logical router static routes

Logical_Router_Policy

Logical router policies

NAT nules

DHCP_Options

DHCP options

ConnectionOVSDB client connections.DNSNative DNS resolutionSSLSSL configuration.

Gateway_Chassis

Gateway_Chassis configuration.

HA_Chassis_Group

 $HA_Chassis_Group\ configuration.$

HA_Chassis HA_Chassis configuration.

BFD BFD configuration.

Static_MAC_Binding


Static_MAC_Binding configuration.

Chassis_Template_Var

Chassis_Template_Var configuration.

TABLE RELATIONSHIPS

The following diagram shows the relationship among tables in the database. Each node represents a table. Tables that are part of the "root set" are shown with double borders. Each edge leads from the table that contains it and points to the table that its value represents. Edges are labeled with their column names, followed by a constraint on the number of allowed values: ? for zero or one, * for zero or more, + for one or more. Thick lines represent strong references; thin lines represent weak references.



NB Global TABLE

Northbound configuration for an OVN system. This table must have exactly one row.

```
Summary:
     Identity:
         name
                                                        string
     Status:
         nb_cfg
                                                         integer
         nb_cfg_timestamp
                                                        integer
         sb_cfg
                                                        integer
         sb_cfg_timestamp
                                                        integer
         hv_cfg
                                                        integer
         hv_cfg_timestamp
                                                        integer
     Common Columns:
         external_ids
                                                         map of string-string pairs
     Common options:
         options
                                                         map of string-string pairs
         Options for configuring OVS BFD:
             options: bfd-min-rx
                                                         optional string
             options: bfd-decay-min-rx
                                                        optional string
             options: bfd-min-tx
                                                        optional string
             options: bfd-mult
                                                        optional string
         options: mac prefix
                                                        optional string
         options: mac_binding_removal_limit
                                                        optional string, containing an integer, in range 0 to
                                                         4,294,967,295
         options: controller_event
                                                        optional string, either true or false
         options: northd_probe_interval
                                                        optional string
         options: ic_probe_interval
                                                        optional string
         options: nbctl_probe_interval
                                                        optional string
         options: northd_trim_timeout
                                                        optional string
         options: use_logical_dp_groups
                                                        optional string
         options: use_parallel_build
                                                        optional string
         options: ignore_lsp_down
                                                        optional string
         options: use_ct_inv_match
                                                        optional string
         options: default_acl_drop
                                                        optional string
         options: debug_drop_domain_id
                                                        optional string
         options : debug_drop_collector_set
                                                        optional string
                                                        optional string, either true or false
         options: use_common_zone
         Options for configuring interconnection route advertisement:
             options: ic-route-adv
                                                        optional string
             options: ic-route-learn
                                                        optional string
             options: ic-route-adv-default
                                                        optional string
             options: ic-route-learn-default
                                                        optional string
             options: ic-route-blacklist
                                                        optional string
     Connection Options:
         connections
                                                        set of Connections
         ssl
                                                        optional SSL
     Security Configurations:
                                                        boolean
         ipsec
     Read-only Options:
```

Details:

Identity:

options: max_tunid

optional string

name: string

The name of the OVN cluster, which uniquely identifies the OVN cluster throughout all OVN clusters supposed to interconnect with each other.

Status:

These columns allow a client to track the overall configuration state of the system.

nb cfg: integer

Sequence number for client to increment. When a client modifies any part of the northbound database configuration and wishes to wait for **ovn-northd** and possibly all of the hypervisors to finish applying the changes, it may increment this sequence number.

nb_cfg_timestamp: integer

The timestamp, in milliseconds since the epoch, when **ovn-northd** sees the latest **nb_cfg** and starts processing.

To print the timestamp as a human-readable date:

date -d "@\$(ovn-nbctl get NB_Global . nb_cfg_timestamp | sed 's/...\$//')"

sb_cfg: integer

Sequence number that **ovn-northd** sets to the value of **nb_cfg** after it finishes applying the corresponding configuration changes to the **OVN_Southbound** database.

sb_cfg_timestamp: integer

The timestamp, in milliseconds since the epoch, when **ovn-northd** finishes applying the corresponding configuration changes to the **OVN Southbound** database successfully.

hv_cfg: integer

Sequence number that **ovn-northd** sets to the smallest sequence number of all the chassis in the system, as reported in the **Chassis_Private** table in the southbound database. Thus, **hv_cfg** equals **nb_cfg** if all chassis are caught up with the northbound configuration (which may never happen, if any chassis is down). This value can regress, if a chassis was removed from the system and rejoins before catching up.

If there are no chassis, then **ovn-northd** copies **nb_cfg** to **hv_cfg**. Thus, in this case, the (nonexistent) hypervisors are always considered to be caught up. This means that hypervisors can be "caught up" even in cases where **sb_cfg** would show that the southbound database is not. To detect when both the hypervisors and the southbound database are caught up, a client should take the smaller of **sb_cfg** and **hv_cfg**.

hv_cfg_timestamp: integer

The largest timestamp, in milliseconds since the epoch, of the smallest sequence number of all the chassis in the system, as reported in the **Chassis_Private** table in the southbound database. In other words, this timestamp reflects the time when the slowest chassis catches up with the northbound configuration, which is useful for end-to-end control plane latency measurement.

Common Columns:

external_ids: map of string-string pairs

See External IDs at the beginning of this document.

Common options:

options: map of string-string pairs

This column provides general key/value settings. The supported options are described individually below.

Options for configuring OVS BFD:

These options apply when **ovn–controller** configures OVS BFD on tunnels interfaces. Please note these parameters refer to legacy OVS BFD implementation and not to OVN BFD one.

options: bfd-min-rx: optional string

BFD option min-rx value to use when configuring BFD on tunnel interfaces.

options: bfd-decay-min-rx: optional string

BFD option **decay-min-rx** value to use when configuring BFD on tunnel interfaces.

options: bfd-min-tx: optional string

BFD option **min-tx** value to use when configuring BFD on tunnel interfaces.

options: bfd-mult: optional string

BFD option **mult** value to use when configuring BFD on tunnel interfaces.

options : mac_prefix: optional string

Configure a given OUI to be used as prefix when L2 address is dynamically assigned, e.g. **00:11:22**

options: mac_binding_removal_limit: optional string, containing an integer, in range 0 to 4,294,967,295 MAC binding aging bulk removal limit. This limits how many rows can expire in a single transaction. Default value is 0 which is unlimited. When we hit the limit next batch removal is delayed by 5 s

options: controller_event: optional string, either true or false

Value set by the CMS to enable/disable ovn-controller event reporting. Traffic into OVS can raise a 'controller' event that results in a Controller_Event being written to the **Controller_Event** table in SBDB. When the CMS has seen the event and taken appropriate action, it can remove the corresponding row in **Controller_Event** table. The intention is for a CMS to see the events and take some sort of action. Please see the **Controller_Event** table in SBDB. It is possible to associate a meter to each controller event type in order to not overload the pinctrl thread under heavy load. Each event type relies on a meter with a defined name:

empty_lb_backends: event-elb

options: northd_probe_interval: optional string

The inactivity probe interval of the connection to the OVN Northbound and Southbound databases from **ovn-northd**, in milliseconds. If the value is zero, it disables the connection keepalive feature.

If the value is nonzero, then it will be forced to a value of at least 1000 ms.

options: ic_probe_interval: optional string

The inactivity probe interval of the connection to the OVN Northbound and Southbound databases from **ovn-ic**, in milliseconds. If the value is zero, it disables the connection keepalive feature.

If the value is nonzero, then it will be forced to a value of at least 1000 ms.

options : nbctl_probe_interval: optional string

The inactivity probe interval of the connection to the OVN Northbound database from **ovn-nbctl** utility, in milliseconds. If the value is zero, it disables the connection keepalive feature.

If the value is nonzero, then it will be forced to a value of at least 1000 ms.

If the value is less than zero, then the default inactivity probe interval for **ovn-nbctl** would be left intact (120000 ms).

options : northd_trim_timeout: optional string

When used, this configuration value specifies the time, in milliseconds, since the last **ovn-northd** active operation after which memory trimming is performed. By default this is set to 30000 (30 seconds).

options : use_logical_dp_groups: optional string

Note: This option is deprecated, the only behavior is to always combine logical flows by datapath groups. Changing the value or removing this option all toghether will have no effect.

ovn–northd combines logical flows that differs only by logical datapath into a single logical flow with logical datapath group attached.

options: use_parallel_build: optional string

If set to **true**, **ovn–northd** will attempt to compute logical flows in parallel.

Parallel computation is enabled only if the system has 4 or more cores/threads available to be used by ovn-northd.

The default value is false.

options: ignore_lsp_down: optional string

If set to false, ARP/ND reply flows for logical switch ports will be installed only if the port is up, i.e. claimed by a Chassis. If set to true, these flows are installed regardless of the status of the port, which can result in a situation that ARP request to an IP is resolved even before the relevant VM/container is running. For environments where this is not an issue, setting it to **true** can reduce the load and latency of the control plane. The default value is **true**.

options: use_ct_inv_match: optional string

If set to false, **ovn—northd** will not use the **ct.inv** field in any of the logical flow matches. The default value is true. If the NIC supports offloading OVS datapath flows but doesn't support offloading ct_state **inv** flag, then the datapath flows matching on this flag (either **+inv** or **-inv**) will not be offloaded. CMS should consider setting **use_ct_inv_match** to **false** in such cases. This results in a side effect of the invalid packets getting delivered to the destination VIF, which otherwise would have been dropped by **OVN**.

options : default_acl_drop: optional string

If set to **true**., **ovn—northd** will generate a logical flow to drop all traffic in the ACL stages. By default this option is set to **false**.

options: debug_drop_domain_id: optional string

If set to a 8-bit number and if **debug_drop_collector_set** is also configured, **ovn-northd** will add a **sample** action to every logical flow that contains a 'drop' action. The 8 most significant bits of the observation_domain_id field will be those specified in the **debug_drop_domain_id**. The 24 least significant bits of the observation_domain_id field will be the datapath's key.

The observation_point_id will be set to the first 32 bits of the logical flow's UUID.

options: debug drop collector set: optional string

If set to a 32-bit number **ovn-northd** will add a **sample** action to every logical flow that contains a 'drop' action. The sample action will have the specified collector_set_id. The value must match that of the local OVS configuration as described in **ovs-actions**(7).

options: use_common_zone: optional string, either true or false

Default value is **false**. If set to **true** the SNAT and DNAT happens in common zone, instead of happening in separate zones, depending on the configuration. However, this option breaks traffic when there is configuration of DGP + LB + SNAT on this LR. The value **true** should be used only in case of HWOL compatibility with GDP.

Options for configuring interconnection route advertisement:

These options control how routes are advertised between OVN deployments for interconnection. If enabled, **ovn-ic** from different OVN deployments exchanges routes between each other through the global **OVN_IC_Southbound** database. Only routers with ports connected to interconnection transit switches participate in route advertisement. For each of these routers, there are two types of routes to be advertised:

Firstly, the static routes configured in the router are advertised.

Secondly, the **networks** configured in the logical router ports that are not on the transit switches are advertised. These are considered as directly connected subnets on the router.

Link local prefixes (IPv4 169.254.0.0/16 and IPv6 FE80::/10) are never advertised.

The learned routes are added to the **static_routes** column of the **Logical_Router** table, with **exter-nal_ids:ic-learned-route** set to the uuid of the row in **Route** table of the **OVN_IC_Southbound** database.

options: ic-route-adv: optional string

A boolean value that enables route advertisement to the global **OVN_IC_Southbound** database. Default is **false**.

options: ic-route-learn: optional string

A boolean value that enables route learning from the global **OVN_IC_Southbound** database. Default is **false**.

options: ic-route-adv-default: optional string

A boolean value that enables advertising default route to the global **OVN_IC_Southbound** database. Default is **false**. This option takes effect only when option **ic-route-adv** is **true**.

options: ic-route-learn-default: optional string

A boolean value that enables learning default route from the global **OVN_IC_Southbound** database. Default is **false**. This option takes effect only when option **ic-route-learn** is **true**.

options: ic-route-blacklist: optional string

A string value contains a list of CIDRs delimited by ",". A route will not be advertised or learned if the route's prefix belongs to any of the CIDRs listed.

Connection Options:

connections: set of Connections

Database clients to which the Open vSwitch database server should connect or on which it should listen, along with options for how these connections should be configured. See the **Connection** table for more information.

ssl: optional SSL

Global SSL configuration.

Security Configurations:

ipsec: boolean

Tunnel encryption configuration. If this column is set to be true, all OVN tunnels will be encrypted with IPsec.

Read-only Options:

options: max_tunid: optional string

The maximum supported tunnel ID. Depends on types of encapsulation enabled in the cluster.

Copp TABLE

This table is used to define control plane protection policies, i.e., associate entries from table Meter to control protocol names.

Summary:

name string (must be unique within table) meters: arp optional string meters: arp-resolve optional string meters: dhcpv4-opts optional string meters: dhcpv6-opts optional string meters: dns optional string meters: event-elb optional string optional string meters: icmp4-error meters: icmp6-error optional string meters: igmp optional string meters: nd-na optional string meters: nd-ns optional string meters: nd-ns-resolve optional string meters: nd-ra-opts optional string meters: tcp-reset optional string meters: bfd optional string meters: reject optional string meters: svc-monitor optional string

map of string-string pairs external_ids

Details:

name: string (must be unique within table)

CoPP name.

meters: arp: optional string

Rate limiting meter for ARP packets (request/reply) used for learning neighbors.

meters: arp-resolve: optional string

Rate limiting meter for packets that require resolving the next-hop (through ARP).

meters: **dhcpv4-opts**: optional string

Rate limiting meter for packets that require adding DHCPv4 options.

meters: dhcpv6-opts: optional string

Rate limiting meter for packets that require adding DHCPv6 options.

meters: dns: optional string

Rate limiting meter for DNS query packets that need to be replied to.

meters: event-elb: optional string

Rate limiting meter for empty load balancer events.

meters: icmp4-error: optional string

Rate limiting meter for packets that require replying with an ICMP error.

meters: icmp6-error: optional string

Rate limiting meter for packets that require replying with an ICMPv6 error.

meters: igmp: optional string

Rate limiting meter for IGMP packets.

meters: nd-na: optional string

Rate limiting meter for ND neighbor advertisement packets used for learning neighbors.

meters : nd-ns: optional string

Rate limiting meter for ND neighbor solicitation packets used for learning neighbors.

meters: nd-ns-resolve: optional string

Rate limiting meter for packets that require resolving the next-hop (through ND).

meters: nd-ra-opts: optional string

Rate limiting meter for packets that require adding ND router advertisement options.

meters: tcp-reset: optional string

Rate limiting meter for packets that require replying with TCP RST packet.

meters: bfd: optional string

Rate limiting meter for BFD packets.

meters: reject: optional string

Rate limiting meter for packets that trigger a reject action

meters: svc-monitor: optional string

Rate limiting meter for packets that are arriving to service monitor MAC address.

external_ids: map of string-string pairs

Logical Switch TABLE

Each row represents one L2 logical switch.

There are two kinds of logical switches, that is, ones that fully virtualize the network (overlay logical switches) and ones that provide simple connectivity to physical networks (bridged logical switches). They work in the same way when providing connectivity between logical ports on same chassis, but differently when connecting remote logical ports. Overlay logical switches connect remote logical ports by tunnels, while bridged logical switches provide connectivity to remote ports by bridging the packets to directly connected physical L2 segments with the help of **localnet** ports. Each bridged logical switch has one or more **localnet** ports, which have only one special address **unknown**.

```
Summary:
     ports
                                                        set of Logical Switch Ports
     load balancer
                                                        set of weak reference to Load_Balancers
     load balancer group
                                                        set of Load Balancer Groups
                                                        set of ACLs
     acls
                                                        set of QoSes
     qos_rules
     dns records
                                                        set of weak reference to DNSes
     forwarding groups
                                                        set of Forwarding Groups
     Naming:
         name
                                                        string
         external_ids: neutron:network_name
                                                        optional string
     IP Address Assignment:
         other config: subnet
                                                        optional string
         other_config : exclude_ips
                                                        optional string
         other config: ipv6 prefix
                                                        optional string
         other_config: mac_only
                                                        optional string, either true or false
     IP Multicast Snooping Options:
         other config: mcast snoop
                                                        optional string, either true or false
         other config: mcast querier
                                                        optional string, either true or false
         other_config : mcast_flood_unregistered
                                                        optional string, either true or false
         other_config: mcast_table_size
                                                        optional string, containing an integer, in range 1 to
                                                        32,766
         other_config : mcast_idle_timeout
                                                        optional string, containing an integer, in range 15 to
                                                        3,600
         other_config: mcast_query_interval
                                                        optional string, containing an integer, in range 1 to
         other_config: mcast_query_max_response
                                                        optional string, containing an integer, in range 1 to 10
         other_config: mcast_eth_src
                                                        optional string
         other config: mcast ip4 src
                                                        optional string
         other_config: mcast_ip6_src
                                                        optional string
     Interconnection:
         other_config: interconn-ts
                                                        optional string
     Tunnel Key:
         other_config: requested-tnl-key
                                                        optional string, containing an integer, in range 1 to
                                                        16,777,215
                                                        optional weak reference to Copp
     copp
     Other options:
         other_config: vlan-passthru
                                                        optional string, either true or false
         other_config: broadcast-arps-to-all-routers
                                                        optional string, either true or false
     Common Columns:
         external ids
                                                        map of string-string pairs
```

ports: set of Logical_Switch_Ports

The logical ports connected to the logical switch.

It is an error for multiple logical switches to include the same logical port.

load_balancer: set of weak reference to Load_Balancers

Set of load balancers associated to this logical switch.

load balancer group: set of Load Balancer Groups

Set of load balancers groups associated to this logical switch.

acls: set of ACLs

Access control rules that apply to packets within the logical switch.

qos_rules: set of QoSes

QoS marking and metering rules that apply to packets within the logical switch.

dns_records: set of weak reference to DNSes

This column defines the DNS records to be used for resolving internal DNS queries within the logical switch by the native DNS resolver. Please see the **DNS** table.

forwarding groups: set of Forwarding Groups

Groups a set of logical port endpoints for traffic going out of the logical switch.

Naming:

These columns provide names for the logical switch. From OVN's perspective, these names have no special meaning or purpose other than to provide convenience for human interaction with the database. There is no requirement for the name to be unique. (For a unique identifier for a logical switch, use its row UUID.)

(Originally, **name** was intended to serve the purpose of a human-friendly name, but the Neutron integration used it to uniquely identify its own switch object, in the format **neutron**–*uuid*. Later on, Neutron started propagating the friendly name of a switch as **external_ids:neutron:network_name**. Perhaps this can be cleaned up someday.)

name: string

A name for the logical switch.

external_ids : neutron:network_name: optional string

Another name for the logical switch.

IP Address Assignment:

These options control automatic IP address management (IPAM) for ports attached to the logical switch. To enable IPAM for IPv4, set **other_config:subnet** and optionally **other_config:exclude_ips**. To enable IPAM for IPv6, set **other_config:ipv6_prefix**. IPv4 and IPv6 may be enabled together or separately.

To request dynamic address assignment for a particular port, use the **dynamic** keyword in the **addresses** column of the port's **Logical_Switch_Port** row. This requests both an IPv4 and an IPv6 address, if IPAM for IPv4 and IPv6 are both enabled.

other_config: subnet: optional string

Set this to an IPv4 subnet, e.g. **192.168.0.0/24**, to enable **ovn-northd** to automatically assign IP addresses within that subnet.

other_config: exclude_ips: optional string

To exclude some addresses from automatic IP address management, set this to a list of the IPv4 addresses or ..-delimited ranges to exclude. The addresses or ranges should be a subset of those in **other_config:subnet**.

Whether listed or not, **ovn-northd** will never allocate the first or last address in a subnet, such as 192.168.0.0 or 192.168.0.255 in 192.168.0.0/24.

Examples:

- 192.168.0.2 192.168.0.10
- 192.168.0.4 192.168.0.30..192.168.0.60 192.168.0.110..192.168.0.120
- 192.168.0.110..192.168.0.120 192.168.0.25..192.168.0.30 192.168.0.144

other_config: ipv6_prefix: optional string

Set this to an IPv6 prefix to enable **ovn-northd** to automatically assign IPv6 addresses using this prefix. The assigned IPv6 address will be generated using the IPv6 prefix and the MAC address (converted to an IEEE EUI64 identifier) of the port. The IPv6 prefix defined here should be a valid IPv6 address ending with ::.

Examples:

- aef0::
- bef0:1234:a890:5678::
- 8230:5678::

other_config: mac_only: optional string, either true or false

Value used to request to assign L2 address only if neither subnet nor ipv6_prefix are specified

IP Multicast Snooping Options:

These options control IP Multicast Snooping configuration of the logical switch. To enable IP Multicast Snooping set **other_config:mcast_snoop** to true. To enable IP Multicast Querier set **other_config:mcast_querier** to true. If IP Multicast Querier is enabled **other_config:mcast_eth_src** and **other_config:mcast_ip4_src** must be set.

other_config: mcast_snoop: optional string, either true or false

Enables/disables IP Multicast Snooping on the logical switch. Default: false.

other_config: mcast_querier: optional string, either true or false

Enables/disables IP Multicast Querier on the logical switch. Only applicable if **other_config:mcast snoop** is enabled. Default: **true**.

other_config: mcast_flood_unregistered: optional string, either true or false

Determines whether unregistered multicast traffic should be flooded or not. Only applicable if **other_config:mcast_snoop** is enabled. Default: **false**.

other_config : mcast_table_size: optional string, containing an integer, in range 1 to 32,766 Number of multicast groups to be stored. Default: 2048.

other_config : mcast_idle_timeout: optional string, containing an integer, in range 15 to 3,600 Configures the IP Multicast Snooping group idle timeout (in seconds). Default: 300 seconds.

other_config: mcast_query_interval: optional string, containing an integer, in range 1 to 3,600 Configures the IP Multicast Querier interval between queries (in seconds). Default: other_config:mcast_idle_timeout / 2.

other_config : mcast_query_max_response: optional string, containing an integer, in range 1 to 10 Configures the value of the "max-response" field in the multicast queries originated by the logical switch. Default: 1 second.

other_config : mcast_eth_src: optional string

Configures the source Ethernet address for queries originated by the logical switch.

other_config : mcast_ip4_src: optional string

Configures the source IPv4 address for queries originated by the logical switch.

other_config : mcast_ip6_src: optional string

Configures the source IPv6 address for queries originated by the logical switch.

Interconnection:

other_config: interconn-ts: optional string

The **name** of corresponding transit switch in **OVN_IC_Northbound** database. This kind of logical switch is created and controlled by **ovn-ic**.

Tunnel Key:

other_config: requested-tnl-key: optional string, containing an integer, in range 1 to 16,777,215

Configures the datapath tunnel key for the logical switch. Usually this is not needed because **ovn-northd** will assign an unique key for each datapath by itself. However, if it is configured, **ovn-northd** honors the configured value. The typical use case is for interconnection: the tunnel keys for transit switches need to be unique globally, so they are maintained in the global **OVN_IC_Southbound** database, and **ovn-ic** simply syncs the value from **OVN_IC_Southbound** through this config.

copp: optional weak reference to Copp

The control plane protection policy from table **Copp** used for metering packets sent to **ovn-controller** from ports of this logical switch.

Other options:

other_config: vlan-passthru: optional string, either true or false

Determines whether VLAN tagged incoming traffic should be allowed. Note that this may have security implications when enabled for a logical switch with a tag=0 localnet port. If not properly isolated from other localnet ports, fabric traffic that belongs to other tagged networks may be passed through such a port.

other_config: broadcast-arps-to-all-routers: optional string, either true or false

Determines whether arp requests and ipv6 neighbor solicitations should be sent to all routers and other switchports (default) or if it should only be sent to switchports where the ip/mac address is unknown. Setting this to false can significantly reduce the load if the logical switch can receive arp requests for ips it does not know about. However setting this to false also means that garps are no longer forwarded to all routers and therefor the mac bindings of the routers are no longer updated.

Common Columns:

external ids: map of string-string pairs

Logical Switch Port TABLE

addresses

DHCP:

port_security

dynamic_addresses

A port within an L2 logical switch.

```
Summary:
```

```
Core Features:
    name
                                                     string (must be unique within table)
    type
                                                     string
Options:
    options
                                                     map of string-string pairs
    Options for router ports:
         options: router-port
                                                     optional string
         options: nat-addresses
                                                     optional string
        options: exclude-lb-vips-from-garp
                                                     optional string
         options: arp_proxy
                                                     optional string
    Options for localnet ports:
        options: network_name
                                                     optional string
        options: ethtype
                                                     optional string
         options: localnet_learn_fdb
                                                     optional string, either true or false
    Options for l2gateway ports:
        options: network_name
                                                     optional string
         options: 12gateway-chassis
                                                     optional string
    Options for vtep ports:
        options: vtep-physical-switch
                                                     optional string
         options: vtep-logical-switch
                                                     optional string
    VMI (or VIF) Options:
         options: requested-chassis
                                                     optional string
        options: activation-strategy
                                                     optional string
        options: iface-id-ver
                                                     optional string
        options: qos_min_rate
                                                     optional string
         options: qos_max_rate
                                                     optional string
        options: qos_burst
                                                     optional string
         options: hostname
                                                     optional string
         VIF Plugging Options:
             options: vif-plug-type
                                                     optional string
             options: vif-plug-mtu-request
                                                     optional string
    Virtual port Options:
         options: virtual-ip
                                                     optional string
         options: virtual-parents
                                                     optional string
    IP Multicast Snooping Options:
         options: mcast_flood
                                                     optional string, either true or false
         options: mcast_flood_reports
                                                     optional string, either true or false
Containers:
    parent_name
                                                     optional string
    tag_request
                                                     optional integer, in range 0 to 4,095
                                                     optional integer, in range 1 to 4,095
    tag
Port State:
    up
                                                     optional boolean
    enabled
                                                     optional boolean
Addressing:
```

set of strings

set of strings

optional string

dhcpv4_options dhcpv6_options mirror_rules ha_chassis_group

Naming:

external_ids : neutron:port_name

Tunnel Key:

options: requested-tnl-key

Common Columns: external ids

map of string-string pairs

optional string

32,767

optional weak reference to DHCP Options optional weak reference to DHCP_Options

optional string, containing an integer, in range 1 to

set of weak reference to Mirrors

optional HA Chassis Group

Details: Core Features:

name: string (must be unique within table)

The logical port name.

For entities (VMs or containers) that are spawned in the hypervisor, the name used here must match those used in the external ids:iface-id in the Open vSwitch database's Interface table, because hypervisors use external_ids:iface-id as a lookup key to identify the network interface of that entity.

For containers that share a VIF within a VM, the name can be any unique identifier. See Containers, below, for more information.

A logical switch port may not have the same name as a logical router port, but the database schema cannot enforce this.

type: string

Specify a type for this logical port. Logical ports can be used to model other types of connectivity into an OVN logical switch. The following types are defined:

(empty string)

A VM (or VIF) interface.

router A connection to a logical router. The value of options:router-port specifies the name of the Logical_Router_Port to which this logical switch port is connected.

localnet

A connection to a locally accessible network from **ovn-controller** instances that have a corresponding bridge mapping. A logical switch can have multiple localnet ports attached. This type is used to model direct connectivity to existing networks. In this case, each chassis should have a mapping for one of the physical networks only. Note: nothing said above implies that a chassis cannot be plugged to multiple physical networks as long as they belong to different switches.

localport

A connection to a local VIF. Traffic that arrives on a **localport** is never forwarded over a tunnel to another chassis. These ports are present on every chassis and have the same address in all of them. This is used to model connectivity to local services that run on every hypervisor.

12gateway

A connection to a physical network.

vtep A port to a logical switch on a VTEP gateway.

external

Represents a logical port which is external and not having an OVS port in the integration bridge. **OVN** will never receive any traffic from this port or send any traffic to this port. OVN can support native services like DHCPv4/DHCPv6/DNS for this port. If **ha_chassis_group** is defined, **ovn-controller** running in the master chassis of the HA chassis group will bind this port to provide these native services. It is expected that this port belong to a bridged logical switch (with a **localnet** port).

It is recommended to use the same HA chassis group for all the external ports of a logical switch. Otherwise, the physical switch might see MAC flap issue when different chassis provide the native services. For example when supporting native DHCPv4 service, DHCPv4 server mac (configured in **options:server_mac** column in table **DHCP_Options**) originating from different ports can cause MAC flap issue. The MAC of the logical router IP(s) can also flap if the same HA chassis group is not set for all the external ports of a logical switch.

Below are some of the use cases where **external** ports can be used.

- VMs connected to SR-IOV nics Traffic from these VMs by passes the kernel stack and local **ovn-controller** do not bind these ports and cannot serve the native services.
- When CMS supports provisioning baremetal servers.

virtual Represents a logical port which does not have an OVS port in the integration bridge and has a virtual ip configured in the **options:virtual-ip** column. This virtual ip can move around between the logical ports configured in the **options:virtual-parents** column.

One of the use case where **virtual** ports can be used is.

 The virtual ip represents a load balancer vip and the virtual parents provide load balancer service in an active-standby setup with the active virtual parent owning the virtual ip.

remote A remote port is to model a port that resides remotely on another OVN, which is on the other side of a transit logical switch for OVN interconnection. This type of ports are created by **ovn-ic** instead of by CMS. Any change to the port will be automatically overwritten by **ovn-ic**.

Options:

options: map of string-string pairs

This column provides key/value settings specific to the logical port **type**. The type-specific options are described individually below.

Options for router ports:

These options apply when **type** is **router**.

options: router-port: optional string

Required. The name of the Logical_Router_Port to which this logical switch port is connected.

options: nat-addresses: optional string

This is used to send gratuitous ARPs for SNAT and DNAT IP addresses via the **localnet** port that is attached to the same logical switch as this type **router** port. This option is specified on a logical switch port that is connected to a gateway router, or a logical switch port that is connected to a distributed gateway port on a logical router.

This must take one of the following forms:

router Gratuitous ARPs will be sent for all SNAT and DNAT external IP addresses and for all load balancer IP addresses defined on the **options:router-port**'s logical router, using the **options:router-port**'s MAC address.

This form of **options:nat-addresses** is valid for logical switch ports where **options:router-port** is the name of a port on a gateway router, or the name of a distributed gateway port.

Supported only in OVN 2.8 and later. Earlier versions required NAT addresses to be manually synchronized.

Ethernet address followed by one or more IPv4 addresses

Example: **80:fa:5b:06:72:b7 158.36.44.22 158.36.44.24**. This would result in generation of gratuitous ARPs for IP addresses 158.36.44.22 and 158.36.44.24 with a MAC address of 80:fa:5b:06:72:b7.

This form of **options:nat-addresses** is only valid for logical switch ports where **options:router-port** is the name of a port on a gateway router.

options: exclude-lb-vips-from-garp: optional string

If **options:nat-addresses** is set to **router**, Gratuitous ARPs will be sent for all SNAT and DNAT external IP addresses defined on the **options:router-port**'s logical router, using the **options:router-port**'s MAC address, not cosidering configured load balancers.

options : arp_proxy: optional string

Optional. A list of MAC and addresses/cidrs or just addresses/cidrs that this logical switch **router** port will reply to ARP/NDP requests. Examples: **169.254.239.254 169.254.239.2**, **0a:58:a9:fe:01:01 169.254.239.254 169.254.239.2 169.254.238.0/24**, **fd7b:6b4d:7b25:d22f::1 fd7b:6b4d:7b25:d22f::2**, **0a:58:a9:fe:01:01 fd7b:6b4d:7b25:d22f::0/64**. Theoptions:routerport's logical router should have a route to forward packets sent to configured proxy ARP MAC/IPs to an appropriate destination.

Options for localnet ports:

These options apply when **type** is **localnet**.

options: network name: optional string

Required. The name of the network to which the **localnet** port is connected. Each hypervisor, via **ovn–controller**, uses its local configuration to determine exactly how to connect to this locally accessible network, if at all.

options: ethtype: optional string

Optional. VLAN EtherType field value for encapsulating VLAN headers. Supported values: 802.1q (default), 802.1ad.

options: localnet_learn_fdb: optional string, either true or false

Optional. Allows localnet port to learn MACs and store them in FDB table if set to **true**. The default value is **false**.

Options for l2gateway ports:

These options apply when type is l2gateway.

options : network_name: optional string

Required. The name of the network to which the **l2gateway** port is connected. The L2 gateway, via **ovn-controller**, uses its local configuration to determine exactly how to connect to this network.

options: l2gateway-chassis: optional string

Required. The chassis on which the **l2gateway** logical port should be bound to. **ovn-controller** running on the defined chassis will connect this logical port to the physical network.

Options for vtep ports:

These options apply when **type** is **vtep**.

options: vtep-physical-switch: optional string

Required. The name of the VTEP gateway.

options: vtep-logical-switch: optional string

Required. A logical switch name connected by the VTEP gateway.

VMI (or VIF) Options:

These options apply to logical ports with **type** having (empty string)

options: requested-chassis: optional string

If set, identifies a specific chassis (by name or hostname) that is allowed to bind this port. Using this option will prevent thrashing between two chassis trying to bind the same port during a live migration. It can also prevent similar thrashing due to a mis-configuration, if a port is accidentally created on more than one chassis.

If set to a comma separated list, the first entry identifies the main chassis and the rest are one or more additional chassis that are allowed to bind the same port.

When multiple chassis are set for the port, and the logical switch is connected to an external network through a **localnet** port, tunneling is enforced for the port to guarantee delivery of packets directed to the port to all its locations. This has MTU implications because the network used for tunneling must have MTU larger than **localnet** for stable connectivity.

If the same host co-hosts more than one controller instance (either belonging to the same or separate clusters), special attention should be given to consistently using unique chassis names used in this option. It is advised that chassis names - and not host names - are used for this option.

options: activation-strategy: optional string

If used with multiple chassis set in **requested-chassis**, specifies an activation strategy for all additional chassis. By default, no activation strategy is used, meaning additional port locations are immediately available for use. When set to "rarp", the port is blocked for ingress and egress communication until a RARP packet is sent from a new location. The "rarp" strategy is useful in live migration scenarios for virtual machines.

options: iface-id-ver: optional string

If set, this port will be bound by **ovn–controller** only if this same key and value is configured in the **external_ids** column in the Open_vSwitch database's **Interface** table.

options: gos min rate: optional string

If set, indicates the minimum guaranteed rate available for data sent from this interface, in bit/s.

options: qos_max_rate: optional string

If set, indicates the maximum rate for data sent from this interface, in bit/s. The traffic will be shaped according to this limit.

options: qos_burst: optional string

If set, indicates the maximum burst size for data sent from this interface, in bits.

options: hostname: optional string

If set, indicates the DHCPv4 option "Hostname" (option code 12) associated for this Logical Switch Port. If DHCPv4 is enabled for this Logical Switch Port, hostname dhcp option will be included in DHCP reply.

VIF Plugging Options:

options: vif-plug-type: optional string

If set, OVN will attempt to perform plugging of this VIF. In order to get this port plugged by the OVN controller, OVN must be built with support for VIF plugging. The default behavior is for the CMS to do the VIF plugging. Each VIF plug provider have their own options namespaced by name, for example "vif-plug:representor:key". Please refer to the VIF plug provider documentation located in Documentation/topics/vif-plug-providers/ for more information.

options: vif-plug-mtu-request: optional string

Requested MTU for plugged interfaces. When set the OVN controller will fill the **mtu_request** column of the Open vSwitch database's **Interface** table. This in turn will make OVS vswitchd update the MTU of the linked interface.

Virtual port Options:

These options apply when **type** is **virtual**.

options: virtual-ip: optional string

This option represents the virtual IPv4 address.

options: virtual-parents: optional string

This options represents a set of logical port names (with in the same logical switch) which can own the **virtual ip** configured in the **options:virtual-ip**. All these virtual parents should add the **virtual ip** in the **port_security** if port security addressed are enabled.

IP Multicast Snooping Options:

These options apply when the port is part of a logical switch which has **other_config** :mcast_snoop set to **true**.

options : mcast_flood: optional string, either true or false

If set to **true**, multicast packets (except reports) are unconditionally forwarded to the specific port. Default: **false**.

options: mcast_flood_reports: optional string, either true or false

If set to **true**, multicast reports are unconditionally forwarded to the specific port. Default: **false**.

Containers:

When a large number of containers are nested within a VM, it may be too expensive to dedicate a VIF to each container. OVN can use VLAN tags to support such cases. Each container is assigned a VLAN ID and each packet that passes between the hypervisor and the VM is tagged with the appropriate ID for the container. Such VLAN IDs never appear on a physical wire, even inside a tunnel, so they need not be unique except relative to a single VM on a hypervisor.

These columns are used for VIFs that represent nested containers using shared VIFs. For VMs and for containers that have dedicated VIFs, they are empty.

parent_name: optional string

The VM interface through which the nested container sends its network traffic. This must match the **name** column for some other **Logical_Switch_Port**.

tag_request: optional integer, in range 0 to 4,095

The VLAN tag in the network traffic associated with a container's network interface. The client can request **ovn-northd** to allocate a tag that is unique within the scope of a specific parent (specified in **parent_name**) by setting a value of **0** in this column. The allocated value is written by **ovn-northd** in the **tag** column. (Note that these tags are allocated and managed locally in **ovn-northd**, so they cannot be reconstructed in the event that the database is lost.) The client can also request a specific non-zero tag and **ovn-northd** will honor it and copy that value to the **tag** column.

When **type** is set to **localnet** or **l2gateway**, this can be set to indicate that the port represents a connection to a specific VLAN on a locally accessible network. The VLAN ID is used to match incoming traffic and is also added to outgoing traffic.

tag: optional integer, in range 1 to 4,095

The VLAN tag allocated by **ovn-northd** based on the contents of the **tag_request** column.

Port State:

up: optional boolean

This column is populated by **ovn-northd**, rather than by the CMS plugin as is most of this database. When a logical port is bound to a physical location in the OVN Southbound database **Binding** table, **ovn-northd** sets this column to **true**; otherwise, or if the port becomes unbound later, it sets it to **false**. If this column is empty, the port is not considered up. This allows the CMS to wait for a VM's (or container's) networking to become active before it allows the VM (or container) to start.

Logical ports of router type are an exception to this rule. They are considered to be always up, that is this column is always set to **true**.

enabled: optional boolean

This column is used to administratively set port state. If this column is empty or is set to **true**, the port is enabled. If this column is set to **false**, the port is disabled. A disabled port has all ingress and egress traffic dropped.

Addressing:

addresses: set of strings

Addresses owned by the logical port.

Each element in the set must take one of the following forms:

Ethernet address followed by zero or more IPv4 or IPv6 addresses (or both)

An Ethernet address defined is owned by the logical port. Like a physical Ethernet NIC, a logical port ordinarily has a single fixed Ethernet address.

When a OVN logical switch processes a unicast Ethernet frame whose destination MAC address is in a logical port's **addresses** column, it delivers it only to that port, as if a MAC learning process had learned that MAC address on the port.

If IPv4 or IPv6 address(es) (or both) are defined, it indicates that the logical port owns the given IP addresses.

If IPv4 address(es) are defined, the OVN logical switch uses this information to synthesize responses to ARP requests without traversing the physical network. The OVN logical router connected to the logical switch, if any, uses this information to avoid issuing ARP requests for logical switch ports.

Note that the order here is important. The Ethernet address must be listed before the IP address(es) if defined.

Examples:

80:fa:5b:06:72:b7

This indicates that the logical port owns the above mac address.

80:fa:5b:06:72:b7 10.0.0.4 20.0.0.4

This indicates that the logical port owns the mac address and two IPv4 addresses.

80:fa:5b:06:72:b7 fdaa:15f2:72cf:0:f816:3eff:fe20:3f41

This indicates that the logical port owns the mac address and 1 IPv6 address.

80:fa:5b:06:72:b7 10.0.0.4 fdaa:15f2:72cf:0:f816:3eff:fe20:3f41

This indicates that the logical port owns the mac address and 1 IPv4 address and 1 IPv6 address.

unknown

This indicates that the logical port has an unknown set of Ethernet addresses. When an OVN logical switch processes a unicast Ethernet frame whose destination MAC address is not in any logical port's **addresses** column, it delivers it to the port (or ports) whose **addresses** columns include **unknown**.

dynamic

Use **dynamic** to make **ovn-northd** generate a globally unique MAC address, choose an unused IPv4 address with the logical port's subnet (if **other_config:subnet** is set in the port's **Logical_Switch**), and generate an IPv6 address from the MAC address (if **other_config:ipv6_prefix** is set in the port's **Logical_Switch**) and store them in the port's **dynamic_addresses** column.

Only one element containing **dynamic** may appear in **addresses**.

dynamic ip

dynamic *ipv6* **dynamic** *ip ipv6*

These act like **dynamic** alone but specify particular IPv4 or IPv6 addresses to use. OVN IPAM will still automatically allocate the other address if configured appropriately. Example: **dynamic 192.168.0.1 2001::1**.

mac dynamic

This acts like **dynamic** alone but specifies a particular MAC address to use. OVN IPAM will still automatically allocate IPv4 or IPv6 addresses, or both, if configured appropriately. Example: **80:fa:5b:06:72:b7 dynamic**

router Accepted only when **type** is **router**. This indicates that the Ethernet, IPv4, and IPv6 addresses for this logical switch port should be obtained from the connected logical router port, as specified by **router-port** in **options**.

The resulting addresses are used to populate the logical switch's destination lookup, and also for the logical switch to generate ARP and ND replies.

If the connected logical router port has a distributed gateway port specified and the logical router has rules specified in **nat** with **external_mac**, then those addresses are also used to populate the switch's destination lookup.

Supported only in OVN 2.7 and later. Earlier versions required router addresses to be manually synchronized.

dynamic addresses: optional string

Addresses assigned to the logical port by **ovn-northd**, if **dynamic** is specified in **addresses**. Addresses will be of the same format as those that populate the **addresses** column. Note that dynamically assigned addresses are constructed and managed locally in ovn-northd, so they cannot be reconstructed in the event that the database is lost.

port security: set of strings

This column controls the addresses from which the host attached to the logical port ("the host") is allowed to send packets and to which it is allowed to receive packets. If this column is empty, all addresses are permitted.

Each element in the set must begin with one Ethernet address. This would restrict the host to sending packets from and receiving packets to the ethernet addresses defined in the logical port's **port_security** column. It also restricts the inner source MAC addresses that the host may send in ARP and IPv6 Neighbor Discovery packets. The host is always allowed to receive packets to multicast and broadcast Ethernet addresses.

Each element in the set may additionally contain one or more IPv4 or IPv6 addresses (or both), with optional masks. If a mask is given, it must be a CIDR mask. In addition to the restrictions described for Ethernet addresses above, such an element restricts the IPv4 or IPv6 addresses from which the host may send and to which it may receive packets to the specified addresses. A masked address, if the host part is zero, indicates that the host is allowed to use any address in the subnet; if the host part is nonzero, the mask simply indicates the size of the subnet. In addition:

- If any IPv4 address is given, the host is also allowed to receive packets to the IPv4 local broadcast address 255.255.255.255 and to IPv4 multicast addresses (224.0.0.0/4). If an IPv4 address with a mask is given, the host is also allowed to receive packets to the broadcast address in that specified subnet.
 - If any IPv4 address is given, the host is additionally restricted to sending ARP packets with the specified source IPv4 address. (RARP is not restricted.)
- If any IPv6 address is given, the host is also allowed to receive packets to IPv6 multicast addresses (ff00::/8).

If any IPv6 address is given, the host is additionally restricted to sending IPv6 Neighbor Discovery Solicitation or Advertisement packets with the specified source address or, for

solicitations, the unspecified address.

If an element includes an IPv4 address, but no IPv6 addresses, then IPv6 traffic is not allowed. If an element includes an IPv6 address, but no IPv4 address, then IPv4 and ARP traffic is not allowed.

This column uses the same lexical syntax as the **match** column in the OVN Southbound database's **Pipeline** table. Multiple addresses within an element may be space or comma separated.

This column is provided as a convenience to cloud management systems, but all of the features that it implements can be implemented as ACLs using the ACL table.

Examples:

80:fa:5b:06:72:b7

The host may send traffic from and receive traffic to the specified MAC address, and to receive traffic to Ethernet multicast and broadcast addresses, but not otherwise. The host may not send ARP or IPv6 Neighbor Discovery packets with inner source Ethernet addresses other than the one specified.

80:fa:5b:06:72:b7 192.168.1.10/24

This adds further restrictions to the first example. The host may send IPv4 packets from or receive IPv4 packets to only 192.168.1.10, except that it may also receive IPv4 packets to 192.168.1.255 (based on the subnet mask), 255.255.255.255, and any address in 224.0.0.0/4. The host may not send ARPs with a source Ethernet address other than 80:fa:5b:06:72:b7 or source IPv4 address other than 192.168.1.10. The host may not send or receive any IPv6 (including IPv6 Neighbor Discovery) traffic.

"80:fa:5b:12:42:ba", "80:fa:5b:06:72:b7 192.168.1.10/24"

The host may send traffic from and receive traffic to the specified MAC addresses, and to receive traffic to Ethernet multicast and broadcast addresses, but not otherwise. With MAC 80:fa:5b:12:42:ba, the host may send traffic from and receive traffic to any L3 address. With MAC 80:fa:5b:06:72:b7, the host may send IPv4 packets from or receive IPv4 packets to only 192.168.1.10, except that it may also receive IPv4 packets to 192.168.1.255 (based on the subnet mask), 255.255.255.255, and any address in 224.0.0.0/4. The host may not send or receive any IPv6 (including IPv6 Neighbor Discovery) traffic.

DHCP:

dhcpv4_options: optional weak reference to DHCP_Options

This column defines the DHCPv4 Options to be included by the **ovn–controller** when it replies to the DHCPv4 requests. Please see the **DHCP_Options** table.

dhcpv6_options: optional weak reference to DHCP_Options

This column defines the DHCPv6 Options to be included by the **ovn–controller** when it replies to the DHCPv6 requests. Please see the **DHCP_Options** table.

mirror_rules: set of weak reference to Mirrors

Mirror rules that apply to logical switch port which is the source. Please see the **Mirror** table.

ha chassis group: optional HA Chassis Group

References a row in the OVN Northbound database's **HA_Chassis_Group** table. It indicates the HA chassis group to use if the **type** is set to **external**. If **type** is not **external**, this column is ignored.

Naming:

external_ids : neutron:port_name: optional string

This column gives an optional human-friendly name for the port. This name has no special meaning or purpose other than to provide convenience for human interaction with the northbound database.

Neutron copies this from its own port object's name. (Neutron ports do are not assigned human-friendly names by default, so it will often be empty.)

Tunnel Key:

options: requested-tnl-key: optional string, containing an integer, in range 1 to 32,767

Configures the port binding tunnel key for the port. Usually this is not needed because **ovn—northd** will assign an unique key for each port by itself. However, if it is configured, **ovn—northd** honors the configured value. The typical use case is for interconnection: the tunnel keys for ports on transit switches need to be unique globally, so they are maintained in the global **OVN_IC_Southbound** database, and **ovn—ic** simply syncs the value from **OVN_IC_Southbound** through this config.

Common Columns:

external_ids: map of string-string pairs

See External IDs at the beginning of this document.

The **ovn-northd** program copies all these pairs into the **external_ids** column of the **Port_Binding** table in **OVN_Southbound** database.

Forwarding_Group TABLE

Each row represents one forwarding group.

Summary:

namestringvipstringvmacstringlivenessboolean

child_port set of 1 or more strings

Common Columns:

external_ids map of string-string pairs

Details:

name: string

A name for the forwarding group. This name has no special meaning or purpose other than to provide convenience for human interaction with the ovn-nb database.

vip: string

The virtual IP address assigned to the forwarding group. It will respond with vmac when an ARP request is sent for vip.

vmac: string

The virtual MAC address assigned to the forwarding group.

liveness: boolean

If set to **true**, liveness is enabled for child ports otherwise it is disabled.

child_port: set of 1 or more strings

List of child ports in the forwarding group.

Common Columns:

external_ids: map of string-string pairs

Address Set TABLE

Each row in this table represents a named set of addresses. An address set may contain Ethernet, IPv4, or IPv6 addresses with optional bitwise or CIDR masks. Address set may ultimately be used in ACLs to compare against fields such as **ip4.src** or **ip6.src**. A single address set must contain addresses of the same type. As an example, the following would create an address set with three IP addresses:

ovn-nbctl create Address_Set name=set1 addresses='10.0.0.1 10.0.0.2 10.0.0.3'

Address sets may be used in the **match** column of the **ACL** table. For syntax information, see the details of the expression language used for the **match** column in the **Logical_Flow** table of the **OVN_Southbound** database.

Summary:

name string (must be unique within table)

addresses set of strings

Common Columns:

external_ids map of string-string pairs

Details:

name: string (must be unique within table)

A name for the address set. Names are ASCII and must match [a-zA-Z_.][a-zA-Z_.0-9]*.

addresses: set of strings

The set of addresses in string form.

Common Columns:

external_ids: map of string-string pairs

Port_Group TABLE

Each row in this table represents a named group of logical switch ports.

Port groups may be used in the **match** column of the **ACL** table. For syntax information, see the details of the expression language used for the **match** column in the **Logical_Flow** table of the **OVN_Southbound** database.

For each port group, there are two address sets generated to the **Address_Set** table of the **OVN_South-bound** database, containing the IP addresses of the group of ports, one for IPv4, and the other for IPv6, with **name** being the **name** of the **Port_Group** followed by a suffix **_ip4** for IPv4 and **_ip6** for IPv6. The generated address sets can be used in the same way as regular address sets in the **match** column of the **ACL** table. For syntax information, see the details of the expression language used for the **match** column in the **Logical Flow** table of the **OVN Southbound** database.

Summary:

name string (must be unique within table)

ports set of weak reference to Logical_Switch_Ports

acls set of ACLs

Common Columns:

external_ids map of string-string pairs

Details:

name: string (must be unique within table)

A name for the port group. Names are ASCII and must match [a-zA-Z_.][a-zA-Z_.0-9]*.

ports: set of weak reference to Logical_Switch_Ports

The logical switch ports belonging to the group in uuids.

acls: set of ACLs

Access control rules that apply to the port group. Applying an ACL to a port group has the same effect as applying the ACL to all logical lswitches that the ports of the port group belong to.

Common Columns:

external_ids: map of string-string pairs

Load Balancer TABLE

Each row represents one load balancer.

Summary:

```
name string
vips map of string-string pairs
protocol optional string, one of sctp, tcp, or udp

Health Checks:
health_check set of Load_Balancer_Health_Checks
ip_port_mappings map of string-string pairs
```

Common Columns:

selection_fields

external_ids map of string-string pairs

Load_Balancer options:

options : rejectoptional string, either true or falseoptions : hairpin_snat_ipoptional stringoptions : skip_snatoptional stringoptions : add_routeoptional string

options : add_routeoptional stringoptions : neighbor_responderoptional stringoptions : templateoptional stringoptions : address-familyoptional stringoptions : affinity_timeoutoptional string

options : ct_flush optional string, either true or false

Details:

name: string

A name for the load balancer. This name has no special meaning or purpose other than to provide convenience for human interaction with the ovn-nb database.

tp_dst, or tp_src

set of strings, one of eth_dst, eth_src, ip_dst, ip_src,

vips: map of string-string pairs

A map of virtual IP addresses (and an optional port number with: as a separator) associated with this load balancer and their corresponding endpoint IP addresses (and optional port numbers with: as separators) separated by commas. If the destination IP address (and port number) of a packet leaving a container or a VM matches the virtual IP address (and port number) provided here as a key, then OVN will statefully replace the destination IP address by one of the provided IP address (and port number) in this map as a value. IPv4 and IPv6 addresses are supported for load balancing; however a VIP of one address family may not be mapped to a destination IP address of a different family. If specifying an IPv6 address with a port, the address portion must be enclosed in square brackets. Examples for keys are "192.168.1.4" and "[fd0f::1]:8800". Examples for value are "10.0.0.1, 10.0.0.2" and "20.0.0.10:8800, 20.0.0.11:8800".

When the **Load_Balancer** is added to the **logical_switch**, the VIP has to be in a different subnet than the one used for the **logical_switch**. Since VIP is in a different subnet, you should connect your logical switch to either a OVN logical router or a real router (this is because the client can now send a packet with VIP as the destination IP address and router's mac address as the destination MAC address).

protocol: optional string, one of sctp, tcp, or udp

Valid protocols are **tcp**, **udp**, or **sctp**. This column is useful when a port number is provided as part of the **vips** column. If this column is empty and a port number is provided as part of **vips** column, OVN assumes the protocol to be **tcp**.

Health Checks:

OVN supports health checks for load balancer endpoints. When health checks are enabled, the load balancer uses only healthy endpoints.

Suppose that vips contains a key-value pair 10.0.0.10:80=10.0.0.4:8080,20.0.0.4:8080. To enable health

checks for this virtual's endpoints, add two key-value pairs to **ip_port_mappings**, with keys **10.0.0.4** and **20.0.0.4**, and add to **health_check** a reference to a **Load_Balancer_Health_Check** row whose **vip** is set to **10.0.0.10**. The same approach can be used for IPv6 as well.

health_check: set of Load_Balancer_Health_Checks

Load balancer health checks associated with this load balancer.

ip port mappings: map of string-string pairs

Maps from endpoint IP to a colon-separated pair of logical port name and source IP, e.g. *port_name:sourc_ip* for IPv4. Health checks are sent to this port with the specified source IP. For IPv6 square brackets must be used around IP address, e.g. *port_name:[sourc_ip]*

For example, in the example above, IP to port mappings might be defined as 10.0.0.4=sw0-p1:10.0.0.2 and 20.0.0.4=sw1-p1:20.0.0.2, if the values given were suitable ports and IP addresses.

For IPv6 IP to port mappings might be defined as [2001::1]=sw0-p1:[2002::1].

selection fields: set of strings, one of eth dst, eth src, ip dst, ip src, tp dst, or tp src

OVN native load balancers are supported using the OpenFlow groups of type **select**. OVS supports two selection methods: **dp_hash** and **hash** (**with optional fields specified**) in selecting the buckets of a group. Please see the OVS documentation (man ovs-ofctl) for more details on the selection methods. Each endpoint IP (and port if set) is mapped to a bucket in the group flow.

CMS can choose the **hash** selection method by setting the selection fields in this column. **ovs-vswitchd** uses the specified fields in generating the hash.

dp_hash selection method uses the assistance of datapath to calculate the hash and it is expected to be faster than **hash** selection method. So CMS should take this into consideration before using the **hash** method. Please consult the OVS documentation and OVS sources for the implementation details.

Common Columns:

external_ids: map of string-string pairs

See External IDs at the beginning of this document.

Load Balancer options:

options: reject: optional string, either true or false

If the load balancer is created with —**reject** option and it has no active backends, a TCP reset segment (for tcp) or an ICMP port unreachable packet (for all other kind of traffic) will be sent whenever an incoming packet is received for this load-balancer. Please note using —**reject** option will disable empty_lb SB controller event for this load balancer.

options : hairpin_snat_ip: optional string

IP to be used as source IP for packets that have been hair-pinned after load balancing. The default behavior when the option is not set is to use the load balancer VIP as source IP. This option may have exactly one IPv4 and/or one IPv6 address on it, separated by a space character.

options: skip_snat: optional string

If the load balancing rule is configured with **skip_snat** option, the option lb_force_snat_ip configured for the logical router that references this load balancer will not be applied for this load balancer.

options: add_route: optional string

If set to **true**, then neighbor routers will have logical flows added that will allow for routing to the VIP IP. It also will have ARP resolution logical flows added. By setting this option, it means there is no reason to create a **Logical_Router_Static_Route** from neighbor routers to this NAT address. It also means that no ARP request is required for neighbor routers to learn the IP-MAC mapping for this VIP IP. For more information about what flows are added for IP routes, please see the **ovn—northd** manpage section on IP Routing.

options: neighbor_responder: optional string

If set to **all**, then routers on which the load balancer is applied reply to ARP/neighbor discovery requests for all VIPs of the load balancer. If set to **reachable**, then routers on which the load balancer is applied reply to ARP/neighbor discovery requests only for VIPs that are part of a router's subnet. If set to **none**, then routers on which the load balancer is applied never reply to ARP/neighbor discovery requests for any of the load balancer VIPs. Load balancers with **options:template=true** do not support **reachable** as a valid mode. The default value of this option, if not specified, is **reachable** for regular load balancers and **none** for template load balancers.

options: template: optional string

Option to be set to **true**, if the load balancer is a template. The load balancer VIPs and backends must be using **Chassis_Template_Var** in their definitions.

Load balancer template VIP supported formats are:

^VIP_VAR[:^PORT_VAR|:port]

where VIP_VAR and PORT_VAR are keys of the Chassis_Template_Var variables records.

Note: The VIP and PORT cannot be combined into a single template variable. For example, a **Chassis_Template_Var** variable expanding to **10.0.0.1:8080** is not valid if used as VIP.

Load balancer template backend supported formats are:

^BACKEND_VAR1[:^PORT_VAR1|:port],^BACKEND_VAR2[:^PORT_VAR2|:port] or

BACKENDS_VAR1, BACKENDS_VAR2

where BACKEND_VAR1, PORT_VAR1, BACKEND_VAR2, PORT_VAR2, BACKENDS_VAR1 and BACKENDS_VAR2 are keys of the Chassis_Template_Var variables records.

options: address-family: optional string

Address family used by the load balancer. Supported values are **ipv4** and **ipv6**. The address-family is only used for load balancers with **options:template=true**. For explicit load balancers, setting the address-family has no effect.

options: affinity_timeout: optional string

If the CMS provides a positive value (in seconds) for **affinity_timeout**, OVN will dnat connections received from the same client to this lb to the same backend if received in the affinity timeslot. Max supported affinity_timeout is 65535 seconds.

options: ct_flush: optional string, either true or false

The value indicates whether ovn-controller should flush CT entries that are related to this LB. The flush happens if the LB is removed, any of the backends is updated/removed or the LB is not considered local anymore by the ovn-controller. This option is set to **false** by default.

Load_Balancer_Group TABLE

Each row represents a logical grouping of load balancers. It is up to the CMS to decide the criteria on which load balancers are grouped together. To simplify configuration and to optimize its processing load balancers that must be associated to the same set of logical switches and/or logical routers should be grouped together.

Summary:

namestring (must be unique within table)load_balancerset of weak reference to Load_Balancers

Details:

name: string (must be unique within table)

A name for the load balancer group. This name has no special meaning or purpose other than to provide convenience for human interaction with the ovn-nb database.

load_balancer: set of weak reference to Load_Balancers

A set of load balancers.

Load_Balancer_Health_Check TABLE

Each row represents one load balancer health check.

Summary:

vip string

Health check options:

options : intervaloptional string, containing an integeroptions : timeoutoptional string, containing an integeroptions : success_countoptional string, containing an integeroptions : failure_countoptional string, containing an integer

Common Columns:

external_ids map of string-string pairs

Details:

vip: string

vip whose endpoints should be monitored for health check.

Health check options:

options : interval: optional string, containing an integer The interval, in seconds, between health checks.

options: timeout: optional string, containing an integer

The time, in seconds, after which a health check times out.

options: success_count: optional string, containing an integer

The number of successful checks after which the endpoint is considered online.

options: failure_count: optional string, containing an integer

The number of failure checks after which the endpoint is considered offline.

Common Columns:

external_ids: map of string-string pairs

ACL TABLE

Each row in this table represents one ACL rule for a logical switch or a port group that points to it through its **acls** column. The **action** column for the highest-**priority** matching row in this table determines a packet's treatment. If no row matches, packets are allowed by default. (Default-deny treatment is possible: add a rule with **priority** 0, 1 as **match**, and **deny** as **action**.)

Summary:

label integer, in range 0 to 4,294,967,295 priority integer, in range 0 to 32,767 direction string, either from-lport or to-lport match string action string, one of allow-related, allow-stateless, allow, drop, pass, or reject tier integer, in range 0 to 3 options: options: apply-after-lb optional string Logging: log boolean name optional string, at most 63 characters long severity optional string, one of alert, debug, info, notice, or warning meter optional string Common Columns: map of string-string pairs options ACL configuration options: options: log-related optional string external_ids map of string-string pairs

Details:

label: integer, in range 0 to 4,294,967,295

Associates an identifier with the ACL. The same value will be written to corresponding connection tracker entry. The value should be a valid 32-bit unsigned integer. This value can help in debugging from connection tracker side. For example, through this "label" we can backtrack to the ACL rule which is causing a "leaked" connection. Connection tracker entries are created only for allowed connections so the label is valid only for allow and allow-related actions.

priority: integer, in range 0 to 32,767

The ACL rule's priority. Rules with numerically higher priority take precedence over those with lower. If two ACL rules with the same priority both match, then the one actually applied to a packet is undefined.

Return traffic from an **allow-related** flow is always allowed and cannot be changed through an ACL.

allow-stateless flows always take precedence before stateful ACLs, regardless of their priority. (Both **allow** and **allow-related** ACLs can be stateful.)

direction: string, either from-lport or to-lport

Direction of the traffic to which this rule should apply:

- **from-lport**: Used to implement filters on traffic arriving from a logical port. These rules are applied to the logical switch's ingress pipeline.
- **to-lport**: Used to implement filters on traffic forwarded to a logical port. These rules are applied to the logical switch's egress pipeline.

match: string

The packets that the ACL should match, in the same expression language used for the **match** column in the OVN Southbound database's **Logical_Flow** table. The **outport** logical port is only available in the **to-lport** direction (the **inport** is available in both directions).

By default all traffic is allowed. When writing a more restrictive policy, it is important to remember to allow flows such as ARP and IPv6 neighbor discovery packets.

Note that you can not create an ACL matching on a port with type=router or type=localnet.

action: string, one of allow-related, allow-stateless, allow, drop, pass, or reject

The action to take when the ACL rule matches:

- allow-stateless: Always forward the packet in stateless manner, omitting connection tracking mechanism, regardless of other rules defined for the switch. May require defining additional rules for inbound replies. For example, if you define a rule to allow outgoing TCP traffic directed to an IP address, then you probably also want to define another rule to allow incoming TCP traffic coming from this same IP address. In addition, traffic that matches stateless ACLs will bypass load-balancer DNAT/un-DNAT processing. Stateful ACLs should be used instead if the traffic is supposed to be load-balanced.
- allow: Forward the packet. It will also send the packets through connection tracking when allow-related rules exist on the logical switch. Otherwise, it's equivalent to allow-stateless.
- allow-related: Forward the packet and related traffic (e.g. inbound replies to an outbound connection).
- **drop**: Silently drop the packet.
- **reject**: Drop the packet, replying with a RST for TCP or ICMPv4/ICMPv6 unreachable message for other IPv4/IPv6-based protocols.
- pass: Pass to the next ACL tier. If using multiple ACL tiers, a match on this ACL will stop evaluating ACLs at the current tier and move to the next one. If not using ACL tiers or if a pass ACL is matched at the final tier, then the options:default_acl_drop option from the NB_Global table is used to determine how to proceed.

tier: integer, in range 0 to 3

The hierarchical tier that this ACL belongs to.

ACLs can be assigned to numerical tiers. When evaluating ACLs, an internal counter is used to determine which tier of ACLs should be evaluated. Tier 0 ACLs are evaluated first. If no verdict can be determined, then tier 1 ACLs are evaluated next. This continues until the maximum tier value is reached. If all tiers of ACLs are evaluated and no verdict is reached, then the **options:default_acl_drop** option from table **NB_Global** is used to determine how to proceed.

In this version of OVN, the maximum tier value for ACLs is 3, meaning there are 4 tiers of ACLs allowed (0–3).

options:

ACLs options.

options: apply-after-lb: optional string

If set to true, the ACL will be applied after load balancing stage. Supported only for **from-lport** direction.

The main use case of this option is to support ACLs matching on the destination IP address of the packet for the backend IPs of load balancers.

OVN will apply the **from-lport** ACLs in two stages. ACLs without this option **apply-after-lb** set, will be applied before the load balancer stage and ACLs with this option set will be applied after the load balancer stage. The priorities are indepedent between these stages and may not be obvious to the CMS. Hence CMS should be extra careful when using this option and should carefully evaluate the priorities of all the ACLs and the default deny/allow ACLs if any.

Logging:

These columns control whether and how OVN logs packets that match an ACL.

log: boolean

If set to **true**, packets that match the ACL will trigger a log message on the transport node or nodes that perform ACL processing. Logging may be combined with any **action**.

If set to **false**, the remaining columns in this group have no significance.

name: optional string, at most 63 characters long

This name, if it is provided, is included in log records. It provides the administrator and the cloud management system a way to associate a log record with a particular ACL.

severity: optional string, one of alert, debug, info, notice, or warning

The severity of the ACL. The severity levels match those of syslog, in decreasing level of severity: **alert**, **warning**, **notice**, **info**, or **debug**. When the column is empty, the default is **info**.

meter: optional string

The name of a meter to rate-limit log messages for the ACL. The string must match the **name** column of a row in the **Meter** table. By default, log messages are not rate-limited. In order to ensure that the same **Meter** rate limits multiple ACL logs separately, set the **fair** column.

Common Columns:

options: map of string-string pairs

This column provides general key/value settings. The supported options are described individually below.

ACL configuration options:

options: log-related: optional string

If set to **true**, then log when reply or related traffic is admitted from a stateful ACL. In order for this option to function, the **log** option must be set to **true** and a **label** must be set, and it must be unique to the ACL. The label is necessary as it is the only means to associate the reply traffic with the ACL to which it belongs. It must be unique, because otherwise it is ambiguous which ACL will be matched. Note: If this option is enabled, an extra flow is installed in order to log the related traffic. Therefore, if this is enabled on all ACLs, then the total number of flows necessary to log the ACL traffic is doubled, compared to if this option is not enabled.

external_ids: map of string-string pairs

Logical Router TABLE

Each row represents one L3 logical router.

```
Summary:
```

 ports
 set of Logical_Router_Ports

 static_routes
 set of Logical_Router_Static_Routes

 policies
 set of Logical_Router_Policys

 enabled
 optional boolean

enabled optional boolean nat set of NATs

load_balancer set of weak reference to Load_Balancers

load_balancer_group set of Load_Balancer_Groups

Naming:

copp optional weak reference to Copp

Options:

options : chassisoptional stringoptions : dnat_force_snat_ipoptional stringoptions : lb_force_snat_ipoptional string

options : requested-tnl-key optional string, containing an integer, in range 1 to

16,777,215

options : snat-ct-zone optional string, containing an integer, in range 0 to

65,535

options: mac_binding_age_threshold optional string, containing an integer, in range 0 to

4,294,967,295

Common Columns:

external_ids map of string-string pairs

Details:

ports: set of Logical_Router_Ports

The router's ports.

static_routes: set of Logical_Router_Static_Routes

Zero or more static routes for the router.

policies: set of Logical_Router_Policys

Zero or more routing policies for the router.

enabled: optional boolean

This column is used to administratively set router state. If this column is empty or is set to **true**, the router is enabled. If this column is set to **false**, the router is disabled. A disabled router has all ingress and egress traffic dropped.

nat: set of NATs

One or more NAT rules for the router. NAT rules only work on Gateway routers, and on distributed routers with one and only one distributed gateway port.

load_balancer: set of weak reference to Load_Balancers

Set of load balancers associated to this logical router. Load balancer Load balancer rules only work on the Gateway routers or routers with one and only one distributed gateway port.

load_balancer_group: set of Load_Balancer_Groups

Set of load balancers groups associated to this logical router.

Naming:

These columns provide names for the logical router. From OVN's perspective, these names have no special

meaning or purpose other than to provide convenience for human interaction with the northbound database. There is no requirement for the name to be unique. (For a unique identifier for a logical router, use its row UUID.)

(Originally, **name** was intended to serve the purpose of a human-friendly name, but the Neutron integration used it to uniquely identify its own router object, in the format **neutron**–*uuid*. Later on, Neutron started propagating the friendly name of a router as **external_ids:neutron:router_name**. Perhaps this can be cleaned up someday.)

name: string

A name for the logical router.

external ids: neutron:router name: optional string

Another name for the logical router.

copp: optional weak reference to Copp

The control plane protection policy from table **Copp** used for metering packets sent to **ovn–controller** from logical ports of this router.

Options:

Additional options for the logical router.

options: chassis: optional string

If set, indicates that the logical router in question is a Gateway router (which is centralized) and resides in the set chassis. The same value is also used by **ovn-controller** to uniquely identify the chassis in the OVN deployment and comes from **external_ids:system-id** in the **Open_vSwitch** table of Open_vSwitch database.

The Gateway router can only be connected to a distributed router via a switch if SNAT and DNAT are to be configured in the Gateway router.

options : dnat_force_snat_ip: optional string

If set, indicates a set of IP addresses to use to force SNAT a packet that has already been DNATed in the gateway router. When multiple gateway routers are configured, a packet can potentially enter any of the gateway router, get DNATted and eventually reach the logical switch port. For the return traffic to go back to the same gateway router (for unDNATing), the packet needs a SNAT in the first place. This can be achieved by setting the above option with a gateway specific set of IP addresses. This option may have exactly one IPv4 and/or one IPv6 address on it, separated by a a space.

options: lb_force_snat_ip: optional string

If set, this option can take two possible type of values. Either a set of IP addresses or the string value - **router_ip**.

If a set of IP addresses are configured, it indicates to use to force SNAT a packet that has already been load-balanced in the gateway router. When multiple gateway routers are configured, a packet can potentially enter any of the gateway routers, get DNATted as part of the load-balancing and eventually reach the logical switch port. For the return traffic to go back to the same gateway router (for unDNATing), the packet needs a SNAT in the first place. This can be achieved by setting the above option with a gateway specific set of IP addresses. This option may have exactly one IPv4 and/or one IPv6 address on it, separated by a space character.

If it is configured with the value **router_ip**, then the load balanced packet is SNATed with the IP of router port (attached to the gateway router) selected as the destination after taking the routing decision.

options: mcast_relay: optional string, either true or false

Enables/disables IP multicast relay between logical switches connected to the logical router. Default: False.

options: dynamic_neigh_routers: optional string, either true or false

If set to **true**, the router will resolve neighbor routers' MAC addresses only by dynamic ARP/ND, instead of prepopulating static mappings for all neighbor routers in the ARP/ND Resolution stage. This reduces number of flows, but requires ARP/ND messages to resolve the IP-MAC bindings when needed. It is **false** by default. It is recommended to set to **true** when a large number of logical routers are connected to the same logical switch but most of them never need to send traffic between each other. By default, ovn-northd does not create mappings to NAT and load balancer addresses. However, for NAT and load balancer addresses that have the **add_route** option added, ovn-northd will create logical flows that map NAT and load balancer IP addresses to the appropriate MAC address. Setting *dynamic_neigh_routers* to **true** will prevent the automatic creation of these logical flows.

options: always_learn_from_arp_request: optional string, either true or false

This option controls the behavior when handling IPv4 ARP requests or IPv6 ND-NS packets - whether a dynamic neighbor (MAC binding) entry is added/updated.

true - Always learn the MAC-IP binding, and add/update the MAC binding entry.

false - If there is a MAC binding for that IP and the MAC is different, or, if TPA of ARP request belongs to any router port on this router, then update/add that MAC-IP binding. Otherwise, don't update/add entries.

It is **true** by default. It is recommended to set to **false** when a large number of logical routers are connected to the same logical switch but most of them never need to send traffic between each other, to reduce the size of the MAC binding table.

options: requested-tnl-key: optional string, containing an integer, in range 1 to 16,777,215

Configures the datapath tunnel key for the logical router. This is not needed because **ovn-northd** will assign an unique key for each datapath by itself. However, if it is configured, **ovn-northd** honors the configured value.

options : snat-ct-zone: optional string, containing an integer, in range 0 to 65,535

Use the requested conntrack zone for SNAT with this router. This can be useful if egress traffic from the host running OVN comes from both OVN and other sources. This way, OVN and the other sources can make use of the same conntrack zone.

options : mac_binding_age_threshold: optional string, containing an integer, in range 0 to 4,294,967,295 MAC binding aging **threshold** value in seconds. MAC binding exceeding this timeout will be automatically removed. The value defaults to 0, which means disabled.

Common Columns:

external ids: map of string-string pairs

QoS TABLE

Each row in this table represents one QoS rule for a logical switch that points to it through its **qos_rules** column. Two types of QoS are supported: DSCP marking and metering. A **match** with the highest-**priority** will have QoS applied to it. If the **action** column is specified, then matching packets will have DSCP marking applied. If the **bandwidth** column is specified, then matching packets will have metering applied. **action** and **bandwidth** are not exclusive, so both marking and metering by defined for the same QoS entry. If no row matches, packets will not have any QoS applied.

Summary:

priority integer, in range 0 to 32,767

direction string, either from-lport or to-lport

match string

action map of string-integer pairs, key must be dscp, value

in range 0 to 63

bandwidth map of string-integer pairs, key either burst or rate,

value in range 1 to 4,294,967,295

external_ids map of string-string pairs

Details:

priority: integer, in range 0 to 32,767

The QoS rule's priority. Rules with numerically higher priority take precedence over those with lower. If two QoS rules with the same priority both match, then the one actually applied to a packet is undefined.

direction: string, either from-lport or to-lport

The value of this field is similar to ACL column in the OVN Northbound database's ACL table.

match: string

The packets that the QoS rules should match, in the same expression language used for the **match** column in the OVN Southbound database's **Logical_Flow** table. The **outport** logical port is only available in the **to-lport** direction (the **inport** is available in both directions).

action: map of string-integer pairs, key must be dscp, value in range 0 to 63

When specified, matching flows will have DSCP marking applied.

• **dscp**: The value of this action should be in the range of 0 to 63 (inclusive).

bandwidth: map of string-integer pairs, key either burst or rate, value in range 1 to 4,294,967,295

When specified, matching packets will have bandwidth metering applied. Traffic over the limit will be dropped.

- **rate**: The value of rate limit in kbps.
- **burst**: The value of burst rate limit in kilobits. This is optional and needs to specify the **rate**.

external_ids: map of string-string pairs

Mirror TABLE

Each row in this table represents a mirror that can be used for port mirroring. These mirrors are referenced by the **mirror_rules** column in the **Logical_Switch_Port** table.

Summary:

name string (must be unique within table)

filter string, one of both, from-lport, or to-lport

sink string

type string, one of erspan, gre, or local

index integer

external_ids map of string-string pairs

Details:

name: string (must be unique within table)
Represents the name of the mirror.

filter: string, one of both, from-lport, or to-lport

The value of this field represents selection criteria of the mirror. **to-lport** mirrors the packets coming into logical port. **from-lport** mirrors the packets going out of logical port. **both** mirrors for both directions.

sink: string

The value of this field represents the destination/sink of the mirror. If the *type* is **gre** or **erspan**, the value indicates the tunnel remote IP (either IPv4 or IPv6). For a *type* of **local**, this field defines a local interface on the OVS integration bridge to be used as the mirror destination. The interface must possess external-ids:mirror-id that matches this string.

type: string, one of erspan, gre, or local

The value of this field specifies the mirror type - gre, erspan or local.

index: integer

The value of this field represents the tunnel ID. If the configured tunnel type is **gre**, this field represents the **GRE** key value and if the configured tunnel type is **erspan** it represents the **erspan_idx** value. It is ignored if the type is **local**.

external_ids: map of string-string pairs

Meter TABLE

Each row in this table represents a meter that can be used for QoS or rate-limiting.

Summary:

name string (must be unique within table)

unit string, either kbps or pktps bands set of 1 or more Meter_Bands

fair optional boolean

external_ids map of string-string pairs

Details:

name: string (must be unique within table)

A name for this meter.

Names that begin with "__" (two underscores) are reserved for OVN internal use and should not be added manually.

unit: string, either kbps or pktps

The unit for **rate** and **burst_rate** parameters in the **bands** entry. **kbps** specifies kilobits per second, and **pktps** specifies packets per second.

bands: set of 1 or more Meter_Bands

The bands associated with this meter. Each band specifies a rate above which the band is to take the action **action**. If multiple bands' rates are exceeded, then the band with the highest rate among the exceeded bands is selected.

fair: optional boolean

This column is used to further describe the desired behavior of the meter when there are multiple references to it. If this column is empty or is set to **false**, the rate will be shared across all rows that refer to the same Meter **name**. Conversely, when this column is set to **true**, each user of the same Meter will be rate-limited on its own.

external ids: map of string-string pairs

Meter Band TABLE

Each row in this table represents a meter band which specifies the rate above which the configured action should be applied. These bands are referenced by the **bands** column in the **Meter** table.

Summary:

action string, must be **drop**

rate integer, in range 1 to 4,294,967,295
burst_size integer, in range 0 to 4,294,967,295
external_ids map of string-string pairs

Details:

action: string, must be drop

The action to execute when this band matches. The only supported action is **drop**.

rate: integer, in range 1 to 4,294,967,295

The rate limit for this band, in kilobits per second or bits per second, depending on whether the parent **Meter** entry's **unit** column specified **kbps** or **pktps**.

burst_size: integer, in range 0 to 4,294,967,295

The maximum burst allowed for the band in kilobits or packets, depending on whether **kbps** or **pktps** was selected in the parent **Meter** entry's **unit** column. If the size is zero, the switch is free to select some reasonable value depending on its configuration.

external_ids: map of string-string pairs

Logical Router Port TABLE

A port within an L3 logical router.

Exactly one **Logical_Router** row must reference a given logical router port.

```
Summary:
```

```
name
                                                    string (must be unique within table)
networks
                                                    set of 1 or more strings
mac
                                                    string
enabled
                                                    optional boolean
Distributed Gateway Ports:
    ha_chassis_group
                                                    optional HA_Chassis_Group
    gateway chassis
                                                    set of Gateway_Chassises
    Options for Physical VLAN MTU Issues:
        options: reside-on-redirect-chassis
                                                    optional string, either true or false
        options: redirect-type
                                                    optional string, either bridged or overlay
ipv6_prefix
                                                    set of strings
ipv6 ra configs:
    ipv6 ra configs: address mode
                                                    optional string
    ipv6_ra_configs : router_preference
                                                    optional string
    ipv6_ra_configs : route_info
                                                    optional string
    ipv6_ra_configs: mtu
                                                    optional string
    ipv6_ra_configs : send_periodic
                                                    optional string
    ipv6 ra configs: max interval
                                                    optional string
    ipv6_ra_configs : min_interval
                                                    optional string
    ipv6 ra configs : rdnss
                                                    optional string
    ipv6_ra_configs: dnssl
                                                    optional string
Options:
                                                    optional string, either true or false
    options: mcast_flood
    options: requested-tnl-key
                                                    optional string, containing an integer, in range 1 to
                                                    32,767
    options: prefix_delegation
                                                    optional string, either true or false
    options: prefix
                                                    optional string, either true or false
    options: route_table
                                                    optional string
    options: gateway_mtu
                                                    optional string, containing an integer, in range 68 to
```

options: gateway mtu bypass

Attachment:

peer

optional string

Common Columns:

external ids map of string-string pairs

Details:

name: string (must be unique within table) A name for the logical router port.

> In addition to provide convenience for human interaction with the northbound database, this column is used as reference by its patch port in Logical_Switch_Port or another logical router port in Logical_Router_Port.

65.535

optional string

A logical router port may not have the same name as a logical switch port, but the database schema cannot enforce this.

networks: set of 1 or more strings

The IP addresses and netmasks of the router. For example, 192.168.0.1/24 indicates that the router's IP address is 192.168.0.1 and that packets destined to 192.168.0.x should be routed to this port.

A logical router port always adds a link-local IPv6 address (fe80::/64) automatically generated from the interface's MAC address using the modified EUI–64 format.

mac: string

The Ethernet address that belongs to this router port.

enabled: optional boolean

This column is used to administratively set port state. If this column is empty or is set to **true**, the port is enabled. If this column is set to **false**, the port is disabled. A disabled port has all ingress and egress traffic dropped.

Distributed Gateway Ports:

Gateways, as documented under **Gateways** in the OVN architecture guide, provide limited connectivity between logical networks and physical ones. OVN support multiple kinds of gateways. The **Logical_Router_Port** table can be used two different ways to configure *distributed gateway ports*, which are one kind of gateway. These two forms of configuration exist for historical reasons. Both of them produce the same kind of OVN southbound records and the same behavior in practice.

If either of these are set, this logical router port represents a distributed gateway port that connects this router to a logical switch with a **localnet** port or a connection to another OVN deployment.

Also mentioned in the OVN architecture guide, distributed gateway ports can also be used for scalability reasons in deployments where logical switches are dedicated to chassises rather than distributed.

The preferred way to configure a gateway is **ha_chassis_group**, but **gateway_chassis** is also supported for backward compatibility. Only one of these should be set at a time on a given LRP, since they configure the same features.

Even when a gateway is configured, the logical router port still effectively resides on each chassis. However, due to the implications of the use of L2 learning in the physical network, as well as the need to support advanced features such as one-to-many NAT (aka IP masquerading), a subset of the logical router processing is handled in a centralized manner on the gateway chassis.

There can be more than one distributed gateway ports configured on each logical router, each connecting to different L2 segments. Load-balancing is not yet supported on logical routers with more than one distributed gateway ports.

For each distributed gateway port, it may have more than one gateway chassises. When more than one gateway chassis is specified, OVN only uses one at a time. OVN can rely on OVS BFD implementation to monitor gateway connectivity, preferring the highest-priority gateway that is online. Priorities are specified in the **priority** column of **Gateway_Chassis** or **HA_Chassis**.

ovn—northd programs the **external_mac** rules specified in the LRP's LR into the peer logical switch's destination lookup on the chassis where the **logical_port** resides. In addition, the logical router's MAC address is automatically programmed in the peer logical switch's destination lookup flow on the gateway chassis. If it is desired to generate gratuitous ARPs for NAT addresses, then set the peer LSP's **options:nat-addresses** to **router**.

OVN 20.03 and earlier supported a third way to configure distributed gateway ports using **options:redirect-chassis** to specify the gateway chassis. This method is no longer supported. Any remaining users should switch to one of the newer methods instead. A **gateway_chassis** may be easily configured from the command line, e.g. **ovn-nbctl lrp-set-gateway-chassis** *lrp chassis*.

ha_chassis_group: optional HA_Chassis_Group

Designates an **HA_Chassis_Group** to provide gateway high availability.

gateway_chassis: set of Gateway_Chassises

Designates one or more Gateway_Chassis for the logical router port.

Options for Physical VLAN MTU Issues:

MTU issues arise in mixing tunnels with logical networks that are bridged to a physical VLAN. For an explanation of the MTU issues, see **Physical VLAN MTU Issues** in the OVN architecture document. The

following options, which are alternatives, provide solutions. Both of them cause packets to be sent over **localnet** instead of tunnels, but they differ in whether some or all packets are sent this way. The most prominent tradeoff between these options is that **reside-on-redirect-chassis** is easier to configure and that **redirect-type** performs better for east-west traffic.

options: reside-on-redirect-chassis: optional string, either true or false

If set to **true**, this option forces all traffic across the logical router port to pass through the gateway chassis using a hop across a **localnet** port. This changes behavior in two ways:

- Without this option, east-west traffic passes directly between source and destination chassis (or even within a single chassis, for co-located VMs). With this option, all east-west traffic passes through the gateway chassis.
- Without this option, traffic between the gateway chassis and other chassis is encapsulated in tunnels. With this option, traffic passes over a **localnet** interface.

This option may usefully be set only on logical router ports that connect a distributed logical router to a logical switch with VIFs. It should not be set on a distributed gateway port.

OVN honors this option only if the logical router has one and only one distributed gateway port and if the LRP's peer switch has a **localnet** port.

options: redirect-type: optional string, either bridged or overlay

If set to **bridged** on a distributed gateway port, this option causes OVN to redirect packets to the gateway chassis over a **localnet** port instead of a tunnel. The relevant chassis must share a **localnet** port.

This feature requires the administrator or the CMS to configure each participating chassis with a unique Ethernet address for the logical router by setting **ovn-chassis-mac-mappings** in the Open vSwitch database, for use by **ovn-controller**.

Setting this option to **overlay** or leaving it unset has no effect. This option may usefully be set only on a distributed gateway port when there is one and only one distributed gateway port on the logical router. It is otherwise ignored.

ipv6_prefix: set of strings

This column contains IPv6 prefix obtained by prefix delegation router according to RFC 3633 *ipv6_ra_configs*:

This column defines the IPv6 ND RA address mode and ND MTU Option to be included by **ovn-controller** when it replies to the IPv6 Router solicitation requests.

ipv6_ra_configs: address_mode: optional string

The address mode to be used for IPv6 address configuration. The supported values are:

- **slaac**: Address configuration using Router Advertisement (RA) packet. The IPv6 prefixes defined in the **Logical_Router_Port** table's **networks** column will be included in the RA's ICMPv6 option Prefix information.
- **dhcpv6_stateful**: Address configuration using DHCPv6.
- dhcpv6_stateless: Address configuration using Router Advertisement (RA) packet. Other IPv6 options are provided by DHCPv6.

ipv6_ra_configs : router_preference: optional string

Default Router Preference (PRF) indicates whether to prefer this router over other default routers (RFC 4191). Possible values are:

- HIGH: mapped to 0x01 in RA PRF field
- MEDIUM: mapped to 0x00 in RA PRF field
- LOW: mapped to 0x11 in RA PRF field

ipv6_ra_configs : route_info: optional string

Route Info is used to configure Route Info Option sent in Router Advertisement according to RFC 4191. Route Info is a comma separated string where each field provides PRF and prefix for a given route (e.g.: HIGH-aef1::11/48,LOW-aef2::11/96) Possible PRF values are:

- HIGH: mapped to 0x01 in RA PRF field
- MEDIUM: mapped to 0x00 in RA PRF field
- LOW: mapped to 0x11 in RA PRF field

ipv6_ra_configs : mtu: optional string

The recommended MTU for the link. Default is 0, which means no MTU Option will be included in RA packet replied by ovn-controller. Per RFC 2460, the mtu value is recommended no less than 1280, so any mtu value less than 1280 will be considered as no MTU Option.

ipv6_ra_configs : send_periodic: optional string

If set to true, then this router interface will send router advertisements periodically. The default is false.

ipv6_ra_configs : max_interval: optional string

The maximum number of seconds to wait between sending periodic router advertisements. This option has no effect if **ipv6_ra_configs:send_periodic** is false. The default is 600.

ipv6_ra_configs : min_interval: optional string

The minimum number of seconds to wait between sending periodic router advertisements. This option has no effect if **ipv6_ra_configs:send_periodic** is false. The default is one-third of **ipv6_ra_configs:max_interval**, i.e. 200 seconds if that key is unset.

ipv6_ra_configs : rdnss: optional string

IPv6 address of RDNSS server announced in RA packets. At the moment OVN supports just one RDNSS server.

ipv6_ra_configs: dnssl: optional string

DNS Search List announced in RA packets. Multiple DNS Search List must be 'comma' separated (e.g. "a.b.c, d.e.f")

Options:

Additional options for the logical router port.

options : mcast_flood: optional string, either true or false

If set to **true**, multicast traffic (including reports) are unconditionally forwarded to the specific port.

This option applies when the port is part of a logical router which has **options**:mcast_relay set to **true**.

Default: false.

options: requested-tnl-key: optional string, containing an integer, in range 1 to 32,767

Configures the port binding tunnel key for the port. Usually this is not needed because **ovn-northd** will assign an unique key for each port by itself. However, if it is configured, **ovn-northd** honors the configured value.

options: prefix_delegation: optional string, either true or false

If set to **true**, enable IPv6 prefix delegation state machine on this logical router port (RFC3633). IPv6 prefix delegation is available just on a gateway router or on a gateway router port.

options: prefix: optional string, either true or false

If set to **true**, this interface will receive an IPv6 prefix according to RFC3663

options : route_table: optional string

Designates lookup Logical_Router_Static_Routes with specified **route_table** value. Routes to directly connected networks from same Logical Router and routes without **route_table** option set

have higher priority than routes with route_table option set.

options: gateway_mtu: optional string, containing an integer, in range 68 to 65,535

If set, logical flows will be added to router pipeline to check packet length. If packet length is greater than the value set, ICMPv4 type 3 (Destination Unreachable) code 4 (Fragmentation Needed and Don't Fragment was Set) or ICMPv6 type 2 (Packet Too Big) code 0 (no route to destination) packets will be generated. This allows for Path MTU Discovery.

options: gateway_mtu_bypass: optional string

When configured, represents a match expression, in the same expression language used for the **match** column in the OVN Southbound database's **Logical_Flow** table. Packets matching this expression will bypass the length check configured through the **options:gateway_mtu** option.

Attachment:

A given router port serves one of two purposes:

- To attach a logical switch to a logical router. A logical router port of this type is referenced by exactly one Logical_Switch_Port of type router. The value of name is set as router-port in column options of Logical_Switch_Port. In this case peer column is empty.
- To connect one logical router to another. This requires a pair of logical router ports, each
 connected to a different router. Each router port in the pair specifies the other in its peer
 column. No Logical_Switch refers to the router port.

peer: optional string

For a router port used to connect two logical routers, this identifies the other router port in the pair by **name**.

For a router port attached to a logical switch, this column is empty.

Common Columns:

external_ids: map of string-string pairs

See External IDs at the beginning of this document.

The **ovn-northd** program copies all these pairs into the **external_ids** column of the **Port_Binding** table in **OVN_Southbound** database.

Logical_Router_Static_Route TABLE

Each record represents a static route.

When multiple routes match a packet, the longest-prefix match is chosen. For a given prefix length, a **dst-ip** route is preferred over a **src-ip** route.

When there are ECMP routes, i.e. multiple routes with same prefix and policy, one of them will be selected based on the 5-tuple hashing of the packet header.

Summary:

ip_prefix string

policy optional string, either dst-ip or src-ip

nexthop string

bfd optional weak reference to **BFD**

route_table string

external_ids : ic-learned-route optional string

Common Columns:

external_ids map of string-string pairs

Common options:

options map of string-string pairs

Details:

ip_prefix: string

IP prefix of this route (e.g. 192.168.100.0/24).

policy: optional string, either dst-ip or src-ip

If it is specified, this setting describes the policy used to make routing decisions. This setting must be one of the following strings:

- **src-ip**: This policy sends the packet to the **nexthop** when the packet's source IP address matches **ip_prefix**.
- **dst-ip**: This policy sends the packet to the **nexthop** when the packet's destination IP address matches **ip_prefix**.

If not specified, the default is **dst-ip**.

nexthop: string

Nexthop IP address for this route. Nexthop IP address should be the IP address of a connected router port or the IP address of a logical port or can be set to **discard** for dropping packets which match the given route.

output_port: optional string

The name of the **Logical_Router_Port** via which the packet needs to be sent out. This is optional and when not specified, OVN will automatically figure this out based on the **nexthop**. When this is specified and there are multiple IP addresses on the router port and none of them are in the same subnet of **nexthop**, OVN chooses the first IP address as the one via which the **nexthop** is reachable.

bfd: optional weak reference to BFD

Reference to BFD row if the route has associated a BFD session

route_table: string

Any string to place route to separate routing table. If Logical Router Port has configured value in **options:route_table** other than empty string, OVN performs route lookup for all packets entering Logical Router ingress pipeline from this port in the following manner:

- 1. First lookup among "global" routes: routes without **route_table** value set and routes to directly connected networks.
- 2. Next lookup among routes with same **route_table** value as specified in LRP's options:route_table field.

external_ids : ic-learned-route: optional string

ovn—ic populates this key if the route is learned from the global **OVN_IC_Southbound** database. In this case the value will be set to the uuid of the row in **Route** table of the **OVN_IC_Southbound** database.

Common Columns:

external_ids: map of string-string pairs

See External IDs at the beginning of this document.

Common options:

options: map of string-string pairs

This column provides general key/value settings. The supported options are described individually below.

options : ecmp_symmetric_reply: optional string

If true, then new traffic that arrives over this route will have its reply traffic bypass ECMP route selection and will be sent out this route instead. Note that this option overrides any rules set in the **Logical_Router_policy** table. This option only works on gateway routers (routers that have **options:chassis** set).

options: origin: optional string

In case ovn-interconnection has been learned this route, it will have its origin set: either "connected" or "static". This key is supposed to be written only by **ovn-ic** daemon. ovn-northd then checks this value when generating Logical Flows. **Logical_Router_Static_Route** records with same **ip_prefix** within same Logical Router will have next lookup order based on **origin** key value:

- 1. connected
- 2. static

Logical Router Policy TABLE

Each row in this table represents one routing policy for a logical router that points to it through its **policies** column. The **action** column for the highest-**priority** matching row in this table determines a packet's treatment. If no row matches, packets are allowed by default. (Default-deny treatment is possible: add a rule with **priority** 0, 1 as **match**, and **drop** as **action**.)

Summary:

priority integer, in range 0 to 32,767

match string

action string, one of allow, drop, or reroute

nexthopoptional stringnexthopsset of stringsoptions: pkt_markoptional string

Common Columns:

external_ids map of string-string pairs

Details:

priority: integer, in range 0 to 32,767

The routing policy's priority. Rules with numerically higher priority take precedence over those with lower. A rule is uniquely identified by the priority and match string.

match: string

The packets that the routing policy should match, in the same expression language used for the **match** column in the OVN Southbound database's **Logical_Flow** table.

By default all traffic is allowed. When writing a more restrictive policy, it is important to remember to allow flows such as ARP and IPv6 neighbor discovery packets.

action: string, one of allow, drop, or reroute

The action to take when the routing policy matches:

- **allow**: Forward the packet.
- drop: Silently drop the packet.
- **reroute**: Reroute packet to **nexthop** or **nexthops**.

nexthop: optional string

Note: This column is deprecated in favor of **nexthops**.

Next-hop IP address for this route, which should be the IP address of a connected router port or the IP address of a logical port.

nexthops: set of strings

Next-hop ECMP IP addresses for this route. Each IP in the list should be the IP address of a connected router port or the IP address of a logical port.

One IP from the list is selected as next hop.

options : pkt_mark: optional string

Marks the packet with the value specified when the router policy is applied. CMS can inspect this packet marker and take some decisions if desired. This value is not preserved when the packet goes out on the wire.

Common Columns:

external_ids: map of string-string pairs

NAT TABLE

Each record represents a NAT rule.

Summary:

type string, one of dnat, dnat_and_snat, or snat external_ip string optional string

external_port_range string

logical_ipstringlogical_portoptional stringallowed_ext_ipsoptional Address_Setexempted_ext_ipsoptional Address_Set

gateway_port optional weak reference to Logical_Router_Port

options : statelessoptional stringoptions : add_routeoptional string

Common Columns:

external_ids map of string-string pairs

Details:

type: string, one of dnat, dnat_and_snat, or snat

Type of the NAT rule.

- When **type** is **dnat**, the externally visible IP address **external_ip** is DNATted to the IP address **logical_ip** in the logical space.
- When type is snat, IP packets with their source IP address that either matches the IP address in logical_ip or is in the network provided by logical_ip is SNATed into the IP address in external_ip.
- When **type** is **dnat_and_snat**, the externally visible IP address **external_ip** is DNATted to the IP address **logical_ip** in the logical space. In addition, IP packets with the source IP address that matches **logical_ip** is SNATed into the IP address in **external_ip**.

external_ip: string

An IPv4 address.

external_mac: optional string

A MAC address.

This is only used on the gateway port on distributed routers. This must be specified in order for the NAT rule to be processed in a distributed manner on all chassis. If this is not specified for a NAT rule on a distributed router, then this NAT rule will be processed in a centralized manner on the gateway port instance on the gateway chassis.

This MAC address must be unique on the logical switch that the gateway port is attached to. If the MAC address used on the **logical_port** is globally unique, then that MAC address can be specified as this **external mac**.

external_port_range: string

L4 source port range

Range of ports, from which a port number will be picked that will replace the source port of to be NATed packet. This is basically PAT (port address translation).

Value of the column is in the format, port_lo-port_hi. For example: external_port_range: "1-30000"

Valid range of ports is 1–65535.

logical_ip: string

An IPv4 network (e.g 192.168.1.0/24) or an IPv4 address.

logical_port: optional string

The name of the logical port where the **logical_ip** resides.

This is only used on distributed routers. This must be specified in order for the NAT rule to be processed in a distributed manner on all chassis. If this is not specified for a NAT rule on a distributed router, then this NAT rule will be processed in a centralized manner on the gateway port instance on the gateway chassis.

allowed_ext_ips: optional Address_Set

It represents Address Set of external ips that NAT rule is applicable to. For SNAT type NAT rules, this refers to destination addresses. For DNAT type NAT rules, this refers to source addresses.

This configuration overrides the default NAT behavior of applying a rule solely based on internal IP. Without this configuration, NAT happens without considering the external IP (i.e dest/source for snat/dnat type rule). With this configuration NAT rule is applied ONLY if external ip is in the input Address Set.

exempted_ext_ips: optional Address_Set

It represents Address Set of external ips that NAT rule is NOT applicable to. For SNAT type NAT rules, this refers to destination addresses. For DNAT type NAT rules, this refers to source addresses.

This configuration overrides the default NAT behavior of applying a rule solely based on internal IP. Without this configuration, NAT happens without considering the external IP (i.e dest/source for snat/dnat type rule). With this configuration NAT rule is NOT applied if external ip is in the input Address Set.

If there are NAT rules in a logical router with overlapping IP prefixes (including /32), then usage of *exempted_ext_ips* should be avoided in following scenario. a. SNAT rule (let us say RULE1) with logical_ip PREFIX/MASK (let us say 50.0.0.0/24). b. SNAT rule (let us say RULE2) with logical_ip PREFIX/MASK+1 (let us say 50.0.0.0/25). c. Now, if exempted_ext_ips is associated with RULE2, then a logical ip which matches both 50.0.0.0/24 and 50.0.0.0/25 may get the RULE2 applied to it instead of RULE1.

allowed_ext_ips and *exempted_ext_ips* are mutually exclusive to each other. If both Address Sets are set for a rule, then the NAT rule is not considered.

gateway_port: optional weak reference to Logical_Router_Port

A distributed gateway port in the **Logical_Router_Port** table where the NAT rule needs to be applied.

When multiple distributed gateway ports are configured on a Logical_Router, applying a NAT rule at each of the distributed gateway ports might not be desired. Consider the case where a logical router has 2 distributed gateway port, one with networks 50.0.10/24 and the other with networks 60.0.0.10/24. If the logical router has a NAT rule of type snat, logical_ip 10.1.1.0/24 and external_ip 50.1.1.20/24, the rule needs to be selectively applied on matching packets entering/leaving through the distributed gateway port with networks 50.0.0.10/24.

When a logical router has multiple distributed gateway ports and this column is not set for a NAT rule, then the rule will be applied at the distributed gateway port which is in the same network as the **external_ip** of the NAT rule, if such a router port exists. If logical router has a single distributed gateway port and this column is not set for a NAT rule, the rule will be applied at the distributed gateway port even if the router port is not in the same network as the **external_ip** of the NAT rule.

options: stateless: optional string

Indicates if a dnat_and_snat rule should lead to connection tracking state or not.

options : add_route: optional string

If set to **true**, then neighbor routers will have logical flows added that will allow for routing to the NAT address. It also will have ARP resolution logical flows added. By setting this option, it means there is no reason to create a **Logical_Router_Static_Route** from neighbor routers to this NAT

address. It also means that no ARP request is required for neighbor routers to learn the IP-MAC mapping for this NAT address. This option only applies to NATs of type **dnat** and **dnat_and_snat**. For more information about what flows are added for IP routes, please see the **ovn-northd** manpage section on IP Routing.

Common Columns:

external_ids: map of string-string pairs

DHCP Options TABLE

OVN implements native DHCPv4 support which caters to the common use case of providing an IPv4 address to a booting instance by providing stateless replies to DHCPv4 requests based on statically configured address mappings. To do this it allows a short list of DHCPv4 options to be configured and applied at each compute host running **ovn-controller**.

OVN also implements native DHCPv6 support which provides stateless replies to DHCPv6 requests.

```
Summary:
```

```
cidr
                                                    string
DHCPv4 options:
    Mandatory DHCPv4 options:
        options: server_id
                                                    optional string
        options: server_mac
                                                    optional string
        options: lease_time
                                                    optional string, containing an integer, in range 0 to
                                                    4,294,967,295
    IPv4 DHCP Options:
        options: router
                                                    optional string
        options: netmask
                                                    optional string
        options : dns server
                                                    optional string
        options: log_server
                                                    optional string
        options: lpr_server
                                                    optional string
        options: swap_server
                                                    optional string
        options: policy filter
                                                    optional string
        options: router_solicitation
                                                    optional string
        options: nis_server
                                                    optional string
        options : ntp_server
                                                    optional string
        options: netbios_name_server
                                                    optional string
        options: classless static route
                                                    optional string
        options: ms classless static route
                                                    optional string
        options : next_server
                                                    optional string
    Boolean DHCP Options:
        options: ip_forward_enable
                                                    optional string, either 0 or 1
        options: router_discovery
                                                    optional string, either 0 or 1
                                                    optional string, either 0 or 1
        options: ethernet encap
    Integer DHCP Options:
        options : default_ttl
                                                    optional string, containing an integer, in range 0 to
                                                    255
        options: tcp_ttl
                                                    optional string, containing an integer, in range 0 to
                                                    255
        options: mtu
                                                    optional string, containing an integer, in range 68 to
                                                   65.535
        options: T1
                                                    optional string, containing an integer, in range 68 to
                                                   4,294,967,295
        options: T2
                                                    optional string, containing an integer, in range 68 to
                                                    4,294,967,295
        options: arp_cache_timeout
                                                    optional string, containing an integer, in range 0 to
                                                    255
        options: tcp_keepalive_interval
                                                    optional string, containing an integer, in range 0 to
        options: netbios node type
                                                    optional string, containing an integer, in range 0 to
                                                    255
    String DHCP Options:
        options: wpad
                                                    optional string
```

options: bootfile name optional string options: path_prefix optional string options: tftp_server_address optional string options: hostname optional string options: domain name optional string options : bootfile_name_alt optional string options: broadcast address optional string DHCP Options of type host_id:

options: tftp_server optional string

DHCP Options of type domains:

options: domain search list optional string

DHCPv6 options:

Mandatory DHCPv6 options:

options: server_id optional string

IPv6 DHCPv6 options:

options : dns server optional string

String DHCPv6 options:

options: domain_search optional string options: dhcpv6_stateless optional string

Common Columns:

external ids map of string-string pairs

Details:

cidr: string

The DHCPv4/DHCPv6 options will be included if the logical port has its IP address in this cidr.

DHCPv4 options:

The CMS should define the set of DHCPv4 options as key/value pairs in the options column of this table. For ovn-controller to include these DHCPv4 options, the dhcpv4_options of Logical_Switch_Port should refer to an entry in this table.

Mandatory DHCPv4 options:

The following options must be defined.

options: server id: optional string

The IP address for the DHCP server to use. This should be in the subnet of the offered IP. This is also included in the DHCP offer as option 54, "server identifier."

options: server_mac: optional string

The Ethernet address for the DHCP server to use.

options: lease_time: optional string, containing an integer, in range 0 to 4,294,967,295

The offered lease time in seconds,

The DHCPv4 option code for this option is 51.

IPv4 DHCP Options:

Below are the supported DHCPv4 options whose values are an IPv4 address, e.g. 192.168.1.1. Some options accept multiple IPv4 addresses enclosed within curly braces, e.g. {192.168.1.2, 192.168.1.3}. Please refer to RFC 2132 for more details on DHCPv4 options and their codes.

options: router: optional string

The IP address of a gateway for the client to use. This should be in the subnet of the offered IP. The DHCPv4 option code for this option is 3.

options: netmask: optional string

The DHCPv4 option code for this option is 1.

options : dns_server: optional string

The DHCPv4 option code for this option is 6.

options: log_server: optional string

The DHCPv4 option code for this option is 7.

options: lpr_server: optional string

The DHCPv4 option code for this option is 9.

options : swap_server: optional string

The DHCPv4 option code for this option is 16.

options : policy_filter: optional string

The DHCPv4 option code for this option is 21.

options: router_solicitation: optional string

The DHCPv4 option code for this option is 32.

options: nis_server: optional string

The DHCPv4 option code for this option is 41.

options : ntp_server: optional string

The DHCPv4 option code for this option is 42.

options: netbios name server: optional string

The DHCPv4 option code for this option is 44.

options : classless_static_route: optional string

The DHCPv4 option code for this option is 121.

This option can contain one or more static routes, each of which consists of a destination descriptor and the IP address of the router that should be used to reach that destination. Please see RFC 3442 for more details.

Example: {30.0.0.0/24,10.0.0.10, 0.0.0.0/0,10.0.0.1}

options: ms_classless_static_route: optional string

The DHCPv4 option code for this option is 249. This option is similar to **classless_static_route** supported by Microsoft Windows DHCPv4 clients.

options: next_server: optional string

The DHCPv4 option code for setting the "Next server IP address" field in the DHCP header.

Boolean DHCP Options:

These options accept a Boolean value, expressed as **0** for false or **1** for true.

options: ip_forward_enable: optional string, either 0 or 1

The DHCPv4 option code for this option is 19.

options : router_discovery: optional string, either **0** or **1**

The DHCPv4 option code for this option is 31.

options: ethernet_encap: optional string, either 0 or 1

The DHCPv4 option code for this option is 36.

Integer DHCP Options:

These options accept a nonnegative integer value.

options: default_ttl: optional string, containing an integer, in range 0 to 255

The DHCPv4 option code for this option is 23.

options: tcp_ttl: optional string, containing an integer, in range 0 to 255

The DHCPv4 option code for this option is 37.

options: mtu: optional string, containing an integer, in range 68 to 65,535

The DHCPv4 option code for this option is 26.

options: T1: optional string, containing an integer, in range 68 to 4,294,967,295

This specifies the time interval from address assignment until the client begins trying to renew its address. The DHCPv4 option code for this option is 58.

options: T2: optional string, containing an integer, in range 68 to 4,294,967,295

This specifies the time interval from address assignment until the client begins trying to rebind its address. The DHCPv4 option code for this option is 59.

options: arp_cache_timeout: optional string, containing an integer, in range 0 to 255

The DHCPv4 option code for this option is 35. This option specifies the timeout in seconds for ARP cache entries.

options: tcp_keepalive_interval: optional string, containing an integer, in range 0 to 255

The DHCPv4 option code for this option is 38. This option specifies the interval that the client TCP should wait before sending a keepalive message on a TCP connection.

options : netbios_node_type: optional string, containing an integer, in range 0 to 255

The DHCPv4 option code for this option is 46.

String DHCP Options:

These options accept a string value.

options: wpad: optional string

The DHCPv4 option code for this option is 252. This option is used as part of web proxy auto discovery to provide a URL for a web proxy.

options: bootfile_name: optional string

The DHCPv4 option code for this option is 67. This option is used to identify a bootfile.

options : path_prefix: optional string

The DHCPv4 option code for this option is 210. In PXELINUX' case this option is used to set a common path prefix, instead of deriving it from the bootfile name.

options: tftp_server_address: optional string

The DHCPv4 option code for this option is 150. The option contains one or more IPv4 addresses that the client MAY use. This option is Cisco proprietary, the IEEE standard that matches with this requirement is option 66 (tftp_server).

options: hostname: optional string

The DHCPv4 option code for this option is 12. If set, indicates the DHCPv4 option "Hostname". Alternatively, this option can be configured in **options:hostname** column in table **Logical_Switch_Port**. If Hostname option value is set in both conflicting **Logical_Switch_Port** and **DHCP_Options** tables, **Logical_Switch_Port** takes precedence.

options: domain name: optional string

The DHCPv4 option code for this option is 15. This option specifies the domain name that client should use when resolving hostnames via the Domain Name System.

options : bootfile_name_alt: optional string

"bootfile_name_alt" option is used to support iPXE. When both "bootfile_name" and "bootfile_name_alt" are provided by the CMS, "bootfile_name" will be used for option 67 if the dhcp request contains etherboot option (175), otherwise "bootfile_name_alt" will be used.

options: broadcast address: optional string

The DHCPv4 option code for this option is 28. This option specifies the IP address used as a broadcast address.

DHCP Options of type host_id:

These options accept either an IPv4 address or a string value.

options : tftp_server: optional string

The DHCPv4 option code for this option is 66.

DHCP Options of type domains:

These options accept string value which is a comma separated list of domain names. The domain names are encoded based on RFC 1035.

options: domain search list: optional string

The DHCPv4 option code for this option is 119.

DHCPv6 options:

OVN also implements native DHCPv6 support. The CMS should define the set of DHCPv6 options as key/value pairs. The define DHCPv6 options will be included in the DHCPv6 response to the DHCPv6 Solicit/Request/Confirm packet from the logical ports having the IPv6 addresses in the **cidr**.

Mandatory DHCPv6 options:

The following options must be defined.

options: server_id: optional string

The Ethernet address for the DHCP server to use. This is also included in the DHCPv6 reply as option 2, "Server Identifier" to carry a DUID identifying a server between a client and a server. **ovn–controller** defines DUID based on Link-layer Address [DUID-LL].

IPv6 DHCPv6 options:

Below are the supported DHCPv6 options whose values are an IPv6 address, e.g. aef0::4. Some options accept multiple IPv6 addresses enclosed within curly braces, e.g. {aef0::4, aef0::5}. Please refer to RFC 3315 for more details on DHCPv6 options and their codes.

options: dns_server: optional string

The DHCPv6 option code for this option is 23. This option specifies the DNS servers that the VM should use.

String DHCPv6 options:

These options accept string values.

options : domain_search: optional string

The DHCPv6 option code for this option is 24. This option specifies the domain search list the client should use to resolve hostnames with DNS.

Example: "ovn.org".

options: dhcpv6_stateless: optional string

This option specifies the OVN native DHCPv6 will work in stateless mode, which means OVN native DHCPv6 will not offer IPv6 addresses for VM/VIF ports, but only reply other configurations, such as DNS and domain search list. When setting this option with string value "true", VM/VIF will configure IPv6 addresses by stateless way. Default value for this option is false.

Common Columns:

external_ids: map of string-string pairs

Connection TABLE

Configuration for a database connection to an Open vSwitch database (OVSDB) client.

This table primarily configures the Open vSwitch database server (ovsdb-server).

The Open vSwitch database server can initiate and maintain active connections to remote clients. It can also listen for database connections.

Summary:

Core Features:

target string (must be unique within table)

Client Failure Detection and Handling:

max_backoff optional integer, at least 1,000

inactivity_probe optional integer

Status:

is_connected boolean status: last_error optional string

status: state optional string, one of ACTIVE, BACKOFF, CON-

NECTING, IDLE, or VOID

status : sec_since_connect optional string, containing an integer, at least 0 **status : sec_since_disconnect** optional string, containing an integer, at least 0

status: locks_heldoptional stringstatus: locks_waitingoptional stringstatus: locks_lostoptional string

status: n_connections optional string, containing an integer, at least 2

status: bound port optional string, containing an integer

Common Columns:

external_ids map of string-string pairs other_config map of string-string pairs

Details:

Core Features:

target: string (must be unique within table)

Connection methods for clients.

The following connection methods are currently supported:

ssl:host[:port]

The specified SSL *port* on the host at the given *host*, which can either be a DNS name (if built with unbound library) or an IP address. A valid SSL configuration must be provided when this form is used, this configuration can be specified via command-line options or the **SSL** table.

If *port* is not specified, it defaults to 6640.

SSL support is an optional feature that is not always built as part of Open vSwitch.

tcp:host[:port]

The specified TCP *port* on the host at the given *host*, which can either be a DNS name (if built with unbound library) or an IP address. If *host* is an IPv6 address, wrap it in square brackets, e.g. tcp:[::1]:6640.

If *port* is not specified, it defaults to 6640.

pssl:[port][:host]

Listens for SSL connections on the specified TCP *port*. Specify 0 for *port* to have the kernel automatically choose an available port. If *host*, which can either be a DNS name (if built with unbound library) or an IP address, is specified, then connections are restricted to the resolved or specified local IPaddress (either IPv4 or IPv6 address). If *host* is an IPv6 address, wrap in square brackets, e.g. **pssl:6640:[::1]**. If *host* is not specified then it listens only on IPv4 (but not IPv6) addresses. A valid SSL configuration must be

provided when this form is used, this can be specified either via command-line options or the **SSL** table.

If *port* is not specified, it defaults to 6640.

SSL support is an optional feature that is not always built as part of Open vSwitch.

ptcp:[port][:host]

Listens for connections on the specified TCP *port*. Specify 0 for *port* to have the kernel automatically choose an available port. If *host*, which can either be a DNS name (if built with unbound library) or an IP address, is specified, then connections are restricted to the resolved or specified local IP address (either IPv4 or IPv6 address). If *host* is an IPv6 address, wrap it in square brackets, e.g. **ptcp:6640:[::1]**. If *host* is not specified then it listens only on IPv4 addresses.

If *port* is not specified, it defaults to 6640.

When multiple clients are configured, the **target** values must be unique. Duplicate **target** values yield unspecified results.

Client Failure Detection and Handling:

max_backoff: optional integer, at least 1,000

Maximum number of milliseconds to wait between connection attempts. Default is implementation-specific.

inactivity_probe: optional integer

Maximum number of milliseconds of idle time on connection to the client before sending an inactivity probe message. If Open vSwitch does not communicate with the client for the specified number of seconds, it will send a probe. If a response is not received for the same additional amount of time, Open vSwitch assumes the connection has been broken and attempts to reconnect. Default is implementation-specific. A value of 0 disables inactivity probes.

Status:

Key-value pair of **is_connected** is always updated. Other key-value pairs in the status columns may be updated depends on the **target** type.

When **target** specifies a connection method that listens for inbound connections (e.g. **ptcp:** or **punix:**), both **n_connections** and **is_connected** may also be updated while the remaining key-value pairs are omitted.

On the other hand, when **target** specifies an outbound connection, all key-value pairs may be updated, except the above-mentioned two key-value pairs associated with inbound connection targets. They are omitted.

is connected: boolean

true if currently connected to this client, **false** otherwise.

status : last_error: optional string

A human-readable description of the last error on the connection to the manager; i.e. **strerror(er-rno)**. This key will exist only if an error has occurred.

status: state: optional string, one of ACTIVE, BACKOFF, CONNECTING, IDLE, or VOID

The state of the connection to the manager:

VOID Connection is disabled.

BACKOFF

Attempting to reconnect at an increasing period.

CONNECTING

Attempting to connect.

ACTIVE

Connected, remote host responsive.

IDLE Connection is idle. Waiting for response to keep-alive.

These values may change in the future. They are provided only for human consumption.

status: sec_since_connect: optional string, containing an integer, at least 0

The amount of time since this client last successfully connected to the database (in seconds). Value is empty if client has never successfully been connected.

status : sec_since_disconnect: optional string, containing an integer, at least 0

The amount of time since this client last disconnected from the database (in seconds). Value is empty if client has never disconnected.

status: locks_held: optional string

Space-separated list of the names of OVSDB locks that the connection holds. Omitted if the connection does not hold any locks.

status: locks_waiting: optional string

Space-separated list of the names of OVSDB locks that the connection is currently waiting to acquire. Omitted if the connection is not waiting for any locks.

status: locks_lost: optional string

Space-separated list of the names of OVSDB locks that the connection has had stolen by another OVSDB client. Omitted if no locks have been stolen from this connection.

status: n_connections: optional string, containing an integer, at least 2

When **target** specifies a connection method that listens for inbound connections (e.g. **ptcp:** or **pssl:**) and more than one connection is actually active, the value is the number of active connections. Otherwise, this key-value pair is omitted.

status: bound_port: optional string, containing an integer

When **target** is **ptcp:** or **pssl:**, this is the TCP port on which the OVSDB server is listening. (This is particularly useful when **target** specifies a port of 0, allowing the kernel to choose any available port.)

Common Columns:

The overall purpose of these columns is described under **Common Columns** at the beginning of this document.

external_ids: map of string-string pairs
other_config: map of string-string pairs

DNS TABLE

Each row in this table stores the DNS records. The **Logical_Switch** table's **dns_records** references these records.

Summary:

recordsmap of string-string pairsexternal_idsmap of string-string pairs

Details:

records: map of string-string pairs

Key-value pair of DNS records with **DNS query name** as the key and value as a string of IP address(es) separated by comma or space. For PTR requests, the key-value pair can be **Reverse IPv4 address.in–addr.arpa** and the value **DNS domain name**. For IPv6 addresses, the key has to be **Reverse IPv6 address.ip6.arpa**.

Example: "vm1.ovn.org" = "10.0.0.4 aef0::4"

Example: "4.0.0.10.in-addr.arpa" = "vm1.ovn.org"

external_ids: map of string-string pairs

SSL TABLE

SSL configuration for ovn-nb database access.

Summary:

private_keystringcertificatestringca_certstringbootstrap_ca_certbooleanssl_protocolsstringssl_ciphersstring

Common Columns:

external_ids map of string-string pairs

Details:

private key: string

Name of a PEM file containing the private key used as the switch's identity for SSL connections to the controller.

certificate: string

Name of a PEM file containing a certificate, signed by the certificate authority (CA) used by the controller and manager, that certifies the switch's private key, identifying a trustworthy switch.

ca_cert: string

Name of a PEM file containing the CA certificate used to verify that the switch is connected to a trustworthy controller.

bootstrap_ca_cert: boolean

If set to **true**, then Open vSwitch will attempt to obtain the CA certificate from the controller on its first SSL connection and save it to the named PEM file. If it is successful, it will immediately drop the connection and reconnect, and from then on all SSL connections must be authenticated by a certificate signed by the CA certificate thus obtained. **This option exposes the SSL connection to a man-in-the-middle attack obtaining the initial CA certificate.** It may still be useful for bootstrapping.

ssl_protocols: string

List of SSL protocols to be enabled for SSL connections. The default when this option is omitted is TLSv1.1,TLSv1.2.

ssl_ciphers: string

List of ciphers (in OpenSSL cipher string format) to be supported for SSL connections. The default when this option is omitted is **HIGH:**!aNULL:!MD5.

Common Columns:

The overall purpose of these columns is described under **Common Columns** at the beginning of this document.

external_ids: map of string-string pairs

Gateway_Chassis TABLE

Association of a chassis to a logical router port. The traffic going out through an specific router port will be redirected to a chassis, or a set of them in high availability configurations.

Summary:

name string (must be unique within table)

chassis_name string

priorityinteger, in range 0 to 32,767optionsmap of string-string pairs

Common Columns:

external_ids map of string-string pairs

Details:

name: string (must be unique within table) Name of the **Gateway_Chassis**.

A suggested, but not required naming convention is **\${port_name}_\${chassis_name}**.

chassis_name: string

Name of the chassis that we want to redirect traffic through for the associated logical router port. The value must match the **name** column of the **Chassis** table in the **OVN_Southbound** database.

priority: integer, in range 0 to 32,767

This is the priority of a chassis among all **Gateway_Chassis** belonging to the same logical router

options: map of string-string pairs

Reserved for future use.

Common Columns:

external_ids: map of string-string pairs

HA_Chassis_Group TABLE

Table representing a group of chassis which can provide high availability services. Each chassis in the group is represented by the table **HA_Chassis**. The HA chassis with highest priority will be the master of this group. If the master chassis failover is detected, the HA chassis with the next higher priority takes over the responsibility of providing the HA. If a distributed gateway router port references a row in this table, then the master HA chassis in this group provides the gateway functionality.

Summary:

name string (must be unique within table)

ha_chassis set of HA_Chassises

Common Columns:

external_ids map of string-string pairs

Details:

name: string (must be unique within table)

Name of the **HA_Chassis_Group**. Name should be unique.

ha_chassis: set of HA_Chassises

A list of HA chassis which belongs to this group.

Common Columns:

external_ids: map of string-string pairs

HA_Chassis TABLE

Summary:

chassis_name string

priority integer, in range 0 to 32,767

Common Columns:

external_ids map of string-string pairs

Details:

chassis_name: string

Name of the chassis which is part of the HA chassis group. The value must match the **name** column of the **Chassis** table in the **OVN_Southbound** database.

priority: integer, in range 0 to 32,767

Priority of the chassis. Chassis with highest priority will be the master.

Common Columns:

external_ids: map of string-string pairs

BFD TABLE

Contains BFD parameter for ovn-controller BFD configuration. OVN BFD implementation is used to provide detection of failures in the path between adjacent forwarding engines, including the OVN interfaces. OVN BFD provides link status info to OVN northd in order to update logical flows according to the status of BFD endpoints. In the current implementation OVN BFD is used to check next-hop status for ECMP routes. Please note BFD table refers to OVN BFD implementation and not to OVS legacy one.

Summary:

```
Configuration:
    logical_port
                                                     string
    dst_ip
                                                     string
    min tx
                                                     optional integer, at least 1
    min_rx
                                                     optional integer
    detect_mult
                                                     optional integer, at least 1
    options
                                                     map of string-string pairs
    external_ids
                                                     map of string-string pairs
Status Reporting:
    status
                                                     optional string, one of admin_down, down, init, or
```

Details:

Configuration:

ovn-northd reads configuration from these columns.

logical_port: string

OVN logical port when BFD engine is running.

dst_ip: string

BFD peer IP address.

min_tx: optional integer, at least 1

This is the minimum interval, in milliseconds, that the local system would like to use when transmitting BFD Control packets, less any jitter applied. The value zero is reserved. Default value is 1000 ms.

min_rx: optional integer

This is the minimum interval, in milliseconds, between received BFD Control packets that this system is capable of supporting, less any jitter applied by the sender. If this value is zero, the transmitting system does not want the remote system to send any periodic BFD Control packets.

detect_mult: optional integer, at least 1

Detection time multiplier. The negotiated transmit interval, multiplied by this value, provides the Detection Time for the receiving system in Asynchronous mode. Default value is 5.

options: map of string-string pairs

Reserved for future use.

external ids: map of string-string pairs

See External IDs at the beginning of this document.

Status Reporting:

ovn–northd writes BFD status into these columns.

status: optional string, one of admin_down, down, init, or up

BFD port logical states. Possible values are:

- admin_down
- down

- init
- up

Static_MAC_Binding TABLE

Each record represents a Static_MAC_Binding entry for a logical router.

Summary:

Configuration:

logical_portstringipstringmacstringoverride_dynamic_macboolean

Details:

Configuration:

ovn–northd reads configuration from these columns and propagates the value to SBDB.

logical_port: string

The logical router port for the binding.

ip: string

The bound IP address.

mac: string

The Ethernet address to which the IP is bound.

override_dynamic_mac: boolean

Override dynamically learnt MACs.

Chassis_Template_Var TABLE

One record per chassis, each containing a map, **variables**, between template variable names and their value for that specific chassis. A template variable has a name and potentially different values on different hypervisors in the OVN cluster. For example, two rows, $R1 = (.chassis=C1, variables=\{(N: V1)\}$ and $R2 = (.chassis=C2, variables=\{(N: V2)\}$ will make **ovn-controller** running on chassis C1 and C2 interpret the token N either as V1 (on C1) or as V2 (on C2). Users can refer to template variables from within other logical components, e.g., within ACL, QoS or Logical_Router_Policy matches or from Load_Balancer VIP and backend definitions.

If a template variable is referenced on a chassis for which that variable is not defined then **ovn–controller** running on that chassis will just interpret it as a raw string literal.

Summary:

chassis string (must be unique within table)

variables map of string-string pairs

Common Columns:

external_ids map of string-string pairs

Details:

chassis: string (must be unique within table)

The chassis this set of variable values applies to.

variables: map of string-string pairs

The set of variable values for a given chassis.

Common Columns:

external_ids: map of string-string pairs