



**Introduction to Cloud Computing** 

Module 3: Virtual Machines (Part 1)

### **OUTLINE**


- Virtual vs. Real
- Computer organization
- OS recap
  - A process as a unit of computation
  - Multiprocessing
  - Virtual views: How a process gets to think that it owns
  - the CPU
  - **infinite** memory
  - all devices to itself


## AMERICAN HERITAGE DICTIONARY DEFINITION

vir·tu·al (vûr□ch□-əl):

- adj.1. Existing or resulting in essence or effect though not in actual fact, form, or name: the virtual extinction of the buffalo.
- 2. Existing in the mind, especially as a product of the imagination. Used in literary criticism of a text.
- 3. Computers Created, simulated, or carried on by means of a computer or computer network: virtual conversations in a chatroom.

## COMPUTER ORGANIZATION





## The CPU Loop: first approximation

```
While TRUE
     Fetch the instruction pointed to by the PC;
     Advance the PC to the next instruction;
     Execute the instruction;
        100000
               LOAD
                       R1
                               @20002
               LOAD
        100020
                       R2
                               @20010
```

### A Process

- Modern operating systems support *multiprogramming*—that is an ability to execute several programs concurrently on one CPU or simultaneously on several CPUs
- A process is a program in execution:
  - A program is a cookbook
  - A CPU is a cook
  - I/O devices are cooking utensils
  - A process is making a dish described in t program)



# Operating System Services To a Process

Program execution (Process or Thread)

Input/Output (I/O) operations

File-system support

Interprocess Communications

Error detection

Resource allocation

Accounting

Protection

### The process's stack and the procedure call

Main line of the process code


100000	LOAD	R1	@20002	Å	Stack Frame
100010	LOAD	R2	@20010		
100020	STORE	R1	@SP		Saved PC
100030	ADD	SP	#-4	/ 1	(100080)
100040	STORE	R2	@SP		Internal variable 2
100050	ADD	SP	#-4		
100060	ADD	SP	#-8		Internal variable 1
100070	JPR	100	00000		Parameter 2
100080	ADD	SP	#16		Parameter 1
100090	•••	<u>                                  </u>	•••		
The procedure code					

10000000	LOAD	R1	@(SP +#20)
•••		•••	•••
10005000	RTP		

### WHERE IS THIS PROCESS?

• In older systems (up until 1960), there was a place in memory for *one* process. The Operating System loaded it and ran it

### Low memory



#### **Problems:**

- 1. Low CPU Utilization
- 2. A need to program device drivers in each process for the devices it uses
- 3. Inability to split a program into manageable independent concurrent pieces
- 4. Effectively, inability to support more than one interactive user

## Multiprogramming

Operating System

Process 1

Process 2

• • •

Process n

Igor Faynberg, Cloud Computing, Lecture 3

### BUT WHILE ONE PROCESS IS WAITING...

...Others had better use the CPU and run!




• Then the OS must get control of the CPU!



## INTERRUPTS AND EXCEPTIONS

### 1. Interrupts




Interrupts occur asynchronously with the execution of the code


## INTERRUPTS AND EXCEPTIONS

1 Exceptions (examples)

3) A *TRAP* 

instruction





1) Memory: Bus error "LOAD R1 7000000000"



2) A nonexecutable instruction: "DIV R1 R2"

Exceptions occur synchronously with the execution of the code

## THE OPERATING SYSTEM (KERNEL) CODE

• A library of subroutine calls, which are performed by the CPU itself

• Addresses of these service routines reside in the interrupt vector table, indexed by the interrupt or exception number. **Kernel Library** 

	Interrupt Vector Table	
0	Disc service routine	
1	Keyboard service routine	
2	Div by 0 exception routine	

### An example: Using a TRAP instruction to set a breakpoint

ADD R1, #1 2A 0001 01

STORE R1, @R2 B3 0001 02

ADD R2, #4 2A 0004 02

Save the instruction and replace it with TRAP #1

ADD R1, #1

**TRAP** #1

ADD R2, #4

0001 02

2A 0001 01

2A 0004 02

## The second approximation of the CPU loop

```
While TRUE
    Fetch the instruction pointed to by the PC;
    Advance the PC to the next instruction;
    Execute the instruction;
         (an exception #x has been raised) OR
         ((an interrupt #x has been raised) AND interrupts are enabled)
        If it is an exception
                                                                 An interrupt stack
          Restore the previous PC value;
                                                                         frame
        Save the STATUS Register and the PC @SP;
        PC = Interrupt Vector[#x];
                             An interrupt service routine
                                                                     Saved PC
                               30000000
                                            DISI
 Interrupt vectors
                                                                      Saved Status
                                             SAVEREGS
                               3000004
                                                                        Register
       2300000
 #1
                                             @SP
 #2
       7000000
                                                                          Saved
                                    . . .
                                                                        registers'
                                            RESTREGS @SP
                               30006000
       3000000
 \#\mathbf{x}
                                                                          image
                                            ENI
                               30006004
                  Introduction to Clo30006008 Le
                                                   Igor Faynberg
```

## A simple *hypervisor-debugger*

### The Go() code


## The service routine for TRAP

```
Go()
    #DISI; /* disable interrupts */
    registers struct.SP =
       registers struct.SP +4;
   #RESTREGS @registers struct;
   #STORE PC @SP+8;
   #STORE STATUS @SP+4
     /* place the PC and Status in
        their proper place within
        the stack frame */
   #ENI; /* enable interrupts */
   #RTI;
```

The TRAP #1 vector stores the address of the TRAP 1 Service Routine:

```
#DISI; /*disable interrupts*/
#SAVEREGS @registers struct;
#ENI; /*enable interrupts */
display(registers struct, PC,
STATUS);
command line();
```

# The process lives through these states



From Silberschatz & al.: Operating Systems Concepts

Igor Faynberg, Introduction to Cloud

## THE PROCESS INFORMATION

**Process ID** 

Process state (ready, running, etc.)

All the registers (including PC and SP)


Memory management information

File information

Children processes information

... many other things ....

## The process table





### PRIVILEGED INSTRUCTIONS

- Instructions that deal with processing interrupts, changing the status register, performing memory management, and the like are mission-critical.
- Critical instructions, by a long-established convention, require CPU processing in a special *supervisory* or *system*—mode
- A CPU may also have a special set of registers, reserved for the system mode. A separate, supervisory stack pointer points to a separate stack
- All exception processing is performed **only** in supervisory mode; an attempt to execute a privileged instruction in a user mode is either ignored [BAD!] or it forces an exception
- (A *Unix* example) Each process therefore actually has two stacks: a  $user\ stack$  and a  $system\ stack$ .


## CPU Mode (an essential security FEATURE)

- To ensure that *only* the OS can execute system code (interrupt processing, memory manipulation, etc.), modern CPU execute the system and user code in different modes
- The mode is typically indicated by a flag in the STATUS register






## The CPU mode state machine



The System Mode and the User Mode are associated with separate stacks

### The modified CPU and the two process stacks




### The CPU loop—the final version


```
While TRUE
     Fetch an instruction pointed to by the PC;
     If the instruction is valid AND
        the instruction is appropriate for the present mode AND
        the parameters are valid for the operation
            Advance the PC to the next instruction;
            Execute the instruction;
      else
         raise an appropriate exception;
     If (an exception #x has been raised) OR
        (an interrupt #x has been raised) AND interrupts are enabled
         Save the STATUS register and PC on the system stack (@SP);
         Switch to the system mode;
        PC = Interrupt Vector[x];
  }
```

## VIRTUALIZATION IN MODERN OPERATING SYSTEMS


- Each *process* thinks that it has
  - huge contiguous memory, starting from address  $\theta$



### How is this memory *virtualization* achieved?




Memory Management Unit (MMU) translates a virtual address into a "real" (physical) address




MDR: Memory Data Register


## Segmentation: The MMU translation processing




## MEMORY REFERENCE TRANSLATION WITH THE MEMORY MANAGEMENT UNIT (MMU)



# VIRTUAL MEMORY: CONTIGUOUS AND "INFINITE"





# PAGES: VIRTUAL MEMORY, PHYSICAL MEMORY, DISC



 $\begin{array}{c|c}
0 & \mathbf{B_1} \\
1 & \mathbf{B_2} \\
2 & \mathbf{B_3} \\
3 & \mathbf{B_4} \\
4 & \mathbf{B_5} \\
5 & \mathbf{B_6}
\end{array}$ 

The Process B Virtual Memory





The Process A Virtual Memory


Free Frame List: 6,7

Physical Memory

### ACCESS PROTECTION RINGS

#### Segment Table revisited


•••	•••	•••	•••	
Start	size	ring	Access type	= {read, write, execute}
•••	• • •	•••	•••	0
	•••	•••		0



Code permitted to access ring i may access ring j if and only if j > i,


### ANOTHER BIT OF HISTORY

- Multics had eight rings
- *OS/2* uses **three** rings: ring *0* for kernel code and device drivers; ring *2* for privileged code (user programs with I/O access permissions); and ring 3, for unprivileged access
- UNIX and Microsoft Windows NT support rings 0 (kernel) and 2 (user programs)



Conclusion: An **OS kernel** by itself
cannot create an
isolated virtual
machine

### A PHYSICAL MACHINE



Peripheral Component Interconnection (PCI)

Igor Faynberg, Cloud

Computing Lecture 2

Note: Integrated Disk Electronics (IDE) is the least expensive current disk technology. IDE support is usually built into the main board.

Small Computer Systems
Interface (SCSI) supports
disks, tapes, and CD-ROM
drives. While IDE disks
provide up to one gigabyte of
storage, SCSI disks are
available with four to 9
gigabytes of storage.

### SUMMARY

- A process as a unit has its own virtual world of resources: A CPU, all I/O devices, an "infinite" memory
- A process relies on an operating system—the government, which ensures that all processes are treated fairly
- The operating system *kernel* is the only entity that can execute privileged instructions; the kernel is entered via traps (internally) and interrupts caused by other events
- A process is aware of other processes
- A machine (Hardware + OS) executes many processes
- Question: How can we *create* a virtual machine?