# **ANQDS v1.0**

# Artificial and Natural Quake Discrimination Software

# **User Manual**

**ANQDS** v1.0 is an open-source and MATLAB-based graphical user interface developed to discriminate the natural and artificial seismic events. The program uses a semi-automatic algorithm based on four different methods to analyze the seismic data:

- Amplitude ratio
- Complexity
- Short-time Fourier transform
- Power spectrum density

It uses two different statistical methods to classify the data:

- Linear discrimination function
- Quadratic discrimination function

ANQDS has the ability to automatically analyze a selected seismic event using the Amplitude ratio and Complexity methods. The program needs user interpretation for analyzes based on the Short-time Fourier transform and Power spectrum density methods.

This software was developed within the scope of AFAD National Earthquake Research Program (UDAP-Ç-19-13). Click to see the software development team.

#### MIT License

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

# 1. Quick Tutorial

#### Installation

**ANQDS** v1.0 requires Matlab 2015a or later versions.

The code includes several subroutines and user interfaces. Please, download the program files and sub folders from GitHub repository.

GitHub repository: <a href="https://github.com/ozkankafadar/ANQDS-v1.0">https://github.com/ozkankafadar/ANQDS-v1.0</a>

#### For installation:

# Option 1:

- If your computer has not a full MATLAB R2015a (64-bit) installation, please, install
  MATLAB Compiler Runtime (MCR), which can be downloaded from MathWorks
  website (http://www.mathworks.com/products/compiler/mcr).
- Run ANQDS v1.0 executable file (ANQDS.exe).


# Option 2:

- If your computer has a MATLAB R2015a or higher version, ANQDS v1.0 can be run using the "Source Code" folder without any installation.
- Please, run MATLAB software and open the "Start.m" file in the "Source Code" folder.
- After that, click the "Run" button (or press F5) in "Editor" panel.

**Note:** Follow the instruction below to give "write permission" to the Temp\_files folder that the program uses for temporary files.

Click the right mouse button on the Temp\_files folder. Then click on properties in the drop-down menu, select a user in the security panel and allow "full control" permission.

# 2. ANQDS v1.0 File System



**ANQDS** v1.0 needs several input files to decide whether a seismic event is natural or artificial. It uses the Excel spreadsheets called **Stations** and **Blasting\_Fields**, located in the **Bin** folder, for information of the stations and quarries in the study area.

#### 2.1. Stations Excel spreadsheet

The **Stations** Excel spreadsheet in **Bin** folder plays a key role for analysis. Because while the program is estimating the source of a seismic event, it uses the weight coefficient of the methods in the Stations Excel spreadsheet.

First of all, the "first estimations" should be performed for each station to obtain the discrimination functions in the amplitude ratio and complexity methods. After that, for each method, the number of events consistent with the "first estimations" are obtained and performed the **Stations** Excel spreadsheet.

The methods used for "first estimation":

- Times and locations of the seismic events
- Amplitudes of the P-wave and S-wave in the seismograms
- First direction of the movement of P-wave in the seismograms

- · Rg phase in the seismograms
- Coda wave attenuation in the seismograms

The **Stations** Excel spreadsheet consists of ten columns including the station name, latitude, longitude, total number of events and the number of events consistent with the "first estimations" for each method. For example; the total number of successful event for amplitude ratio method (LDF) is 99 for ADCV station. So, this value is divided by 2 and 50% ratio were obtained as 49.5 for A-LDF. Similarly, it is calculated as 49.5 for A-QDF.

A	А	В	С	D	E	F	G	Н	T.	J
1	STATION	LATITUDE	LONGITUDE	EVENT	A-LDF	A-QDF	C-LDF	C-QDF	STFT	PS
2	ADCV	38.808	42.7246	101	49.5	49.5	45.5	45.5	72	70
3	AFYN	38.2714	30.5027	100	47.5	49	43.5	45	77	81
4	AFYO	38.7871	30.2988	79	31	32.5	32.5	32	49	38
5	AHAN	41.1639	42.6244	40	0	0	0	0	40	40
6	AKAS	36.2326	29.6052	62	0	0	0	0	61	59
7	AKCA	37.7942	37.6882	100	48.5	48.5	46	45.5	72	68
8	AKCD	38.2956	37.9224	100	43	47	45	47	84	78
9	AKDA	40.1034	41.3636	38	0	0	0	0	38	38
10	AKHS	38.8788	27.8138	100	43	47.5	43	47.5	91	72
11	AKO	37.4615	35.446	114	53	54.5	53	56	83	84
12	AKPI	39.5039	33.9967	100	44	46.5	43	48.5	81	79

A-LDF: Amplitude ratio (LDF), A-QDF: Amplitude ratio (QDF),

C-LDF: Complexity (LDF), C-QDF: Complexity (QDF),

STFT: Short-time Fourier transform,

PS: Power spectrum density

# 2.2. Blasting\_Fields Excel spreadsheet

The **Blasting\_Fields** Excel spreadsheet in the **Bin** folder includes the latitude and longitude information of the quarries in Turkey.

	A B		С	D	
1	NAME	LATIDUTE	LONGITUDE	LOCATION	
2	Noname	28.1285964	41.55989725	Noname	
3	Noname	28.23263042	41.51022964	Noname	
4	Noname	28.10541597	41.16366208	Noname	
5	Noname	28.07613971	41.17181974	Noname	
6	Noname	28.09474282	41.18415464	Noname	
7	Noname	28.09219686	41.19302745	Noname	
8	Noname	28.10004037	41.19983398	Noname	
9	Noname	28.11788819	41.20163849	Noname	
10	Noname	28.16192188	41.21324321	Noname	

# 2.3. MAT files in the AmplitudeRatio\_Complexity

The **AmplitudeRatio\_Complexity** folder includes the MAT files comprising the parameters that are required to calculate the amplitude ratio and complexity values based on the LDF and QDF statistical approaches for each station.

For example, the structure of the ADCV.MAT file belonging to ADCV station:

ADCV.mat (MAT-file)				
■ Name	Value			
istasyon	'ADCV'			
SL_g	101x1 double			
	101x1 double			
SL_k	101x1 double			
	101x1 double			
group	101x1 cell			
🗗 f_gl	function_handle			
	function_handle			
🗹 f_gq	function_handle			
f_kq	function_handle			

#### The MATLAB code to be used to create this MAT file is as follows:

```
stationName = 'Your Station Name';
[parameters, group, ~] = xlsread('Data.xlsx','Sayfa1');
amp1 = parameters(:,1);
amp2 = parameters(:,2);
comp1 = parameters(:,3);
comp2 = parameters(:.4):
[Amp X,Amp Y] = meshgrid(linspace(min(amp2),max(amp2)),linspace(min(amp1),max(amp1)));
Amp_X = Amp_X(:); Amp_Y = Amp_Y(:);
[Comp_X,Comp_Y] =
meshgrid(linspace(min(comp2),max(comp2)),linspace(min(comp1),max(comp1)));
Comp X = Comp X(:); Comp Y = Comp Y(:);
[\sim,\sim,\sim,\sim,\text{coef\_amp\_linear}] = \text{classify}([Amp\_X Amp\_Y],[amp2 amp1],group,'linear');
[~,~,~,coef comp linear] = classify([Comp X Comp Y],[comp2 comp1],group,'linear');
[~,~,~,coef amp quadratic] = classify([Amp X Amp Y],[amp2 amp1],group,'quadratic');
[~,~,~,coef_comp_quadratic] = classify([Comp_X Comp_Y],[comp2 comp1],group,'quadratic');
% Amplitude ratio (LDF)
K amp linear = coef amp linear(1,2).const;
L amp linear = coef amp linear(1,2).linear;
Function amp linear = @(x,y) K amp linear + L amp linear(1)*x + L amp linear(2)*y;
% Complexity (LDF)
K_comp_linear = coef_comp_linear(1,2).const;
L comp linear = coef comp linear(1,2).linear;
Function comp linear = @(x,y) K comp linear + L comp linear(1)*x + L comp linear(2)*y;
% Amplitude ratio (QDF)
K_amp_quadratic = coef_amp_quadratic(1,2).const;
L amp quadratic = coef amp quadratic(1,2).linear;
Q_amp_quadratic = coef_amp_quadratic(1,2).quadratic;
Function amp quadratic= @(x,y) K amp quadratic + [x y]^*L amp quadratic + sum(([x y]^*L)
y]*Q_amp_quadratic) .* [x y], 2);
% Complexity (QDF)
K comp quadratic = coef comp quadratic(1,2).const;
L_comp_quadratic = coef_comp_quadratic(1,2).linear;
Q_comp_quadratic = coef_comp_quadratic(1,2).quadratic;
Function comp quadratic= @(x,y) K comp quadratic + [x y]^*L comp quadratic + sum(([x y]^*L) comp quadratic + [x y]^*L
y]*Q_comp_quadratic) .* [x y], 2);
save([stationName, '.mat'])
```

$\square$	А	В	С	D	Е
1	1.1542	3.95539	2.17028	1.65574	EQ
2	0.63992	3.81271	1.40252	3.42465	EQ
3	0.52356	3.83589	0.85049	3.8181	QB
4	0.35012	3.64435	0.43323	5.84772	QB
5	1.90686	4.0294	3.63706	1.60306	EQ
6	1.72692	4.09736	1.53317	1.51669	EQ
7	1.64609	4.50571	3.33	3.56124	EQ
8	1.66747	5.12538	4.53214	2.50751	EQ
9	2.40011	5.4061	5.17947	1.57834	EQ
10	0.48828	4.11951	0.66578	2.22343	EQ
11	0.46608	4.21645	0.84875	2.45499	QB
12	3.34153	5.57148	6.91883	2.10648	EQ

An example format is given above for the Data.xlsx file. The file contains the logarithm of the maximum amplitude of S-wave (log(As)), amplitude ratio (As/Ap), complexity (C) and spectral ratio (Sr) obtained from the seismograms recorded by a station (EQ: Natural seismic event, QB: Artificial seismic event).

# 2.4. Power spectra Excel spreadsheet in the Power\_Spectra folder

The **Power\_Spectra** folder includes the Excel spreadsheets that consists of the frequency and amplitude values of the maximum and minimum power spectra obtained for each station. For this process, the power spectra of all seismograms for a station are calculated and estimates the maximum and minimum limits of these spectra. In this file, the columns from left to right show x and y coordinates for minimum values of natural events, maximum values of natural events, minimum values of artificial events and maximum values of artificial events, respectively.

	Α	В	С	D	Е	F	G	Н
1	1.03E+00	9.36E+11	1.02E+00	3.78E+05	1.02E+00	1.39E+10	1.01E+00	2.50E+06
2	1.15E+00	1.83E+12	1.14E+00	6.59E+05	1.14E+00	2.66E+10	1.13E+00	3.46E+06
3	1.28E+00	2.28E+12	1.28E+00	1.15E+06	1.27E+00	4.10E+10	1.26E+00	4.78E+06
4	1.43E+00	3.57E+12	1.42E+00	1.61E+06	1.42E+00	7.88E+10	1.41E+00	5.32E+06
5	1.61E+00	4.47E+12	1.59E+00	2.51E+06	1.58E+00	1.09E+11	1.58E+00	8.20E+06
6	1.79E+00	6.25E+12	1.78E+00	3.51E+06	1.77E+00	1.68E+11	1.75E+00	1.02E+07
7	2.00E+00	8.73E+12	1.99E+00	4.40E+06	1.98E+00	2.32E+11	1.96E+00	1.26E+07
8	2.25E+00	9.79E+12	2.22E+00	5.50E+06	2.21E+00	3.21E+11	2.19E+00	1.40E+07
9	2.50E+00	1.37E+13	2.48E+00	6.89E+06	2.45E+00	4.45E+11	2.45E+00	1.56E+07
10	2.80E+00	1.37E+13	2.78E+00	7.72E+06	2.74E+00	6.15E+11	2.73E+00	1.73E+07
11	3.13E+00	1.72E+13	3.10E+00	8.65E+06	3.07E+00	8.50E+11	3.05E+00	1.73E+07
12	3.50E+00	1.93E+13	3.47E+00	9.69E+06	3.43E+00	9.45E+11	3.40E+00	1.72E+07
13	3.91E+00	2.16E+13	3.89E+00	8.70E+06	3.82E+00	1.05E+12	3.80E+00	1.72E+07


# 2.5. MAT files in the Temp\_Files folder

The program creates automatically the parameters required for analysis to the **Temp\_Files** folder for each station. These files are automatically deleted from the **Temp\_Files** folder when the program is closed or a different seismic event is selected using the LOAD button.

# 3. ANQDS v1.0 Graphical User Interface

# 3.1. Main Window

The **ANQDS** v1.0 main program window is a Windows form with tools to display and analyze seismograms recorded by one or more stations. The detailed descriptions of the tools on the form are given below:



# 3.1.1. Menu




By clicking the LOAD button, the directory containing the station records of the event to be analyzed is selected. The program is designed to read the SAC data file format.

The ARRIVAL TIME panel is used to select the P-wave arrival time and signal finish time needed for the Amplitude ratio and Complexity methods. The button is used to reset the arrival times.


The BAND-PASS FILTER (Hz) panel allows to apply the band-pass filter to the seismograms. Thus, P-wave and S-wave arrival times can be selected more precisely. The default values of the cut-off frequencies of the low-pass and high-pass filters are defined as 1 Hz and 10 Hz and these frequencies can be customized. The houton is used to apply the band-pass filter. Besides, the clear button is used to obtain the raw data.

If the event directory is selected, the main menu will look like as follows:



# 3.1.2. Seismogram Panels

**ANQDS** v1.0 displays the available components in the directory of the selected event. The vertical component seismogram must be in the event directory. There is no such requirement for horizontal component seismograms. However, it is recommended to select the S wave arrival time over the horizontal components. The selected P-wave and S-wave arrival times are displayed on both vertical and horizontal components. Zoom feature has been activated to allow precise selection of first arrivals. When the zoom feature is active, the displayed while navigating the signal with the mouse.





# 3.1.3. Status Bar



The status bar is an information panel that displays the name of the selected event directory FOLDER NAME: 6.06.2019 08.39.13, the number of stations available in the directory NUMBER OF STATION: 3, and the name of the station station analysis.

In addition, there is a MAP button within the status bar that can be used to display the map designed to display the location of the seismic event , recording stations and quarries in the region.







Detailed information can be displayed by clicking the station and quarries icons with the left mouse button.

# 3.2. "RESULTS" Window

The RESULTS window consists of four panels:



# 3.2.1. Amplitude Ratio and Complexity Analysis Panel




The blue lines in the graphics indicate the discrimination functions, and the black stars show the amplitude ratio and complexity values. For stations that do not have the MAT files required for the amplitude and complexity methods, the message "**No function information**" is displayed.

Amplitude Ratio (LDF and QDF): The black stars show the ratio of the maximum amplitudes of the S- to P-wave versus the logarithm of the maximum amplitude of the S-wave in the vertical component of the seismogram.


Complexity (LDF and QDF): The black stars show the complexity versus the spectral ratio.

# 3.2.2. Short-Time Fourier Transform Analysis Panel




In the panel, the vertical component seismogram and short-time Fourier transform are displayed. So the time-frequency content of the signal can be monitored in details.

# 3.2.3. Power Spectrum Density Analysis Panel



The red and blue dashed lines represent the power spectrum density ranges calculated from the natural and artificial events recorded at the station, respectively.

# 3.2.4. Station Report Panel



analysis are displayed. Analysis results of the short-time Fourier transform and power spectrum density are user-defined, and drop-down lists Undefined are provided for selection. In the drop-down list; It includes Undefined, Natural and Artificial options. The short-time Fourier transform and power spectrum density should be examined by the user, and the source type of the seismic event should be selected. If the event type is not selected, the


In the panel, the weighting percentages for each method and source types obtained from the

If any station in the event directory is not to be included in the analysis, the Include to Analysis checkbox should be disabled. By default, all stations are assumed to be included in the analysis.

results of these two methods are not included in the analysis.

Natural (%):100.00 Artificial (%):0.00

**ANQDS** v1.0 calculates the success percentages for both station-based and overall analyzes. In the left panel, success percentages are displayed for a station.



Click the General Result button to display the overall analysis percentage values calculated based on all stations. In addition, by clicking the button, each analysis

and next

analysis button

>> ar

are used to navigate through the results of the analyzed stations.

# **Software Development Team**

Assoc. Prof. Dr. Özkan KAFADAR
Kocaeli University
Department of Construction Technology
okafadar@kocaeli.edu.tr

Assoc. Prof. Dr. Erman ŞENTÜRK Kocaeli University Department of Geomatics Engineering erman.senturk@kocaeli.edu.tr

Dr. Hamdullah LİVAOĞLU Kocaeli University hamdullah.livaoglu@kocaeli.edu.tr

# **Project Team**

Prof. Dr. Fadime SERTÇELİK
Assoc. Prof. Dr. Tahir Serkan IRMAK
Assoc. Prof. Dr. Özkan KAFADAR
Dr. Evrim YAVUZ
Dr. Hamdullah LİVAOĞLU
Assoc. Prof. Dr. Erman ŞENTÜRK
Senior Geophysics Engineer Bahar TÜRKYILMAZ
Senior Geophysics Engineer Nalan CEYDİLEK
Senior Geophysics Engineer Gözde MERTER
Senior Geophysics Engineer Seher GÖZSÜZ
Assoc. Prof. Dr. Serpil GERDAN

